

# ASIS-for-GNAT Reference Manual Release 2017




## CONTENTS

1 About This Manual		7	
2	ASIS-for-GNAT and the ASIS Standard		
3	ASIS Extensions  3.1 Asis.Extensions	11 11 11 12	
4	Implementation-Specific Features and Implementation Permissions  4.1 Interacting with the Underlying Ada Implementation  4.1.1 Format of the Parameters String  4.1.2 Parameters of Asis.Implementation.Initialize  4.1.3 Parameters of Asis.Implementation.Finalize  4.1.4 Parameters of Asis.Ada_Environments.Associate  4.2 Implementation Permissions  4.2.1 Asis.Implementation.Permissions Queries  4.2.2 Processing Implicit Elements  4.2.3 Processing Several Contexts at a Time  4.2.4 Implementation-Defined Types and Values  4.3 ASIS Queries Having Specific Implementation Permissions or Implementation-Specific Results  4.4 Processing of Predefined Input-Output Packages  4.5 Representation clauses and -gnatI GNAT option  4.6 Dynamic Context Modes	13 13 13 14 14 14 16 16 17 17 18 18 21 22 22	
5	Debugging Information5.1 Interpreting Debug Images5.2 ASIS Debug Flags	23 23 24	
A	GNU Free Documentation License	25	
In	ndex	31	



GNAT, The GNU Ada Development Environment The GNAT Ada Compiler Version 2017

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, with the Front-Cover Texts being "GNAT Reference Manual", and with no Back-Cover Texts. A copy of the license is included in the section entitled *GNU Free Documentation License*.



ONE

## **ABOUT THIS MANUAL**

This Manual contains reference material for developers using ASIS-for-GNAT — GNAT's implementation of the Ada Semantic Interface Specification (ASIS). It provides information about ASIS-for-GNAT's implementation-specific characteristics and current implementation limitations. (The term 'implementation-specific' in ASIS means what is called 'implementation-defined' in the Ada Reference Manual.)

ASIS has been designed as a portable basis for many kinds of Ada code analysis tools. However, for situations where a developer may need to exploit the characteristics of a particular Ada compiler, ASIS also contains a number of implementation-specific features. These allow interfacing with the underlying Ada implementation, as well as exploiting the implementation permissions for particular queries.

Of course, any ASIS application that uses implementation-specific features may be nonportable. You should follow good programming practice and isolate and clearly document any sections of your program that make use of such features in a nonportable manner.

#### **What This Manual Contains**

This manual contains the following chapters:

- ASIS-for-GNAT and the ASIS Standard, describes the relationship between ASIS-for-GNAT and the existing ASIS International Standard.
- ASIS Extensions, describes the contents of the packages Asis. Extensions, Asis. Extensions. Flat\_Kinds and Asis. Extensions. Iterator.
- Implementation-Specific Features and Implementation Permissions, presents the aspects of the ASIS definition that are implementation specific and describes their treatment in ASIS-for-GNAT.
- Debugging Information, describes the kinds of debugging information that you can generate with ASIS-for-GNAT.

## What You Should Know Before Reading This Manual


This Reference Manual assumes that you are familiar with Ada 95 language as defined by the International Standard ISO/IEC-8652:1995, and with ASIS 95 as defined by the ASIS 95 International Standard ISO/IEC 15291:1999.

This Manual supplements the information presented in the ASIS-for-GNAT User's Guide and uses the terminology introduced there.

### **Related Information**

For more information, please refer to the following documents:

- · GNAT User's Guide
- · ASIS-for-GNAT User's Guide
- · Ada 95 Reference Manual
- · ASIS 95 Standard



**TWO** 

## ASIS-FOR-GNAT AND THE ASIS STANDARD


ASIS-for-GNAT implements ASIS 95 and contains several extensions (see *ASIS Extensions*) as allowed by the ASIS Standard, Section 1.1.3.1.

The differences between the GNAT and standard ASIS are that ASIS-for-GNAT:

- includes GNAT-specific comment headers at the beginning of each source file;
- supplies additional context clauses;
- defines the packages' private parts;
- is formatted to comply with GNAT coding style;
- declares the Is\_Dispatching\_Operation query in Asis.Declarations rather than in Asis.Expressions.

This query has A\_Declaration Element as its argument and, according to the general principles of the ASIS package hierarchy, it should be in the Asis.Declarations spec;

- for the optional Data Decomposition Annex, the package Asis.Data\_Decomposition.Portable\_Transfer is not provided;
- includes extensions that support features introduced in Ada 2005.



THREE

## **ASIS EXTENSIONS**

ASIS-for-GNAT provides some additional types and queries as ASIS extensions. All these queries are defined and documented in the hierarchy headed by package Asis. Extensions. They are referred as 'ASIS extensions' or 'ASIS extension queries' below.

All the ASIS extensions obey the general ASIS rules:

- When using ASIS extensions, you have to follow the required sequencing of calls
- Only ASIS-defined exceptions propagate outside ASIS extension queries

If the documentation of an ASIS extension query contains a list of 'appropriate' Element kinds, then the query can be applied only to Elements from this list, and it raises ASIS\_Inappropriate\_Element with Value\_Error status otherwise. If the documentation of an ASIS extension query contains a list of 'expected' element kinds, then the query can be applied to an Element having any kind, but it returns a meaningful result only for Elements from this list.

The current set of ASIS extensions originated from the ASIS implementation needs and from the development of some ASIS tools inside the ASIS-for-GNAT team. The Asis.Extensions hierarchy is not necessarily frozen: some further extension queries may be added, and suggestions from ASIS application developers are welcome.

Note that some of the ASIS extensions are implemented as ASIS secondary queries — that is, the implementation of such a query is a sequence of primary ASIS queries. Some other extensions are pure extensions; that is, their implementation is based on direct access to GNAT's internal data structures.

## 3.1 Asis Extensions

This package, whose spec is located in the file asis-extensions.ads, contains the declarations of various ASIS extensions, including dynamic Element and Compilation\_Unit list types, placeholder actual parameters for Asis.Iterator.Traverse\_Element, additional Element structural and semantic queries, queries that return information about the status of the source file for a Compilation\_Unit, queries returning the (images of the) values of static expressions, etc.

## 3.2 Asis.Extensions.Flat\_Kinds

The ASIS Element classification hierarchy is based on a set of Ada enumeration types, each corresponding to a 'level' in the hierarchy. The package Asis.Extensions.Flat\_Kinds, whose spec is located in the file asis-extensions-flat\_kinds.ads, defines the enumeration type Flat\_Element\_Kinds; this type combines the values of all these types and thus provides a 'flat' view onto the syntactic Element classification.

## 3.3 Asis.Extensions.Iterator

This package, whose spec is located in the file asis-extensions-iterator.ads, contains the declarations of Traverse\_Unit generic procedure that is a generalization of the standard ASIS Asis.Iterator.Traverse\_Element iterator. Traverse\_Unit provides the depth-first traversal of the whole syntactical structure of the ASIS Compilation Unit.

**FOUR** 

## IMPLEMENTATION-SPECIFIC FEATURES AND IMPLEMENTATION PERMISSIONS

ASIS permits four kinds of implementation-specific behavior.

First, ASIS subprograms that define an interface between an ASIS implementation and the underlying Ada implementation have implementation-specific parameters. There are three such queries — Asis.Implementation.Initialize, Asis.Implementation.Finalize and Asis.Ada\_Environments.Associate.

Each has a string parameter named Parameters with an implementation-specific meaning. The meaning of the Parameters string in ASIS-for-GNAT is discussed in *Interacting with the Underlying Ada Implementation*.

Second, in some areas the ASIS standard explicitly grants the implementation permission to provide restricted functionality; generally this allows omitting features that could present considerable implementation difficulty. Such permissions usually affect more than one ASIS query. The ASIS package Asis. Implementation. Permissions contains boolean queries identifying the choices made by a given ASIS implementation. The ASIS-for-GNAT approach to these implementation permissions is discussed in *Implementation Permissions*.

Third, the ASIS standard defines specific implementation permissions for some queries. Also, the result of a query may be implementation specific because of the nature of the query. See ASIS Queries Having Specific Implementation Permissions or Implementation-Specific Results.

Finally, ASIS-for-GNAT provides special Context manipulation mechanisms that supplement those defined in the ASIS standard. These additional Context modes may be useful for some ASIS applications.

## 4.1 Interacting with the Underlying Ada Implementation

This section describes how to use the Parameters string to pass implementation-specific information to several ASIS subprograms.

## 4.1.1 Format of the Parameters String

A Parameters string is passed to three ASIS subprograms: Asis.Implementation.Initialize, Asis.Implementation.Finalize, and Asis.Ada\_Environments.Associate.

The Parameters string comprises substrings delimited by separators. The substrings are called *parameters* (with lower-case 'p') below. A separator is a non-empty string comprising characters from the set <Space>, <LF>, and <CR>. There may be 0 or more parameters in a Parameters string, and there may be separators before the first and/or after the last parameter.

Each of the queries Asis.Implementation.Initialize, Asis.Implementation.Finalize, and Asis.Ada\_Environments.Associate has specific rules for the format of its parameters. If some parameter is

not well-formed, then either a warning message is generated or else the ASIS\_Failed exception is raised with the Parameter Error status. The descriptions below explain the situations where ASIS Failed is raised.

## 4.1.2 Parameters of Asis. Implementation. Initialize

The allowed parameters for Asis. Implementation. Initialize are as follows:

- -d<flag> The specific ASIS-for-GNAT debug flag named <flag> is set ON
- -dall All the ASIS-for-GNAT debug flags are set ON
- -k Keep going even if an internal implementation error is detected. When a non-ASIS exception is raised, it is replaced by raising ASIS\_Failed with Unhandled\_Exception\_Error status (this is the only case when Unhandled\_Exception\_Error is set) and the Diagnosis string containing the name and the message from the non-ASIS exception originally raised
- -nbb No bug box. Do not output to Standard\_Error the bug box containing the description of the internal implementation bug. Implies -k
- -sv Set the strong GNAT/ASIS version check when reading the tree files
- **-wv** Set the weak GNAT/ASIS version check when reading the tree files
- -we All ASIS warnings are treated as errors.

When execution reaches the point where the warning would occur, the ASIS\_Failed exception is raised; the warning message is the ASIS Diagnosis string.

-ws All ASIS warning messages are suppressed.

The <flag> value for the -d parameter may be any lower case letter from a through z or any digit from 0 through 9, although not all of the 36 possible flags are implemented. For more information, refer to the documentation in the source file a4g-a\_debug.adb. See also ASIS Debug Flags.

If more then one parameter controlling the warning mode is set in the Parameters string, all but the last one are ignored.

## 4.1.3 Parameters of Asis. Implementation. Finalize

No parameters are allowed for Asis. Implementation. Finalize.

Asis.Implementation.Finalize resets all the general ASIS-for-GNAT parameters to their default values (that is, all the debug flags are set OFF, and the warning mode is set to the default warning mode).

## 4.1.4 Parameters of Asis. Ada Environments. Associate

The following parameters are allowed:

- -C1 The Context comprises a single tree file, whose name is given as the next parameter in the Parameters string.
- -CN The Context comprises a set of one or more tree files, whose names are given as the next set of parameters in the Parameters string.
- **-CA** The Context comprises all the tree files in the tree search path.
- **-FS** All the trees considered as making up a given Context are created 'on the fly', whether or not the corresponding tree file already exists. Once created, a tree file then is reused as long as the Context remains open.
- **-FT** Only pre-created trees are used; no tree files are created by ASIS.

- **-FM** Mixed approach: if a needed tree does not exist, an attempt is made to create it 'on the fly'.
- -SA Source files for all the Compilation\_Units belonging to the Context (except the predefined Standard package) are considered in the consistency check when opening the Context.
- -SE Only existing source files for all the Compilation\_Units belonging to the Context are considered in the consistency check when opening the Context.
- -SN No source files from the underlying file system are taken into account when checking the consistency of the set of tree files making up the Context.
- -I<dir> Defines the directory in which to search for source files when compiling sources to create a tree 'on the fly'.
- **--GCC=compiler\_name** Defines the program to be called to create the tree on the fly
- -gnatec<file> Defines the additional configuration file to be used when calling GNAT to create the tree on the fly for -FS or -FM Context
- -gnatA Avoid processing gnat.adc when calling GNAT to create the tree on the fly for -FS or -FM Context
- **-T<dir>** Defines the directory in which to search for a tree file.
- **<fiie\_name>** Defines the name of a tree file (used in conjunction with -C1 or -CN).

For the -I and -T parameters, <dir> should denote an existing directory in the underlying file system. The '.' and '..' notations are allowed, as well as relative or absolute directory names. If <dir> does not denote an existing directory, ASIS\_Failed with Parameter\_Error status is raised.

For ASIS  $\neg FS$  or  $\neg FM$  Context, Context parameters  $\neg I$ ,  $\neg gnatec$  and  $\neg gnatA$  are passed to the GNAT call to create the tree on the fly and these parameters have exactly the same meaning as they have for GNAT.

A tree file name given by a <file\_name> parameter may or may not contain directory information.

Any relative directory name or file name containing relative directory information should start from '.' or '..'.

If a directory or a file name used as a part of some Context parameter contains space characters, this name should be quoted.

The search path associated with an ASIS Context consists of the directories listed as parameters for the Asis.Ada\_Environments.Associate query, in the same order as they are included in the actual Parameters string. The ASIS source search path consists only of the directories following  $\neg T$ , and the ASIS tree search path consists only of the directories are present in the value of the Parameters string, then the ASIS source (tree) search path consists of the current directory only. Otherwise the current directory is included in the ASIS search path if and only if it is set explicitly as  $\neg T$ . respectively.

If an ASIS Context is associated with an -FS or -FM option, the Context source search path is used to locate sources of the units for which tree files need to be created, and to locate other source files needed during compilation. For example, if we have:

```
Asis.Ada_Environments.Associate
(My_Context,
"My_Context_Name",
"-CA -FS -I./dir -I.");
```

then, when processing a call:

#### **ASIS-for-GNAT Reference Manual 2017**

ASIS first tries to locate the source file foo.ads in ./dir, and if this attempt fails, it tries to locate it in the current directory. If there is no such file in the current directory, ASIS continues the search by looking into the directories listed in the value of ADA\_INCLUDE\_PATH environment variable. If the source file is found (say in the current directory), ASIS creates the tree file by calling the compiler:

```
$ gcc -c -gnatc -gnatt -I./dir -I. -I- foo.ads
```

If an ASIS Context is associated with -CA option, then, when this Context is opened, ASIS processes all the tree files located in the tree search path associated with the Context.

The following further rules define the required combinations of parameters in the actual Parameters string:

- -C1 and -CN require -FT
- -FS and -FM require -SA

In case an incompatible combination is set, ASIS\_Failed with Parameter\_Error status is raised.

If the actual Parameters string passed to Associate contains no parameters, the default parameters are -CA, -FT, and -SA.

The -FS and -FM options define *dynamic Context modes*; they allow the content of a Context (that is, the set of ASIS Compilation\_Units contained in the Context) to be changed while the Context is open. See *Dynamic Context Modes* for more details.

For the Name parameter of the Asis.Ada\_Environments.Associate query, any string can be passed as an actual parameter. No verification is performed on the contents, and no semantics are associated with this parameter.

## 4.2 Implementation Permissions

This section describes how ASIS-for-GNAT deals with implementation permissions.

## 4.2.1 Asis. Implementation. Permissions Queries

The Boolean queries defined in the Asis.Implementation.Permissions package return the following results:

Query	Value
Is_Formal_Parameter_Named_Notation_Supported	True
Default_In_Mode_Supported	True
Generic_Actual_Part_Normalized	False
Record_Component_Associations_Normalized	False
Is_Prefix_Call_Supported	True
Function_Call_Parameters_Normalized	False
Call_Statement_Parameters_Normalized	False
Discriminant_Associations_Normalized	False
Is_Line_Number_Supported	True
Is_Span_Column_Position_Supported	True
Is_Commentary_Supported	True
Attributes_Are_Supported	False
Implicit_Components_Supported	False(*)
Object_Declarations_Normalized	False
Predefined_Operations_Supported	False(*)
Inherited_Declarations_Supported	True(*)
Inherited_Subprograms_Supported	True(*)
Generic_Macro_Expansion_Supported	True

<sup>(\*)</sup> See also Processing Implicit Elements.

## 4.2.2 Processing Implicit Elements

ASIS Elements represent both explicit and implicit components of Ada programs. (An example of an implicit construct is an inherited subprogram of a derived type.) Some ASIS queries can return implicit Elements (that is, Elements representing implicit Ada constructs). Any syntactic or semantic query should accept an implicit Element as an Element parameter, but the ASIS Standard allows an implementation not to support implicit Elements at all, or to support them only partially. If an implementation does not support the implicit Element representing a particular kind of construct, then an ASIS query that is supposed to process this implicit Element should return either a Nil\_Element or a Nil\_Element\_List depending on whether the query returns a single Element or an Element\_List.

Implicit Elements are partially supported by ASIS-for-GNAT.

ASIS-for-GNAT supports implicit  ${\tt Elements}$  for the following constructs:

- Derived user-defined subprograms
- · Derived enumeration literals
- · Derived record components

ASIS-for-GNAT does not support implicit Elements representing implicit declarations of predefined type operations (such as '=', or the '+' operation for numeric types).

## 4.2.3 Processing Several Contexts at a Time

According to the ASIS Standard, the number of ASIS Contexts that can be associated and opened at a time, as well as the number of ASIS Compilation\_Units that can be processed at a time, are implementation specific. ASIS-for-GNAT does not impose any restriction on the number of Contexts opened at the same time, or on the number of Compilation\_Units that can be obtained from all the opened Contexts, as long as the application does not go beyond general system resource limitations.

However, for a Context associated with an -FS or -FM option, all the trees created 'on the fly' while obtaining Compilation\_Units from this Context are placed in the current directory. If the current directory also contains

some tree files belonging to another <code>Context</code>, the latter may become corrupted. To process more than one <code>Context</code> safely, an application should have at most one <code>Context</code> associated with the <code>-FS</code> or <code>-FM</code> option. Moreover, if among <code>Contexts</code> processed at the same time there is one that can create trees 'on the fly', then the other <code>Contexts</code> should not use tree files located in the current directory.

## 4.2.4 Implementation-Defined Types and Values

All the implementation-defined types, subtypes and values depend on the subtype Implementation\_Defined\_Integer\_Type and on the Implementation\_Defined\_Integer\_Constant defined in package Asis. ASIS-for-GNAT's declarations for these entities are the same as in the ASIS Standard:

```
subtype Implementation_Defined_Integer_Type is Integer;
Implementation_Defined_Integer_Constant : constant := 2**31-1;
```

All the ASIS (sub)types used as list indexes for ASIS array types have Implementation\_Defined\_Integer\_Constant as an upper bound.

## 4.3 ASIS Queries Having Specific Implementation Permissions or Implementation-Specific Results

This section documents queries having implementation permissions (given under -- | IP sentinel in the ASIS definition) and queries whose behavior is otherwise implementation specific. Such queries are presented below in their order of appearance in the ASIS Standard. The clause and subclause numbers shown are those from the ASIS Standard.

The results returned by the ASIS Debug\_Image queries are discussed in *Interpreting Debug Images*.

ASIS 8 package Asis.Ada\_Environments

ASIS 8.1 function Default\_Name

• Null string is returned.

ASIS 8.2 function Default\_Parameters

• Null string is returned;.

ASIS 8.4 procedure Open

- For a Context associated with the -CA option:
  - If -FS is also set, nothing is done.
  - If the -FT or -FM is set, all the tree files (that is, files having .adt suffix) in the tree search path associated with the Context are processed. ASIS reads in each tree file and checks that it was created with the -gnatc option. Tree files that cannot be read in or that were not created with the -gnatc option are ignored. For each other tree ASIS collects some 'black-box' information about the Compilation\_Units that it represents, and performs a consistency check for every unit it encounters in the tree (see ASIS-for-GNAT User's Guide for a discussion of the consistency problem). If any consistency check fails, ASIS\_Failed is raised and the Context remains closed.
- For a Context associated with a -C1 or -CN option, ASIS processes all the tree files associated with the Context, collecting 'black-box' information and performing consistency checks for all the encountered Compilation Units. If for any reason a tree file cannot be successfully read in for a Context associated with a -C1 option, ASIS\_Failed is raised and the Context remains closed. If a tree read fails for a Context

associated with a -CN option, an ASIS warning is generated and the Context opening process continues. If any consistency check fails, ASIS Failed is raised and the Context remains closed.

ASIS 9 package Asis.Ada\_Environments.Containers

• ASIS-for-GNAT supports the trivial Container model. Every Context contains exactly one Container, whose content and name are the same as its enclosing Context

ASIS 10 package Asis. Compilation\_Units

ASIS 10.3 function Unit Origin

- A\_Predefined\_Unit origin is returned for those compilation units listed in RM95, Annex A(2), and only
  for these units.
- An\_Implementation\_Unit origin is returned for compilation units that are the components of the GNAT Run-Time Library, but that are not listed in RM95, Annex A(2).
- An\_Application\_Unit origin is returned for all other compilation units.

ASIS 10.6 function Library\_Unit\_Declaration and ASIS 10.7 function Compilation\_Unit\_Body

• When processing a Context associated with an -FS or -FM option, if ASIS cannot find a needed unit in the tree files that have been already processed, it tries to create the needed tree by locating the source of the unit and compiling it 'on the fly'. If this attempt fails for any reason, Nil\_Compilation\_Unit is returned.

ASIS 10.13 function Corresponding\_Declaration

- ASIS-for-GNAT does not make use of ASIS Compilation\_Units of An\_Unknown\_Unit kind.
- $\bullet \ \ If \ an \ argument \ is \ of \ A\_Public\_Declaration\_And\_Body \ class, \ Nil\_Compilation\_Unit \ is \ returned.$

ASIS 10.14 function Corresponding\_Body

• ASIS-for-GNAT does not make use of ASIS Compilation\_Units of An\_Unknown\_Unit kind.

ASIS 10.22 function Can Be Main Program

- For GNAT, any parameterless library procedure and any parameterless library function returning a result of an integer type is classified by this query as a (possible) main subprogram for a partition.
- If for such a library subprogram both spec and body exist as ASIS Compilation\_Units retrievable from a given ASIS Context, both are considered as Can\_Be\_Main\_Program.

ASIS 10.24 function Text\_Name

- This function returns the name of the source file containing the source of Compilation\_Unit. This name may or may not contain a prefix denoting the directory in the underlying file system. If present, the directory may be given in absolute or relative form, depending on the command line options that were used for the call to GNAT that created the corresponding tree file.
- This function does not check the existence of the corresponding source file in the underlying file system, it just reflects the situation which was in effect when the corresponding tree file was created. Thus, if you delete or move the corresponding source file after creating the tree, the full file name returned by this function will be incorrect.
- Use the query Asis.Extensions.Source\_File\_Status to get the information about the current status of the source file for a Compilation\_Unit.

ASIS 10.25 function Text\_Form

• In the GNAT compilation model all source files are ordinary text files in the underlying file system. Therefore this function always returns a <code>Nil\_Asis\_String</code> to indicate that <code>Text\_IO.Open</code> uses the default options for manipulating Ada sources.

ASIS 10.26 function Object\_Name

 Returns a null string. In the GNAT environment, creating an object file has no connection with creating trees for ASIS.

ASIS 10.27 function Object\_Form

· Returns a null string.

ASIS 10.29 function Has Attribute

• Returns False. ASIS-for-GNAT does not provide any additional attributes for Compilation Units.

ASIS 10.30 function Attribute\_Value\_Delimiter

• Returns a wide string of length one containing the LF wide character.

ASIS 10.31 function Attribute\_Values

• A null string is returned.

ASIS 11 package Asis. Compilation\_Units. Times

ASIS 11.2 function Time\_Of\_Last\_Update

• This function returns the time stamp (the time of the latest change) of the corresponding source file. The corresponding source file is the source file whose name is returned by Asis.Compilation\_Units.Text\_Name.

ASIS 11.3 function Compilation\_CPU\_Duration

 This function always returns zero duration, because the CPU compilation duration concept does not apply to ASIS-for-GNAT

ASIS 11.4 function Attribute Time

• This function always returns Nil\_ASIS\_Time because ASIS-for-GNAT does not provide any Compilation\_Unit attributes

ASIS 13 package Asis. Elements

ASIS 13.3 function Context\_Clause\_Elements

- This function returns exactly those clauses and pragmas that are in the source for the unit.
- Returns Nil\_Element\_List if the argument unit is of A\_Nonexistent\_Declaration, A\_Nonexistent\_Body or An\_Unknown\_Unit kind
- Returns Nil\_Element\_List for the predefined package Standard. For all other predefined Ada compilation units, returns their context clauses as they appear in the sources held in the GNAT Run-Time Library.

ASIS 13.4 function Configuration\_Pragmas

• This function always returns Nil\_Element\_List, because in the GNAT compilation environment "a list of pragmas that apply to all future compilation\_unit elements compiled into The\_Context" essentially depends on the GNAT options set when compiling a unit (in particular the -gnatA and -gnatec options), and this cannot be determined from the content of the given Context.

ASIS 13.5 function Compilation\_Pragmas

- If the argument unit has been compiled on its own to produce a corresponding tree file, then the result contains the configuration pragmas from the GNAT configuration file(s) involved in this compilation. Otherwise (that is, if the argument unit has been compiled only as an effect of compiling some other unit), the result contains only those pragmas that belong to the unit's source file.
- A pragma that appears in the unit's context clause is included in the result list only if it is a configuration pragma.
- Returns Nil Element List for the predefined package Standard.

ASIS 13.31 function Is Equal

• Two elements representing configuration pragmas belonging to A\_Configuration\_Compilation unit (or components thereof) are considered as being equal only if they are created by the same compilation (belong to the same tree).

ASIS 13.36 function Enclosing\_Element

• ASIS-for-GNAT does not require the Element\_Context parameter. The Enclosing\_Element function with two parameters just calls the Enclosing\_Element function with one parameter for its Element parameter.

ASIS 15 package Asis. Declarations

ASIS 15.24 function Body\_Block\_Statement

• If the body passed as the actual parameter has no declarative items of its own, Asis.Statements.Is\_Declare\_Block returns False.

ASIS 18 package Asis. Statements

ASIS 18.14 function Is Declare Block

• If the argument represents the dummy block statement created by Asis.Declarations.Body\_Block\_Statement function, the result will be True if and only if the corresponding body has declarative items.

ASIS 20 package Asis. Text

ASIS 20.1 type Line

• Lines in ASIS-for-GNAT do not contain any end-of-line characters (see RM95, 2.2(2)).

ASIS 20.22 function Delimiter\_Image

• Returns a wide string of length one, containing the LF wide character.

## 4.4 Processing of Predefined Input-Output Packages

The GNAT compiler transforms the structure of the predefined input-output packages ( $Ada.Text\_IO$ , Ada.Wide\_Text\_IO and Ada.Wide\_Text\_IO) to optimize compilations of their clients. The documentation of Ada.Text\_IO says:

```
-- Note: the generic subpackages of Text_IO (Integer_IO, Float_IO, Fixed_IO,
-- Modular_IO, Decimal_IO and Enumeration_IO) appear as private children in
-- GNAT. These children are with'ed automatically if they are referenced, so
-- this rearrangement is invisible to user programs, but has the advantage
-- that only the needed parts of Text_IO are processed and loaded.
```

The same happens for Ada.Wide\_Text\_IO and Ada.Wide\_Wide\_Text\_IO. In this situation ASIS follows not the Ada Standard, but the actual code contained in the GNAT Run-Time Library. That is, the Enclosing\_Compilation\_Unit for an ASIS Element representing Ada.Text\_IO.Integer\_IO will be not the Compilation\_Unit that contains the whole package Ada.Text\_IO, but the Compilation\_Unit representing its private child as it is described above.

The Asis.Extensions package contains a query named Is\_Sub\_Package\_Implemented\_As\_Child\_Unit that allows to detect such private children of predefined Ada text input-output packages.

## 4.5 Representation clauses and -gnatI GNAT option

GNAT -gnatI allows to ignore all the representation clauses in the code being compiled. This allows to compile the code if it contains representation clauses that are illegal in the given compilation environment. ASIS can process tree files created with -gnatI, and for the ASIS Context that is based on such trees, ASIS does not yield Elements that correspond to representation clauses.

Note that you will see these representation clauses in the text images of the enclosing Elements, but nevertheless you will not be able to get them as subcomponents of such Elements.

## 4.6 Dynamic Context Modes

If an ASIS Context is defined with an -FS or -FM option, then ASIS may compile sources 'on the fly' to obtain Compilation\_Units. Thus the content of the Context will not necessarily remain frozen when the Context is open — when ASIS gets a new Compilation\_Unit, it 'adds' it to the Context. The -FS and -FM options are referred to as dynamic Context modes.

The difference between the two modes is as follows:

- **-FS** ASIS does not take into account any existing tree file when opening a Context.
- **-FM** ASIS first processes the tree files in the tree search path. If a given Compilation\_Unit is present in the existing set of tree files, these tree files are used; otherwise ASIS tries to locate the source of the unit and to compile it to produce a tree file.

For both -FS and -FM Contexts, once a tree file is created it is added to the set of tree files making up the Context and then it is reused (without recreating it from sources again) for the queries dealing with Compilation\_Units represented by this tree.

An advantage of these dynamic Context modes is that you do not have to create the tree files explicitly; to users of an ASIS application based on such Context modes the application appears to operate directly from source files. But there is also a drawback, a consequence of the fact that the content of a Context may change while the Context is open: some ASIS queries dealing with Compilation\_Units or returning lists of Compilation\_Units raise the ASIS\_Failed exception (with Use\_Error status).

These queries are as follows:

```
Asis.Compilation_Units:
   Library_Unit_Declarations
   Compilation_Unit_Bodies
   Compilation_Units
   Corresponding_Children
```

Another limitation of the dynamic Context mode is that ASIS uses the standard GNAT naming scheme to compute the name of the source to be compiled from the name of the corresponding Ada compilation unit. That is, if the name of the source containing the code of some unit does not follow the GNAT naming scheme, then ASIS will not locate this source, and it will treat this unit as Nil\_Compilation\_Unit.

**FIVE** 

## **DEBUGGING INFORMATION**

There are two kinds of the debugging information available in ASIS-for-GNAT — debug images returned by the ASIS query Debug\_Image (for Contexts, Compilation\_Units and Elements); and debug output generated by ASIS queries when the corresponding implementation debug flag is set ON during ASIS initialization (see *Parameters of Asis.Implementation.Initialize*).

## 5.1 Interpreting Debug Images

It is straightforward to interpret the debug images generated for the main ASIS abstractions, because most of the information directly corresponds to ASIS concepts. The following details of debug images are implementation specific.

- Context
  - Context Id This is the internal Context Id used in the implementation data structures. This Id is
    assigned to a Context when it is associated for the first time, and it remains unchanged and unique
    until ASIS is finalized.
  - All tree files The number of tree files making up the given Context.
- Compilation\_Unit
  - Compilation\_Unit Id This is the internal Compilation\_Unit Id used in the implementation data structures. This Id remains unchanged and unique until the unit's enclosed Context is closed.
  - Is consistent True if the same version of the unit's source was used for all the tree files making up the enclosed unit's context, and False otherwise
- Element
  - Node, R\_Node, Node\_Field\_1 Tree nodes on which the internal representation of a given Element is based. They are meaningful only in the tree file indicated in the Enclosing\_Tree field of the debug image
  - Special Case Implementation-specific indication of the cases when the Element needs some special
    processing.
  - Obtained from the tree The Id and the name of the tree file from which the tree-specific fields of the internal representation of given Element were obtained
  - Rel\_Sloc Indicates the (relative) position of the source text of the Element, counting from the beginning of the source of its enclosing compilation unit. Applies to implicit Elements also.

## 5.2 ASIS Debug Flags

ASIS provides several internal debug flags, which are described in a\_debug.adb. When one or more of these flags is set, useful internal debugging information is directed to Standard\_Output. Although this information is not always user-oriented, you may find the following debug flags helpful when you are developing an ASIS application:

- -dc Outputs the content of the internal data structures for a Context, when the Context is closed and dissociated. By analyzing this information, you may map other debug information onto unit and tree Ids.
- -di Turns off including the location of an Element into the result generated by Debug\_Image. This may be useful if an ASIS program crashes because of some problem with ASIS structural queries (structural queries are used by Element's Debug\_Image query to compute the source location of the argument).
- -do When the Context is opened, lists the tree files being processed, and the ones selected to represent a given Context
- -dt Outputs a message whenever a tree file is read in. This information may be useful for analyzing and reducing the tree swapping profile of your application.

**APPENDIX** 

Δ

## **GNU FREE DOCUMENTATION LICENSE**

Version 1.3, 3 November 2008

Copyright 2000, 2001, 2002, 2007, 2008 Free Software Foundation, Inc http://fsf.org/

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### **Preamble**

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

## 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The **Document**, below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "**Modified Version**" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called **Opaque**.

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

The "publisher" means any person or entity that distributes copies of the Document to the public.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

## 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

## 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- 1. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- 2. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- 3. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- 4. Preserve all the copyright notices of the Document.
- 5. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- 6. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- 7. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- 8. Include an unaltered copy of this License.
- 9. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- 10. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- 11. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- 12. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- 13. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- 14. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- 15. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

#### 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

## 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

## 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

#### 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

#### 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, or distribute it is void, and will automatically terminate your rights under this License.

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, receipt of a copy of some or all of the same material does not give you any rights to use it.

### 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation. If the Document specifies that a proxy can decide which future versions of this License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Document.

## 11. RELICENSING

"Massive Multiauthor Collaboration Site" (or "MMC Site") means any World Wide Web server that publishes copyrightable works and also provides prominent facilities for anybody to edit those works. A public wiki that anybody can edit is an example of such a server. A "Massive Multiauthor Collaboration" (or "MMC") contained in the site means any set of copyrightable works thus published on the MMC site.

"CC-BY-SA" means the Creative Commons Attribution-Share Alike 3.0 license published by Creative Commons Corporation, a not-for-profit corporation with a principal place of business in San Francisco, California, as well as future copyleft versions of that license published by that same organization.

"Incorporate" means to publish or republish a Document, in whole or in part, as part of another Document.

An MMC is "eligible for relicensing" if it is licensed under this License, and if all works that were first published under this License somewhere other than this MMC, and subsequently incorporated in whole or in part into the MMC, (1) had no cover texts or invariant sections, and (2) were thus incorporated prior to November 1, 2008.

#### **ASIS-for-GNAT Reference Manual 2017**

The operator of an MMC Site may republish an MMC contained in the site under CC-BY-SA on the same site at any time before August 1, 2009, provided the MMC is eligible for relicensing.

#### ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright © YEAR YOUR NAME. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with ... Texts." line with this:

with the Invariant Sections being LIST THEIR TITLES, with the Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.

## **INDEX**

A	Compilation_CPU_Duration function (implementation	
A_Predefined_Unit, 19	permissions), 20	
An_Application_Unit, 19	Compilation_Pragmas function (implementation permis-	
An_Implementation_Unit, 19	sions), 20	
An_Unknown_Unit, 19	Compilation_Unit_Body function (implementation per-	
ASIS Extensions, 11	missions), 19	
Asis.Ada_Environments implementation permissions, 18	Configuration_Pragmas function (implementation	
Asis.Ada_Environments.Associate procedure, 13, 14	permissions), 20	
Asis.Ada_Environments.Containers implementation per-	Consistency checking, 15, 18	
missions, 19	Context_Clause_Elements function (implementation per-	
Asis.Compilation_Units implementation permissions, 19	missions), 20	
Asis.Compilation_Units.Times implementation	Corresponding_Body function (implementation permis-	
permissions, 20	sions), 19	
Asis.Declarations implementation permissions, 21	Corresponding_Declaration function (implementation	
Asis.Declarations package, 9	permissions), 19	
Asis.Elements implementation permissions, 20	D	
Asis.Expressions package, 9		
Asis.Extensions package, 11	Debug flag parameter (to Asis.Implementation.Initialize),	
Asis.Extensions.Flat_Kinds package, 11	14	
Asis.Extensions.Iterator package, 12	Debug flags, 24	
Asis.Implementation.Finalize procedure, 13, 14	Debug images, 23	
Asis.Implementation.Initialize procedure, 13, 14	Debug_Image query, 18, 23	
Asis.Implementation.Permissions package, 13	Debugging information, 23	
Asis.Implementation.Permissions queries, 16	Default_Name function (implementation permissions), 18	
Asis.Statements implementation permissions, 21	Default_Parameters function (implementation	
Asis.Text implementation permissions, 21	permissions), 18	
ASIS_Failed exception, 13–16, 18, 19, 22	Delimiter_Image function (implementation permissions),	
ASIS_Inappropriate_Element exception, 11	21	
Attribute_Time function (implementation permissions),	Diagnosis string, 14	
20	Dynamic Context modes, 16, 22	
Attribute_Value_Delimiter function (implementation per-	E	
missions), 20		
Attribute_Values function (implementation permissions),	<b>₹</b>	
20	permissions), 21	
В	F	
	Flat_Element_Kinds type, 11	
Body_Block_Statement function (implementation		
permissions), 21	Н	
C	Has_Attribute function (implementation permissions), 20	
Can_Be_Main_Program function (implementation per-	I	
missions), 19	Implementation limits, 17	
	•	

#### **ASIS-for-GNAT Reference Manual 2017**

```
Implementation permissions, 13, 16, 18
Implementation-specific features, 13
Implementation Defined Integer Constant named num-
Implementation_Defined_Integer_Type subtype, 18
Implicit Element\ s, 17
Is Declare Block
                       function
                                       (implementation
         permissions), 21
Is Dispatching Operation query, 9
Is_Equal function (implementation permissions), 21
Library Unit Declaration function (implementation per-
         missions), 19
Line type (implementation permissions), 21
Name parameter (to Asis.Ada_Environments.Associate),
         16
0
Object_Form function (implementation permissions), 20
Object_Name function (implementation permissions), 19
Open procedure (implementation permissions), 18
Parameter_Error error status, 13, 16
Parameters string format, 13
Processing of Predefined Input-Output Packages, 21
R
Representation clauses and -gnatI GNAT option, 22
Search path, 15
Т
Text_Form function (implementation permissions), 19
Text_Name function (implementation permissions), 19
Time_Of_Last_Update function (implementation permis-
         sions), 20
Tree file, 14, 22
Tree swapping profile, 24
U
Unit_Origin function (implementation permissions), 19
Use_Error error status, 22
V
Value Error error status, 11
W
Warning messages, 14, 19
```