AVIATION WEATHER PRODUCTS Area Forecasts


Bureau of Meteorology > Weather Services > Aviatior



The Area Forecast system is designed primarily to meet the needs of general aviation pilots.

Area Forecasts

The Area Forecast system is designed primarily to meet the needs of general aviation pilots. The system provides for the routine issue of forecasts for designated areas and the prompt issue of amendments when prescribed criteria are satisfied. Forecasts are issued for the numbered areas shown in the map below.



More detail of the area forecast zones is contained in the *Airservices Australia* publication Planning Chart Australia (PCA).

There may be variations in commencement of validity between different regions and between those times when daylight saving is or is not operating. However the following principles apply:

- the standard validity period is twelve hours but this may vary from state to state.
- an Area Forecast covering daylight hours will be available as soon as practicable in the morning.
- Area Forecasts are not prepared for those times when air traffic volume is so low as not to justify routine issues. In these cases a flight forecast will service any individual flights.
- Area Forecasts will generally be available a minimum of one hour before commencement of validity.



Message Identifier Validity Period Area Number Overview Subdivisions Winds & Temperatures Cloud Weather Visibility Freezing Level Icing Turbulence Critical Locations Remarks

Cloud amount is given using the following abbreviations:

Code	Cloud Amount
FEW	Few (1 to 2 oktas)
SCT	Scattered (3 to 4 oktas)
BKN	Broken (5 to 7 oktas)
OVC	Overcast (8 oktas)

...except for cumulonimbus and towering cumulus, for which amount is described as:

Code	Cloud Amount
ISOL	Isolated
OCNL	Occasional (well separated)
FRQ	Frequent (little or no separation)
EMBD	Embedded (in layers of other cloud)

Cloud type is given using the following abbreviations:

Code	Cloud Type
CU	Cumulus
SC	Stratocumulus
СВ	Cumulonimbus
TCU	Towering cumulus
ST	Stratus
AS	Altostratus
AC	Altocumulus
NS	Nimbostratus

Message Structure

Message Identifier

The forecast is identified as AREA FORECAST unless the forecast is an amendment in which case it will be identified AMEND AREA FORECAST. In amended forecasts, any amended section will be annotated with AMD preceding the section heading.

Validity Period

The validity period is written DDHHMMTO DDHHMM, where DD is the day of the month and HHMM is the time in hours and minutes UTC.

Area Number

The relevant forecast zone is specified by an area forecast number. The zones are given in detail on Airservices *Australia's Planning Chart Australia (PCA)*. Note that Areas 24, 87 and 88 are only designated for the purpose of Area QNH. Any flights in these areas can be provided with a route forecast.

Overview

The overview will highlight any conditions which may inhibit safe operations for pilots flying under visual flight rules, and will make reference, where necessary, to any spatial and temporal variations. It will assist the pilot in making the following types of decisions:

- Are the meteorological conditions Visual Meteorological Conditions (VMC), marginal, Instrument Flight Rules (IFR) or too poor for flying?
- Is it better to plan for a coastal or inland track?
- If bad weather is encountered, what is the contingency plan? Return? Change altitude? Change heading? Land immediately?

Subdivisions

Area forecasts may be divided into spatial, temporal or weather-related subdivisions. Spatial subdivisions are given using PCA locations or lat/lon coordinates.

Winds and Temperatures

Upper level winds are given for 2000 (or 3000 in elevated regions), 5000, 7000, 10 000, 14 000 and 18 500 feet. The expected mean wind direction is given in three figures to the nearest ten degrees True, followed by a solidus (/), followed by the mean wind speed in two figures to the nearest five knots, e.g. 290/40. CALM and VRB (variable) are used when appropriate. A REMARKS section may be included below the WIND section to provide further information.

Upper level temperatures are given for 10 000, 14 000 and 18 500 feet. These are given in whole degrees Celsius, following the forecast of the upper wind for the level concerned, e.g. 290/40 PS08, 300/50 ZERO, 360/10 MS10. The abbreviation PS is used for positive temperatures, and MS (minus) is used for negative temperatures.

Cloud

The inclusion of cloud is restricted to:

- any cumulonimbus (CB) or towering cumulus (TCU)
- any cloud with a base at or below 5000 feet above the highest terrain in the area covered by the forecast
- any broken or overcast cloud with base at or below 20 000 feet above mean sea level (MSL)
- any cloud associated with any forecast precipitation, moderate or severe icing or moderate or severe turbulence.

Cloud amount and type are given using the abbreviations in the tables on the left.

If no, or no significant, cloud is expected throughout the area or subdivision, the format used is NIL or NIL SIGNIFICANT.

When CU and SC, or AC and AS, occur together at similar heights, they are combined, i.e. CU/SC or AC/AS.

Cloud base and tops are given in feet above MSL.

Abbreviations and Codes Used in Area Forecasts

Area Forecasts		
Code	Description	
AC	Altocumulus	
AC/AS	Altocumulus and	
	Altostratus with bases	
	at the same level	
AS	Altostratus	
AMD	Amendment	
BKN	Broken	
CAVOK	Cloud and visibility	
	and weather ok	
СВ	Cumulonimbus	
CU	Cumulus	
CU/SC	Cumulus and	
	Stratocumulus with	
	bases at the same level	
DZ	Drizzle	
EMBD	Embedded	
FEW	Few	
FG	Fog	
FM	From (only used in	
	Critical Locations	
	section)	
FRQ	Frequent	
GR	Hail	
GS	Small Hail	
INTER	Intermittent variations	
	(only used in Critical	
	Locations section)	
ISOL	Isolated	
MOD	Moderate	
NS	Nimbostratus	
OCNL	Occasional	
OVC	Overcast	
RA	Rain	
SC	Stratocumulus	
SCT	Scattered	
SEV	Severe	
SH	Shower	
SN	Snow	
ST	Stratus	
TCU	Towering Cumulus	
TEMPO	Temporary variations	
	(only used in Critical	
	Locations section)	
TS	Thunderstorm	
Z	Code for UTC	
	(universal time)	

Weather

Forecast weather is given using the abbreviations and codes in the tables on the left. If no, or no significant, weather is expected throughout the area or subdivision, the format used is NIL or NIL SIGNIFICANT.

Visibility

Horizontal visibility is given in metres to the nearest 100 metres up to and including 5000 metres, and in whole kilometers above that value. Forecast visibilities of 50 metres or less are given as ZERO. The forecast value is followed by the units used e.g. 8KM or 1000M. Significant variations of visibility are included.

If the visibility is forecast to be above 10 kilometres, the words UNRESTRICTED or GOOD are used.

Significant vertical variations of horizontal visibility will be given. Information is supplied on the depth of any layers affected by drizzle, haze and duststorms.

Freezing Level

Freezing level is the height in feet above MSL where the air temperature is zero degrees Celsius. Reference is made to any variations in height greater than 1000 feet, and to the occurrence of more than one freezing level.

lcing

This section provides information on the expected occurrence of moderate or severe icing in precipitation or cloud including convective cloud.

The height in feet above MSL of the bottom and top of the layer is given as, for example, MOD IN RA 5000/8000.

When the layer of icing is expected to extend above 20 000 feet, descriptions such as MOD ABOVE 14000 are used.

Turbulence

This section provides information on moderate or severe turbulence including turbulence associated with convective cloud.

The height above MSL of the bottom and top of any layer(s) is given as, for example, MOD IN CLOUD 12000/16000

When the turbulence is expected to extend to ground level, descriptions such as BELOW 8000 are used.

When the turbulence is expected to be confined to clouds, descriptions such as MOD IN CLOUD BELOW 8000 are used.

When the turbulence is expected to extend above 20 000 feet, descriptions such as SEV ABOVE 15000 are used.

Critical Locations

These are locations such as gaps in mountain ranges which are frequently used by general aviation aircraft.

Critical location forecasts are appended to Area Forecasts for Bowral and Mt Victoria (NSW) on AREA 21, Mt Victoria and Murrurundi (NSW) on AREA 20, and Kilmore Gap (Vic) on AREA 30.

Critical location forecasts are written in a mixture of plain language and TAF format making reference as necessary to cloud, visibility and weather.

CAVOK is used to indicate visibility greater than 10 KM, cloud ceiling above 5000 FT above ground level and nil significant weather.

Remarks

This section will include any relevant information not included elsewhere in the forecast.

Example

```
AMEND AREA FORECAST 071700 TO 080500 AREA 21
OVERVIEW:
LOW CLOUD, DRIZZLE AND SCATTERED FOG W OF MVI/YSCB/YCOM TILL 01Z.
ISOLATED FOGS REMAINDER TIL 01Z
SUBDIVISIONS:
A: W OF MVI/YSCB/YCOM
B: REMAINDER
WIND:
2000
         5000
                 7000
                          10000
                                       14000
                                                     18500
280/15 290/15 280/10 300/15 MS03 300/20 MS09 300/25 MS20
AMD CLOUD:
A: BKN ST 2000/5000 TILL 03Z. BKN CU 3000/7000 ISOL TOPS TO 13000
B: SCT CU/SC 2500/5000 COAST, INCREASING TO 5000/7000 AFTER 02Z.
AMD WEATHER
A: DZ, FG TILL 03Z
B: FG TILL 01Z
VISIBILITY:
500M IN FOG, 3000M IN DZ
FREEZING LEVEL:
5000FT
TCING:
MOD IN LARGE CU 5000/13000 FT
TURBULENCE:
MOD IN LARGE CU
CRITICAL LOCATIONS (HEIGHT ABOVE MSL)
MT VICTORIA: BKN ST 3700 (CLOUD ON GROUND)
BOWRAL: 9999 SCT SC 5000
REMARKS:
FOR CLARIFICATION OF METEOROLOGICAL ISSUES CALL 02 9296 1527.
```



Airservices Australia is the official distributor of aviation forecasts, warnings and observations issued by the Bureau of Meteorology. Airservices' flight briefing services are available at www.airservicesaustralia.com. Telephone contact details for elaborative briefings are contained in Airservices' Aeronautical Information Publication Australia (AIP), which is available online through their website.

Other brochures produced by the Bureau of Meteorology's aviation weather services program can be found at www.bom.gov.au/aviation/knowledge-centre.