CS307 Operating Systems

Virtual Memory

Fan Wu

Department of Computer Science and Engineering Shanghai Jiao Tong University Spring 2020




Background

- Code needs to be in memory to execute, but entire program rarely used
 - Error code, unusual routines, large data structures
- Entire program code not needed at the same time
- Consider ability to execute partially-loaded program
 - Program no longer constrained by limits of physical memory
 - Program could be larger than physical memory



Virtual Memory That is Larger Than Physical Memory





Virtual Memory

- Virtual Memory separation of user logical memory from physical memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows memory address spaces to be shared by several processes
 - Allows for more efficient process creation
 - More programs running concurrently
 - Less I/O needed to load or swap processes
- Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation




Demand Paging

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
 - Less I/O needed, no unnecessary I/O
 - Less memory needed
 - Faster response
 - More users
- Page is needed ⇒ reference to it
 - invalid reference ⇒ abort
 - not-in-memory ⇒ bring to memory
- Lazy swapper (pager) never swaps a page into memory unless page will be needed



Swap Paged Memory to Disk Space




Valid-Invalid Bit

- With each page table entry a valid—invalid bit is associated (v ⇒ in-memory – memory resident, i ⇒ not-in-memory)
- Initially, valid—invalid bit is set to i on all entries
- Example of a page table snapshot:

Frame #	valid	-invalid bit
	V	
	V	
	V	
	V	
	i	
	i	
	i	
page table		•

■ During address translation, if valid–invalid bit in page table entry is i ⇒ page fault

Page Table with Pages Not in Main Memory





Page Fault


■ If there is a reference to a page and the page is not in memory, the reference will trap to operating system:

page fault

- 1. Operating system looks at page table to decide:
 - Invalid reference ⇒ abort
 - Just not in memory
- 2. Get empty frame
- 3. Swap page into frame via scheduled disk operation
- Reset tables to indicate page now in memory Set validation bit = v
- 5. Restart the instruction that caused the page fault



Steps in Handling a Page Fault







What Happens if There is no Free Frame?

- Page replacement find some page in memory, but not really in use, page it out
 - Algorithm terminate? swap out? replace the page?
 - Performance want an algorithm which will result in minimum number of page faults



Page Replacement





memory



Page Replacement

- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory



Page Replacement Algorithms

- Page-replacement algorithm
 - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
 - String is just page numbers, not full addresses
 - Repeated access to the same page, which is still in memory, does not cause a page fault
- In all our examples, the reference string is

7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1

Page-Replacement Algorithms


- First-In-First-Out (FIFO) Page Replacement
- Optimal Page Replacement
- Least Recently Used (LRU) Page Replacement
- LRU Approximation Page Replacement
- Counting Page Replacement



FIFO Page Replacement

■ When a page must be replaced, the oldest page is chosen.

reference string



page frames


- Page faults: 15
- Consider the following reference string:

0 1 2 3 0 1 2 3 0 1 2 3

Optimal Page Replacement

Replace page that will not be used for longest period of time

reference string




- Page faults: 9
- How do you know this?
 - Can't read the future
- Used for measuring how well your algorithm performs

Least Recently Used (LRU) Page Replacement

- Use past knowledge rather than future
- Replace page that has not been used in most amount of time
- Associate time of last use with each page



page frames



- 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used

LRU Approximation Algorithms

■ Reference bit/ byte


- With each page associate a bit, initially = 0
- When page is referenced, bit set to 1
- Replace any with reference bit = 0 (if one exists)
 - We do not specify the order, however

Second-chance algorithm

- Generally FIFO, plus hardware-provided reference bit
- Circular replacement
- If page to be replaced has
 - Reference bit = 0 -> replace it
 - Reference bit = 1 then:
 - set reference bit 0, leave page in memory
 - replace next page, subject to same rules



Second-Chance Algorithm



Counting Algorithms

- Keep a counter of the number of references that have been made to each page
- Least Frequently Used (LFU) Algorithm: replaces page with smallest count
- Most Frequently Used (MFU) Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used
- Not commonly used

Homework

- Reading
 - Chapter 9
- Exercise
 - See course website



Pop Quiz

■ A memory system has three frames. Consider the following reference string

0 1 2 3 2 3 0 4 5 2 3 1 4 3 2 6 3 2 1 2

Draw a diagram to show the page replacement using **Second-Chance Algorithm** and calculate the number of page faults.

Demand Paging

System Characteristics									
Size of memory	16 bytes								
Frame Size	4 bytes per frame								
Memory Management Structure	Inverted Page Table								
Replacement Policy	LRU, Global Replacement								
Virtual Page Size	4 bytes per page								
Logical Addressing Space Size	32 bytes								
Backing Store Size	12 blocks								
Backing Store Block Size	4 bytes per block								



Process Table

Process ID	0	1	2
Process Size (Bytes)	12	14	13
Pages allocated	3	4	4
Backing Store Map			
(Page → Block)			
Page 0	BS 0	BS 3	BS 7
Page 1	BS 1	BS 4	BS 8
Page 2	BS 2	BS 5	BS 9
Page 3		BS 6	BS 10

System Snapshot

Main Memory

Address	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15
Contents	О	T	О	N	G	F	U	N	_	_	-	-	A	D	*	F

Backing Store

Block	0	1	2	3	4	5	6	7	8	9	10
Contents	THRE	AD*F	UN	RATE	*MON	OTON	IC	DEMA	ND*P	AGIN	G

Inverted Page Table

Frame	Page #	PID	Valid Bit	Ref Word (Low = older)	Modified Bit
0	2	1	T	2	F
1	3	2	T	1	T
2	-	-	F	-	-
3	1	0	T	3	F



PID 0: Write 'A' at logical memory Address 11

Main Memory

Address	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15
Contents	О	T	О	N	G	F	U	N	-	-	-	-	A	D	*	F
Change									U	N	-	A				

Process ID	0
Process Size (Bytes)	12
Pages allocated	3
Backing Store Map	
$(Page \rightarrow Block)$	
Page 0	BS 0
Page 1	BS 1
Page 2	BS 2
Page 3	

Backing Store

Block	0	1	2	3	4	5	6	7	8	9	10
Contents	THRE	AD*F	UN	RATE	*MON	OTON	IC	DEMA	ND*P	AGIN	G
Change											

Inverted Page Table

Frai	me	VP#	ŧ	PID	_	Valid	Bit	Ref Word (Lov	v = older)	Modified Bit		
0		2		1		T		2		F		
1		3		2		T		1		Τ		
2		-	2	-	0	F	T	-	4	-	T	
3		1		0		T		3		F		



PID 1: Read logical memory Address 6

Main Memory

Address	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15
Contents	О	T	О	N	G	F	U	N	-	-	-	-	A	D	*	F
Change					*	M	О	N	U	N	-	A				

Process ID	1
Process Size (Bytes)	14
Pages allocated	4
Backing Store Map	
$(Page \rightarrow Block)$	
Page 0	BS 3
Page 1	BS 4
Page 2	BS 5
Page 3	BS 6

Backing Store

Block	0	1	2	3	4	5	6	7	8	9	10
Contents	THRE	AD*F	UN	RATE	*MON	OTON	IC	DEMA	ND*P	AGIN	G
Change											GFUN

Inverted Page Table

Frai	rame VP#		PID		Valid Bit		Ref Word (Low = older)		Modified Bit		
0		2		1		T		2		F	
1		3	1	2	1	T		1	5	Τ	F
2		-	2	-	0	F	Т	-	4	-	T
3		1		0		T		3		F	

