#### roscpp overview (/roscpp/Overview): Initialization and Shutdown

(/roscpp/Overview/Initialization%20and%20Shutdown) | Basics (/roscpp/Overview/Messages) |
Advanced: Traits [ROS C Turtle] (/roscpp/Overview/MessagesTraits) | Advanced: Custom Allocators
[ROS C Turtle] (/roscpp/Overview/MessagesCustomAllocators) | Advanced: Serialization and Adapting
Types [ROS C Turtle] (/roscpp/Overview/MessagesSerializationAndAdaptingTypes) | Publishers and
Subscribers (/roscpp/Overview/Publishers%20and%20Subscribers) | Services
(/roscpp/Overview/Services) | Parameter Server (/roscpp/Overview/Parameter%20Server) | Timers
(Periodic Callbacks) (/roscpp/Overview/Timers) | NodeHandles (/roscpp/Overview/NodeHandles) |
Callbacks and Spinning (/roscpp/Overview/Callbacks%20and%20Spinning) | Logging
(/roscpp/Overview/Logging) | Names and Node Information
(/roscpp/Overview/Names%20and%20Node%20Information) | Time | Exceptions
(/roscpp/Overview/Exceptions) | Compilation Options (/roscpp/Overview/Compilation%20Options) |
Advanced: Internals (/roscpp/Overview/Internals) | tf/Overview (/tf/Overview) | tf/Tutorials (/tf/Tutorials) |
C++ Style Guide (/CppStyleGuide)

#### Contents

- 1. Time and Duration
  - 1. Getting the Current Time
    - 1. Time zero
  - 2. Creating Time and Duration Instances
  - 3. Converting Time and Duration Instances
  - 4. Time and Duration Arithmetic
- 2. Sleeping and Rates
- 3. Wall Time

## 1. Time and Duration

See also: oros::TimeBase API docs

(http://docs.ros.org/latest/api/rostime/html/classros\_1\_1TimeBase.html), ●ros::DurationBase API docs (http://docs.ros.org/latest/api/rostime/html/classros 1 1DurationBase.html)

ROS has builtin time and duration primitive types, which roslib (/roslib) provides as the ros::Time and ros::Duration classes, respectively. A Time is a specific moment (e.g. "today at 5pm") whereas a Duration is a period of time (e.g. "5 hours"). Durations can be negative.

Times and durations have identical representations:

int32 sec int32 nsec

ROS has the ability to setup a simulated Clock (/Clock) for nodes. Instead of using platform time routines, you should use roscpp's time routines for accessing the current time, which will work seamlessly with simulated Clock (/Clock) time as well as wall-clock time.

### 1.1 Getting the Current Time

ros::Time::now()

Get the current time as a ros:: Time instance:

```
Toggle line numbers

1 ros::Time begin = ros::Time::now();
```

#### 1.1.1 Time zero

When using simulated Clock (/Clock) time, now() returns time  $\theta$  until first message has been received on /clock, so  $\theta$  means essentially that the client does not know clock time yet. A value of  $\theta$  should therefore be treated differently, such as looping over now() until non-zero is returned.

### 1.2 Creating Time and Duration Instances

You can create a Time or Duration to a specific value as well, either floating-point seconds:

```
Toggle line numbers

1 ros::Time a_little_after_the_beginning(0.001);
2 ros::Duration five_seconds(5.0);
```

or through the two-integer constructor:

```
Toggle line numbers

1 ros::Time a_little_after_the_beginning(0, 1000000);
2 ros::Duration five_seconds(5, 0);
```

### 1.3 Converting Time and Duration Instances

Time and Duration objects can also be turned into floating point seconds:

```
Toggle line numbers

1 double secs =ros::Time::now().toSec();
2
3 ros::Duration d(0.5);
4 secs = d.toSec();
```

### 1.4 Time and Duration Arithmetic

Like other primitive types, you can perform arithmetic operations on Times and Durations. People are often initially confused on what arithmetic with these instances is like, so it's good to run through some examples:

```
1 hour + 1 hour = 2 hours (duration + duration = duration)
2 hours - 1 hour = 1 hour (duration - duration = duration)
Today + 1 day = tomorrow (time + duration = time)
Today - tomorrow = -1 day (time - time = duration)
Today + tomorrow = error (time + time is undefined)
```

Arithmetic with Time and Duration instances is similar to the above examples:

```
Toggle line numbers

1 ros::Duration two_hours = ros::Duration(60*60) + ros::Duration(60*60);
2 ros::Duration one_hour = ros::Duration(2*60*60) - ros::Duration(60*60);
3 ros::Time tomorrow = ros::Time::now() + ros::Duration(24*60*60);
4 ros::Duration negative_one_day = ros::Time::now() - tomorrow;
```

# 2. Sleeping and Rates

```
bool ros::Duration::sleep()
```

Sleep for the amount of time specified by the duration:

```
Toggle line numbers

1 ros::Duration(0.5).sleep(); // sleep for half a second
2
```

#### ros::Rate

roslib provides a ros::Rate convenience class which makes a best effort at maintaining a particular rate for a loop. For example:

```
ros::Rate r(10); // 10 hz
while (ros::ok())
{
    ... do some work ...
    r.sleep();
}
```

In the above example, the Rate instance will attempt to keep the loop at 10hz by accounting for the time used by the work done during the loop.

**Note:** It is generally recommended to use Timers instead of Rate. See the Timers Tutorial (/roscpp\_tutorials/Tutorials/Timers) for details.

## 3. Wall Time

For cases where you want access to the actual wall-clock time even if running inside simulation, roslib provides Wall versions of all its time constructs, i.e. ros::WallTime, ros::WallDuration, and ros::WallRate which have identical interfaces to ros::Time, ros::Duration, and ros::Rate respectively.

Except where otherwise noted, the

ROS wiki is licensed under the

Wiki: roscpp/Overview/T ime (last edited 2017-07-10 22:17:20 by BryceWilley (/BryceWilley))

Creative Commons Attribution 3.0

(http://creativecommons.org/licenses/by/3.0/) | Find us on Google+

(https://plus.google.com/113789706402978299308)

Brought to you by: Open Source Robotics Foundation

(http://www.osrfoundation.org)