Table of Contents

Snyk Code Local Engine

Installation

Prerequisites

- Deployment Requirements
 - Shared Cluster Deployments
- Network Requirements
 - Outbound Proxy

Basic Deployments

- · Pulling the Snyk Code Local Engine Helm Chart
- · Configuring the Snyk Code Local Engine Helm Chart
 - Pulling Snyk Code Local Engine Docker Images
 - Enabling Required Services
 - Enabling CLI, IDEs or PR Checks
 - · Setting the Snyk Tenant
 - EU Tenant
 - AU Tenant
- Installing Snyk Code Local Engine with Helm
- · Upgrading Snyk Code Local Engine with Helm
- Removing Snyk Code Local Engine
- Private Registry
- What Next?

Configuring Connections

Configuring Snyk Broker

- Single SCM Mode
- Universal Mode
 - Universal Broker Connection Types
 - GitHub Enterprise
 - GitHub Server App
 - GitHub
 - BitBucket Server
 - BitBucket Server Bearer Auth
 - GitLab
 - Azure Repos

- · Multiple Instances of an SCM type
- Multiple Azure Repos Organisations
- High Availability Mode

Configuring GitHub Server App

- Create a Custom GitHub App
- Create Brokered Integrations
- Configure Snyk Code Local Engine

Advanced Deployments

- Shared Cluster
 - Using

Secret Management

- External Secrets
 - Creating Secrets
 - Session Secret
 - Redis Secrets
 - S3 Secret
 - JWT Secret
 - Consuming Secrets

Networking

Core Networking

- Re-using the Ingress definition
 - Pre-requisites
 - · Updating the inbuilt Ingress definition
- · Custom Ingress
 - Pre-requisites
 - · Disabling the built-in Ingress
- Enabling TLS
 - · Adding a Certificate
 - Self Signed Certificates
- Outbound Proxy Support
 - Further Proxy Configuration
- Private Certificate Authority Support for SCM
- Private Certificate Authority Support for both SCM and Proxy

Post Installation

Snyk Code Local Engine Health

· Healthy Response

- Unhealthy Response
- · Healthy Response
- · Healthy Response

Snyk Configuration

- Enabling Snyk Code Local Engine for Snyk CLI/IDE
 - · Configure the Snyk CLI
- Updating Snyk Code Local Engine Snyk Configuration
- · What Next?

Helm Parameters

- Parameters
 - Enable Snyk Code Services
 - Global Parameters
 - Deeproxy parameters (EU/AU Snyk Tenants only)
 - Broker Client parameters (any SCM flows only)

Changelog

- 2025-01-09
- Changed
- Removed
- Fixed
 - 2024-10-28
- Added
- Fixed
- Changed
 - 2024-08-19
- Added
- Changed
- Removed
- Fixed
 - 2024-06-21
- Added
- Fixed
- Changed
 - 2024-04-15
- Fixed
- Changed
 - 2024-03-14
- Fixed
- Changed
- Added

- 2024-02-08
- Added
- Fixed
- Changed
- Removed
 - 2024-01-26
- Added
- Fixed
- Changed
 - 2024-01-16
- Fixed
- Changed
 - 2024-01-11
- Changed
 - 2023-12-07
- Fixed
 - 2023-12-07
- Added
- Changed
 - 2023-11-27
- Fixed
 - 2023-11-23
- Changed
- Removed
- Fixed
 - 2023-11-10
- Changed
 - 2023-11-08
- Changed
- Fixed
 - 2023-10-17
- Changed
 - 2023-10-17
- Added
- Changed
- v2.6.1
 - 2023-09-20
 - Changed
- v2.6.0
 - 2023-09-18

- Added
- Changed
- Fixed
- Removed
- v2.5.0
 - 2023-09-04
 - Added
 - Changed
 - Fixed
- v2.4.2
 - 2023-08-17
 - Added
 - Changed
 - Deprecated
- v2.4.1
 - 2023-07-14
 - Added
- v2.4.0
 - 2023-07-13
 - Added
- v2.3.0
 - 2023-07-12
 - Added
- v2.2.3
 - 2023-06-15
 - Added
- v2.2.2
 - 2023-06-13
 - Fixed
- v2.2.1
 - 2023-06-09
 - Added
 - Fixed
- v2.2.0
 - 2023-05-12
 - Added
 - Removed
- v2.0.0
 - 2023-04-20
 - Added

- Removed
- Changed


Snyk Code Local Engine

Welcome to the Snyk Code Local Engine documentation.

This documentation will guide you through the process of:

- · Becoming familiar with Snyk Code Local Engine,
- · Installing Snyk Code Local Engine on your infrastructure, and
- Testing your installation of Snyk Code Local Engine

Snyk Code Local Engine is a fully contained version of the Snyk Code Engine, meaning users do not need to upload code to the internet.



When using Snyk Code Local Engine, no source code leaves the perimeter of your organization. All analysis is performed internally, with only analysis results being sent to Snyk for review through the Snyk Web UI.

To install Snyk Code Local Engine, start with Installation Prerequisites. Some activities will require Snyk to make changes on Snyk systems to activate your installation of Snyk Code Local Engine.

For any questions or additional support, please reach out to your Snyk Representative.

Installation

Prerequisites

Before proceeding to install Snyk Code Local Engine, ensure you have:

- · Image Pull Secrets (these are provided to you by Snyk), and
- Snyk Broker Settings (to connect to your private Source Code Management system)
- An installation of Helm 3.8.0 or higher (NOTE: we only support install and upgrade via helm).
- Access to your target Kubernetes Cluster to deploy the Snyk Code Local Engine Helm Chart

Deployment Requirements

Refer to Snyk Code Local Engine System Requirements for the most up-to-date requirements.

Shared Cluster Deployments

Snyk Code Local Engine can be installed on a shared Kubernetes Cluster. This does not change resource requirements, and comes with additional concerns. Review Advanced Deployment Models - Shared Cluster to understand the impact.

Network Requirements

Snyk Code Local Engine will communicate with Snyk to:

- Trigger Code Analyses
- Check Snyk Code Local Engine settings for Snyk CLI
- · Manage inbound webhooks from SCM

Depending on selected functionality. The domains Snyk Code Local Engine requires outbound connectivity (supporting WebSockets) to are *.snyk.io. All outbound connections are secured with HTTPS/TLS encryption.

Outbound Proxy

Connections to Snyk domains from Snyk Code Local Engine may be routed through a proxy. Review Outbound Proxy for further information.

Basic Deployments

Snyk Code Local Engine leverages Helm for installation. Follow these steps to obtain the Snyk Code Local Engine Helm Chart and perform basic configuration.

Pulling the Snyk Code Local Engine Helm Chart

Snyk Code Local Engine Helm Charts are hosted on Dockerhub, and can be obtained by:

```
1 $ helm registry login -u <username> registry-1.docker.io
2 Password:
3 Login suceeded
```

Where username and password are those provided by Snyk.

Once authenticated, pull the Snyk Code Local Engine Helm Chart:

```
1 helm pull oci://registry-1.docker.io/snyk/snyk-code-local-engine <--version x.y.z>
```

Optionally provide a version, otherwise Helm will fetch the latest version of the Chart.

Configuring the Snyk Code Local Engine Helm Chart

Configuration of Snyk Code Local Engine to suit your environment and requirements is carried out by modifying the values-customer-settings.yaml file provided with this documentation.

This YAML file will be used to keep settings between Snyk Code Local Engine upgrades, and may contain sensitive information.

Pulling Snyk Code Local Engine Docker Images

Snyk Code Local Engine uses a mixture of Snyk and third party Docker images. Add your imgePullSecret information to the values-customer-settings.yaml file:

```
1 global:
2 imagePullSecret:
3 credentials:
4 username: <username>
5 password: <password>
```

Helm will create a Kubernetes Secret with these credentials to allow your cluster to pull Snyk images from Dockerhub.

Enabling Required Services

Snyk Code Local Engine consists of multiple services which provide functionality for different integration methods and features.

To enable and deploy the services required for your desired usage set the tag values to true in values-customer-settings.yaml:

```
tags:

scm: false # set to true to deploy services required for SCM integration

scmPrCheck: false # set to true to deploy services required for SCM PR check functionality

cli: false # set to true to deploy services required for CLI integration

ide: false # set to true to deploy services required for supported IDE plugins
```

Enabling CLI, IDEs or PR Checks

Snyk Code Local Engine needs to be accessible from outside the cluster for CLI, IDEs or PR checks to work. By default, this functionality is disabled.

If using the inbuilt ingress template, set the following in values-customer-settings.yaml:

```
1 global:
2 ingress:
3 enabled: true
```

Depending on your Kubernetes Cluster you may wish to use a custom Ingress Controller and/or a custom Ingress template.

For PR Checks, ensure the following is set in values-customer-settings.yaml:

```
global:
localEngineUrl: "http(s)://your-scle-domain-or-ip-here(:1234)"
```

Where the value for global.localEngineUrl resolves to the Kubernetes ingress used for Snyk Code Local Engine.

JetBrains IDE limitation: To ensure Snyk Code scans are directed to SCLE please set up your SCLE organization ID in the JetBrains IDE settings and restart the IDE. Having to change organization only applies if Snyk Code without using the SCLE was used beforehand.

Setting the Snyk Tenant

By default, Snyk Code Local Engine will connect to the US Snyk Tenant.

If using an alternative tenant, replace any occurrence of snyk.io to the geographic alternative in this documentation.

To use an alternative tenant, configure the following in values-customer-settings.yaml:

EU Tenant

```
broker-client:
brokerServerUrl: "https://broker.eu.snyk.io"
brokerDispatcherUrl: "https://api.eu.snyk.io"
deeproxy:
verificationEndpoint: "https://api.eu.snyk.io/v1/validate/token/snyk-to-deepcode-proxy-validation"
```

AU Tenant

```
broker-client:
brokerServerUrl: "https://broker.au.snyk.io"
brokerDispatcherUrl: "https://api.au.snyk.io"
deeproxy:
verificationEndpoint: "https://api.au.snyk.io/v1/validate/token/snyk-to-deepcode-proxy-validation"
```

Note: See Data Residency At Snyk for other information (CLI, IDE, Web URL).

Installing Snyk Code Local Engine with Helm

The following should be used to install Snyk Code Local Engine for the first time on a Kubernetes cluster:

```
helm upgrade --wait <DEPLOYMENT_NAME> ./snyk-code-local-engine-<version>.tgz -i -f values-customer-settings.yaml -n <NAMESPACE>
```

Where:

- f values-customer-settings.yaml passes any values from this YAML file to the Helm Chart, and
- -n <NAMESPACE> is optional use this if installing Snyk Code Local Engine to a Shared Cluster. If not specified, the default namespace is used.

If a re-install is needed (i.e a resource that cannot be patched is changed), first remove the installation and then install again.

Upgrading Snyk Code Local Engine with Helm

As Snyk Code Local Engine is stateless, upgrades may be performed without considering any data loss. The same command may be used to perform an upgrade:

```
helm upgrade --wait <DEPLOYMENT_NAME> ./snyk-code-local-engine-<version>.tgz -i -f values-customer-settings.yaml -n <NAMESPACE>
```

Versions within the same minor or patch increment are safe to install without removal. Upgrades from a previous major version should be a clean installation (remove and install).

Version Change	Upgrade/Clean Install	Process
x.y.1 to x.y.2	Upgrade	Perform the helm upgrade command
x.1.z to x.2.z	Upgrade	Perform the helm upgrade command
1.y.z to 2.y.z	Clean Install	First remove the installation and perform the helm upgrade command

Removing Snyk Code Local Engine

Snyk Code Local Engine may be removed with:

```
1 helm delete <DEPLOYMENT_NAME> -n <NAMESPACE>
```

This removes all components deployed by the Helm Chart. The --purge option may be used to delete all history if required.

Private Registry

Use the following steps in order to work with your private registry:

- 1. Configure customer-values-settings file, make sure you mark which analysis flows will be used by settings the tags
- 2. Get the list of images and tags to pull by executing the following command: helm template ./snyk-code-local-engine-<version>.tgz -f values-customer-settings.yaml | yq '.. | .image? | select(.)' | sort | uniq
- 3. Push the images to your registry in the following format:
 - · Any snyk images should reside within the snyk namespace
 - minio, redis images should reside within the bitnami namespace
 - envoy image should reside within the envoyproxy namespace

```
snyk/
1
2 ├── broker/
3
   code-pr-check-service/
   — deepcode-suggest_v6/
4
5
   ├─ deeproxy/
    files-bundle-store/
6
7
    ├─ sast-analysis-api/
8
     scm-bundle-store/
9
    service-health-aggregator/
10 envoyproxy/
11
   — envoy/
12
    bitnami/
13
    — minio/
   ├─ redis/
```

4. Make sure you set the global.imageRegistry value in values-customer-settings.yaml to your private registry include any namespace paths above those mentioned previously. For example: global.imageRegistry: my.private.registry.io/parent/path will pull snyk images from my.private.registry.io/parent/path/snyk and so on.

Note: If your private registry requires authentication, ensure to set credentials as describe in values-customer-settings.yaml.

After setting previous steps Helm will now use images from the specified registry.

What Next?

- Check the health of a running Snyk Code Local Engine installation
- Set up any networking for your installation
- Configure your installation with Snyk

Configuring Connections

Configuring Snyk Broker

A deployment of the Snyk Broker is created if using one or more SCM integrations and/or enabling PR Checks with Snyk Code Local Engine.

Snyk Broker is responsible for:

- Managing webhooks from one or more SCM(s) towards Snyk Code Local Engine
- Integrating with one or more private SCM(s) when importing a project via the Snyk UI

Each integration between your SCM and Snyk Code Local Engine (via the Broker) is identified by a Broker Token; a UUID generated by the Snyk Platform when the integration is created. Contact your Snyk representative to configure these for you.

Single SCM Mode

From versions 2.0.0 of Snyk Code Local Engine, specify .broker-client.brokerType and the associated authentication information required for the targeted SCM in values-customer-settings.yaml.

An example is shown below:

```
broker-client:
brokerType: github-enterprise
brokerToken: <br/>
githubToken: <github-enterprise-pat>
githubHost: <your.private.ghe.instance.tld>
```

The following SCMs are not supported in Single SCM Mode:

• github-server-app

Universal Mode

As of version 2.8.0 of Snyk Code Local Engine, the Broker may be configured in Universal mode to support:

- · Multiple SCM types, and/or
- · Multiple instances of a single SCM, and/or
- For Azure Repos, multiple Azure Repos Organizations, and/or
- The GitHub Server App integration

Each connection is specified within the universalBrokerConnections map, with any connection-specific configuration (authentication, broker token, host) included within the individual connection object.

An example is shown below, defining a github-enterprise connection:

```
1
         broker-client:
2
             brokerType: universal
             universalBrokerConnections:
3
4
                 myGithubEnterpriseConnection:
5
                     type: github-enterprise
                     auth: <github-enterprise-pat>
6
7
                     brokerToken: <broker-token>
8
                     githubHost: <your.private.ghe.instance.tld>
9
                 <another-connection>
10
                 <another-connection>
```

Where myGithubEnterpriseConnection may be any alphanumeric string that gives context to the connection.

Universal Broker Connection Types

Specify each connection as an object within the broker-client.universalBrokerConnections key according to the SCM type.

GitHub Enterprise

```
myGithubEnterpriseConnection:
type: github-enterprise
brokerToken: <br/>
githubHost: <your-ghe-host>
auth: <your-ghe-pat>
```

GitHub Server App

Note: GitHub Server App is in Closed Beta, and must be activated for use by Snyk

At least one githubServerApp must be defined within broker-client.githubServerApps . See Configuring Github Server App for further detail.

```
myGitHubServerApp:
type: github-server-app
brokerToken: <br/>
githubAppInstallationId: <your-gh-app-install-id>
githubServerAppName: <your-gh-server-app-name>
```

GitHub

```
myGithubConnection:
type: github
brokerToken: <broker-token>
auth: <your-gh-pat>
```

BitBucket Server

```
1 myBitbucket:
2   type: bitbucket-server
3   brokerToken: <br/>4   auth: <your-bb-password>
5   bitbucketUsername: <your-bb-user>
6   bitbucketHost: <your-bb-host>
```

BitBucket Server Bearer Auth

```
myBitbucketBearerAuth:
type: bitbucket-server-bearer-auth
brokerToken: <broker-token>
auth: <your-bb-pat>
bitbucketHost: <your-bb-host>
```

GitLab

```
myGitlab:
type: gitlab

brokerToken: <broker-token>
auth: <your-gl-token>
gitlabHost: <your-gl-host>
```

Azure Repos

```
myAzureRepos:
type: azure-repos
brokerToken: <broker-token>
azureReposOrg: <your-azure-org>
azureReposHost: <your-azure-host>
auth: <your-azure-repos-token>
```

Multiple Instances of an SCM type

Recommended for Multiple Snyk Organisations using Snyk Code Local Engine with SCM access tokens scoped to different repositories. This approach does not implement credential pooling or High Availability mode for Broker.

We suggest naming the connections by their associated Snyk Organisations or a similar SCM-related identifier:

```
broker-client:
 1
 2
       brokerType: universal
 3
       universalBrokerConnections:
 4
         myProductOrganisation:
 5
           type: github-enterprise
 6
           auth: <github-enterprise-pat>
 7
           brokerToken: <br/> <br/> toker-token>
 8
           githubHost: <your.private.ghe.instance.tld>
 9
         mySecurityOrganisation:
10
           type: github-enterprise
11
           auth: <another-github-enterprise-pat>
12
           brokerToken: <another-broker-token>
13
           gitHubHost: <your.private.ghe.instance.tld>
```

Multiple Azure Repos Organisations

Specify multiple azure-repos connections, each targeting a different Azure Repos Organisation. The Azure Repos PAT may be re-used across connections if permissions allow, or discrete tokens may be created per-org. We suggest naming the connections after the targeted Azure Repos Organisation or similar:

```
1
         broker-client:
 2
             brokerType: universal
 3
             universalBrokerConnections:
 4
                 azureReposOrgName:
 5
                     type: azure-repos
 6
                     auth: <azure-repos-pat>
 7
                     azureReposOrg: <org-name>
                     azureReposHost: <your.azure-repos.host.tld>
 8
 9
                     brokerToken: <broker-token>
10
                 anotherAzureReposOrgName:
11
                    type: azure-repos
12
                     auth: <azure-repos-pat>
13
                     azureReposOrg: <another-org-name>
                     azureReposHost: <your.azure-repos.host.tld>
14
15
                     brokerToken: <another-broker-token>
16
```

Note: Helm supports rendering YAML anchors. To re-use variables across connections, consider:

```
1
         broker-client:
 2
             brokerType: universal
 3
             universalBrokerConnections:
 4
                 azureReposOrgName:
 5
                     type: azure-repos
 6
                     auth: &azureReposAuth <azure-repos-pat>
 7
                     azureReposHost: &azureReposHost <your.azure-repos.host.tld>
 8
 9
                 anotherAzureReposOrgName:
10
                     type: azure-repos
11
                     auth: *azureReposAuth
12
                     azureReposHost: *azureReposHost
```

High Availability Mode

As of version 2.8.1 of Snyk Code Local Engine, High Availability Mode for the Snyk Broker is available.

By default one replica of the Snyk Broker is deployed with Snyk Code Local Engine. To increase the number of replicas, set:

```
broker-client:
replicaCount: <integer: 2, 3, 4>
highAvailabilityMode:
enabled: true
```

The maximum number of Snyk Broker replicas is 4. Enabling High Availability Mode is recommended for Kubernetes clusters that may cycle out nodes without warning, or for installations of Snyk Code Local Engine with high levels of traffic.

See public documentation for High Availability Mode for further information.

If using a Snyk Tenant other than US, ensure brokerDispatcherUrl is set to your regional equivalent - see Setting the Snyk Tenant.

Configuring GitHub Server App

Note: GitHub Server App is in Closed Beta, and must be activated for use by Snyk

The GitHub Server App integration (see public docs) requires additional setup for use with Snyk Code Local Engine.

As an overview, the following steps must be carried out:

- 1. Create a Custom GitHub App
- 2. Create Brokered Integrations
- 3. Configure Snyk Code Local Engine

Before following these steps, ensure:

- · Sufficient permissions are present to create a GitHub App,
- A valid Snyk API token is present associated with a User or Service Account with View Organization, View Integrations and Edit Integrations permissions

Create a Custom GitHub App

Steps for creating a GitHub App should be followed once.

- 1. Navigate to https://<your.ghe.tld>/settings/apps/new
- 2. Set a memorable name for your GitHub App
- 3. Set Homepage URL to https://github.com/apps/snyk-io
- 4. Set Webhook URL to https://app.snyk.io/api/hidden/scm-apps/api/github-app/webhook,or your regional equivalent
- 5. Set the following Repository permissions:
- Checks: Read and write
- Commit statuses: Read and write
- Contents: Read and write
- Projects: Read and write
 - 1. If using PR Checks, set these additional Repository permissions:
- Pull requests: Read and write
- Webhooks: Read and write
- 1. Set the following Organisation permissions:
- Members: Read-only
- 1. Subscribe to Repository events

- 2. Under "Where can this GitHub App be installed?", set Any account
- 3. Create the App. At this stage, GitHub will present an App ID and a Client ID. Capture these, and generate a new Private Key.

The following steps should be performed once per GitHub Organisation that should be onboarded to Snyk Code Local Engine.

- 1. Navigate to https://<your.ghe.tld>/settings/apps/<your-app-name> and select Install App from the sidebar.
- 2. Find the GitHub organisation to onboard to Snyk Code Local Engine and press Install.
- 3. Specify either "All repositories" or select specific resource(s) to grant access Snyk Code Local Engine access to.
- 4. Finally, capture the Installation ID from the address bar (https://<your.ghe.tld>/organisations/<your-org>/settings/installations/<installId>).

At this stage, validate the following items are present:

- · A GitHub App Client ID
- A GitHub App ID
- · A GitHub App Private Key
- · One or more GitHub App Installation IDs

Create Brokered Integrations

Once per Snyk Organisation create a GitHub Server App integration, replacing api.snyk.io with your regional equivalent:

```
1
    curl --location 'https://api.snyk.io/v1/org/:orgId/integrations' \
2
      --header "Content-Type: application/json; charset=utf-8" \
3
      --header "Authorization Token: token <your-snyk-api-token>" \
4
      --data '{
5
        "type": "github-server-app",
        "broker": {
6
7
          "enabled": true
8
          }
9
        }'
```

A successful response will contain a brokerToken in the body. Each brokerToken will correspond to one entry in the .Values.universalBrokerConnections map, linked to one GitHub App Installation ID.

A new tile will appear on your Snyk Org under "Integrations".

Configure Snyk Code Local Engine

Each github-server-app connection references a named object under broker-client.githubServerApps for the GitHub App Client ID, App ID and Private Key.

For example, the following configuration in values-customer-settings.yaml defines one GitHub Server App connected to two GitHub Organisations, which are each connected to their own Snyk Organisation:

```
1
     broker-client:
 2
     type: universal
 3
       githubServerApps:
       myGHSA: #define a GitHub App called myGHSA
 4
          githubAppClientId: <your-client-id>
 5
 6
          githubAppId: <your-app-id>
 7
          githubAppPrivateKey: |-
            <your private key</pre>
 8
 9
            as a multiline
10
            string>
     universalBrokerConnections:
11
       myGHSAInstall:
12
13
          type: github-server-app
14
           #Specify the Broker Token from Snyk Organisation A
           brokerToken: <your-broker-token>
15
           githubAppInstallationId: <your-installation-id>
16
17
           #Match a named GitHub App under `broker-client.githubServerApps`
18
         githubServerAppName: myGHSA
19
        myOtherGHSAInstall:
          type: github-server-app
20
           #Specify the Broker Token from Snyk Organisation B
21
22
           brokerToken: <another-broker-token>
23
           githubAppInstallationId: <your-other-installation-id>
           #Match a named GitHub App under `broker-client.githubServerApps`
24
           githubServerAppName: myGHSA
25
```

Update or install Snyk Code Local Engine - the new GitHub Server App integrations will be ready for use.

Advanced Deployments

Shared Cluster

Using a shared Kubernetes cluster allows Snyk Code Local Engine to be installed alongside pre-existing workloads. The following considerations are important:

- Snyk Code Local Engine has significant resource requirements and may negatively impact other workloads
 already running on the cluster if capacity is low. Snyk Code Local Engine may be unable to fully schedule. See
 Snyk Code Local Engine Requirements to ensure your cluster has adequate resources available.
- By default, Kubernetes schedules pods for Snyk Code Local Engine on any available node within the cluster. See Using tolerations, affinity or nodeSelector for advanced resource targeting.
- By default, Helm installs to the default namespace. To change this, provide a namespace with -n <namespace> to Helm when installing. If the namespace does not exist, provide the --create-namespace flag as well (assuming your user is privleged to create namespaces).

Using tolerations, affinity or nodeSelector

This section will build on information given in Kubernetes documentation

To target some/all of the workloads to particular nodes, specify the some/all of the mechanisms as follows (example values are provided, adjust these to match your own node labels/other running workloads):

```
1
     service_name:
         nodeSelector: #matches a node with label `NodeType` and value `large`
 2
 3
             NodeType: large
        tolerations: #matches if a node has taint `bigNode` with value `"true"`. The taint
 4
 5
    blocks other workloads that do not have this toleration.
             - key: "bigNode"
 6
 7
               operator: "Equal"
               value: "true"
 8
 9
               effect: "NoSchedule"
         affinity: #schedules only on nodes with `kubernetes.io/os:linux`
10
11
             nodeAffinity:
12
             requiredDuringSchedulingIgnoredDuringExecution:
13
                 nodeSelectorTerms:
14
                 - matchExpressions:
15
                 - key: kubernetes.io/os
16
                     operator: In
17
                     values:
```

This approach is recommended for the heaviest workloads in Snyk Code Local Engine (bundle, suggest) to avoid the considerations mentioned in Shared Cluster.

Making these changes in values-customer-settings.yaml could look like:

```
1  ...
2  suggest:
3    ...
4   nodeSelector:
5    NodeType: large
6    ...
```

Secret Management

Snyk Code Local Engine makes use of Kubernetes Secrets to authenticate access to internal components. By default, these secrets are managed by the Helm Chart.

The inbuilt secret lifecycle is:

- 1. On installation, create Opaque secrets using the randAlphaNum Helm function to generate values for required keys which are then base64 encoded and persisted to the deployment.
- 2. On upgrade, Helm will attempt to lookup the value(s) of a pre-existing secret:
 - a. If the lookup succeeds (a value exists on the cluster), Helm will not re-generate the secret.
 - b. If the lookup fails, Helm will re-generate the secret.

To use an external secret management solution with Snyk Code Local Engine, the following steps may be followed:

External Secrets

First create secrets for consumption by Snyk Code Local Engine. Then instruct Snyk Code Local Engine to consume these secrets, disabling the inbuilt secret generation mechanism.

Creating Secrets

Create secrets in the namespace Snyk Code Local Engine will be deployed to. Secrets are expressed with required key(s) and the format of the value(s) required. Any regex strings are provided to indicate the value that *would* be automatically generated by Snyk Code Local Engine if using the internal secret mechanism:

Session Secret

Function: Used for internal session authentication

Кеу	Format	Internal Secret Autogenerated Value
SESSION_SECRET	Alphanumeric string	[a-zA-Z0-9]{64}

Redis Secrets

Function: Used to secure access to any Redis deployments

Кеу	Format	Internal Secret Autogenerated Value
REDIS_PASSWORD	Alphanumeric string	[a-zA-Z0-9]{32}

S3 Secret

Function: Used to secure access to S3 deployments

Кеу	Format	Internal Secret Autogenerated Value
root-user	Alphanumeric string	admin
root-password	Alphanumeric string	[a-zA-Z0-9]{16}
region	Alphanumeric string	us-east-1
name	Alphanumeric string	scm-bundle-store-s3

JWT Secret

Function: Used for encrypting operations on objects stored in the object store

Кеу	Format	Internal Secret Autogenerated Value
jwtSecretKey	Alphanumeric string	[a-zA-Z0-9]{16}

Consuming Secrets

Update the values-customer-settings.yaml file to match the following:

```
global:
localEngine:
sessionSecretName: << the name of the secret created >>
redisSecretName: << the name of the secret created >>
s3SecretName: << the name of the secret created >>
jwtSecretName: << the name of the secret created >>
```

Networking

Core Networking

Re-using the Ingress definition

Follow this documentation to re-use this definition with your own Ingress Controller.

Pre-requisites

- [REQUIRED]: Obtain the Ingress Class Name for your clusters Ingress Controller.
- [RECOMMENDED]: Set up a DNS record for Snyk Code Local Engine.

Updating the inbuilt Ingress definition

Set the following in values-customer-settings.yaml:

```
1 global:
2 ingress:
3 enabled: true
4 ingressClassName: <<name-of-ingress-class>>
5 host: <<fdqn-dns-record>>
```

Where:

- ingressClassName is the name of the IngressClass definition on your cluster
- host is an optional DNS record resolving to your Ingress, which will be used by the Ingress Controller.

Custom Ingress

The inbuilt Ingress definition is used by default to automatically provision routes to the appropriate Snyk Code Local Engine services. If you wish to recreate the Ingress for any other reason, follow these steps.

Pre-requisites

All the inbound requests should be forwarded to internal-proxy service, port 10000.

The internal-proxy Service is created by default, and will expose its respective backend pod(s) via ClusterIP.

Disabling the built-in Ingress

Set the following in values-customer-settings.yaml:

```
global:
ingress:
enabled: false
```

Enabling TLS

Note: If using a custom ingress, these steps may not apply.

Adding a Certificate

By default, Snyk Code Local Engine is not secured by TLS. To enable TLS on the provided Ingress:

- · a DNS record must be created,
- · a certificate generated,
- the following changes made in the values-customer-settings.yaml file:

```
1
     global:
 2
       localEngineUrl: "https://<HOST>"
 3
 4
 5
      ingress:
 6
         . . .
        host: "<HOST>"
 7
 8
        tls:
 9
          enabled: true
10
           secret:
11
12
             key: |
13
14
             cert: |
15
               <CFRT>
```

Where <HOST> is the domain used when the TLS <CERT> and <KEY> were generated.

Read more about securing an ingress with TLS here and TLS secrets in general.

Self Signed Certificates

If using a self-signed certificate to secure Snyk Code Local Engine, append the --insecure option to any snyk commands, or provide the CA to snyk by setting NODE_EXTRA_CA_CERTS. This help article provides further information and support.

Outbound Proxy Support

Note: Snyk Code Local Engine does not support proxied connections to an external SCM. The following section is for proxying outbound traffic to Snyk domains only.

Components in Snyk Code Local Engine will make TLS-secured outbound connections to Snyk domains (app.snyk.io, api.snyk.io and broker.snyk.io for the default US tenant) to:

- · Authenticate users of the CLI and IDE.
- Make analysis results available on the Snyk Web UI.

If outbound connections to the internet require a proxy, the following may be configured in the values-customer-settings.yaml file:

```
1
    global:
 2
       . . .
 3
      proxy:
 4
       configMapName: 'proxy-configmap' #default, do not change
 5
        enabled: true
 6
       url: <proxy-url>
 7
       tlsRejectUnauthorized: [false|true]
       usePrivateCaCert: [false|true]
 8
9
10
      privateCaCert:
        enabled: [false|true]
11
12
          ----BEGIN CERTIFICATE----
13
14
15
           ----END CERTIFICATE----
        certMountPath: "/etc/config"
16
```

Where:

- global.proxy.enabled is set to true to use an external proxy,
- global.proxy.url is the proxy URL, of form http(s)://<user>:<password>@<uri>:<port>,
- global.proxy.tlsRejectUnauthorized should be set to true only if your proxy requires a certificate and one cannot be provided,
- global.proxy.usePrivateCaCert should be set to true if providing a certificate for the external proxy (see global.privateCaCert),
- global.privateCaCert.cert should be set to the full certificate chain required to trust your proxy. This should be a multi-line string in PEM format. This must be specified if global.proxy.usePrivateCaCert is true.

Further Proxy Configuration

- If your proxy uses whitelisting, ensure the appropriate domain for your Snyk tenant are added for example, app.snyk.io, api.snyk.io and broker.snyk.io (if using broker) for the default US tenant.
- If your proxy certificate and/or authentication information changes, update the value(s) above and re-apply Helm. Any running pods that use the proxy will be recreated with the new proxy configuration.

Private Certificate Authority Support for SCM

If the SCM used with Snyk Code Local Engine requires clients to trust a private/self-signed certificate, the following may be configured in the values-customer-settings.yaml file:

```
1  global:
2  privateCaCert:
3  enabled: true
4  cert: |
5     ----BEGIN CERTIFICATE----
6     ...
7  ----END CERTIFICATE----
```

Where:

- global.privateCaCert.enabled is set to true to provide a certificate to components that interact with an SCM,
- global.privateCaCert.cert should be set to the full certificate chain required to trust your SCM. This should be a multi-line string in PEM format.

Private Certificate Authority Support for both SCM and Proxy

To enforce certificate trust towards both SCM and Proxy, provide one or more CA certificates to the global.privateCaCert.cert key:

```
global:
 2
     . . .
 3
     proxy:
 4
       enabled: true
 5
       6
       tlsRejectUnauthorized: false
 7
       usePrivateCaCert: true
 8
9
      privateCaCert:
10
       enabled: true
11
12
          ----BEGIN CERTIFICATE----
13
14
          ----END CERTIFICATE----
15
          ----BEGIN CERTIFICATE----
16
17
          ----END CERTIFICATE----
```

These certificates will be concatenated to a single file and mounted by all services that interact with the outbound proxy, the SCM, or both.

Post Installation

Snyk Code Local Engine Health

Snyk Code Local Engine exposes useful endpoints to interrogate the status of your installation.

/ Or /status

Query either / or /status to report on the status of your installation:

```
1 curl http[s]://<LOCAL_ENGINE_URL>/
```

or:

```
1 curl http[s]://<LOCAL_ENGINE_URL>/status
```

NOTE: The response will be cached by default for 60 seconds.

Healthy Response

The following message is returned if all pods and services are running:

```
1 {
2    "message": "Snyk Code is healthy! ",
3    "ok": true,
4    "version": "<version_of_snyk_code_local_engine>"
5 }
```

Unhealthy Response

A JSON object is returned with details of the unhealthy workloads. If response code 503 is returned, the service-health-aggregator pod may be unable to start correctly.

/broker/healthcheck

The /broker/healthcheck endpoint ensures the broker-client pod is able to communicate with Snyk correctly.

```
1 curl http(s)://<LOCAL_ENGINE_URL>/broker/healthcheck
```

Healthy Response

```
1 {
2    "ok": true,
3    "websocketConnectionOpen": true,
4    "brokerServerUrl": "https://broker.snyk.io",
5    "version": "<version_of_broker>",
6    "transport": "websocket"
7 }
```

/api/healthcheck

The /api/healthcheck endpoint tests the health of the sast-analysis-api pod.

```
1 curl http[s]://<LOCAL_ENGINE_URL>/api/healthcheck
```

Healthy Response

```
1 { "gitSha": "sha", "ok": true }
```

Snyk Configuration

Note: At this point, you should have a running installation of Snyk Code Local Engine. As IP addresses may be dynamic/change, it is highly recommended to set up a DNS record.

If using either the Snyk CLI or PR Checks, Snyk requires one of the following once a Snyk Code Local Engine installation is complete:

- · The DNS name of the ingress of the cluster, or
- · The IP address of the ingress of the cluster

This allows the Snyk CLI/IDE plugins to function correctly.

To specify the DNS name or IP address of the ingress:

• Add the following to values-customer-settings.yaml:

```
global:
...
localEngineUrl: <either your assigned DNS record or your IP address - for example, http://local-engine.domain or http://lo.170.1.40>
```

• Execute helm upgrade --wait <DEPLOYMENT_NAME> snyk-code-local-engine-<VERSION>.tgz -i -f values-customer-settings.yaml

If an IP address was previously provided to your Snyk representative, please update us with your new DNS record.

Enabling Snyk Code Local Engine for Snyk CLI/IDE

Once enabled, the Snyk Code Local Engine URL/IP address will be shown in Settings, under the Snyk Code section.

Configure the Snyk CLI

If using a particular Snyk Organization for Snyk Code Local Engine, ensure that either:

- The --org=<LOCAL_ENGINE_ORG_NAME> flag is set when using the Snyk CLI, or
- snyk config set org=<LOCAL_ENGINE_ORG_NAME> is executed

This ensures Snyk Code analysis requests are directed to Snyk Code Local Engine.

To confirm, check the output of snyk code test -d:

```
1 ...
2 snyk-code ---> API request log => HTTP GET http://<LOCAL_ENGINE_URL_OR_IP>/api/filters
3 ...
```

Updating Snyk Code Local Engine - Snyk Configuration

If either of these change:

- The DNS name assigned to the ingress of the cluster, or
- If not using DNS records, the IP address assigned to the ingress of the cluster, or
- TLS encryption is enabled/disabled,

Snyk must be provided with the updated DNS name/IP address.

What Next?

Once your cluster is configured, Snyk Code Local Engine is ready for use. Results will appear on the Snyk Web UI after setting up PR Checks or importing Projects.

Helm Parameters

The available Helm Parameters are listed below.

Parameters

Enable Snyk Code Services

Name	Description	Value
tags.scm	Enable services required for SCM Imports	false
tags.scmPrCheck	Enable services required for SCM PR Checks	false
tags.cli	Enable services required for CLI	false
tags.ide	Enable services required for IDE	false

Global Parameters

Name	Description	Value
global.imagePull Secret.enabled	Disable if an Image Pull Secret is not required	true
global.imagePull Secret.name	The name of the Image Pull Secret to be created	<pre>snyk-code- local-engine- pull-secret</pre>
global.imagePull Secret.credentia ls.username	A Username to authenticate against a Docker registry	пп
global.imagePull Secret.credentia ls.password	A Password to authenticate against a Docker registry	п п
global.imagePull Secrets	Set to '[]' if your image registry does not require authentication, or '[<existing-secret-name>] if re-using credentials that already exist on your Kubernetes cluster</existing-secret-name>	["snyk-code- local-engine- pull-secret"]

Name	Description	Value
global.imageRegi stry	Optionally define a private image registry address if using non- default image registries (hostname/port only, no protocol)	п п
global.localEngi neUrl	The full URL including schema that points to the cluster ingress. Required for CLI/PR Checks.	п п
global.proxy.ena bled	Set to true to enable outbound proxy support	false
global.proxy.url	Proxy URL, including schema: http[s]://username:password@proxy:port	пп
global.proxy.tls RejectUnauthoriz ed	Set to true to trust any and all certificates presented by the proxy	false
global.proxy.use PrivateCaCert	Set to true to enable private CA support for the proxy - see global.privateCaCert	false
global.privateCa Cert.enabled	Set to true to enable trust of private CA certificate(s) towards the SCM and/or proxy	false
global.privateCa Cert.cert	Multiline string containing any/all certificates for connections to the SCM and/or proxy in PEM format ()	и и
global.privateCa Cert.certMountPa th	A fully qualified path to mount the certificate	/etc/config
global.ingress.e nabled	Set to true to create an Ingress for CLI/PR Checks	false
global.ingress.h ost	Optionally define the host associated with this ingress - otherwise leave blank	пп
global.ingress.i ngressClassName	Optionally define the Ingress Class for this ingress - otherwise leave blank	пп
global.ingress.a nnotations	Optionally define any annotations to add to the ingress - otherwise leave blank	{}

Name	Description	Value
global.ingress.t ls.enabled	Set to true to enable TLS on the in-built ingress	false
<pre>global.ingress.t ls.secret.name</pre>	Either specify the name of a pre-existing Kubernetes secret containing TLS secrets, or leave blank to create a new secret	и и
global.ingress.t ls.secret.key	The TLS key for TLS encryption, in PEM format	н н
global.ingress.t ls.secret.cert	The TLS certificate for TLS encryption, in PEM format	11 11
<pre>global.localEngi ne.redisSecretNa me</pre>	Optionally specify the name of a pre-existing Kubernetes secret containing Redis authentication data	и и
<pre>global.localEngi ne.sessionSecret Name</pre>	Optionally specify the name of a pre-existing Kubernetes secret containing session secret data	пп
<pre>global.localEngi ne.s3SecretName</pre>	Optionally specify the name of a pre-existing Kubernetes secret containing S3 authentication data	и и
<pre>global.localEngi ne.jwtSecretName</pre>	Optionally specify the name of a pre-existing Kubernetes secret containing S3 encryption data	и и

Deeproxy parameters (EU/AU Snyk Tenants only)

Name	Description	Value
deeproxy.verifica	Optionally specify the geographically-	https://api.snyk.io/v1/validate/to
tionEndpoint	appropriate endpoint. Set to US tenant by	ken/snyk-to-deepcode-proxy-
	default	validation

Broker Client parameters (any SCM flows only)

Name	Description	Value
broker-	Broker Token is a value from Snyk. Get this from the Snyk	пп

Name	Description	Value
client.brokerToken	integration settings page or your Snyk Representative	
<pre>broker- client.brokerType</pre>	Define the SCM Broker will connect to	11 11
broker- client.universalBroke rConnections	A map of Universal Broker client connections	{}
broker- client.githubHost	GHE URL - Ex: your.ghe.domain.com (do not prepend HTTPS) - For GHE Cloud use api.github.com	и и
broker- client.githubApi	GHE API Address - do not prepend HTTPS	н п
broker- client.githubGraphQl	GHE Graph QL Address - do not prepend HTTPS	пп
broker- client.githubToken	Github Token - for GitHub or GitHub Enterprise	и и
broker- client.bitbucketUsern ame	Bitbucket Server Username	пп
broker- client.bitbucketPassw ord	Bitbucket Server Password	н п
broker- client.bitbucketHost	Bitbucket Server Host URL - do not prepend HTTPS	пп
broker- client.bitbucketToke n	Bitbucket Server Personal Access Token	пп
broker- client.gitlabHost	GitLab URL - do not prepend HTTPS	и и
broker- client.gitlabToken	GitLab Token	пп

Name	Description	Value
broker- client.azureReposOrg	Azure Repos Organization	и и
broker- client.azureReposHos t	Azure Repos Hostname - do not prepend HTTPS	и и
broker- client.azureReposToke n	Azure Repos Token	и и
broker- client.codeSnippet.en abled	Set to enable viewing of analysis results in the Snyk UI. Caution - will allow Snyk servers to fetch source code files	false
broker- client.largeManifestF ileRule.enabled	Set to enable in order to be able to fetch large manifest files (> 1Mb). Available only for 'github' and 'github-enterprise' broker types/connections	false
broker- client.brokerServerUr l	Modify if using Snyk Private Cloud/a different Snyk tenant.	https://broke r.snyk.io
broker- client.highAvailabili tyMode.enabled	Set to true for High Availability Broker. Will take effect with 2, 3 or 4 replicas of Broker	false
broker- client.brokerDispatch erUrl	Modify if using Snyk Private Cloud/a different Snyk tenant. Required if highAvailabilityMode.enabled=true.	https://api.s nyk.io
broker- client.replicaCount	The number of Broker Clients to run. Set if using High Availability Broker (maximum 4 replicas)	1

Changelog

All notable changes to Code Local Engine project will be documented in this file.

The format is based on Keep a Changelog, and this project adheres to Semantic Versioning.

v2.11.0

2025-01-09

Changed

- · Snyk Code rules updated
- Updated broker-client to 4.203.4
- Update routing to handle Code PR checks in sast-analysis-api instead of code-pr-check-service. The code-pr-check-service has been made redundant and is pending removal.

Removed

• The broker-client no longer supports body logging (broker-client.logEnableBody). This value is deprecated, and has no effect if specified.

Fixed

scm-bundle-store and minio images upgraded to resolve a vulnerability in the Golang SSH package. This
vulnerability was not reachable in SCLE.

v2 10 0

2024-10-28

Added

- broker-client supports the GitHub Server App integration type this functionality is in Closed Beta. Discuss with your Snyk representative for enablement.
- New documentation to support configuration of GitHub Server App connections with Snyk Code Local Engine

Fixed

- Corrected github-com to github when specifying a Universal Broker connection to github.com
- Removed the ephemeral-storage limit for scm-bundle-store. This prevents pods that were previously being replaced by Kubernetes when exceeding ephemeral-storage limits remaining until cluster-level garbage

collection occurs, keeping health checks accurate.

Changed

- · Snyk Code rules updated
- Updated broker-client to 4.196.7

v2 9 0

2024-08-19

Added

- Included . snyk ignore file for Minio
- · Add Snyk Code Local Engine documentation as a pdf

Changed

- broker-client now deploys as a statefulset to increase stability when running in HA mode
- Updated scm-bundle-store to use Minio instead of MongoDB for backend storage
- global.localEngine.mongodbSecretName is deprecated, replaced by global.localEngine.s3SecretName and global.localEngine.jwtSecretName.
- Updated broker-client to 4.193.4

Removed

· References to the MongoDB image are removed

Fixed

- Removed the deprecated form of deeproxy.verificationEndpoint from values-customer-settings.yaml,
 using api.snyk.io instead
- Added broker-client.brokerDispatcherUrl to values-customer-settings.yaml for High Availability Broker

v282

2024-06-21

Added

• Support for Personal Access Token in Bitbucket Server

Fixed

- Resolved an ingress deployment failure when TLS secret name is provided. The fix ensures that Snyk Code Local Engine can now correctly use a pre-existing TLS secret for the certificate and key material when specified
- Corrected Broker behaviour when encountering non-ASCII characters in payloads
- · Resolves some C++ analyses reporting all issues on line 1

Changed

- Updated broker-client to 4.190.3
- Update Snyk Code services with latest rulesets

v2.8.1

2024-04-15

Fixed

· Updated values-customer-settings.yaml file with new settings for Universal Broker

Changed

- Updated MongoDB image to Debian 12 version
- Updated ignores for MongoDB
- Updated broker-client to 4.181.1

v2.8.0

2024-03-14

Fixed

- · Removed local analysis queue debug endpoints
- · Corrected a filter for the GitLab Snyk Broker that would cause some requests to fail

Changed

- Updated the list of images to remove the standalone mongodb image, which is no longer required
- Updated broker-client to v4.179.3

Added

- Support for multiple SCMs/instances of SCMs via Broker in Universal mode
- · Updated snyk ignore file for Redis

v2.7.11

2024-02-08

Added

• Added versioned snyk ignore (.snyk) files. These files detail any vulnerabilities within Snyk Code Local Engine that are either unreachable or otherwise not valid.

Fixed

Resolved a Helm validation bug for Broker

Changed

- · Snyk Code rules updated
- Updated broker-client to v4.174.1

Removed

• scm-bundle-store.server.useTokenAuth is now deprecated - repository detection should ensure the presence of required headers for self-hosted Azure DevOps/TFS servers. This value now has no effect.

v2.7.10

2024-01-26

Added

• scm-bundle-store.server.useTokenAuth for compatibility with self-hosted Azure DevOps Server

Fixed

- Corrected documentation for using EU or AU Snyk tenants with Snyk Code Local Engine
- · Resolved a bug that caused git requests to Azure DevOps Server to fail

Changed

- · Snyk Code rules updated
- · Introduced additional validation rules for EU or AU Snyk tenant usage

- Updates the default Snyk API domain from https://snyk.io to https://api.snyk.io
- Updated the broker-client to v4.172.6

v2.7.9

2024-01-16

Fixed

· Resolved a bug preventing cleanup jobs from running successfully

Changed

- · Updates to Snyk images for updated rulesets
- Updated the broker-client to v4.172.2

v2.7.8

2024-01-11

Changed

- Documentation updated to include alternative tenant setup
- Updates to Snyk images for new rulesets
- Updated the broker-client to v4.171.9

v2.7.7

2023-12-07

Fixed

- · Snyk Code rules updated
- Suggest services updated JDK to remove vulnerabilities
- Documentation updated to remove "Overview" section and streamline introduction to Snyk Code Local Engine

v2.7.6

2023-12-07

Added

• CronJobs to clean up older/expired data in MongoDB

Changed

Minimum Kubernetes version is now 1.21

v2.7.5

2023-11-27

Fixed

• Fixed non-reachable vulnerabilities in the scm-bundle-store and mongodb components.

v2.7.4

2023-11-23

Changed

• Corrected the list of images under the Private Registry section

Removed

• The scm-meld component is no longer required and has been removed

Fixed

• Resolved an "Unauthorized" failure during IDE and CLI scans occurring after a proxy CA certificate change. The fix ensures that Snyk Code Local Engine properly picks up the new configuration when redeployed.

v2.7.3

2023-11-10

Changed

• The /status endpoint is now also presented on / for better compatibility with Load Balancer health checks

v2.7.2

2023-11-08

Changed

- Updated the broker-client to v4.169.2
- · Updates to latest Snyk Code rules
- · Updates to Snyk Code services

Fixed

• Fixed outbound CA support for SCM when a proxy is not utilized

v2.7.1

2023-10-17

Changed

• Updated the architectural diagram with suggest-sticky component

v2.7.0

2023-10-17

Added

- Introduced a new largeManifestFileRule value, gives the option to add rule for fetching large manifest file. Avaliable for Github and Github Enterprise only.
- Caching mechanism for IDE scans by the new suggest-sticky component.

Changed

· Updated architecture diagram with new internal-proxy connectivity

v2.6.1

2023-09-20

Changed

- Updated Ingress template to include the host key if specified
- Updated documentation for JetBrains IDE

v2.6.0

2023-09-18

Added

internal-proxy component (based on envoy) replaces routes previously defined by the Ingress resource

Changed

- Updated the broker-client to v4.163.0
- Ingress resource simplified defies one route (/) and removes the need for request rewriting/regex capture groups

Fixed

- · Updated documentation for proxy and custom Certificate Authority support for better clarity
- Specify the brokerServerUrl by default in the values-customer-settings.yaml file

Removed

- Any references to the previously-used MongoDB Sharded cluster in documentation
- The pre-packaged NGINX Ingress Controller is removed. Functionality is handled internally by the internal-proxy component

v250

2023-09-04

Added

• Allows python projects that use poetry to be scanned by Snyk Open Source through the broker

Changed

- Updated the broker-client to v4.161.0
- · Updated Snyk Code services for latest analysis rules
- Changed database infrastructure for scm-bundle-store from a sharded MongoDB cluster to a single MongoDB instance

Fixed

• Fixed an upgrade/stability issue with MongoDB by migrating to a single MongoDB instance

v2.4.2

2023-08-17

Added

- Snyk Code Local Engine now supports custom CAs towards SCMs via global.privateCaCert.* values.
- A subset of available Helm values are listed in documentation
- A subset of available Helm values are subject to input validation
- The IDE has been added to the Architecture diagram

Changed

· NGINX Ingress documentation has been updated to better reflect usage and deployment options

Deprecated

• The global.proxy.cert and global.proxy.useCustomCert values are both deprecated.

v2.4.1

2023-07-14

Added

- The inbuilt NGINX Ingress Controller is now disabled by default, and is separate from the Ingress resource. This enables customers to re-use their own instance of NGINX Ingress Controller without manually manipulating the Chart.
 - To enable the NGINX Ingress Controller, set global.ingressController.enabled: true.

v240

2023-07-13

Added

- Support for custom image registries:
 - · Authenticated/unauthenticated private registries
 - · Custom image pull secrets

2023-07-12

Added

• IDE Scans for VSCode v1.21 and higher

v2.2.3

2023-06-15

Added

- Update of scm-meld to support custom CA override
- Update of files-bundle-store to improve CPU usage, and concurrency

v2.2.2

2023-06-13

Fixed

- Suggest has been upgraded with some key bug fixes:
 - Better queueing mechanism to reduce stuck analyses
 - Introduced better analyses timeout mechanisms
 - · Suggest runs as non-root

v2.2.1

2023-06-09

Added

• Migrates additional services to run as non-root

Fixed

- Inconsistency when deploying Local Engine to a custom namespace
- · Webhook creation for PR checks

v2.2.0

2023-05-12

Added

- Modular service deployment, only deploy the services needed for the intended use case
- · PR check functionality
- · Ability to configure self managed secrets
- Partial standardisation of service base images (more to follow)
- Partial migration of services not to run as root anymore (more to follow)
- · Updates core Snyk Code services to include new rule sets

Removed

• We removed CRDs and ClusterRoles - no more cluster-wide access needed.

v2.0.0

2023-04-20

Added

- Includes the "new" Snyk Code stack, giving customers parity between Snyk SaaS and Local Engine environments.
- We host the Helm Chart on Dockerhub customers can pull the Helm Chart with the same credentials for v1.Documentation and the values-customer-settings.yaml are still shared manually with the customer.

Removed

• We removed CRDs and ClusterRoles - no more cluster-wide access needed.

Changed

- This release does not include PR Checks. CLI scans/ Imports are currently supported.
- This release does not include pulling images from a custom registry.
- This release does not include centralised logging.