

```
package
패키지 생성
```

\$ cd ~/Workspaces/ros2 ws/src \$ ros2 pkg create simple_service_pkg --build-type ament python --dependencies rclpy std srvs

```
SetBool.srv
서비스 인터페이스
std srvs/srv/SetBool
# Request
bool data
# Response
bool success
string message
```

```
service server.py
서비스 서버
src/simple_service_pkg/simple_service_pkg/service_server.py
import rclpy
from rclpy.node import Node
from std srvs.srv import SetBool
class PowerServer(Node):
   def __init__(self):
        super().__init__('service_server_node')
        self.srv = self.create service(SetBool,
'power_service', self.power_cb)
       self.get logger().info('Service Server
Running...')
    def power_cb(self, request, response):
       self.get logger().info('Request Received...')
        if request.data:
            response.success = True
            response.message = 'Power On'
       elif not request.data:
            response.success = True
            response.message = 'Power Off'
        else:
            response.success = False
            response.message = 'Error'
       print(request)
       print(response)
       return response
def main(args=None):
    rclpv.init(args=args)
   node = PowerServer()
    try:
        rclpy.spin(node)
    except KeyboardInterrupt:
       node.get_logger().info('Keyboard Interrupt')
    finally:
       node.destroy_node()
        rclpy.shutdown()
if __name__ == '__main__':
    main()
```

```
service client.py
서비스 클라이언트
src/simple service pkg/simple service pkg/service client.py
import rclpy
from rclpv.node import Node
from std srvs.srv import SetBool
class PowerClient(Node):
    def init (self):
       super().__init__('service_client_node')
       self.client = self.create client(SetBool,
'power_service')
       self.req = SetBool.Request()
       self.get_logger().info('Service Client Start')
    def send_request(self, user_input):
        self.req.data = (user input.lower() == 'on')
        self.client.wait_for_service()
       self.future = self.client.call_async(self.req)
       rclpy.spin_until_future_complete(self,
self.future)
        self.result = self.future.result()
        return self.result
def main(args=None):
   rclpy.init(args=args)
   node = PowerClient()
   try:
        #pass
       user_input = input('Enter an power "on" or
"off" : ')
       res = node.send_request(user_input)
       node.get_logger().info('Server returned: ' +
res.message)
   except KeyboardInterrupt:
       node.get logger().info('Keyboard Interrupt')
   finally:
       node.destroy node()
       rclpy.shutdown()
if __name__ == '__main__':
   main()
```

```
setup.py
'console scripts': [
    service server =
simple_service_pkg.service_server:main',
    service client =
simple service pkg.service client:main'
```

```
build & run
 $ cd ~/Workspaces/ros2 ws
 $ colcon build --symlink-install --packages-select
simple service pkg
 $ source
~/Workspaces/ros2_ws/install/local_setup.bash
노드 실행(ros2 run)
 $ ros2 pkg executables simple service pkg
 $ ros2 run simple service pkg service server
 $ ros2 run simple_service_pkg service_client
```