
Device Enrollment

Windows


Add devices (skip this section if no Devices available)

You can add Windows Autopilot devices by importing a CSV file with their information.

In <u>Intune in the Azure portal</u>, choose <u>Device enrollment</u> > <u>Windows enrollment</u> > <u>Devices</u> > <u>Import</u>.



2. Under **Add Windows Autopilot devices**, browse to a CSV file listing the devices that you want to add. The file should list the serial numbers, Windows product IDs, hardware hashes, and optional order IDs of the devices.



- 3. Choose **Import** to start importing the device information. Importing can take several minutes.
- 4. After import is complete, choose **Device enrollment > Windows enrollment > Windows Autopilot > Devices > Sync**. A message displays that the synchronization is in progress. The process might take a few minutes to complete, depending on how many devices are being synchronized.
- 5. Refresh the view to see the new devices.

Create an Autopilot device group

- 1. In <u>Intune in the Azure portal</u>, choose **Groups** > **New group**.
- 2. In the **Group** blade:
 - a. For **Group type**, choose **Security**.
 - b. Type a Group name and Group description.
 - c. For **Membership type**, choose either **Assigned**.
- 3. If you chose **Assigned** for **Membership type** in the previous step, then in the **Group** blade, choose **Members** and add Autopilot devices to the group. Autopilot devices that aren't yet enrolled are devices where the name equals the serial number of the device.
- 4. If you chose **Dynamic Devices** for **Membership type** above, then in the **Group** blade, choose **Dynamic device members** and type any of the following code in the **Advanced rule** box.
 - If you want to create a group that includes all of your Autopilot devices, type (device.devicePhysicalIDs -any _ -contains "[ZTDId]")

• If you want to create a group that includes all of your Autopilot devices with a specific order ID, type: (device.devicePhysicalIds -any _ -eq "[OrderID]:179887111881")

If you want to create a group that includes all of your Autopilot devices with a specific Purchase Order ID, type: (device.devicePhysicalIds -any _ -eq
 "[PurchaseOrderId]:76222342342")

After adding the **Advanced rule** code, choose **Save**.

Choose Create.

Create an Autopilot deployment profile

Autopilot deployment profiles are used to configure the Autopilot devices.

- In <u>Intune in the Azure portal</u>, choose <u>Device enrollment > Windows enrollment > Deployment Profiles > Create Profile</u>.
- 2. Type a Name and optional Description.
- 3. If you want all devices in the assigned groups to automatically convert to Autopilot, set **Convert all targeted devices to Autopilot** to **Yes**. All non-Autopilot devices in assigned groups will register with the Autopilot deployment service. Allow 48 hours for the registration to be processed.
- 4. For **Deployment mode**, choose **User-driven**: Devices with this profile are associated with the user enrolling the device. User credentials are required to enroll the device.
- 5. In the Join to Azure AD as box, choose Azure AD joined.
- 6. Choose **Out-of-box experience (OOBE)**, configure the following options, and then choose **Save**:
 - End-user license agreement (EULA): (Windows 10, version 1709 or later) Choose No.
 - Privacy settings: Choose No.
 - Hide change account options (Windows Insider only): Choose Hide to prevent change
 account options from displaying on the company sign-in and domain error pages. This
 option requires company branding to be configured in Azure Active Directory.
 - User account type: Choose Standard user.
 - Apply computer name template (Windows Insider only): Choose Yes to create a
 template to use when naming a device during enrollment. Names must be 15 characters or
 less, and can have letters, numbers, and hyphens. Names can't be all numbers. Use the
 <u>%SERIAL% macro</u> to add a hardware-specific serial number. Or, use the <u>%RAND:x% macro</u>
 to add a random string of numbers, where x equals the number of digits to add.

7. Choose **Create** to create the profile. The Autopilot deployment profile is now available to assign to devices.

Assign an Autopilot deployment profile to a device group


- In <u>Intune in the Azure portal</u>, choose **Device enrollment > Windows enrollment >** Deployment profiles > choose a profile.
- 2. In the specific profile blade, choose **Assignments**.
- 3. Choose **Select groups**, then in the **Select groups** blade, choose the group(s) that you want to assign the profile to, then choose **Select**.

Assign a user to a specific Autopilot device (skip this section if no Devices available)


You can assign a user to a specific Autopilot device. This assignment pre-fills a user from Azure Active Directory in the <u>company-branded</u> sign-in page during Windows setup. It also lets you set a custom greeting name. It doesn't pre-fill or modify Windows sign-in. Only licensed Intune users can be assigned in this manner.

Prerequisites: Azure Active Directory Company Portal has been configured and the most recent Windows 10 Insider Preview Build.


1. In the <u>Intune in the Azure portal</u>, choose **Device enrollment > Windows enrollment > Devices** > choose the device > **Assign user**.



2. Choose an Azure user licensed to use Intune and choose **Select**.



3. In the **User Friendly Name** box, type a friendly name or just accept the default. This string is the friendly name that displays when the user signs in during Windows setup.



4. Choose Ok.