Package 'mxnet'

November 1, 2019

```
Type Package
Title MXNet: A Flexible and Efficient Machine Learning Library for Heterogeneous Distributed Sys-
Version 1.6.0
Date 2017-06-27
Author Tianqi Chen, Qiang Kou, Tong He, Anirudh Acharya <a href="https://github.com/anirudhacharya">https://github.com/anirudhacharya</a>
Maintainer Qiang Kou <qkou@qkou.info>
Repository apache/incubator-mxnet
Description MXNet is a deep learning framework designed for both efficiency
      and flexibility. It allows you to mix the flavours of deep learning programs
      together to maximize the efficiency and your productivity.
License Apache License (== 2.0)
URL https://github.com/apache/incubator-mxnet/tree/master/R-package
BugReports https://github.com/apache/incubator-mxnet/issues
Imports methods,
      Rcpp (>= 0.12.1),
      DiagrammeR (>= 0.9.0),
      visNetwork (>= 1.0.3),
      data.table,
      isonlite,
      magrittr,
      stringr
Suggests testthat,
      mlbench,
      knitr,
      rmarkdown,
      imager,
      covr
Depends R (>= 3.4.4)
LinkingTo Rcpp
VignetteBuilder knitr
```

RoxygenNote 6.1.1 **Encoding** UTF-8

R topics documented:

rguments	15
s.array.MXNDArray	15
s.matrix.MXNDArray	16
hildren	16
tx	16
lim.MXNDArray	17
graph.viz	17
m2rec	18
nternals	19
s.mx.context	19
s.mx.dataiter	19
s.mx.ndarray	20
s.mx.symbol	20
s.serialized	21
ength.MXNDArray	21
nx.apply	21
nx.callback.early.stop	22
nx.callback.log.speedometer	22
nx.callback.log.train.metric	23
nx.callback.save.checkpoint	23
nx.cpu	24
nx.ctx.default	
nx.exec.backward	24
nx.exec.forward	25
nx.exec.update.arg.arrays	25
nx.exec.update.aux.arrays	25
nx.exec.update.grad.arrays	26
nx.gpu	26
nx.infer.rnn	26
nx.infer.rnn.one	
nx.infer.rnn.one.unroll	27
nx.init.create	28
nx.init.internal.default	28
nx.init.normal	29
nx.init.uniform	29
nx.init.Xavier	29
nx.io.arrayiter	30
nx.io.bucket.iter	30
nx.io.CSVIter	31
nx.io.extract	32
nx.io.ImageDetRecordIter	33
nx io ImageRecordInt8Iter	36

mx.io.ImageRecordIter	39
mx.io.ImageRecordIter_v1	
mx.io.ImageRecordUInt8Iter	
mx.io.ImageRecordUInt8Iter_v1	49
mx.io.LibSVMIter	
mx.io.MNISTIter	
mx.kv.create	
mx.lr_scheduler.FactorScheduler	
mx.lr_scheduler.MultiFactorScheduler	
mx.metric.accuracy	56
mx.metric.custom	
mx.metric.logistic_acc	56
mx.metric.logloss	
mx.metric.mae	
mx.metric.mse	
mx.metric.Perplexity	58
mx.metric.rmse	
mx.metric.rmsle	
mx.metric.top_k_accuracy	
mx.mlp	
mx.model.buckets	
mx.model.FeedForward.create	
mx.model.init.params	
mx.model.load	
mx.model.save	
mx.nd.abs	
mx.nd.Activation	
mx.nd.adam.update	
mx.nd.add.n	
mx.nd.all.finite	66
mx.nd.amp.cast	67
mx.nd.amp.multicast	67
mx.nd.arccos	68
mx.nd.arccosh	
mx.nd.arcsin	
mx.nd.arcsinh	
mx.nd.arctan	
mx.nd.arctanh	70
mx.nd.argmax	71
mx.nd.argmax.channel	71
mx.nd.argmin	72
mx.nd.argsort	73
mx.nd.array	73
mx.nd.batch.dot	74
mx.nd.batch.take	75
mx.nd.BatchNorm	75
mx.nd.BatchNorm.v1	77
my nd DilingarCamplar	70

mx.nd.BlockGrad	. 79
mx.nd.broadcast.add	
mx.nd.broadcast.axes	81
mx.nd.broadcast.axis	
mx.nd.broadcast.div	. 82
mx.nd.broadcast.equal	83
mx.nd.broadcast.greater	
mx.nd.broadcast.greater.equal	
mx.nd.broadcast.hypot	
mx.nd.broadcast.lesser	
mx.nd.broadcast.lesser.equal	. 86
mx.nd.broadcast.like	
mx.nd.broadcast.logical.and	
mx.nd.broadcast.logical.or	
mx.nd.broadcast.logical.xor	
mx.nd.broadcast.maximum	
mx.nd.broadcast.minimum	
mx.nd.broadcast.minus	
mx.nd.broadcast.mod	
mx.nd.broadcast.mul	
mx.nd.broadcast.not.equal	
mx.nd.broadcast.plus	
mx.nd.broadcast.power	
mx.nd.broadcast.sub	
mx.nd.broadcast.sto	
mx.nd.Cast	
mx.nd.cast	
mx.nd.cast.storage	
mx.nd.cbrt	
mx.nd.ceil	
mx.nd.choose.element.0index	
mx.nd.clip	
mx.nd.Concat	
mx.nd.concat	
mx.nd.Convolution	
mx.nd.Convolution.v1	
mx.nd.copyto	
mx.nd.Correlation	
mx.nd.cos	
mx.nd.cosh	
mx.nd.Crop	
mx.nd.crop	
mx.nd.ctc.loss	
mx.nd.CTCLoss	
mx.nd.cumsum	
mx.nd.Custom	
mx.nd.Deconvolution	
mx.nd.degrees	114

mx.nd.depth.to.space	. 115
mx.nd.diag	
mx.nd.dot	. 116
mx.nd.Dropout	. 118
mx.nd.ElementWiseSum	. 119
mx.nd.elemwise.add	. 119
mx.nd.elemwise.div	. 120
mx.nd.elemwise.mul	. 120
mx.nd.elemwise.sub	. 121
mx.nd.Embedding	. 121
mx.nd.erf	. 122
mx.nd.erfinv	. 123
mx.nd.exp	. 123
mx.nd.expand.dims	. 124
mx.nd.expm1	. 124
mx.nd.fill.element.0index	. 125
mx.nd.fix	. 125
mx.nd.Flatten	. 126
mx.nd.flatten	. 126
mx.nd.flip	. 127
mx.nd.floor	. 127
mx.nd.ftml.update	. 128
mx.nd.ftrl.update	. 129
mx.nd.FullyConnected	. 130
mx.nd.gamma	. 131
mx.nd.gammaln	. 131
mx.nd.gather.nd	. 132
mx.nd.GridGenerator	. 132
mx.nd.GroupNorm	. 133
mx.nd.hard.sigmoid	
mx.nd.identity	
mx.nd.IdentityAttachKLSparseReg	. 135
mx.nd.InstanceNorm	
mx.nd.khatri.rao	
mx.nd.L2Normalization	. 137
mx.nd.LayerNorm	. 138
mx.nd.LeakyReLU	. 139
mx.nd.linalg.det	
mx.nd.linalg.extractdiag	
mx.nd.linalg.extracttrian	
mx.nd.linalg.gelqf	
mx.nd.linalg.gemm	
mx.nd.linalg.gemm2	
mx.nd.linalg.inverse	
mx.nd.linalg.makediag	
mx.nd.linalg.maketrian	
mx.nd.linalg.potrf	
mx.nd.linalg.potri	

mx.nd.linalg.slogdet	
mx.nd.linalg.sumlogdiag	. 150
mx.nd.linalg.syrk	. 151
mx.nd.linalg.trmm	. 152
mx.nd.linalg.trsm	. 153
mx.nd.LinearRegressionOutput	
mx.nd.load	. 154
mx.nd.log	. 155
mx.nd.log.softmax	. 155
mx.nd.log10	. 156
mx.nd.log1p	. 157
mx.nd.log2	. 157
mx.nd.logical.not	
mx.nd.LogisticRegressionOutput	
mx.nd.LRN	
mx.nd.MAERegressionOutput	
mx.nd.make.loss	
mx.nd.MakeLoss	
mx.nd.max	
mx.nd.max.axis	
mx.nd.mean	
mx.nd.min	
mx.nd.min.axis	
mx.nd.moments	
mx.nd.mp.nag.mom.update	
mx.nd.mp.sgd.mom.update	
mx.nd.mp.sgd.update	
mx.nd.multi.all.finite	
mx.nd.multi.lars	
mx.nd.multi.mp.sgd.mom.update	
mx.nd.multi.mp.sgd.update	
mx.nd.multi.sgd.mom.update	
mx.nd.multi.sgd.update	
mx.nd.multi.sum.sq	
mx.nd.nag.mom.update	
mx.nd.nanprod	
mx.nd.nansum	
mx.nd.negative	
mx.nd.norm	
mx.nd.normal	
mx.nd.one.hot	
mx.nd.ones	
mx.nd.ones.like	
mx.nd.Pad	
mx.nd.pad	
mx.nd.pick	
mx.nd.Pooling	
mx nd Pooling v1	185

mx.nd.preloaded.multi.mp.sgd.mom.update	
mx.nd.preloaded.multi.mp.sgd.update	
mx.nd.preloaded.multi.sgd.mom.update	. 187
mx.nd.preloaded.multi.sgd.update	. 188
mx.nd.prod	. 189
mx.nd.radians	. 189
mx.nd.random.exponential	. 190
mx.nd.random.gamma	
mx.nd.random.generalized.negative.binomial	
mx.nd.random.negative.binomial	. 192
mx.nd.random.normal	
mx.nd.random.pdf.dirichlet	
mx.nd.random.pdf.exponential	. 194
mx.nd.random.pdf.gamma	. 195
mx.nd.random.pdf.generalized.negative.binomial	. 196
mx.nd.random.pdf.negative.binomial	
mx.nd.random.pdf.normal	. 198
mx.nd.random.pdf.poisson	. 199
mx.nd.random.pdf.uniform	. 199
mx.nd.random.poisson	
mx.nd.random.randint	
mx.nd.random.uniform	. 201
mx.nd.ravel.multi.index	. 202
mx.nd.rcbrt	. 203
mx.nd.reciprocal	
mx.nd.relu	
mx.nd.repeat	. 204
mx.nd.reset.arrays	. 205
mx.nd.Reshape	. 205
mx.nd.reshape	
mx.nd.reshape.like	
mx.nd.reverse	
mx.nd.rint	. 210
mx.nd.rmsprop.update	
mx.nd.rmspropalex.update	
mx.nd.RNN	
mx.nd.ROIPooling	. 214
mx.nd.round	. 216
mx.nd.rsqrt	
mx.nd.sample.exponential	. 217
mx.nd.sample.gamma	
mx.nd.sample.generalized.negative.binomial	. 219
mx.nd.sample.multinomial	. 220
mx.nd.sample.negative.binomial	. 221
mx.nd.sample.normal	. 222
mx.nd.sample.poisson	. 223
mx.nd.sample.uniform	. 224
mx nd save	225

mx.nd.scatter.nd	225
mx.nd.SequenceLast	
1	
mx.nd.SequenceMask	
mx.nd.SequenceReverse	
mx.nd.sgd.mom.update	
mx.nd.sgd.update	
mx.nd.shape.array	
mx.nd.shuffle	
mx.nd.sigmoid	
mx.nd.sign	. 233
mx.nd.signsgd.update	. 234
mx.nd.signum.update	. 234
mx.nd.sin	
mx.nd.sinh	
mx.nd.size.array	
mx.nd.slice.axis	
mx.nd.slice.like	
mx.nd.SliceChannel	
mx.nd.smooth.11	
mx.nd.Softmax	
mx.nd.softmax	
mx.nd.softmax.cross.entropy	
mx.nd.SoftmaxActivation	
mx.nd.SoftmaxOutput	
mx.nd.softmin	
mx.nd.softsign	
mx.nd.sort	. 248
mx.nd.space.to.depth	. 248
mx.nd.SpatialTransformer	. 249
mx.nd.split	. 250
mx.nd.sqrt	. 251
mx.nd.square	
mx.nd.squeeze	
mx.nd.stack	
mx.nd.stop.gradient	
mx.nd.sum	
mx.nd.sum.axis	
mx.nd.SVMOutput	
<u>*</u>	
mx.nd.swapaxes	
mx.nd.SwapAxis	
mx.nd.take	
mx.nd.tan	
mx.nd.tanh	
mx.nd.tile	
mx.nd.topk	. 260
mx.nd.transpose	. 261
mx.nd.trunc	. 262
mx.nd.uniform	. 263

mx.nd.unravel.index	263
mx.nd.UpSampling	264
mx.nd.where	265
mx.nd.zeros	
mx.nd.zeros.like	
mx.opt.adadelta	
mx.opt.adagrad	
mx.opt.adam	
mx.opt.create	
mx.opt.get.updater	
mx.opt.nag	
mx.opt.rmsprop	
mx.opt.sgd	
mx.profiler.config	
mx.profiler.state	
mx.rnorm	
mx.runif	
mx.serialize	
mx.set.seed	
mx.simple.bind	
mx.symbol.abs	
mx.symbol.Activation	
mx.symbol.adam_update	
mx.symbol.add_n	
mx.symbol.all_finite	
mx.symbol.amp_cast	
mx.symbol.amp_multicast	
mx.symbol.arccos	
mx.symbol.arccosh	
mx.symbol.arcsin	
mx.symbol.arcsinh	
mx.symbol.arctan	
mx.symbol.arctanh	
mx.symbol.argmax	
mx.symbol.argmax_channel	
mx.symbol.argmin	
mx.symbol.argsort	286
mx.symbol.BatchNorm	
mx.symbol.BatchNorm_v1	289
mx.symbol.batch_dot	290
mx.symbol.batch_take	291
mx.symbol.BilinearSampler	292
mx.symbol.BlockGrad	293
mx.symbol.broadcast_add	294
mx.symbol.broadcast_axes	295
mx.symbol.broadcast_axis	296
mx.symbol.broadcast_div	297
mx symbol broadcast equal	297

10

mx.symbol.broadcast_greater	208
mx.symbol.broadcast_greater_equal	
mx.symbol.broadcast_hypot	
mx.symbol.broadcast_lesser	
·	
mx.symbol.broadcast_lesser_equal	
mx.symbol.broadcast_like	
mx.symbol.broadcast_logical_and	
mx.symbol.broadcast_logical_or	
mx.symbol.broadcast_logical_xor	
mx.symbol.broadcast_maximum	
mx.symbol.broadcast_minimum	
mx.symbol.broadcast_minus	. 306
mx.symbol.broadcast_mod	. 307
mx.symbol.broadcast_mul	. 308
mx.symbol.broadcast_not_equal	. 308
mx.symbol.broadcast_plus	
mx.symbol.broadcast_power	
mx.symbol.broadcast sub	
mx.symbol.broadcast_to	
mx.symbol.Cast	
mx.symbol.cast	
mx.symbol.cast_storage	
mx.symbol.cbrt	
mx.symbol.ceil	
mx.symbol.choose_element_0index	
mx.symbol.clip	
mx.symbol.Concat	
mx.symbol.concat	
mx.symbol.Convolution	
mx.symbol.Convolution_v1	
mx.symbol.Correlation	. 322
mx.symbol.cos	. 324
mx.symbol.cosh	. 324
mx.symbol.Crop	
mx.symbol.crop	
mx.symbol.CTCLoss	
mx.symbol.ctc_loss	
mx.symbol.cumsum	
mx.symbol.Custom	
·	
mx.symbol.Deconvolution	
mx.symbol.degrees	
mx.symbol.depth_to_space	
mx.symbol.diag	
mx.symbol.dot	
mx.symbol.Dropout	
mx.symbol.ElementWiseSum	
mx.symbol.elemwise_add	. 338
mx.svmbol.elemwise div	. 338

	220
mx.symbol.elemwise_mul	
mx.symbol.elemwise_sub	
mx.symbol.Embedding	
mx.symbol.erf	
mx.symbol.erfinv	
mx.symbol.exp	
$mx.symbol.expand_dims \ \ldots \ \ldots$	
mx.symbol.expm1	
mx.symbol.fill_element_0index	
mx.symbol.fix	
mx.symbol.Flatten	
mx.symbol.flatten	
mx.symbol.flip	
$mx.symbol.floor \dots $	
mx.symbol.ftml_update	
mx.symbol.ftrl_update	. 350
mx.symbol.FullyConnected	. 351
mx.symbol.gamma	. 352
mx.symbol.gammaln	. 352
mx.symbol.gather_nd	. 353
mx.symbol.GridGenerator	. 353
mx.symbol.Group	. 354
mx.symbol.GroupNorm	. 355
mx.symbol.hard_sigmoid	
mx.symbol.identity	. 356
mx.symbol.IdentityAttachKLSparseReg	. 357
mx.symbol.infer.shape	. 357
mx.symbol.InstanceNorm	. 358
mx.symbol.khatri_rao	. 359
mx.symbol.L2Normalization	. 360
mx.symbol.LayerNorm	. 361
mx.symbol.LeakyReLU	. 362
mx.symbol.linalg_det	. 363
mx.symbol.linalg_extractdiag	. 364
mx.symbol.linalg_extracttrian	
mx.symbol.linalg_gelqf	
mx.symbol.linalg_gemm	
mx.symbol.linalg gemm2	
mx.symbol.linalg_inverse	
mx.symbol.linalg_makediag	
mx.symbol.linalg_maketrian	
mx.symbol.linalg_potrf	
mx.symbol.linalg_potri	
mx.symbol.linalg_slogdet	
mx.symbol.linalg_sumlogdiag	
mx.symbol.linalg_syrk	
mx.symbol.linalg_trmm	
mx.symbol.linalg_trsm	

mx.symbol.LinearRegressionOutput	379
mx.symbol.load	
mx.symbol.load.json	
mx.symbol.log	
mx.symbol.log10	
mx.symbol.log1p	
mx.symbol.log2	. 382
mx.symbol.logical_not	
mx.symbol.LogisticRegressionOutput	
mx.symbol.log_softmax	
mx.symbol.LRN	
mx.symbol.MAERegressionOutput	
mx.symbol.MakeLoss	
mx.symbol.make_loss	
mx.symbol.max	
mx.symbol.max_axis	
mx.symbol.mean	
mx.symbol.moments	
mx.symbol.mp_nag_mom_update	
mx.symbol.mp_sgd_mom_update	
mx.symbol.mp_sgd_update	
mx.symbol.multi_all_finite	
mx.symbol.multi_lars	
mx.symbol.multi_mp_sgd_mom_update	
mx.symbol.multi_mp_sgd_update	
mx.symbol.multi_sgd_mom_update	
mx.symbol.multi_sgd_update	
mx.symbol.multi_sum_sq	
mx.symbol.nag_mom_update	
mx.symbol.nanprod	
mx.symbol.nansum	
mx.symbol.negative	
mx.symbol.norm	
mx.symbol.normal	
mx.symbol.normal	
mx.symbol.one hot	
mx.symbol.Pad	
mx.symbol.pad	
mx.symbol.pick	
mx.symbol.Pooling	
mx.symbol.Pooling_v1	
mx.symbol.preloaded_multi_mp_sgd_mom_update	
mx.symbol.preloaded_multi_mp_sgd_update	
mx.symbol.preloaded_multi_sgd_mom_update	
mx.symbol.preloaded_multi_sgd_update	
mx.symbol.prod	
mx.symbol.radians	
HIA.SVIIIDOLTAHUOHI EXDONEHUAL	. 41/

mx.symbol.random_gamma	. 418
mx.symbol.random_generalized_negative_binomial	. 419
mx.symbol.random_negative_binomial	. 420
mx.symbol.random_normal	. 421
mx.symbol.random_pdf_dirichlet	
mx.symbol.random_pdf_exponential	
mx.symbol.random_pdf_gamma	
mx.symbol.random_pdf_generalized_negative_binomial	
mx.symbol.random_pdf_negative_binomial	
mx.symbol.random_pdf_normal	
mx.symbol.random_pdf_poisson	
mx.symbol.random_pdf_uniform	
mx.symbol.random_poisson	
mx.symbol.random_randint	
mx.symbol.random_uniform	
mx.symbol.ravel_multi_index	
mx.symbol.rcbrt	
mx.symbol.reciprocal	
mx.symbol.relu	
mx.symbol.repeat	
mx.symbol.reset_arrays	
mx.symbol.Reshape	
mx.symbol.reshape	
mx.symbol.reshape_like	
mx.symbol.reverse	
mx.symbol.rint	
mx.symbol.rmspropalex_update	
mx.symbol.rmsprop_update	
mx.symbol.RNN	
mx.symbol.ROIPooling	
mx.symbol.round	
mx.symbol.rsqrt	
mx.symbol.sample_exponential	
mx.symbol.sample_gamma	
mx.symbol.sample_generalized_negative_binomial	
mx.symbol.sample_multinomial	
mx.symbol.sample_negative_binomial	
mx.symbol.sample_negative_binomiai	
mx.symbol.sample_poisson	
mx.symbol.sample_uniform	
mx.symbol.save	
mx.symbol.scatter_nd	
mx.symbol.SequenceLast	
mx.symbol.SequenceMask	
mx.symbol.SequenceReverse	
mx.symbol.sgd_mom_update	
mx.symbol.sgd_update	
mx symbol shape array	464

mx.symbol.shuffle	464
mx.symbol.sigmoid	
mx.symbol.sign	
mx.symbol.signsgd_update	
mx.symbol.signum_update	
mx.symbol.sin	
mx.symbol.sinh	
mx.symbol.size_array	
mx.symbol.slice	
mx.symbol.SliceChannel	
mx.symbol.slice_axis	
mx.symbol.slice_like	
mx.symbol.smooth_11	
mx.symbol.Softmax	
mx.symbol.softmax	
mx.symbol.SoftmaxActivation	
mx.symbol.SoftmaxOutput	
mx.symbol.softmax_cross_entropy	
mx.symbol.softmin	
mx.symbol.softsign	
mx.symbol.sort	
mx.symbol.space_to_depth	
mx.symbol.SpatialTransformer	
mx.symbol.split	
mx.symbol.sqrt	
mx.symbol.square	
mx.symbol.squeeze	
mx.symbol.stack	
mx.symbol.stop_gradient	
mx.symbol.sum	
mx.symbol.sum_axis	
mx.symbol.SVMOutput	
mx.symbol.swapaxes	
mx.symbol.SwapAxis	
mx.symbol.take	
mx.symbol.tan	
mx.symbol.tanh	
mx.symbol.tile	
mx.symbol.topk	
mx.symbol.transpose	
mx.symbol.trunc	
mx.symbol.uniform	
mx.symbol.unravel_index	
mx.symbol.UpSampling	
mx.symbol.Variable	
mx.symbol.where	
mx.symbol.zeros_like	
mx.unserialize	505

arguments 15

mxnet					 												
mxnet.export					 												
Ops.MXNDArray .					 												
outputs					 												
predict.MXFeedFor	ward]	Mo	del		 												
print.MXNDArray					 												
rnn.graph					 												
rnn.graph.unroll					 												

510

arguments

Index

Get the arguments of symbol.

Description

Get the arguments of symbol.

Usage

```
arguments(x)
```

Arguments

Х

The input symbol

as.array.MXNDArray

as.array operator overload of mx.ndarray

Description

as.array operator overload of mx.ndarray

Usage

```
## S3 method for class 'MXNDArray'
as.array(nd)
```

Arguments

nd

The mx.ndarray

16 ctx

as.matrix.MXNDArray

as.matrix operator overload of mx.ndarray

Description

as.matrix operator overload of mx.ndarray

Usage

```
## S3 method for class 'MXNDArray'
as.matrix(nd)
```

Arguments

nd

The mx.ndarray

children

Gets a new grouped symbol whose output contains inputs to output nodes of the original symbol.

Description

Gets a new grouped symbol whose output contains inputs to output nodes of the original symbol.

Usage

```
children(x)
```

Arguments

Х

The input symbol

ctx

Get the context of mx.ndarray

Description

Get the context of mx.ndarray

Usage

ctx(nd)

Arguments

nd

The mx.ndarray

dim.MXNDArray 17

dim.MXNDArray

Dimension operator overload of mx.ndarray

Description

Dimension operator overload of mx.ndarray

Usage

```
## S3 method for class 'MXNDArray'
dim(nd)
```

Arguments

nd

The mx.ndarray

graph.viz

Convert symbol to Graphviz or visNetwork visualisation.

Description

Convert symbol to Graphviz or visNetwork visualisation.

Usage

```
graph.viz(symbol, shape = NULL, direction = "TD", type = "graph",
  graph.width.px = NULL, graph.height.px = NULL)
```

Arguments

symbol a string representing the symbol of a model.

shape a numeric representing the input dimensions to the symbol.

direction a string representing the direction of the graph, either TD or LR.

type a string representing the rendering engine of the graph, either graph or vis.

 ${\tt graph.width.px} \ \ a \ {\tt numeric} \ {\tt representing} \ the \ size \ (width) \ of \ the \ {\tt graph}. \ In \ pixels$

graph.height.px

a numeric representing the size (height) of the graph. In pixels

Value

a graph object ready to be displayed with the print function.

im2rec

:2	Comment in a series in the immediate of the formal	
im2rec	Convert images into image recordio format	

Description

Convert images into image recordio format

Usage

```
im2rec(image_lst, root, output_rec, label_width = 1L, pack_label = 0L,
  new_size = -1L, nsplit = 1L, partid = 0L, center_crop = 0L,
  quality = 95L, color_mode = 1L, unchanged = 0L,
  inter_method = 1L, encoding = ".jpg")
```

Arguments

image_lst	The image lst file
root	The root folder for image files
output_rec	The output rec file
label_width	The label width in the list file. Default is 1.
pack_label	Whether to also pack multi dimenional label in the record file. Default is 0.
new_size	The shorter edge of image will be resized to the newsize. Original images will be packed by default.
nsplit	It is used for part generation, logically split the image.lst to NSPLIT parts by position. Default is 1.
partid	It is used for part generation, pack the images from the specific part in image.lst. Default is 0.
center_crop	Whether to crop the center image to make it square. Default is 0.
quality	JPEG quality for encoding (1-100, default: 95) or PNG compression for encoding (1-9, default: 3).
color_mode	Force color (1), gray image (0) or keep source unchanged (-1). Default is 1.
unchanged	Keep the original image encoding, size and color. If set to 1, it will ignore the others parameters.
inter_method	NN(0), BILINEAR(1), CUBIC(2), AREA(3), LANCZOS4(4), AUTO(9), RAND(10). Default is 1.
encoding	The encoding type for images. It can be '.jpg' or '.png'. Default is '.jpg'.

internals 19

internals

Get a symbol that contains all the internals

Description

Get a symbol that contains all the internals

Usage

```
internals(x)
```

Arguments

Χ

The input symbol

is.mx.context

Check if the type is mxnet context.

Description

Check if the type is mxnet context.

Usage

```
is.mx.context(x)
```

Value

Logical indicator

is.mx.dataiter

Judge if an object is mx.dataiter

Description

Judge if an object is mx.dataiter

Usage

```
is.mx.dataiter(x)
```

Value

Logical indicator

20 is.mx.symbol

is.mx.ndarray

Check if src.array is mx.ndarray

Description

Check if src.array is mx.ndarray

Usage

```
is.mx.ndarray(src.array)
```

Value

Logical indicator

Examples

```
mat = mx.nd.array(1:10)
is.mx.ndarray(mat)
mat2 = 1:10
is.mx.ndarray(mat2)
```

is.mx.symbol

Judge if an object is mx.symbol

Description

Judge if an object is mx.symbol

Usage

```
is.mx.symbol(x)
```

Value

Logical indicator

is.serialized 21

is.serialized

Check if the model has been serialized into RData-compatiable format.

Description

Check if the model has been serialized into RData-compatiable format.

Usage

```
is.serialized(model)
```

Value

Logical indicator

length.MXNDArray

Length operator overload of mx.ndarray

Description

Length operator overload of mx.ndarray

Usage

```
## S3 method for class 'MXNDArray'
length(nd)
```

Arguments

nd

The mx.ndarray

mx.apply

Apply symbol to the inputs.

Description

Apply symbol to the inputs.

Usage

```
mx.apply(x, ...)
```

Arguments

x The symbol to be applied

kwargs The keyword arguments to the symbol

mx.callback.early.stop

Early stop with different conditions

Description

Early stopping applying different conditions: hard thresholds or epochs number from the best score. Tested with "epoch.end.callback" function.

Usage

```
mx.callback.early.stop(train.metric = NULL, eval.metric = NULL,
bad.steps = NULL, maximize = FALSE, verbose = FALSE)
```

Arguments

train.metric	Numeric. Hard threshold for the metric of the training data set (optional)
eval.metric	Numeric. Hard threshold for the metric of the evaluating data set (if set, optional)
bad.steps	Integer. How much epochs should gone from the best score? Use this option with evaluation data set
maximize	Logical. Do your model use maximizing or minimizing optimization?

verbose Logical

mx.callback.log.speedometer

Calculate the training speed

Description

Calculate the training speed

Usage

```
mx.callback.log.speedometer(batch.size, frequency = 50)
```

Arguments

frequency The frequency of the training speed update

batch_size The batch size

```
mx.callback.log.train.metric
```

Log training metric each period

Description

Log training metric each period

Usage

```
mx.callback.log.train.metric(period, logger = NULL)
```

Arguments

period The number of batch to log the training evaluation metric

logger The logger class

mx.callback.save.checkpoint

Save checkpoint to files each period iteration.

Description

Save checkpoint to files each period iteration.

Usage

```
mx.callback.save.checkpoint(prefix, period = 1)
```

Arguments

prefix The prefix of the model checkpoint.

24 mx.exec.backward

mx.cpu

Create a mxnet CPU context.

Description

Create a mxnet CPU context.

Arguments

dev.id

optional, default=0 The device ID, this is meaningless for CPU, included for interface compatibility.

Value

The CPU context.

mx.ctx.default

Set/Get default context for array creation.

Description

Set/Get default context for array creation.

Usage

```
mx.ctx.default(new = NULL)
```

Arguments

new

optional takes mx.cpu() or mx.gpu(id), new default ctx.

Value

The default context.

mx.exec.backward

Peform an backward on the executors This function will MUTATE the state of exec

Description

Peform an backward on the executors This function will MUTATE the state of exec

Usage

```
mx.exec.backward(exec, ...)
```

mx.exec.forward 25

mx.exec.forward Peform an fo state of exec	ard on the executors This function will MUTATE the
---	--

Description

Peform an forward on the executors This function will MUTATE the state of exec

Usage

```
mx.exec.forward(exec, is.train = TRUE)
```

```
mx.exec.update.arg.arrays
```

Update the executors with new arrays This function will MUTATE the state of exec

Description

Update the executors with new arrays This function will MUTATE the state of exec

Usage

```
mx.exec.update.arg.arrays(exec, arg.arrays, match.name = FALSE,
    skip.null = FALSE)
```

```
mx.exec.update.aux.arrays
```

Update the executors with new arrays This function will MUTATE the state of exec

Description

Update the executors with new arrays This function will MUTATE the state of exec

Usage

```
mx.exec.update.aux.arrays(exec, arg.arrays, match.name = FALSE,
    skip.null = FALSE)
```

26 mx.infer.rnn

```
mx.exec.update.grad.arrays
```

Update the executors with new arrays This function will MUTATE the state of exec

Description

Update the executors with new arrays This function will MUTATE the state of exec

Usage

```
mx.exec.update.grad.arrays(exec, arg.arrays, match.name = FALSE,
    skip.null = FALSE)
```

mx.gpu

Create a mxnet GPU context.

Description

Create a mxnet GPU context.

Arguments

dev.id

optional, default=0 The GPU device ID, starts from 0.

Value

The GPU context.

mx.infer.rnn

Inference of RNN model

Description

Inference of RNN model

Usage

```
mx.infer.rnn(infer.data, model, ctx = mx.cpu())
```

Arguments

infer.data DataIter

model Model used for inference

ctx

mx.infer.rnn.one 27

mx.infer.rnn.one

Inference for one-to-one fusedRNN (CUDA) models

Description

Inference for one-to-one fusedRNN (CUDA) models

Usage

```
mx.infer.rnn.one(infer.data, symbol, arg.params, aux.params,
input.params = NULL, ctx = mx.cpu())
```

Arguments

infer.data

Data iterator created by mx.io.bucket.iter

symbol

Symbol used for inference

ctx

mx.infer.rnn.one.unroll

Inference for one-to-one unroll models

Description

Inference for one-to-one unroll models

Usage

```
mx.infer.rnn.one.unroll(infer.data, symbol, num_hidden, arg.params,
  aux.params, init_states = NULL, ctx = mx.cpu())
```

Arguments

infer.data NDArray

symbol Model used for inference

num_hidden

ctx

28 mx.init.internal.default

mx.init.create

Create initialization of argument like arg.array

Description

Create initialization of argument like arg.array

Usage

```
mx.init.create(initializer, shape.array, ctx = NULL,
    skip.unknown = TRUE)
```

Arguments

initializer The initializer.

shape.array A named list that represents the shape of the weights

ctx mx.context The context of the weights skip.unknown Whether skip the unknown weight types

mx.init.internal.default

Internal default value initialization scheme.

Description

Internal default value initialization scheme.

Usage

```
mx.init.internal.default(name, shape, ctx, allow.unknown = FALSE)
```

Arguments

name the name of the variable.

shape the shape of the array to be generated.

mx.init.normal 29

mx.init.normal

Create a initializer that initialize the weight with normal(0, sd)

Description

Create a initializer that initialize the weight with normal(0, sd)

Usage

```
mx.init.normal(sd)
```

Arguments

sd

The standard deviation of normal distribution

mx.init.uniform

Create a initializer that initialize the weight with uniform [-scale, scale]

Description

Create a initializer that initialize the weight with uniform [-scale, scale]

Usage

```
mx.init.uniform(scale)
```

Arguments

scale

The scale of uniform distribution

mx.init.Xavier

Xavier initializer

Description

Create a initializer which initialize weight with Xavier or similar initialization scheme.

Usage

```
mx.init.Xavier(rnd_type = "uniform", factor_type = "avg",
  magnitude = 3)
```

30 mx.io.bucket.iter

Arguments

rnd_type A string of character indicating the type of distribution from which the weights

are initialized.

factor_type A string of character.

magnitude A numeric number indicating the scale of random number range.

mx.io.arrayiter

Create MXDataIter compatible iterator from R's array

Description

Create MXDataIter compatible iterator from R's array

Usage

```
mx.io.arrayiter(data, label, batch.size = 128, shuffle = FALSE)
```

Arguments

data The data array.

label The label array.

batch.size The batch size used to pack the array.

shuffle Whether shuffle the data

mx.io.bucket.iter

Create Bucket Iter

Description

Create Bucket Iter

Usage

```
mx.io.bucket.iter(buckets, batch.size, data.mask.element = 0,
    shuffle = FALSE, seed = 123)
```

Arguments

buckets The data array.

batch.size The batch size used to pack the array.

data.mask.element

The element to mask

shuffle Whether shuffle the data

seed The random seed

mx.io.CSVIter 31

mx.io.CSVIter	Returns the CSV file iterator.	
---------------	--------------------------------	--

Description

In this function, the 'data_shape' parameter is used to set the shape of each line of the input data. If a row in an input file is '1,2,3,4,5,6" and 'data_shape' is (3,2), that row will be reshaped, yielding the array [[1,2],[3,4],[5,6]] of shape (3,2).

Usage

```
mx.io.CSVIter(...)
```

Arguments

data.csv	string, required The input CSV file or a directory path.
data.shape	Shape(tuple), required The shape of one example.
label.csv	string, optional, default='NULL' The input CSV file or a directory path. If NULL, all labels will be returned as 0.
label.shape	Shape(tuple), optional, default=[1] The shape of one label.
batch.size	int (non-negative), required Batch size.
round.batch	boolean, optional, default=1 Whether to use round robin to handle overflow batch or not.
prefetch.buffe	r
	long (non-negative), optional, default=4 Maximum number of batches to prefetch.
ctx	'cpu', 'gpu',optional, default='gpu' Context data loader optimized for.
dtype	None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, default='None' Output data type. "None" means no change.

Details

By default, the 'CSVIter' has 'round_batch' parameter set to "True". So, if 'batch_size' is 3 and there are 4 total rows in CSV file, 2 more examples are consumed at the first round. If 'reset' function is called after first round, the call is ignored and remaining examples are returned in the second round.

If one wants all the instances in the second round after calling 'reset', make sure to set 'round_batch' to False.

If "data_csv = 'data/'" is set, then all the files in this directory will be read.

"reset()" is expected to be called only after a complete pass of data.

By default, the CSVIter parses all entries in the data file as float32 data type, if 'dtype' argument is set to be 'int32' or 'int64' then CSVIter will parse all entries in the file as int32 or int64 data type accordingly.

Examples::

32 mx.io.extract

```
// Contents of CSV file "data/data.csv". 1,2,3 2,3,4 3,4,5 4,5,6
// Creates a 'CSVIter' with 'batch_size'=2 and default 'round_batch'=True. CSVIter = mx.io.CSVIter(data_csv
= 'data/data.csv', data_shape = (3,), batch_size = 2)
// Two batches read from the above iterator are as follows: [[ 1. 2. 3.] [ 2. 3. 4.]] [[ 3. 4. 5.] [ 4. 5.
6.]]
// Creates a 'CSVIter' with default 'round_batch' set to True. CSVIter = mx.io.CSVIter(data_csv =
'data/data.csv', data_shape = (3,), batch_size = 3)
// Two batches read from the above iterator in the first pass are as follows: [[1. 2. 3.] [2. 3. 4.] [3.
4. 5.]]
[[4. 5. 6.] [1. 2. 3.] [2. 3. 4.]]
// Now, 'reset' method is called. CSVIter.reset()
// Batch read from the above iterator in the second pass is as follows: [[ 3. 4. 5.] [ 4. 5. 6.] [ 1. 2.
3.]]
// Creates a 'CSVIter' with 'round_batch'=False. CSVIter = mx.io.CSVIter(data_csv = 'data/data.csv',
data_shape = (3,), batch_size = 3, round_batch=False)
// Contents of two batches read from the above iterator in both passes, after calling // 'reset' method
before second pass, is as follows: [[1. 2. 3.] [2. 3. 4.] [3. 4. 5.]]
[[4. 5. 6.] [2. 3. 4.] [3. 4. 5.]]
// Creates a 'CSVIter' with 'dtype'='int32' CSVIter = mx.io.CSVIter(data_csv = 'data/data.csv',
data_shape = (3,), batch_size = 3, round_batch=False, dtype='int32')
// Contents of two batches read from the above iterator in both passes, after calling // 'reset' method
before second pass, is as follows: [[1 2 3] [2 3 4] [3 4 5]]
[[4 5 6] [2 3 4] [3 4 5]]
Defined in src/io/iter_csv.cc:L308
```

Value

iter The result mx.dataiter

mx.io.extract

Extract a certain field from DataIter.

Description

Extract a certain field from DataIter.

Usage

```
mx.io.extract(iter, field)
```

 ${\tt mx.io.ImageDetRecordIter}$

Create iterator for image detection dataset packed in recordio.

Description

Create iterator for image detection dataset packed in recordio.

Usage

```
mx.io.ImageDetRecordIter(...)
```

Arguments

shuffle

8					
path.imglist	string, optional, default=" Dataset Param: Path to image list.				
path.imgrec	string, optional, default='./data/imgrec.rec' Dataset Param: Path to image record file.				
aug.seq	string, optional, default='det_aug_default' Augmentation Param: the augmenter names to represent sequence of augmenters to be applied, seperated by comma. Additional keyword parameters will be seen by these augmenters. Make sure you don't use normal augmenters for detection tasks.				
label.width	int, optional, default='-1' Dataset Param: How many labels for an image, -1 for variable label size.				
data.shape	Shape(tuple), required Dataset Param: Shape of each instance generated by the DataIter.				
preprocess.thre	eads				
	int, optional, default='4' Backend Param: Number of thread to do preprocessing.				
verbose	boolean, optional, default=1 Auxiliary Param: Whether to output parser information.				
num.parts	int, optional, default='1' partition the data into multiple parts				
part.index	int, optional, default='0' the index of the part will read				
shuffle.chunk.s	size				
	long (non-negative), optional, default=0 the size(MB) of the shuffle chunk, used with shuffle=True, it can enable global shuffling				
shuffle.chunk.seed					
	int, optional, default='0' the seed for chunk shuffling				
label.pad.width	n				
	int, optional, default='0' pad output label width if set larger than 0, -1 for auto estimate				
label.pad.value	e				
	float, optional, default=-1 label padding value if enabled				

boolean, optional, default=0 Augmentation Param: Whether to shuffle data.

seed int, optional, default='0' Augmentation Param: Random Seed.

batch.size int (non-negative), required Batch size.

round.batch boolean, optional, default=1 Whether to use round robin to handle overflow

batch or not.

prefetch.buffer

long (non-negative), optional, default=4 Maximum number of batches to prefetch.

ctx 'cpu', 'gpu', optional, default='gpu' Context data loader optimized for.

dtype None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, de-

fault='None' Output data type. "None" means no change.

resize int, optional, default='-1' Augmentation Param: scale shorter edge to size before

applying other augmentations, -1 to disable.

rand.crop.prob float, optional, default=0 Augmentation Param: Probability of random cropping,

<= 0 to disable

min.crop.scales

tuple of <float>, optional, default=[0] Augmentation Param: Min crop scales.

max.crop.scales

tuple of <float>, optional, default=[1] Augmentation Param: Max crop scales.

min.crop.aspect.ratios

tuple of <float>, optional, default=[1] Augmentation Param: Min crop aspect

ratios.

max.crop.aspect.ratios

tuple of <float>, optional, default=[1] Augmentation Param: Max crop aspect

ratios.

min.crop.overlaps

tuple of <float>, optional, default=[0] Augmentation Param: Minimum crop

IOU between crop_box and ground-truths.

max.crop.overlaps

tuple of <float>, optional, default=[1] Augmentation Param: Maximum crop

IOU between crop_box and ground-truth.

min.crop.sample.coverages

tuple of <float>, optional, default=[0] Augmentation Param: Minimum ratio of intersect/crop_area between crop box and ground-truths.

max.crop.sample.coverages

tuple of <float>, optional, default=[1] Augmentation Param: Maximum ratio of intersect/crop_area between crop box and ground-truths.

min.crop.object.coverages

tuple of <float>, optional, default=[0] Augmentation Param: Minimum ratio of

intersect/gt_area between crop box and ground-truths.

max.crop.object.coverages

tuple of <float>, optional, default=[1] Augmentation Param: Maximum ratio of intersect/gt area between crop box and ground-truths.

num.crop.sampler

int, optional, default='1' Augmentation Param: Number of crop samplers.

crop.emit.mode 'center', 'overlap',optional, default='center' Augmentation Param: Emition mode for invalid ground-truths after crop. center: emit if centroid of object is out of

crop region; overlap: emit if overlap is less than emit_overlap_thresh.

emit.overlap.thresh

float, optional, default=0.300000012 Augmentation Param: Emit overlap thresh for emit mode overlap only.

max.crop.trials

Shape(tuple), optional, default=[25] Augmentation Param: Skip cropping if fail crop trail count exceeds this number.

rand.pad.prob float, optional, default=0 Augmentation Param: Probability for random padding.

max.pad.scale float, optional, default=1 Augmentation Param: Maximum padding scale.

max.random.hue int, optional, default='0' Augmentation Param: Maximum random value of H channel in HSL color space.

random.hue.prob

float, optional, default=0 Augmentation Param: Probability to apply random hue.

max.random.saturation

int, optional, default='0' Augmentation Param: Maximum random value of S channel in HSL color space.

random.saturation.prob

float, optional, default=0 Augmentation Param: Probability to apply random saturation.

max.random.illumination

int, optional, default='0' Augmentation Param: Maximum random value of L channel in HSL color space.

random.illumination.prob

float, optional, default=0 Augmentation Param: Probability to apply random illumination.

max.random.contrast

float, optional, default=0 Augmentation Param: Maximum random value of delta contrast.

random.contrast.prob

float, optional, default=0 Augmentation Param: Probability to apply random contrast.

rand.mirror.prob

float, optional, default=0 Augmentation Param: Probability to apply horizontal flip aka. mirror.

fill.value int, optional, default='127' Augmentation Param: Filled color value while padding.

inter.method int, optional, default='1' Augmentation Param: 0-NN 1-bilinear 2-cubic 3-area 4-lanczos4 9-auto 10-rand.

data. shape Shape(tuple), required Dataset Param: Shape of each instance generated by the DataIter.

'fit', 'force', 'shrink',optional, default='force' Augmentation Param: How image data fit in data_shape. force: force reshape to data_shape regardless of aspect ratio; shrink: ensure each side fit in data shape, preserve aspect ratio; fit:

fit image to data_shape, preserve ratio, will upscale if applicable.

mean.img string, optional, default=" Augmentation Param: Mean Image to be subtracted.

mean.r float, optional, default=0 Augmentation Param: Mean value on R channel.

mean.g	float, optional, default=0 Augmentation Param: Mean value on G channel.
mean.b	float, optional, default=0 Augmentation Param: Mean value on B channel.
mean.a	float, optional, default=0 Augmentation Param: Mean value on Alpha channel.
std.r	float, optional, default= 0 Augmentation Param: Standard deviation on R channel.
std.g	float, optional, default=0 Augmentation Param: Standard deviation on G channel.
std.b	float, optional, default=0 Augmentation Param: Standard deviation on B channel.
std.a	float, optional, default=0 Augmentation Param: Standard deviation on Alpha channel.
scale	float, optional, default=1 Augmentation Param: Scale in color space.

Value

iter The result mx.dataiter

mx.io.ImageRecordInt8Iter

Iterating on image RecordIO files

Description

 $..\ note:: ``ImageRecordInt8Iter'` is \ deprecated. \ Use \ ImageRecordIter(dtype='int8') \ instead.$

Usage

```
mx.io.ImageRecordInt8Iter(...)
```

Arguments

path.imglist	string, optional, default=" Path to the image list (.lst) file. Generally created with tools/im2rec.py. Format (Tab separated): <index of="" record=""> <one labels="" more="" or=""> <relative folder="" from="" path="" root="">.</relative></one></index>
path.imgrec	string, optional, default=" Path to the image RecordIO (.rec) file or a directory path. Created with tools/im2rec.py.
path.imgidx	string, optional, default=" Path to the image RecordIO index (.idx) file. Created with tools/im2rec.py.
aug.seq	string, optional, default='aug_default' The augmenter names to represent sequence of augmenters to be applied, seperated by comma. Additional keyword parameters will be seen by these augmenters.
label.width	int, optional, default='1' The number of labels per image.
data.shape	Shape(tuple), required The shape of one output image in (channels, height, width) format.

preprocess. threads

int, optional, default='4' The number of threads to do preprocessing.

verbose boolean, optional, default=1 If or not output verbose information.

num.parts int, optional, default='1' Virtually partition the data into these many parts.

part.index int, optional, default='0' The *i*-th virtual partition to be read.

device.id int, optional, default='0' The device id used to create context for internal NDAr-

ray. Setting device_id to -1 will create Context::CPU(0). Setting device_id to valid positive device id will create Context::CPUPinned(device_id). Default is

0.

shuffle.chunk.size

long (non-negative), optional, default=0 The data shuffle buffer size in MB. Only

valid if shuffle is true.

shuffle.chunk.seed

int, optional, default='0' The random seed for shuffling

seed. aug int or None, optional, default='None' Random seed for augmentations. shuffle boolean, optional, default=0 Whether to shuffle data randomly or not.

seed int, optional, default='0' The random seed. batch.size int (non-negative), required Batch size.

round.batch boolean, optional, default=1 Whether to use round robin to handle overflow

batch or not.

prefetch.buffer

long (non-negative), optional, default=4 Maximum number of batches to prefetch.

ctx 'cpu', 'gpu', optional, default='gpu' Context data loader optimized for.

dtype None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, de-

fault='None' Output data type. "None" means no change.

resize int, optional, default='-1' Down scale the shorter edge to a new size before

applying other augmentations.

rand.crop boolean, optional, default=0 If or not randomly crop the image

random.resized.crop

boolean, optional, default=0 If or not perform random resized cropping on the

image, as a standard preprocessing for resnet training on ImageNet data.

max.rotate.angle

int, optional, default='0' Rotate by a random degree in "[-v, v]"

max.aspect.ratio

float, optional, default=0 Change the aspect (namely width/height) to a random value. If min_aspect_ratio is None then the aspect ratio ins sampled from [1 - max_aspect_ratio, 1 + max_aspect_ratio], else it is in "[min_aspect_ratio,

max aspect ratio]"

min.aspect.ratio

float or None, optional, default=None Change the aspect (namely width/height) to a random value in "[min_aspect_ratio, max_aspect_ratio]"

max.shear.ratio

float, optional, default=0 Apply a shear transformation (namely "(x,y)->(x+my,y)") with "m" randomly chose from "[-max_shear_ratio, max_shear_ratio]"

int, optional, default='-1' Crop both width and height into a random size in max.crop.size "[min_crop_size, max_crop_size]. "Ignored if "random_resized_crop" is True.

int, optional, default='-1' Crop both width and height into a random size in min.crop.size "[min_crop_size, max_crop_size]. "Ignored if "random_resized_crop" is True.

max.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min_random_scale, max_random_scale]". Ignored if "random_resized_crop" is True.

min.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min random scale, max random scale]"Ignored if "random resized crop" is True.

max.random.area

float, optional, default=1 Change the area (namely width * height) to a random value in "[min random area, max random area]". Ignored if "random resized crop" is False.

min.random.area

saturation

float, optional, default=1 Change the area (namely width * height) to a random value in "[min_random_area, max_random_area]". Ignored if "random_resized_crop" is False.

float, optional, default=1e+10 Set the maximal width and height after all resize max.img.size and rotate argumentation are applied

min.img.size float, optional, default=0 Set the minimal width and height after all resize and rotate argumentation are applied

brightness float, optional, default=0 Add a random value in "[-brightness, brightness]" to the brightness of image.

float, optional, default=0 Add a random value in "[-contrast, contrast]" to the contrast contrast of image.

> float, optional, default=0 Add a random value in "[-saturation, saturation]" to the saturation of image.

pca.noise float, optional, default=0 Add PCA based noise to the image.

int, optional, default='0' Add a random value in "[-random_h, random_h]" to random.h the H channel in HSL color space.

int, optional, default='0' Add a random value in "[-random_s, random_s]" to random.s the S channel in HSL color space.

random.1 int, optional, default='0' Add a random value in "[-random_1, random_1]" to the

L channel in HSL color space.

int, optional, default='-1' Rotate by an angle. If set, it overwrites the "max_rotate_angle" rotate

option.

int, optional, default='255' Set the padding pixels value to "fill_value". fill.value

Shape(tuple), required The shape of a output image. data.shape

inter.method int, optional, default='1' The interpolation method: 0-NN 1-bilinear 2-cubic

3-area 4-lanczos4 9-auto 10-rand.

pad int, optional, default='0' Change size from "[width, height]" into "[pad + width

+ pad, pad + height + pad]" by padding pixes

Details

This iterator is identical to "ImageRecordIter" except for using "int8" as the data type instead of "float".

Defined in src/io/iter_image_recordio_2.cc:L941

Value

iter The result mx.dataiter

mx.io.ImageRecordIter Iterates on image RecordIO files

Usage

```
mx.io.ImageRecordIter(...)
```

Arguments

path.imglist

	pa282200	with tools/im2rec.py. Format (Tab separated): <index of="" record=""> <one labels="" more="" or=""> <relative folder="" from="" path="" root="">.</relative></one></index>
	path.imgrec	string, optional, default=" Path to the image RecordIO (.rec) file or a directory path. Created with tools/im2rec.py.
	path.imgidx	string, optional, default=" Path to the image RecordIO index (.idx) file. Created with tools/im2rec.py.
	aug.seq	string, optional, default='aug_default' The augmenter names to represent sequence of augmenters to be applied, seperated by comma. Additional keyword parameters will be seen by these augmenters.
	label.width	int, optional, default='1' The number of labels per image.
	data.shape	Shape(tuple), required The shape of one output image in (channels, height, width) format.
preprocess.threads		
		int, optional, default='4' The number of threads to do preprocessing.
	verbose	boolean, optional, default=1 If or not output verbose information.
	num.parts	int, optional, default='1' Virtually partition the data into these many parts.
	part.index	int, optional, default='0' The *i*-th virtual partition to be read.
	device.id	int, optional, default='0' The device id used to create context for internal NDArray. Setting device_id to -1 will create Context::CPU(0). Setting device_id to valid positive device id will create Context::CPUPinned(device_id). Default is 0.
	shuffle.chunk.size	

shuffle.chunk.size

long (non-negative), optional, default=0 The data shuffle buffer size in MB. Only valid if shuffle is true.

string, optional, default=" Path to the image list (.lst) file. Generally created

shuffle.chunk.seed

int, optional, default='0' The random seed for shuffling

seed. aug int or None, optional, default='None' Random seed for augmentations. shuffle boolean, optional, default=0 Whether to shuffle data randomly or not.

seed int, optional, default='0' The random seed.

batch.size int (non-negative), required Batch size.

round.batch boolean, optional, default=1 Whether to use round robin to handle overflow

batch or not.

prefetch.buffer

long (non-negative), optional, default=4 Maximum number of batches to prefetch.

ctx 'cpu', 'gpu', optional, default='gpu' Context data loader optimized for.

dtype None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, de-

fault='None' Output data type. "None" means no change.

resize int, optional, default='-1' Down scale the shorter edge to a new size before

applying other augmentations.

rand.crop boolean, optional, default=0 If or not randomly crop the image

random.resized.crop

boolean, optional, default=0 If or not perform random resized cropping on the image, as a standard preprocessing for resnet training on ImageNet data.

max.rotate.angle

int, optional, default='0' Rotate by a random degree in "[-v, v]"

max.aspect.ratio

float, optional, default=0 Change the aspect (namely width/height) to a random value. If min_aspect_ratio is None then the aspect ratio ins sampled from [1 - max_aspect_ratio, 1 + max_aspect_ratio], else it is in "[min_aspect_ratio, max_aspect_ratio]"

min.aspect.ratio

float or None, optional, default=None Change the aspect (namely width/height) to a random value in "[min_aspect_ratio, max_aspect_ratio]"

max.shear.ratio

float, optional, default=0 Apply a shear transformation (namely "(x,y)->(x+my,y)") with "m" randomly chose from "[-max_shear_ratio, max_shear_ratio]"

max.crop.size int, optional, default='-1' Crop both width and height into a random size in "[min_crop_size, max_crop_size]."Ignored if "random_resized_crop" is True.

min.crop.size int, optional, default='-1' Crop both width and height into a random size in "[min_crop_size, max_crop_size]."Ignored if "random_resized_crop" is True.

max.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min_random_scale, max_random_scale]". Ignored if "random_resized_crop" is True.

min.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min_random_scale, max_random_scale]"Ignored if "random_resized_crop" is True.

max.random.area

float, optional, default=1 Change the area (namely width * height) to a random value in "[min_random_area, max_random_area]". Ignored if "random_resized_crop" is False.

min.random.area

float, optional, default=1 Change the area (namely width * height) to a random value in "[min_random_area, max_random_area]". Ignored if "random_resized_crop" is False.

max.img.size float, optional, default=1e+10 Set the maximal width and height after all resize

and rotate argumentation are applied

min.img.size float, optional, default=0 Set the minimal width and height after all resize and

rotate argumentation are applied

brightness float, optional, default=0 Add a random value in "[-brightness, brightness]" to

the brightness of image.

contrast float, optional, default=0 Add a random value in "[-contrast, contrast]" to the

contrast of image.

saturation float, optional, default=0 Add a random value in "[-saturation, saturation]" to

the saturation of image.

pca.noise float, optional, default=0 Add PCA based noise to the image.

random.h int, optional, default='0' Add a random value in "[-random h, random h]" to

the H channel in HSL color space.

random.s int, optional, default='0' Add a random value in "[-random_s, random_s]" to

the S channel in HSL color space.

random. 1 int, optional, default='0' Add a random value in "[-random_l, random_l]" to the

L channel in HSL color space.

rotate int, optional, default='-1' Rotate by an angle. If set, it overwrites the "max_rotate_angle"

option.

fill.value int, optional, default='255' Set the padding pixels value to "fill_value".

data. shape Shape(tuple), required The shape of a output image.

inter.method int, optional, default='1' The interpolation method: 0-NN 1-bilinear 2-cubic

3-area 4-lanczos4 9-auto 10-rand.

pad int, optional, default='0' Change size from "[width, height]" into "[pad + width

+ pad, pad + height + pad]" by padding pixes

mirror boolean, optional, default=0 Whether to mirror the image or not. If true, images

are flipped along the horizontal axis.

rand.mirror boolean, optional, default=0 Whether to randomly mirror images or not. If true,

50

\itemmean.imgstring, optional, default="Filename of the mean image.

\itemmean.rfloat, optional, default=0 The mean value to be subtracted on the R

channel

\itemmean.gfloat, optional, default=0 The mean value to be subtracted on the G

channel

\itemmean.bfloat, optional, default=0 The mean value to be subtracted on the B

channel

\itemmean.afloat, optional, default=0 The mean value to be subtracted on the alpha channel

\itemstd.rfloat, optional, default=1 Augmentation Param: Standard deviation on R channel.

\itemstd.gfloat, optional, default=1 Augmentation Param: Standard deviation on G channel.

\itemstd.bfloat, optional, default=1 Augmentation Param: Standard deviation on B channel.

\itemstd.afloat, optional, default=1 Augmentation Param: Standard deviation on Alpha channel.

\itemscalefloat, optional, default=1 Multiply the image with a scale value.

\itemmax.random.contrastfloat, optional, default=0 Change the contrast with a value randomly chosen from "[-max_random_contrast, max_random_contrast]"

\itemmax.random.illuminationfloat, optional, default=0 Change the illumination with a value randomly chosen from "[-max_random_illumination, max_random_illumination]" iter The result mx.dataiter

Reads batches of images from .rec RecordIO files. One can use "im2rec.py" tool (in tools/) to pack raw image files into RecordIO files. This iterator is less flexible to customization but is fast and has lot of language bindings. To iterate over raw images directly use "ImageIter" instead (in Python).

Example::

data_iter = mx.io.ImageRecordIter(path_imgrec="./sample.rec", # The target record file. data_shape=(3, 227, 227), # Output data shape; 227x227 region will be cropped from the original image. batch_size=4, # Number of items per batch. resize=256 # Resize the shorter edge to 256 before cropping. # You can specify more augmentation options. Use help(mx.io.ImageRecordIter) to see all the options.) # You can now use the data_iter to access batches of images. batch = data_iter.next() # first batch. images = batch.data[0] # This will contain 4 (=batch_size) images each of 3x227x227. # process the images ... data_iter.reset() # To restart the iterator from the beginning.

Defined in src/io/iter_image_recordio_2.cc:L904

mx.io.ImageRecordIter_v1

Iterating on image RecordIO files

Usage

```
mx.io.ImageRecordIter_v1(...)
```

Arguments

path.imglist

string, optional, default=" Path to the image list (.lst) file. Generally created with tools/im2rec.py. Format (Tab separated): <index of record> <one or more labels> <relative path from root folder>.

path.imgrec string, optional, default="Path to the image RecordIO (.rec) file or a directory

path. Created with tools/im2rec.py.

path.imgidx string, optional, default="Path to the image RecordIO index (.idx) file. Created

with tools/im2rec.py.

aug.seq string, optional, default='aug_default' The augmenter names to represent se-

quence of augmenters to be applied, seperated by comma. Additional keyword

parameters will be seen by these augmenters.

label.width int, optional, default='1' The number of labels per image.

data.shape Shape(tuple), required The shape of one output image in (channels, height,

width) format.

preprocess.threads

int, optional, default='4' The number of threads to do preprocessing.

verbose boolean, optional, default=1 If or not output verbose information.

num.parts int, optional, default='1' Virtually partition the data into these many parts.

part.index int, optional, default='0' The *i*-th virtual partition to be read.

device.id int, optional, default='0' The device id used to create context for internal NDAr-

ray. Setting device_id to -1 will create Context::CPU(0). Setting device_id to valid positive device id will create Context::CPUPinned(device_id). Default is

0.

shuffle.chunk.size

long (non-negative), optional, default=0 The data shuffle buffer size in MB. Only

valid if shuffle is true.

shuffle.chunk.seed

int, optional, default='0' The random seed for shuffling

seed.aug int or None, optional, default='None' Random seed for augmentations. shuffle boolean, optional, default=0 Whether to shuffle data randomly or not.

seed int, optional, default='0' The random seed.

batch.size int (non-negative), required Batch size.

round.batch boolean, optional, default=1 Whether to use round robin to handle overflow

batch or not.

prefetch.buffer

long (non-negative), optional, default=4 Maximum number of batches to prefetch.

ctx 'cpu', 'gpu', optional, default='gpu' Context data loader optimized for.

dtype None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, de-

fault='None' Output data type. "None" means no change.

resize int, optional, default='-1' Down scale the shorter edge to a new size before

applying other augmentations.

rand.crop boolean, optional, default=0 If or not randomly crop the image

random.resized.crop

boolean, optional, default=0 If or not perform random resized cropping on the image, as a standard preprocessing for resnet training on ImageNet data.

max.rotate.angle

int, optional, default='0' Rotate by a random degree in "[-v, v]"

max.aspect.ratio

float, optional, default=0 Change the aspect (namely width/height) to a random value. If min_aspect_ratio is None then the aspect ratio ins sampled from [1 - max_aspect_ratio, 1 + max_aspect_ratio], else it is in "[min_aspect_ratio, max_aspect_ratio]"

min.aspect.ratio

float or None, optional, default=None Change the aspect (namely width/height) to a random value in "[min_aspect_ratio, max_aspect_ratio]"

max.shear.ratio

float, optional, default=0 Apply a shear transformation (namely "(x,y)->(x+my,y)") with "m" randomly chose from "[-max_shear_ratio, max_shear_ratio]"

max.crop.size int, optional, default='-1' Crop both width and height into a random size in "[min_crop_size, max_crop_size]."Ignored if "random_resized_crop" is True.

min.crop.size int, optional, default='-1' Crop both width and height into a random size in "[min_crop_size, max_crop_size]."Ignored if "random_resized_crop" is True.

max.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min_random_scale, max_random_scale]". Ignored if "random_resized_crop" is True.

min.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min_random_scale, max_random_scale]"Ignored if "random_resized_crop" is True.

max.random.area

float, optional, default=1 Change the area (namely width * height) to a random value in "[min_random_area, max_random_area]". Ignored if "random_resized_crop" is False.

min.random.area

float, optional, default=1 Change the area (namely width * height) to a random value in "[min_random_area, max_random_area]". Ignored if "random_resized_crop" is False.

max.img.size float, optional, default=1e+10 Set the maximal width and height after all resize and rotate argumentation are applied

min.img.size float, optional, default=0 Set the minimal width and height after all resize and rotate argumentation are applied

brightness float, optional, default=0 Add a random value in "[-brightness, brightness]" to the brightness of image.

contrast float, optional, default=0 Add a random value in "[-contrast, contrast]" to the contrast of image.

saturation float, optional, default=0 Add a random value in "[-saturation, saturation]" to the saturation of image.

pca.noise float, optional, default=0 Add PCA based noise to the image.

random.h int, optional, default='0' Add a random value in "[-random_h, random_h]" to the H channel in HSL color space.

random.s int, optional, default='0' Add a random value in "[-random_s, random_s]" to the S channel in HSL color space.

random. 1 int, optional, default='0' Add a random value in "[-random_l, random_l]" to the

L channel in HSL color space.

rotate int, optional, default='-1' Rotate by an angle. If set, it overwrites the "max_rotate_angle"

option.

fill.value int, optional, default='255' Set the padding pixels value to "fill_value".

data. shape Shape(tuple), required The shape of a output image.

inter.method int, optional, default='1' The interpolation method: 0-NN 1-bilinear 2-cubic

3-area 4-lanczos4 9-auto 10-rand.

pad int, optional, default='0' Change size from "[width, height]" into "[pad + width

+ pad, pad + height + pad]" by padding pixes

mirror boolean, optional, default=0 Whether to mirror the image or not. If true, images

are flipped along the horizontal axis.

rand.mirror boolean, optional, default=0 Whether to randomly mirror images or not. If true,

50

\itemmean.imgstring, optional, default="Filename of the mean image.

\itemmean.rfloat, optional, default=0 The mean value to be subtracted on the R channel

\itemmean.gfloat, optional, default=0 The mean value to be subtracted on the G

\itemmean.bfloat, optional, default=0 The mean value to be subtracted on the B channel

\itemmean.afloat, optional, default=0 The mean value to be subtracted on the alpha channel

\itemstd.rfloat, optional, default=1 Augmentation Param: Standard deviation on R channel.

\itemstd.gfloat, optional, default=1 Augmentation Param: Standard deviation on G channel.

\itemstd.bfloat, optional, default=1 Augmentation Param: Standard deviation on B channel.

\itemstd.afloat, optional, default=1 Augmentation Param: Standard deviation on Alpha channel.

\itemscalefloat, optional, default=1 Multiply the image with a scale value.

\itemmax.random.contrastfloat, optional, default=0 Change the contrast with a value randomly chosen from "[-max_random_contrast, max_random_contrast]"

 $\verb|\titemmax.random.illumination float|, optional|, default=0 Change the illumination$

with a value randomly chosen from "[-max_random_illumination, max_random_illumination]" iter The result mx.dataiter

.. note::

"ImageRecordIter_v1" is deprecated. Use "ImageRecordIter" instead.

Read images batches from RecordIO files with a rich of data augmentation options.

One can use "tools/im2rec.py" to pack individual image files into RecordIO files.

Defined in src/io/iter_image_recordio.cc:L352

$\verb|mx.io.ImageRecordUInt8Iter| \\$

Iterating on image RecordIO files

Description

 $..\ note:: ImageRecordUInt8Iter\ is\ deprecated.\ Use\ ImageRecordIter(dtype='uint8')\ instead.$

Usage

```
mx.io.ImageRecordUInt8Iter(...)
```

Arguments

_	
path.imglist	string, optional, default=" Path to the image list (.lst) file. Generally created with tools/im2rec.py. Format (Tab separated): <index of="" record=""> <one labels="" more="" or=""> <relative folder="" from="" path="" root="">.</relative></one></index>
path.imgrec	string, optional, default=" Path to the image RecordIO (.rec) file or a directory path. Created with tools/im2rec.py.
path.imgidx	string, optional, default=" Path to the image RecordIO index (.idx) file. Created with tools/im2rec.py.
aug.seq	string, optional, default='aug_default' The augmenter names to represent sequence of augmenters to be applied, seperated by comma. Additional keyword parameters will be seen by these augmenters.
label.width	int, optional, default='1' The number of labels per image.
data.shape	Shape(tuple), required The shape of one output image in (channels, height, width) format.
preprocess.thre	eads
	int, optional, default='4' The number of threads to do preprocessing.
verbose	boolean, optional, default=1 If or not output verbose information.
num.parts	int, optional, default='1' Virtually partition the data into these many parts.
part.index	int, optional, default='0' The *i*-th virtual partition to be read.
device.id	int, optional, default='0' The device id used to create context for internal NDArray. Setting device_id to -1 will create Context::CPU(0). Setting device_id to valid positive device id will create Context::CPUPinned(device_id). Default is 0.
shuffle.chunk.	size
	long (non-negative), optional, default=0 The data shuffle buffer size in MB. Only valid if shuffle is true.
shuffle.chunk.s	
	int, optional, default='0' The random seed for shuffling
seed.aug	int or None, optional, default='None' Random seed for augmentations.
shuffle	boolean, optional, default=0 Whether to shuffle data randomly or not.

seed int, optional, default='0' The random seed.

batch.size int (non-negative), required Batch size.

round.batch boolean, optional, default=1 Whether to use round robin to handle overflow

batch or not.

prefetch.buffer

long (non-negative), optional, default=4 Maximum number of batches to prefetch.

ctx 'cpu', 'gpu', optional, default='gpu' Context data loader optimized for.

dtype None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, de-

fault='None' Output data type. "None" means no change.

resize int, optional, default='-1' Down scale the shorter edge to a new size before

applying other augmentations.

rand.crop boolean, optional, default=0 If or not randomly crop the image

random.resized.crop

boolean, optional, default=0 If or not perform random resized cropping on the image, as a standard preprocessing for resnet training on ImageNet data.

max.rotate.angle

int, optional, default='0' Rotate by a random degree in "[-v, v]"

max.aspect.ratio

float, optional, default=0 Change the aspect (namely width/height) to a random value. If min_aspect_ratio is None then the aspect ratio ins sampled from [1 - max_aspect_ratio, 1 + max_aspect_ratio], else it is in "[min_aspect_ratio, max_aspect_ratio]"

min.aspect.ratio

float or None, optional, default=None Change the aspect (namely width/height) to a random value in "[min_aspect_ratio, max_aspect_ratio]"

max.shear.ratio

float, optional, default=0 Apply a shear transformation (namely "(x,y)->(x+my,y)") with "m" randomly chose from "[-max_shear_ratio, max_shear_ratio]"

max.crop.size

int, optional, default='-1' Crop both width and height into a random size in "[min_crop_size, max_crop_size]."Ignored if "random_resized_crop" is True.

min.crop.size

int, optional, default='-1' Crop both width and height into a random size in "[min_crop_size, max_crop_size]."Ignored if "random_resized_crop" is True.

max.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min_random_scale, max_random_scale]". Ignored if "random_resized_crop" is True.

min.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min_random_scale, max_random_scale]"Ignored if "random_resized_crop" is True.

max.random.area

float, optional, default=1 Change the area (namely width * height) to a random value in "[min_random_area, max_random_area]". Ignored if "random_resized_crop" is False.

min.random.area		
	float, optional, default=1 Change the area (namely width * height) to a random value in "[min_random_area, max_random_area]". Ignored if "random_resized_crop" is False.	
max.img.size	float, optional, default=1e+10 Set the maximal width and height after all resize and rotate argumentation are applied	
min.img.size	float, optional, default=0 Set the minimal width and height after all resize and rotate argumentation are applied	
brightness	float, optional, default=0 Add a random value in "[-brightness, brightness]" to the brightness of image.	
contrast	float, optional, default=0 Add a random value in "[-contrast, contrast]" to the contrast of image.	
saturation	float, optional, default=0 Add a random value in "[-saturation, saturation]" to the saturation of image.	
pca.noise	float, optional, default=0 Add PCA based noise to the image.	
random.h	int, optional, default='0' Add a random value in "[-random_h, random_h]" to the H channel in HSL color space.	
random.s	int, optional, default='0' Add a random value in "[-random_s, random_s]" to the S channel in HSL color space.	
random.l	int, optional, default='0' Add a random value in "[-random_l, random_l]" to the L channel in HSL color space.	
rotate	int, optional, default='-1' Rotate by an angle. If set, it overwrites the "max_rotate_angle" option.	
fill.value	int, optional, default='255' Set the padding pixels value to "fill_value".	
data.shape	Shape(tuple), required The shape of a output image.	
inter.method	int, optional, default='1' The interpolation method: 0-NN 1-bilinear 2-cubic 3-area 4-lanczos4 9-auto 10-rand.	
pad	int, optional, default='0' Change size from "[width, height]" into "[pad + width + pad, pad + height + pad]" by padding pixes	

Details

This iterator is identical to "ImageRecordIter" except for using "uint8" as the data type instead of "float".

Defined in src/io/iter_image_recordio_2.cc:L923

Value

iter The result mx.dataiter

mx.io.ImageRecordUInt8Iter_v1

Iterating on image RecordIO files

Description

.. note::

Usage

mx.io.ImageRecordUInt8Iter_v1(...)

Arguments

guments		
path.imglist	string, optional, default=" Path to the image list (.lst) file. Generally created with tools/im2rec.py. Format (Tab separated): <index of="" record=""> <one labels="" more="" or=""> <relative folder="" from="" path="" root="">.</relative></one></index>	
path.imgrec	string, optional, default=" Path to the image RecordIO (.rec) file or a directory path. Created with tools/im2rec.py.	
path.imgidx	string, optional, default=" Path to the image RecordIO index (.idx) file. Created with tools/im2rec.py.	
aug.seq	string, optional, default='aug_default' The augmenter names to represent sequence of augmenters to be applied, seperated by comma. Additional keyword parameters will be seen by these augmenters.	
label.width	int, optional, default='1' The number of labels per image.	
data.shape	Shape(tuple), required The shape of one output image in (channels, height, width) format.	
preprocess.threads		
	int, optional, default='4' The number of threads to do preprocessing.	
verbose	boolean, optional, default=1 If or not output verbose information.	
num.parts	int, optional, default='1' Virtually partition the data into these many parts.	
part.index	int, optional, default='0' The *i*-th virtual partition to be read.	
device.id	int, optional, default='0' The device id used to create context for internal NDArray. Setting device_id to -1 will create Context::CPU(0). Setting device_id to valid positive device id will create Context::CPUPinned(device_id). Default is 0.	
shuffle.chunk.s	size	
	long (non-negative), optional, default=0 The data shuffle buffer size in MB. Only valid if shuffle is true.	
shuffle.chunk.seed		
	int, optional, default='0' The random seed for shuffling	
seed.aug	int or None, optional, default='None' Random seed for augmentations.	
shuffle	boolean, optional, default=0 Whether to shuffle data randomly or not.	

seed int, optional, default='0' The random seed.

batch.size int (non-negative), required Batch size.

round.batch boolean, optional, default=1 Whether to use round robin to handle overflow

batch or not.

prefetch.buffer

long (non-negative), optional, default=4 Maximum number of batches to prefetch.

ctx 'cpu', 'gpu', optional, default='gpu' Context data loader optimized for.

dtype None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, de-

fault='None' Output data type. "None" means no change.

resize int, optional, default='-1' Down scale the shorter edge to a new size before

applying other augmentations.

rand.crop boolean, optional, default=0 If or not randomly crop the image

random.resized.crop

boolean, optional, default=0 If or not perform random resized cropping on the image, as a standard preprocessing for resnet training on ImageNet data.

max.rotate.angle

int, optional, default='0' Rotate by a random degree in "[-v, v]"

max.aspect.ratio

float, optional, default=0 Change the aspect (namely width/height) to a random value. If min_aspect_ratio is None then the aspect ratio ins sampled from [1 - max_aspect_ratio, 1 + max_aspect_ratio], else it is in "[min_aspect_ratio, max_aspect_ratio]"

min.aspect.ratio

float or None, optional, default=None Change the aspect (namely width/height) to a random value in "[min_aspect_ratio, max_aspect_ratio]"

max.shear.ratio

float, optional, default=0 Apply a shear transformation (namely "(x,y)->(x+my,y)") with "m" randomly chose from "[-max_shear_ratio, max_shear_ratio]"

max.crop.size

int, optional, default='-1' Crop both width and height into a random size in "[min_crop_size, max_crop_size]."Ignored if "random_resized_crop" is True.

min.crop.size

int, optional, default='-1' Crop both width and height into a random size in "[min_crop_size, max_crop_size]."Ignored if "random_resized_crop" is True.

max.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min_random_scale, max_random_scale]". Ignored if "random_resized_crop" is True.

min.random.scale

float, optional, default=1 Resize into "[width*s, height*s]" with "s" randomly chosen from "[min_random_scale, max_random_scale]"Ignored if "random_resized_crop" is True.

max.random.area

float, optional, default=1 Change the area (namely width * height) to a random value in "[min_random_area, max_random_area]". Ignored if "random_resized_crop" is False.

min.random.area		
	float, optional, default=1 Change the area (namely width * height) to a random value in "[min_random_area, max_random_area]". Ignored if "random_resized_crop" is False.	
max.img.size	float, optional, default=1e+10 Set the maximal width and height after all resize and rotate argumentation are applied	
min.img.size	float, optional, default=0 Set the minimal width and height after all resize and rotate argumentation are applied	
brightness	float, optional, default=0 Add a random value in "[-brightness, brightness]" to the brightness of image.	
contrast	float, optional, default=0 Add a random value in "[-contrast, contrast]" to the contrast of image.	
saturation	float, optional, default=0 Add a random value in "[-saturation, saturation]" to the saturation of image.	
pca.noise	float, optional, default=0 Add PCA based noise to the image.	
random.h	int, optional, default='0' Add a random value in "[-random_h, random_h]" to the H channel in HSL color space.	
random.s	int, optional, default='0' Add a random value in "[-random_s, random_s]" to the S channel in HSL color space.	
random.l	int, optional, default='0' Add a random value in "[-random_l, random_l]" to the L channel in HSL color space.	
rotate	int, optional, default='-1' Rotate by an angle. If set, it overwrites the "max_rotate_angle" option.	
fill.value	int, optional, default='255' Set the padding pixels value to "fill_value".	
data.shape	Shape(tuple), required The shape of a output image.	
inter.method	int, optional, default='1' The interpolation method: 0-NN 1-bilinear 2-cubic 3-area 4-lanczos4 9-auto 10-rand.	
pad	int, optional, default='0' Change size from "[width, height]" into "[pad + width + pad, pad + height + pad]" by padding pixes	

Details

 $\hbox{``ImageRecordUInt8Iter_v1'' is deprecated. Use \hbox{``ImageRecordUInt8Iter'' instead.}}\\$

This iterator is identical to "ImageRecordIter" except for using "uint8" as the data type instead of "float".

Defined in src/io/iter_image_recordio.cc:L377

Value

iter The result mx.dataiter

52 mx.io.LibSVMIter

mx.io.LibSVMIter	Returns the LibSVM iterator which returns data with 'csr' storage
	type. This iterator is experimental and should be used with care.

Description

The input data is stored in a format similar to LibSVM file format, except that the **indices are expected to be zero-based instead of one-based, and the column indices for each row are expected to be sorted in ascending order**. Details of the LibSVM format are available 'here. https://www.csie.ntu.edu.tw/~cjlin/libsvmtools/datasets/.

Usage

```
mx.io.LibSVMIter(...)
```

Arguments

data.libsvm	string, required The input zero-base indexed LibSVM data file or a directory path.
data.shape	Shape(tuple), required The shape of one example.
label.libsvm	string, optional, default='NULL' The input LibSVM label file or a directory path. If NULL, all labels will be read from "data_libsvm".
label.shape	Shape(tuple), optional, default=[1] The shape of one label.
num.parts	int, optional, default='1' partition the data into multiple parts
part.index	int, optional, default='0' the index of the part will read
batch.size	int (non-negative), required Batch size.
round.batch	boolean, optional, default=1 Whether to use round robin to handle overflow batch or not.
prefetch.buffer	
	long (non-negative), optional, default=4 Maximum number of batches to prefetch.
ctx	'cpu', 'gpu',optional, default='gpu' Context data loader optimized for.
dtype	None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, default='None' Output data type. "None" means no change.

Details

The 'data_shape' parameter is used to set the shape of each line of the data. The dimension of both 'data_shape' and 'label_shape' are expected to be 1.

The 'data_libsvm' parameter is used to set the path input LibSVM file. When it is set to a directory, all the files in the directory will be read.

When 'label_libsvm' is set to "NULL", both data and label are read from the file specified by 'data_libsvm'. In this case, the data is stored in 'csr' storage type, while the label is a 1D dense array.

mx.io.MNISTIter 53

The 'LibSVMIter' only support 'round_batch' parameter set to "True". Therefore, if 'batch_size' is 3 and there are 4 total rows in libsym file, 2 more examples are consumed at the first round.

When 'num_parts' and 'part_index' are provided, the data is split into 'num_parts' partitions, and the iterator only reads the 'part_index'-th partition. However, the partitions are not guaranteed to be even.

"reset()" is expected to be called only after a complete pass of data.

Example::

- # Contents of libsym file "data.t". 1.0 0:0.5 2:1.2 -2.0 -3.0 0:0.6 1:2.4 2:1.2 4 2:-1.2
- # Creates a 'LibSVMIter' with 'batch_size'=3. »> data_iter = mx.io.LibSVMIter(data_libsvm = 'data.t', data_shape = (3,), batch_size = 3) # The data of the first batch is stored in csr storage type »> batch = data_iter.next() »> csr = batch.data[0] <CSRNDArray 3x3 @cpu(0)> »> csr.asnumpy() [[0.5 0. 1.2] [0. 0. 0.] [0.6 2.4 1.2]] # The label of first batch »> label = batch.label[0] »> label [1. -2. -3.] <NDArray 3 @cpu(0)>
- »> second_batch = data_iter.next() # The data of the second batch »> second_batch.data[0].asnumpy()
 [[0. 0. -1.2] [0.5 0. 1.2] [0. 0. 0.]] # The label of the second batch »> second_batch.label[0].asnumpy()
 [4. 1. -2.]
- »> data_iter.reset() # To restart the iterator for the second pass of the data

When 'label_libsvm' is set to the path to another LibSVM file, data is read from 'data_libsvm' and label from 'label_libsvm'. In this case, both data and label are stored in the csr format. If the label column in the 'data_libsvm' file is ignored.

Example::

- # Contents of libsym file "label.t" 1.0 -2.0 0:0.125 -3.0 2:1.2 4 1:1.0 2:-1.2
- # Creates a 'LibSVMIter' with specified label file »> data_iter = mx.io.LibSVMIter(data_libsvm = 'data.t', data_shape = (3,), label_libsvm = 'label.t', label_shape = (3,), batch_size = 3)
- # Both data and label are in csr storage type >> batch = data_iter.next() >> csr_data = batch.data[0] <CSRNDArray 3x3 @cpu(0)> >> csr_data.asnumpy() [[0.5 0. 1.2] [0. 0. 0.] [0.6 2.4 1.2]] >> csr_label = batch.label[0] <CSRNDArray 3x3 @cpu(0)> >> csr_label.asnumpy() [[0. 0. 0.] [0.125 0. 0.] [0. 0. 1.2]]

Defined in src/io/iter_libsvm.cc:L298

Value

iter The result mx.dataiter

mx.io.MNISTIter

Iterating on the MNIST dataset.

Description

One can download the dataset from http://yann.lecun.com/exdb/mnist/

Usage

```
mx.io.MNISTIter(...)
```

54 mx.kv.create

Arguments

image string, optional, default='./train-images-idx3-ubyte' Dataset Param: Mnist im-

age path.

label string, optional, default='./train-labels-idx1-ubyte' Dataset Param: Mnist label

path.

batch.size int, optional, default='128' Batch Param: Batch Size.

shuffle boolean, optional, default=1 Augmentation Param: Whether to shuffle data.

flat boolean, optional, default=0 Augmentation Param: Whether to flat the data into

1D.

seed int, optional, default='0' Augmentation Param: Random Seed.

silent boolean, optional, default=0 Auxiliary Param: Whether to print out data info.

num.parts int, optional, default='1' partition the data into multiple parts

part.index int, optional, default='0' the index of the part will read

prefetch.buffer

long (non-negative), optional, default=4 Maximum number of batches to prefetch.

ctx 'cpu', 'gpu', optional, default='gpu' Context data loader optimized for.

dtype None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, de-

fault='None' Output data type. "None" means no change.

Details

Defined in src/io/iter_mnist.cc:L265

Value

iter The result mx.dataiter

mx.kv.create Create a mxnet KVStore.

Description

Create a mxnet KVStore.

Arguments

type string(default="local") The type of kystore.

Value

The kystore.

```
mx.lr_scheduler.FactorScheduler
```

Learning rate scheduler. Reduction based on a factor value.

Description

Learning rate scheduler. Reduction based on a factor value.

Usage

```
mx.lr_scheduler.FactorScheduler(step, factor_val, stop_factor_lr = 1e-08,
    verbose = TRUE)
```

Arguments

step (integer) Schedule learning rate after n updates factor (double) The factor for reducing the learning rate

Value

scheduler function

```
mx.lr_scheduler.MultiFactorScheduler
```

Multifactor learning rate scheduler. Reduction based on a factor value at different steps.

Description

Multifactor learning rate scheduler. Reduction based on a factor value at different steps.

Usage

```
mx.lr_scheduler.MultiFactorScheduler(step, factor_val,
   stop_factor_lr = 1e-08, verbose = TRUE)
```

Arguments

step (array of integer) Schedule learning rate after n updates factor (double) The factor for reducing the learning rate

Value

scheduler function

mx.metric.accuracy

Accuracy metric for classification

Description

Accuracy metric for classification

Usage

```
mx.metric.accuracy
```

Format

An object of class mx.metric of length 3.

mx.metric.custom

Helper function to create a customized metric

Description

Helper function to create a customized metric

Usage

```
mx.metric.custom(name, feval)
```

```
mx.metric.logistic_acc
```

Accuracy metric for logistic regression

Description

Accuracy metric for logistic regression

Usage

```
{\tt mx.metric.logistic\_acc}
```

Format

An object of class mx.metric of length 3.

mx.metric.logloss 57

mx.metric.logloss

LogLoss metric for logistic regression

Description

LogLoss metric for logistic regression

Usage

```
mx.metric.logloss
```

Format

An object of class mx.metric of length 3.

mx.metric.mae

MAE (Mean Absolute Error) metric for regression

Description

MAE (Mean Absolute Error) metric for regression

Usage

mx.metric.mae

Format

An object of class mx.metric of length 3.

mx.metric.mse

MSE (Mean Squared Error) metric for regression

Description

MSE (Mean Squared Error) metric for regression

Usage

mx.metric.mse

Format

An object of class mx.metric of length 3.

58 mx.metric.rmsle

mx.metric.Perplexity Perplexity metric for language model

Description

Perplexity metric for language model

Usage

```
mx.metric.Perplexity
```

Format

An object of class mx.metric of length 3.

mx.metric.rmse

RMSE (Root Mean Squared Error) metric for regression

Description

RMSE (Root Mean Squared Error) metric for regression

Usage

mx.metric.rmse

Format

An object of class mx.metric of length 3.

mx.metric.rmsle

RMSLE (Root Mean Squared Logarithmic Error) metric for regression

Description

RMSLE (Root Mean Squared Logarithmic Error) metric for regression

Usage

```
mx.metric.rmsle
```

Format

An object of class mx.metric of length 3.

```
mx.metric.top_k_accuracy
```

Top-k accuracy metric for classification

Description

Top-k accuracy metric for classification

Usage

```
mx.metric.top_k_accuracy
```

Format

An object of class mx. metric of length 3.

mx.mlp

Convenience interface for multiple layer perceptron

Description

Convenience interface for multiple layer perceptron

Usage

```
mx.mlp(data, label, hidden_node = 1, out_node, dropout = NULL,
    activation = "tanh", out_activation = "softmax",
    ctx = mx.ctx.default(), ...)
```

Arguments

data the input matrix. Only mx.io.DataIter and R array/matrix types supported.

label the training label. Only R array type supported.

hidden_node a vector containing number of hidden nodes on each hidden layer as well as the

output layer.

out_node the number of nodes on the output layer.

dropout a number in [0,1) containing the dropout ratio from the last hidden layer to the

output layer.

activation either a single string or a vector containing the names of the activation functions.

out_activation a single string containing the name of the output activation function.

ctx whether train on cpu (default) or gpu.

... other parameters passing to mx.model.FeedForward.create/

eval.metric the evaluation metric/

60 mx.model.buckets

Examples

```
require(mlbench)
data(Sonar, package="mlbench")
Sonar[,61] = as.numeric(Sonar[,61])-1
train.ind = c(1:50, 100:150)
train.x = data.matrix(Sonar[train.ind, 1:60])
train.y = Sonar[train.ind, 61]
test.x = data.matrix(Sonar[-train.ind, 1:60])
test.y = Sonar[-train.ind, 61]
model = mx.mlp(train.x, train.y, hidden_node = 10, out_node = 2, out_activation = "softmax",
               learning.rate = 0.1)
preds = predict(model, test.x)
```

mx.model.buckets

Train RNN with bucket support

Description

Train RNN with bucket support

Usage

```
mx.model.buckets(symbol, train.data, eval.data = NULL, metric = NULL,
 arg.params = NULL, aux.params = NULL, fixed.params = NULL,
 num.round = 1, begin.round = 1,
 initializer = mx.init.uniform(0.01), optimizer = "sgd", ctx = NULL,
 batch.end.callback = NULL, epoch.end.callback = NULL,
 kvstore = "local", verbose = TRUE, metric_cpu = TRUE)
```

Arguments

symbol	Symbol or list of Symbols representing the model
train.data	Training data created by mx.io.bucket.iter
eval.data	Evaluation data created by mx.io.bucket.iter
num.round	int, number of epoch
verbose	

```
mx.model.FeedForward.create
```

Create a MXNet Feedforward neural net model with the specified training.

Description

Create a MXNet Feedforward neural net model with the specified training.

Usage

```
mx.model.FeedForward.create(symbol, X, y = NULL, ctx = NULL,
  begin.round = 1, num.round = 10, optimizer = "sgd",
  initializer = mx.init.uniform(0.01), eval.data = NULL,
  eval.metric = NULL, epoch.end.callback = NULL,
  batch.end.callback = NULL, array.batch.size = 128,
  array.layout = "auto", kvstore = "local", verbose = TRUE,
  arg.params = NULL, aux.params = NULL, input.names = NULL,
  output.names = NULL, fixed.param = NULL,
  allow.extra.params = FALSE, metric_cpu = TRUE, ...)
```

Arguments

symbol	The symbolic configuration of the neural network.	
X	mx.io.DataIter or R array/matrix The training data.	
у	R array, optional label of the data This is only used when X is R array.	
ctx	mx.context or list of mx.context, optional The devices used to perform training.	
begin.round	integer (default=1) The initial iteration over the training data to train the model.	
num.round	integer (default=10) The number of iterations over training data to train the model.	
optimizer	string, default="sgd" The optimization method.	
initializer,	initializer object. default=mx.init.uniform(0.01) The initialization scheme for parameters.	
eval.data	$mx.io. Data Iter\ or\ list(data=R.array,\ label=R.array),\ optional\ The\ validation\ set\ used\ for\ validation\ evaluation\ during\ the\ progress$	
eval.metric	function, optional The evaluation function on the results.	
epoch.end.callback		
	function, optional The callback when iteration ends.	
batch.end.callback		
	function, optional The callback when one mini-batch iteration ends.	
array.batch.size		
	integer (default=128) The batch size used for R array training.	

array.layout can be "auto", "colmajor", "rowmajor", (detault=auto) The layout of array. "row-

major" is only supported for two dimensional array. For matrix, "rowmajor" means $\dim(X) = c(\text{nexample}, \text{nfeatures})$, "colmajor" means $\dim(X) = c(\text{nfeatures}, \text{nexample})$ "auto" will auto detect the layout by match the feature size, and will report error when X is a square matrix to ask user to explicitly specify layout.

kvstore string (default="local") The parameter synchronization scheme in multiple de-

vices.

verbose logical (default=TRUE) Specifies whether to print information on the iterations

during training.

arg.params list, optional Model parameter, list of name to NDArray of net's weights.

aux.params list, optional Model parameter, list of name to NDArray of net's auxiliary states.

input.names optional The names of the input symbols.

output.names optional The names of the output symbols.

fixed.param The parameters to be fixed during training. For these parameters, not gradients

will be calculated and thus no space will be allocated for the gradient.

allow.extra.params

Whether allow extra parameters that are not needed by symbol. If this is TRUE, no error will be thrown when arg_params or aux_params contain extra parameters that is not needed by symbol. If this is TRUE,

ters that is not needed by the executor.

Value

model A trained mxnet model.

mx.model.init.params Parameter initialization

Description

Parameter initialization

Usage

```
mx.model.init.params(symbol, input.shape, output.shape, initializer, ctx)
```

Arguments

symbol The symbolic configuration of the neural network.

input.shape The shape of the input for the neural network.

output.shape The shape of the output for the neural network. It can be NULL.

initializer, initializer object. The initialization scheme for parameters.

ctx mx.context. The devices used to perform initialization.

mx.model.load 63

my	model	load	
IIIX .	IIIOGET	. IUau	

Load model checkpoint from file.

Description

Load model checkpoint from file.

Usage

```
mx.model.load(prefix, iteration)
```

Arguments

prefix string prefix of the model name

iteration integer Iteration number of model we would like to load.

 ${\tt mx.model.save}$

Save model checkpoint into file.

Description

Save model checkpoint into file.

Usage

```
mx.model.save(model, prefix, iteration)
```

Arguments

model The feedforward model to be saved.

prefix string prefix of the model name

iteration integer Iteration number of model we would like to load.

64 mx.nd.Activation

mx.nd.abs

Returns element-wise absolute value of the input.

Description

Example::

Arguments

data

NDArray-or-Symbol The input array.

Details

```
abs([-2, 0, 3]) = [2, 0, 3]
```

The storage type of "abs" output depends upon the input storage type:

- abs(default) = default - abs(row_sparse) = row_sparse - abs(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L721

Value

out The result mx.ndarray

mx.nd.Activation

Applies an activation function element-wise to the input.

Description

The following activation functions are supported:

Arguments

data NDArray-or-Symbol The input array.

act.type 'relu', 'sigmoid', 'softrelu', 'softsign', 'tanh', required Activation function to be

applied.

Details

```
- 'relu': Rectified Linear Unit, :math: 'y = max(x, 0)' - 'sigmoid': :math: 'y = \frac{1}{2} + exp(-x)'
```

- 'tanh': Hyperbolic tangent, :math: ' $y = \frac{xp(-x)exp(x) - exp(-x)exp(x) + exp(-x)}{- softPlus}$; :math: ' $y = \frac{1}{2} \frac{xp(-x)exp(x) - exp(-x)exp(x)}{- softSexp(x) - exp(-x)exp(x)}$; :math: ' $y = \frac{1}{2} \frac{xp(-x)exp(x) - exp(-x)exp(x)}{- softSexp(x) - exp(-x)exp(x)}$; :math: ' $y = \frac{1}{2} \frac{xp(-x)exp(x) - exp(-x)exp(x)}{- exp(-x)exp(x)}$; :math: ' $y = \frac{1}{2} \frac{xp(-x)exp(x) - exp(-x)exp(x)}{- exp(-x)exp(x)}$; :math: ' $y = \frac{1}{2} \frac{xp(-x)exp(x) - exp(-x)exp(x)}{- exp(-x)exp(x)}$; :math: ' $y = \frac{1}{2} \frac{xp(-x)exp(x)}{- exp(-x)exp(x)}$; : $y = \frac{1}{2} \frac{xp$

Defined in src/operator/nn/activation.cc:L168

Value

mx.nd.adam.update 65

of AdaGrad.	mx.nd.adam.update	Update function for Adam optimizer. Adam is seen as a generalization of AdaGrad.
-------------	-------------------	--

Description

Adam update consists of the following steps, where g represents gradient and m, v are 1st and 2nd order moment estimates (mean and variance).

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
mean	NDArray-or-Symbol Moving mean
var	NDArray-or-Symbol Moving variance
lr	float, required Learning rate
beta1	float, optional, default=0.899999976 The decay rate for the 1st moment estimates.
beta2	float, optional, default=0.999000013 The decay rate for the 2nd moment estimates.
epsilon	float, optional, default=9.99999994e-09 A small constant for numerical stability.
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
lazy.update	boolean, optional, default=1 If true, lazy updates are applied if gradient's stype is row_sparse and all of w, m and v have the same stype

Details

```
g_t = \Lambda J(W_{t-1}) + (1 - \beta_1) g_t + (1 - \beta_2)
g_t^2 \ W_t = W_{t-1} - \alpha \ frac \ m_t \ v_t + epsilon
```

It updates the weights using::

```
m = beta1*m + (1-beta1)*grad v = beta2*v + (1-beta2)*(grad**2) w += - learning_rate * m / (sqrt(v)) + (sqrt(v)) 
+ epsilon)
```

However, if grad's storage type is "row_sparse", "lazy_update" is True and the storage type of weight is the same as those of m and v, only the row slices whose indices appear in grad.indices are updated (for w, m and v)::

66 mx.nd.all.finite

```
for row in grad.indices: m[row] = beta1*m[row] + (1-beta1)*grad[row] v[row] = beta2*v[row] + (1-beta2)*(grad[row]**2) w[row] += - learning_rate * m[row] / (sqrt(v[row]) + epsilon)

Defined in src/operator/optimizer_op.cc:L686
```

Value

out The result mx.ndarray

mx.nd.add.n

Adds all input arguments element-wise.

Description

```
.. math:: add\_n(a_1, a_2, ..., a_n) = a_1 + a_2 + ... + a_n
```

Arguments

args

NDArray-or-Symbol[] Positional input arguments

Details

"add_n" is potentially more efficient than calling "add" by 'n' times.

The storage type of "add_n" output depends on storage types of inputs

- add_n(row_sparse, row_sparse, ..) = row_sparse - add_n(default, csr, default) = default - add_n(any input combinations longer than 4 (>4) with at least one default type) = default - otherwise, "add_n" falls all inputs back to default storage and generates default storage

Defined in src/operator/tensor/elemwise_sum.cc:L155

Value

out The result mx.ndarray

mx.nd.all.finite

Check if all the float numbers in the array are finite (used for AMP)

Description

Defined in src/operator/contrib/all_finite.cc:L101

Arguments

data NDArray Array

init.output boolean, optional, default=1 Initialize output to 1.

Value

mx.nd.amp.cast 67

mx.nd.amp.cast Cast function between low precision float/FP32 used by AMP.	
--	--

Description

It casts only between low precision float/FP32 and does not do anything for other types.

Arguments

data NDArray-or-Symbol The input.

dtype 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', required Output

data type.

Details

Defined in src/operator/tensor/amp_cast.cc:L37

Value

out The result mx.ndarray

mx.nd.amp.multicast	Cast function used by AMP, that casts its inputs to the common widest
	type.

Description

It casts only between low precision float/FP32 and does not do anything for other types.

Arguments

data NDArray-or-Symbol[] Weights

num.outputs int, required Number of input/output pairs to be casted to the widest type.

cast.narrow boolean, optional, default=0 Whether to cast to the narrowest type

Details

Defined in src/operator/tensor/amp_cast.cc:L71

Value

68 mx.nd.arccosh

mx.nd.arccos

Returns element-wise inverse cosine of the input array.

Description

The input should be in range '[-1, 1]'. The output is in the closed interval :math: '[0, \pi]'

Arguments

data

NDArray-or-Symbol The input array.

Details

```
.. math:: arccos([-1, -.707, 0, .707, 1]) = [\pi, 3\pi/4, \pi/4, \pi/4, \pi/4, \pi/4, \pi/4]
```

The storage type of "arccos" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L206

Value

out The result mx.ndarray

mx.nd.arccosh

Returns the element-wise inverse hyperbolic cosine of the input array, \computed element-wise.

Description

The storage type of "arccosh" output is always dense

Arguments

data

NDArray-or-Symbol The input array.

Details

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L474

Value

mx.nd.arcsin 69

mx.nd.arcsin

Returns element-wise inverse sine of the input array.

Description

The input should be in the range '[-1, 1]'. The output is in the closed interval of [:math:'-\pi/2', :math:'\pi/2'].

Arguments

data

NDArray-or-Symbol The input array.

Details

```
.. math:: \arcsin([-1, -.707, 0, .707, 1]) = [-\pi/2, -\pi/4, 0, \pi/4, \pi/2]
```

The storage type of "arcsin" output depends upon the input storage type:

- arcsin(default) = default - arcsin(row_sparse) = row_sparse - arcsin(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L187

Value

out The result mx.ndarray

mx.nd.arcsinh

Returns the element-wise inverse hyperbolic sine of the input array, \ computed element-wise.

Description

The storage type of "arcsinh" output depends upon the input storage type:

Arguments

data

NDArray-or-Symbol The input array.

Details

```
- arcsinh(default) = default - arcsinh(row_sparse) = row_sparse - arcsinh(csr) = csr
Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L436
```

Value

70 mx.nd.arctanh

mx.nd.arctan

Returns element-wise inverse tangent of the input array.

Description

The output is in the closed interval :math: '[-\pi/2, \pi/2]'

Arguments

data

NDArray-or-Symbol The input array.

Details

```
.. math:: arctan([-1, 0, 1]) = [-\pi/4, 0, \pi/4]
```

The storage type of "arctan" output depends upon the input storage type:

- $arctan(default) = default - arctan(row_sparse) = row_sparse - arctan(csr) = csr$

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L227

Value

out The result mx.ndarray

mx.nd.arctanh

Returns the element-wise inverse hyperbolic tangent of the input array, \computed element-wise.

Description

The storage type of "arctanh" output depends upon the input storage type:

Arguments

data

NDArray-or-Symbol The input array.

Details

```
- arctanh(default) = default - arctanh(row_sparse) = row_sparse - arctanh(csr) = csr
Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L515
```

Value

mx.nd.argmax 71

mx.nd.argmax	Returns indices of the maximum values along an axis.

Description

In the case of multiple occurrences of maximum values, the indices corresponding to the first occurrence are returned.

Arguments

data NDArray-or-Symbol The input

axis int or None, optional, default='None' The axis along which to perform the reduction. Negative values means indexing from right to left. "Requires axis to be set as int, because global reduction is not supported yet."

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axis is left in the

result as dimension with size one.

Details

```
Examples::
```

```
x = [[ 0., 1., 2.], [ 3., 4., 5.]]
// argmax along axis 0 argmax(x, axis=0) = [ 1., 1., 1.]
// argmax along axis 1 argmax(x, axis=1) = [ 2., 2.]
// argmax along axis 1 keeping same dims as an input array argmax(x, axis=1, keepdims=True) = [[ 2.], [ 2.]]
```

Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L52

Value

out The result mx.ndarray

mx.nd.argmax.channel Returns argmax indices of each channel from the input array.

Description

The result will be an NDArray of shape (num_channel,).

Arguments

data NDArray-or-Symbol The input array

72 mx.nd.argmin

Details

In case of multiple occurrences of the maximum values, the indices corresponding to the first occurrence are returned.

Examples::

```
x = [[0., 1., 2.], [3., 4., 5.]]

argmax\_channel(x) = [2., 2.]
```

Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L97

Value

out The result mx.ndarray

mx.nd.argmin Returns indices of th	ie minimum values along an ax	is.
------------------------------------	-------------------------------	-----

Description

In the case of multiple occurrences of minimum values, the indices corresponding to the first occurrence are returned.

Arguments

data	NDArray-or-Symbol The input
axis	int or None, optional, default='None' The axis along which to perform the reduction. Negative values means indexing from right to left. "Requires axis to be set as int, because global reduction is not supported yet."
keepdims	boolean, optional, default=0 If this is set to 'True', the reduced axis is left in the result as dimension with size one.

Details

```
Examples::
```

```
 x = [[\ 0.,\ 1.,\ 2.],\ [\ 3.,\ 4.,\ 5.]]  // argmin along axis 0 argmin(x, axis=0) = [\ 0.,\ 0.,\ 0.] 
 // argmin along axis 1 argmin(x, axis=1) = [\ 0.,\ 0.] 
 // argmin along axis 1 keeping same dims as an input array argmin(x, axis=1, keepdims=True) = [[\ 0.],\ [\ 0.]] 
 Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L77
```

Value

```
out The result mx.ndarray
```

mx.nd.argsort 73

mx.nd.argsort	Returns the indices that would sort an input array along the given axis.

Description

This function performs sorting along the given axis and returns an array of indices having same shape as an input array that index data in sorted order.

Arguments

data	NDArray-or-Symbol The input array
axis	int or None, optional, default='-1' Axis along which to sort the input tensor. If not given, the flattened array is used. Default is -1.
is.ascend	boolean, optional, default=1 Whether to sort in ascending or descending order.
dtype	'float16', 'float32', 'float64', 'int32', 'int64', 'uint8', optional, default='float32' DType of the output indices. It is only valid when ret_typ is "indices" or "both". An error will be raised if the selected data type cannot precisely represent the indices.

Details

```
Examples::
```

```
x = [[ 0.3, 0.2, 0.4], [ 0.1, 0.3, 0.2]]

// sort along axis -1 argsort(x) = [[ 1., 0., 2.], [ 0., 2., 1.]]

// sort along axis 0 argsort(x, axis=0) = [[ 1., 0., 1.] [ 0., 1., 0.]]

// flatten and then sort argsort(x, axis=None) = [ 3., 1., 5., 0., 4., 2.]

Defined in src/operator/tensor/ordering_op.cc:L181
```

Value

out The result mx.ndarray

mx.nd.array	Create a new mx.ndarray that copies the content from src on ctx.

Description

Create a new mx.ndarray that copies the content from src on ctx.

Usage

```
mx.nd.array(src.array, ctx = NULL)
```

74 mx.nd.batch.dot

Arguments

src.array Source array data of class array, vector or matrix.

ctx optional The context device of the array. mx.ctx.default() will be used in default.

Value

```
An mx.ndarray
An Rcpp_MXNDArray object
```

Examples

```
mat = mx.nd.array(x)
mat = 1 - mat + (2 * mat)/(mat + 0.5)
as.array(mat)
```

mx.nd.batch.dot

Batchwise dot product.

Description

"batch_dot" is used to compute dot product of "x" and "y" when "x" and "y" are data in batch, namely N-D ($N \ge 3$) arrays in shape of '($B0, ..., B_i, ..., E_i$).

Arguments

1hs NDArray-or-Symbol The first inputrhs NDArray-or-Symbol The second input

transpose.a boolean, optional, default=0 If true then transpose the first input before dot.
transpose.b boolean, optional, default=0 If true then transpose the second input before dot.
forward.stype None, 'csr', 'default', 'row_sparse', optional, default='None' The desired stor-

age type of the forward output given by user, if the combination of input storage types and this hint does not matchany implemented ones, the dot operator will perform fallback operation and still produce an output of the desired storage type.

Details

```
For example, given "x" with shape '(B_0, ..., B_i, N, M)' and "y" with shape '(B_0, ..., B_i, M, K)', the result array will have shape '(B_0, ..., B_i, N, K)', which is computed by:: batch_dot(x,y)[b_0, ..., b_i, :, :] = dot(x[b_0, ..., b_i, :, :], y[b_0, ..., b_i, :, :]) Defined in src/operator/tensor/dot.cc:L126
```

Value

mx.nd.batch.take 75

mx.nd.batch.take	Takes elements	from a data batch.
IIIX . IIU . DU LCIII . LUNC	Tunes cientenis	mom a aana bancin.

Description

.. note:: 'batch_take' is deprecated. Use 'pick' instead.

Arguments

a NDArray-or-Symbol The input array indices NDArray-or-Symbol The index array

Details

Given an input array of shape "(d0, d1)" and indices of shape "(i0,)", the result will be an output array of shape "(i0,)" with::

```
output[i] = input[i, indices[i]]
```

Examples::

```
x = [[1., 2.], [3., 4.], [5., 6.]]
```

// takes elements with specified indices batch_take(x, [0,1,0]) = [1. 4. 5.]

Defined in src/operator/tensor/indexing_op.cc:L774

Value

out The result mx.ndarray

h normalization.	h normalization.
------------------	------------------

Description

Normalizes a data batch by mean and variance, and applies a scale "gamma" as well as offset "beta".

Arguments

data	NDArray-or-S	Symbol Input	data to bate	h normalization

gamma NDArray-or-Symbol gamma array beta NDArray-or-Symbol beta array

moving.mean NDArray-or-Symbol running mean of input moving.var NDArray-or-Symbol running variance of input

eps double, optional, default=0.0010000000474974513 Epsilon to prevent div 0.

Must be no less than CUDNN_BN_MIN_EPSILON defined in cudnn.h when

using cudnn (usually 1e-5)

76 mx.nd.BatchNorm

float, optional, default=0.899999976 Momentum for moving average momentum

fix.gamma boolean, optional, default=1 Fix gamma while training

use.global.stats

boolean, optional, default=0 Whether use global moving statistics instead of local batch-norm. This will force change batch-norm into a scale shift operator.

output.mean.var

boolean, optional, default=0 Output the mean and inverse std

int, optional, default='1' Specify which shape axis the channel is specified axis

cudnn.off boolean, optional, default=0 Do not select CUDNN operator, if available

min.calib.range

float or None, optional, default=None The minimum scalar value in the form of float32 obtained through calibration. If present, it will be used to by quantized batch norm op to calculate primitive scale.Note: this calib_range is to calib bn

output.

max.calib.range

float or None, optional, default=None The maximum scalar value in the form of float32 obtained through calibration. If present, it will be used to by quantized batch norm op to calculate primitive scale. Note: this calib range is to calib bn output.

Details

Assume the input has more than one dimension and we normalize along axis 1. We first compute the mean and variance along this axis:

.. math::

```
data\underline{nean[i]} = mean(data[:,i,:,...]) \cdot data\underline{var[i]} = var(data[:,i,:,...])
```

Then compute the normalized output, which has the same shape as input, as following:

.. math::

```
out[:,i,:,...] = \frac{(i)+\exp[i]+\exp[i]}{2}
```

Both *mean* and *var* returns a scalar by treating the input as a vector.

Assume the input has size *k* on axis 1, then both "gamma" and "beta" have shape *(k,)*. If "output_mean_var" is set to be true, then outputs both "data_mean" and the inverse of "data_var", which are needed for the backward pass. Note that gradient of these two outputs are blocked.

Besides the inputs and the outputs, this operator accepts two auxiliary states, "moving_mean" and "moving_var", which are *k*-length vectors. They are global statistics for the whole dataset, which are updated by::

moving_mean = moving_mean * momentum + data_mean * (1 - momentum) moving_var = moving var * momentum + data var * (1 - momentum)

If "use_global_stats" is set to be true, then "moving_mean" and "moving_var" are used instead of "data_mean" and "data_var" to compute the output. It is often used during inference.

The parameter "axis" specifies which axis of the input shape denotes the 'channel' (separately normalized groups). The default is 1. Specifying -1 sets the channel axis to be the last item in the input shape.

mx.nd.BatchNorm.v1 77

Both "gamma" and "beta" are learnable parameters. But if "fix_gamma" is true, then set "gamma" to 1 and its gradient to 0.

.. Note:: When "fix_gamma" is set to True, no sparse support is provided. If "fix_gamma is" set to False, the sparse tensors will fallback.

Defined in src/operator/nn/batch_norm.cc:L571

Value

out The result mx.ndarray

mx.nd.BatchNorm.v1

Batch normalization.

Description

This operator is DEPRECATED. Perform BatchNorm on the input.

Arguments

data	NDArray-or-Syl	mbol Input data to	batch normalization

gamma NDArray-or-Symbol gamma array beta NDArray-or-Symbol beta array

eps float, optional, default=0.0010000005 Epsilon to prevent div 0

momentum float, optional, default=0.899999976 Momentum for moving average

fix.gamma boolean, optional, default=1 Fix gamma while training

use.global.stats

boolean, optional, default=0 Whether use global moving statistics instead of

local batch-norm. This will force change batch-norm into a scale shift operator.

output.mean.var

boolean, optional, default=0 Output All,normal mean and var

Details

Normalizes a data batch by mean and variance, and applies a scale "gamma" as well as offset "beta".

Assume the input has more than one dimension and we normalize along axis 1. We first compute the mean and variance along this axis:

```
.. math::
```

```
data\_mean[i] = mean(data[:,i,:,...]) \setminus data\_var[i] = var(data[:,i,:,...])
```

Then compute the normalized output, which has the same shape as input, as following:

.. math::

```
out[:,i,:,...] = \frac{(i)+\exp[i]+\exp[i]}{2}
```

Both *mean* and *var* returns a scalar by treating the input as a vector.

Assume the input has size *k* on axis 1, then both "gamma" and "beta" have shape *(k,)*. If "output_mean_var" is set to be true, then outputs both "data_mean" and "data_var" as well, which are needed for the backward pass.

Besides the inputs and the outputs, this operator accepts two auxiliary states, "moving_mean" and "moving_var", which are *k*-length vectors. They are global statistics for the whole dataset, which are updated by::

moving_mean = moving_mean * momentum + data_mean * (1 - momentum) moving_var = moving_var * momentum + data_var * (1 - momentum)

If "use_global_stats" is set to be true, then "moving_mean" and "moving_var" are used instead of "data_mean" and "data_var" to compute the output. It is often used during inference.

Both "gamma" and "beta" are learnable parameters. But if "fix_gamma" is true, then set "gamma" to 1 and its gradient to 0.

There's no sparse support for this operator, and it will exhibit problematic behavior if used with sparse tensors.

Defined in src/operator/batch_norm_v1.cc:L95

Value

out The result mx.ndarray

mx.nd.BilinearSampler Applies bilinear sampling to input feature map.

Description

Bilinear Sampling is the key of [NIPS2015] \"Spatial Transformer Networks\". The usage of the operator is very similar to remap function in OpenCV, except that the operator has the backward pass.

Arguments

data NDArray-or-Symbol Input data to the BilinearsamplerOp.

grid NDArray-or-Symbol Input grid to the BilinearsamplerOp.grid has two channels:

x_src, y_src

cudnn.off boolean or None, optional, default=None whether to turn cudnn off

Details

Given :math: 'data' and :math: 'grid', then the output is computed by

.. math:: $x_src = grid[batch, 0, y_dst, x_dst] \setminus y_src = grid[batch, 1, y_dst, x_dst] \setminus output[batch, channel, y_dst, x_dst] = G(data[batch, channel, y_src, x_src)$

:math:'x_dst', :math:'y_dst' enumerate all spatial locations in :math:'output', and :math:'G()' denotes the bilinear interpolation kernel. The out-boundary points will be padded with zeros.The shape of the output will be (data.shape[0], data.shape[1], grid.shape[2], grid.shape[3]).

mx.nd.BlockGrad 79

The operator assumes that :math:'data' has 'NCHW' layout and :math:'grid' has been normalized to [-1, 1].

BilinearSampler often cooperates with GridGenerator which generates sampling grids for BilinearSampler. GridGenerator supports two kinds of transformation: "affine" and "warp". If users want to design a CustomOp to manipulate :math: 'grid', please firstly refer to the code of GridGenerator.

```
Example 1::
```

```
## Zoom out data two times data = array([[[1, 4, 3, 6], [1, 8, 8, 9], [0, 4, 1, 5], [1, 0, 1, 3]]]])

affine_matrix = array([[2, 0, 0], [0, 2, 0]])

affine_matrix = reshape(affine_matrix, shape=(1, 6))

grid = GridGenerator(data=affine_matrix, transform_type='affine', target_shape=(4, 4))

out = BilinearSampler(data, grid)

out [[[[0, 0, 0, 0], [0, 3.5, 6.5, 0], [0, 1.25, 2.5, 0], [0, 0, 0, 0]]]

Example 2::

## shift data horizontally by -1 pixel

data = array([[[1, 4, 3, 6], [1, 8, 8, 9], [0, 4, 1, 5], [1, 0, 1, 3]]]])

warp_maxtrix = array([[[1, 1, 1, 1], [1, 1, 1, 1], [1, 1, 1, 1], [1, 1, 1, 1]], [[0, 0, 0, 0], [0, 0, 0, 0], [0, 0, 0, 0], [0, 0, 0, 0]]])

grid = GridGenerator(data=warp_matrix, transform_type='warp') out = BilinearSampler(data, grid) out [[[4, 3, 6, 0], [8, 8, 9, 0], [4, 1, 5, 0], [0, 1, 3, 0]]]

Defined in src/operator/bilinear_sampler.cc:L256
```

Value

out The result mx.ndarray

mx.nd.BlockGrad

Stops gradient computation.

Description

Stops the accumulated gradient of the inputs from flowing through this operator in the backward direction. In other words, this operator prevents the contribution of its inputs to be taken into account for computing gradients.

Arguments

data

NDArray-or-Symbol The input array.

80 mx.nd.broadcast.add

Details

```
Example::
```

```
v1 = [1, 2] v2 = [0, 1] a = Variable('a') b = Variable('b') b_stop_grad = stop_gradient(3 * b) loss = MakeLoss(b_stop_grad + a) executor = loss.simple_bind(ctx=cpu(), a=(1,2), b=(1,2)) executor.forward(is_train=True, a=v1, b=v2) executor.outputs [ 1. 5.] executor.backward() executor.grad_arrays [ 0. 0.] [ 1. 1.]

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L327
```

Value

out The result mx.ndarray

mx.nd.broadcast.add

Returns element-wise sum of the input arrays with broadcasting.

Description

'broadcast_plus' is an alias to the function 'broadcast_add'.

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
Example::
```

```
x = [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] y = [[\ 0.],\ [\ 1.]] broadcast_add(x, y) = [[\ 1.,\ 1.,\ 1.],\ [\ 2.,\ 2.,\ 2.]] broadcast_plus(x, y) = [[\ 1.,\ 1.,\ 1.],\ [\ 2.,\ 2.,\ 2.]]
Supported sparse operations: broadcast_add(csr, dense(1D)) = dense broadcast_add(dense(1D), csr) = dense Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L58
```

Value

mx.nd.broadcast.axes 81

mx.nd.broadcast.axes Broadcasts the input array over particular axes.

Description

Broadcasting is allowed on axes with size 1, such as from '(2,1,3,1)' to '(2,8,3,9)'. Elements will be duplicated on the broadcasted axes.

Arguments

data	NDArray-or-Symbol The input
axis	Shape(tuple), optional, default=[] The axes to perform the broadcasting.
size	Shape(tuple), optional, default=[] Target sizes of the broadcasting axes.

Details

'broadcast_axes' is an alias to the function 'broadcast_axis'.

Example::

```
// given x of shape (1,2,1) x = [[[ 1.], [ 2.]]]
```

// broadcast x on on axis 2 broadcast_axis(x, axis=2, size=3) = [[[1., 1., 1.], [2., 2., 2.]]] // broadcast x on on axes 0 and 2 broadcast_axis(x, axis=(0,2), size=(2,3)) = [[[1., 1., 1.], [2., 2., 2.]], [[1., 1., 1.], [2., 2., 2.]]]

Defined in src/operator/tensor/broadcast_reduce_op_value.cc:L58

Value

out The result mx.ndarray

mx.nd.broadcast.axis Broadcasts the input array over particular axes.

Description

Broadcasting is allowed on axes with size 1, such as from '(2,1,3,1)' to '(2,8,3,9)'. Elements will be duplicated on the broadcasted axes.

Arguments

data	NDArray-or-Symbol The input
axis	Shape(tuple), optional, default=[] The axes to perform the broadcasting.
size	Shape(tuple), optional, default=[] Target sizes of the broadcasting axes.

82 mx.nd.broadcast.div

Details

'broadcast_axes' is an alias to the function 'broadcast_axis'.

Example::

```
// given x of shape (1,2,1) x = [[[ 1.], [ 2.]]]
```

// broadcast x on on axis 2 broadcast_axis(x, axis=2, size=3) = [[[1., 1., 1.], [2., 2., 2.]]] // broadcast x on on axes 0 and 2 broadcast_axis(x, axis=(0,2), size=(2,3)) = [[[1., 1., 1.], [2., 2., 2.]], [[1., 1., 1.], [2., 2., 2.]]]

Defined in src/operator/tensor/broadcast_reduce_op_value.cc:L58

Value

out The result mx.ndarray

mx.nd.broadcast.div

Returns element-wise division of the input arrays with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

$$x = [[6., 6., 6.], [6., 6., 6.]]$$

 $y = [[2.], [3.]]$

broadcast_div(x, y) = [[3., 3., 3.], [2., 2., 2.]]

Supported sparse operations:

broadcast_div(csr, dense(1D)) = csr

Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L187

Value

mx.nd.broadcast.equal 83

mx.nd.broadcast.equal Returns the result of element-wise **equal to ** (==) comparison operation with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
 \begin{aligned} x &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ y &= [[\ 0.],\ [\ 1.]] \\ broadcast\_equal(x,y) &= [[\ 0.,\ 0.,\ 0.],\ [\ 1.,\ 1.,\ 1.]] \\ Defined in src/operator/tensor/elemwise\_binary\_broadcast\_op\_logic.cc:L46 \end{aligned}
```

Value

out The result mx.ndarray

```
mx.nd.broadcast.greater
```

Returns the result of element-wise **greater than** (>) comparison operation with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
x = [[ 1., 1., 1.], [ 1., 1., 1.]]
y = [[ 0.], [ 1.]]
broadcast_greater(x, y) = [[ 1., 1., 1.], [ 0., 0., 0.]]
```

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L82

Value

out The result mx.ndarray

```
mx.nd.broadcast.greater.equal
```

Returns the result of element-wise **greater than or equal to** (>=) comparison operation with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
 \begin{aligned} x &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ y &= [[\ 0.],\ [\ 1.]] \\ broadcast\_greater\_equal(x,\ y) &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ Defined in src/operator/tensor/elemwise\_binary\_broadcast\_op\_logic.cc:L100 \end{aligned}
```

Value

out The result mx.ndarray

mx.nd.broadcast.hypot Returns the hypotenuse of a right angled triangle, given its "legs" with broadcasting.

Description

It is equivalent to doing :math: $\frac{1^2 + x_2^2}{\cdot}$.

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

mx.nd.broadcast.lesser 85

Details

```
Example::
```

```
x = [[ 3., 3., 3.]]

y = [[ 4.], [ 4.]]

broadcast_hypot(x, y) = [[ 5., 5., 5.], [ 5., 5., 5.]]

z = [[ 0.], [ 4.]]
```

broadcast_hypot(x, z) = [[3., 3., 3.], [5., 5., 5.]]

Defined in src/operator/tensor/elemwise_binary_broadcast_op_extended.cc:L158

Value

out The result mx.ndarray

mx.nd.broadcast.lesser

Returns the result of element-wise **lesser than** (<) comparison operation with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
x = [[ 1., 1., 1.], [ 1., 1., 1.]]

y = [[ 0.], [ 1.]]

broadcast_lesser(x, y) = [[ 0., 0., 0.], [ 0., 0., 0.]]
```

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L118

Value

86 mx.nd.broadcast.like

```
mx.nd.broadcast.lesser.equal
```

Returns the result of element-wise **lesser than or equal to** (<=) comparison operation with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
x = [[1., 1., 1.], [1., 1., 1.]]

y = [[0.], [1.]]

broadcast_lesser_equal(x, y) = [[0., 0., 0.], [1., 1., 1.]]

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L136
```

Value

out The result mx.ndarray

mx.nd.broadcast.like Broadcasts lhs to have the same shape as rhs.

Description

Broadcasting is a mechanism that allows NDArrays to perform arithmetic operations with arrays of different shapes efficiently without creating multiple copies of arrays. Also see, 'Broadcasting https://docs.scipy.org/doc/numpy/user/basics.broadcasting.html '_ for more explanation.

Arguments

lhs	NDArray-or-Symbol First input.
rhs	NDArray-or-Symbol Second input.
lhs.axes	Shape or None, optional, default=None Axes to perform broadcast on in the first input array
rhs.axes	Shape or None, optional, default=None Axes to copy from the second input array

Details

Broadcasting is allowed on axes with size 1, such as from '(2,1,3,1)' to '(2,8,3,9)'. Elements will be duplicated on the broadcasted axes.

For example::

```
broadcast\_like([[1,2,3]], [[5,6,7],[7,8,9]]) = [[1., 2., 3.], [1., 2., 3.]]) \\ broadcast\_like([9], [1,2,3,4,5], lhs\_axes=(0,), rhs\_axes=(-1,)) = [9,9,9,9,9]
```

Defined in src/operator/tensor/broadcast_reduce_op_value.cc:L135

Value

out The result mx.ndarray

```
{\tt mx.nd.broadcast.logical.and}
```

Returns the result of element-wise **logical and** with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
 \begin{aligned} x &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ y &= [[\ 0.],\ [\ 1.]] \\ broadcast\_logical\_and(x,\ y) &= [[\ 0.,\ 0.,\ 0.],\ [\ 1.,\ 1.,\ 1.]] \\ Defined in src/operator/tensor/elemwise\_binary\_broadcast\_op\_logic.cc:L154 \end{aligned}
```

Value

```
mx.nd.broadcast.logical.or
```

Returns the result of element-wise **logical or** with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
x = [[1, 1, 0], [1, 1, 0]]

y = [[1], [0]]

broadcast_logical_or(x, y) = [[1, 1, 1, 1], [1, 1, 0]]

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L172
```

Value

out The result mx.ndarray

```
mx.nd.broadcast.logical.xor
```

Returns the result of element-wise **logical xor** with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
x = [[1, 1, 0], [1, 1, 0]]

y = [[1], [0]]

broadcast_logical_xor(x, y) = [[0, 0, 1], [1, 1, 0]]

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L190
```

mx.nd.broadcast.maximum 89

Value

out The result mx.ndarray

```
mx.nd.broadcast.maximum
```

Returns element-wise maximum of the input arrays with broadcasting.

Description

This function compares two input arrays and returns a new array having the element-wise maxima.

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
Example::
```

```
x = [[ 1., 1., 1.], [ 1., 1., 1.]]
y = [[ 0.], [ 1.]]
broadcast_maximum(x, y) = [[ 1., 1., 1.], [ 1., 1., 1.]]
```

Defined in src/operator/tensor/elemwise_binary_broadcast_op_extended.cc:L81

Value

out The result mx.ndarray

```
mx.nd.broadcast.minimum
```

Returns element-wise minimum of the input arrays with broadcasting.

Description

This function compares two input arrays and returns a new array having the element-wise minima.

Arguments

lhs	NDArray-or-Symbol First input to the function
rhs	NDArray-or-Symbol Second input to the function

90 mx.nd.broadcast.minus

Details

```
Example::
```

```
x = [[ 1., 1., 1.], [ 1., 1., 1.]]
y = [[ 0.], [ 1.]]
broadcast_maximum(x, y) = [[ 0., 0., 0.], [ 1., 1., 1.]]
```

 $broadcast_maximum(x, y) = [[0., 0., 0.], [1., 1., 1.]]$

Defined in src/operator/tensor/elemwise_binary_broadcast_op_extended.cc:L117

Value

out The result mx.ndarray

mx.nd.broadcast.minus Returns element-wise difference of the input arrays with broadcasting.

Description

'broadcast_minus' is an alias to the function 'broadcast_sub'.

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

Example::

```
x = [[1., 1., 1.], [1., 1., 1.]]

y = [[0.], [1.]]

broadcast_sub(x, y) = [[1., 1., 1.], [0., 0., 0.]]

broadcast_minus(x, y) = [[1., 1., 1.], [0., 0., 0.]]
```

Supported sparse operations:

 $broadcast_sub/minus(csr, dense(1D)) = dense \ broadcast_sub/minus(dense(1D), csr) = dense \ dense(1D)$

Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L106

Value

mx.nd.broadcast.mod 91

mx.nd.broadcast.mod

Returns element-wise modulo of the input arrays with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
x = [[8., 8., 8.], [8., 8., 8.]]

y = [[2.], [3.]]

broadcast_mod(x, y) = [[0., 0., 0.], [2., 2., 2.]]

Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L222
```

Value

out The result mx.ndarray

mx.nd.broadcast.mul

Returns element-wise product of the input arrays with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

92 mx.nd.broadcast.plus

Value

out The result mx.ndarray

```
mx.nd.broadcast.not.equal
```

Returns the result of element-wise **not equal to ** (!=) comparison operation with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
 \begin{aligned} x &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ y &= [[\ 0.],\ [\ 1.]] \\ broadcast\_not\_equal(x,\ y) &= [[\ 1.,\ 1.,\ 1.],\ [\ 0.,\ 0.,\ 0.]] \\ Defined in src/operator/tensor/elemwise\_binary\_broadcast\_op\_logic.cc:L64 \end{aligned}
```

Value

out The result mx.ndarray

mx.nd.broadcast.plus Returns element-wise sum of the input arrays with broadcasting.

Description

'broadcast_plus' is an alias to the function 'broadcast_add'.

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
Example::
```

```
x = [[1., 1., 1.], [1., 1., 1.]]
y = [[0.], [1.]]
broadcast_add(x, y) = [[ 1., 1., 1.], [ 2., 2., 2.]]
broadcast_plus(x, y) = [[ 1., 1., 1.], [ 2., 2., 2.]]
```

Supported sparse operations:

broadcast_add(csr, dense(1D)) = dense broadcast_add(dense(1D), csr) = dense

Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L58

Value

out The result mx.ndarray

mx.nd.broadcast.power Returns result of first array elements raised to powers from second array, element-wise with broadcasting.

Description

Example::

Arguments

1hs NDArray-or-Symbol First input to the function NDArray-or-Symbol Second input to the function rhs

Details

```
x = [[1., 1., 1.], [1., 1., 1.]]
y = [[0.], [1.]]
broadcast_power(x, y) = [[ 2., 2., 2.], [ 4., 4., 4.]]
Defined in src/operator/tensor/elemwise_binary_broadcast_op_extended.cc:L45
```

Value

94 mx.nd.broadcast.to

mx.nd.broadcast.sub

Returns element-wise difference of the input arrays with broadcasting.

Description

'broadcast_minus' is an alias to the function 'broadcast_sub'.

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the function

Details

```
Example::
```

```
x = [[1., 1., 1.], [1., 1., 1.]]

y = [[0.], [1.]]

broadcast_sub(x, y) = [[1., 1., 1.], [0., 0., 0.]]

broadcast_minus(x, y) = [[1., 1., 1.], [0., 0., 0.]]
```

Supported sparse operations:

broadcast_sub/minus(csr, dense(1D)) = dense broadcast_sub/minus(dense(1D), csr) = dense Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L106

Value

out The result mx.ndarray

mx.nd.broadcast.to

Broadcasts the input array to a new shape.

Description

Broadcasting is a mechanism that allows NDArrays to perform arithmetic operations with arrays of different shapes efficiently without creating multiple copies of arrays. Also see, 'Broadcasting https://docs.scipy.org/doc/numpy/user/basics.broadcasting.html '_ for more explanation.

Arguments

data NDArray-or-Symbol The input

shape Shape(tuple), optional, default=[] The shape of the desired array. We can set the

dim to zero if it's same as the original. E.g 'A = broadcast_to(B, shape=(10, 0,

0)) has the same meaning as 'A = broadcast_axis(B, axis=0, size=10)'.

mx.nd.Cast 95

Details

Broadcasting is allowed on axes with size 1, such as from '(2,1,3,1)' to '(2,8,3,9)'. Elements will be duplicated on the broadcasted axes.

For example::

```
broadcast_to([[1,2,3]], shape=(2,3)) = [[1., 2., 3.], [1., 2., 3.]])
```

The dimension which you do not want to change can also be kept as '0' which means copy the original value. So with 'shape=(2,0)', we will obtain the same result as in the above example.

Defined in src/operator/tensor/broadcast_reduce_op_value.cc:L82

Value

out The result mx.ndarray

mx.nd.Cast

Casts all elements of the input to a new type.

Description

```
.. note:: "Cast" is deprecated. Use "cast" instead.
```

Arguments

data NDArray-or-Symbol The input.

dtype 'bool', 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', required

Output data type.

Details

Example::

```
cast([0.9, 1.3], dtype='int32') = [0, 1] cast([1e20, 11.1], dtype='float16') = [inf, 11.09375] cast([300, 11.1, 10.9, -1, -3], dtype='uint8') = [44, 11, 10, 255, 253]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L665

Value

96 mx.nd.cast.storage

mχ	nd	cast

Casts all elements of the input to a new type.

Description

```
.. note:: "Cast" is deprecated. Use "cast" instead.
```

Arguments

data NDArray-or-Symbol The input.

dtype 'bool', 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', required

Output data type.

Details

Example::

```
cast([0.9, 1.3], dtype='int32') = [0, 1] cast([1e20, 11.1], dtype='float16') = [inf, 11.09375] cast([300, 11.1, 10.9, -1, -3], dtype='uint8') = [44, 11, 10, 255, 253]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L665

Value

out The result mx.ndarray

mx.nd.cast.storage

Casts tensor storage type to the new type.

Description

When an NDArray with default storage type is cast to csr or row_sparse storage, the result is compact, which means:

Arguments

data NDArray-or-Symbol The input.

stype 'csr', 'default', 'row_sparse', required Output storage type.

mx.nd.cbrt 97

Details

- for csr, zero values will not be retained - for row_sparse, row slices of all zeros will not be retained The storage type of "cast_storage" output depends on stype parameter:

```
    - cast_storage(csr, 'default') = default - cast_storage(row_sparse, 'default') = default - cast_storage(default, 'csr') = csr - cast_storage(default, 'row_sparse') = row_sparse - cast_storage(csr, 'csr') = csr - cast_storage(row_sparse, 'row_sparse') = row_sparse
```

Example::

```
dense = [[0., 1., 0.], [2., 0., 3.], [0., 0., 0.], [0., 0., 0.]]
```

cast to row_sparse storage type rsp = cast_storage(dense, 'row_sparse') rsp.indices = [0, 1] rsp.values = [[0., 1., 0.], [2., 0., 3.]]

cast to csr storage type csr = cast_storage(dense, 'csr') csr.indices = [1, 0, 2] csr.values = [1, 2, 3.] csr.indptr = [0, 1, 3, 3, 3]

Defined in src/operator/tensor/cast_storage.cc:L71

Value

out The result mx.ndarray

mx.nd.cbrt

Returns element-wise cube-root value of the input.

Description

```
.. math:: cbrt(x) = \sqrt{3}x
```

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

```
cbrt([1, 8, -125]) = [1, 2, -5]
```

The storage type of "cbrt" output depends upon the input storage type:

- cbrt(default) = default - cbrt(row_sparse) = row_sparse - cbrt(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L216

Value

mx.nd.ceil

Returns element-wise ceiling of the input.

Description

The ceil of the scalar x is the smallest integer i, such that $i \ge x$.

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

```
ceil([-2.1, -1.9, 1.5, 1.9, 2.1]) = [-2., -1., 2., 2., 3.]
```

The storage type of "ceil" output depends upon the input storage type:

- ceil(default) = default - ceil(row_sparse) = row_sparse - ceil(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L818

Value

out The result mx.ndarray

mx.nd.choose.element.0index

Picks elements from an input array according to the input indices along the given axis.

Description

Given an input array of shape "(d0, d1)" and indices of shape "(i0,)", the result will be an output array of shape "(i0,)" with::

Arguments

data	NDArray-or-Symbol The input array
index	NDArray-or-Symbol The index array

axis int or None, optional, default='-1' int or None. The axis to picking the elements.

Negative values means indexing from right to left. If is 'None', the elements in

the index w.r.t the flattened input will be picked.

keepdims boolean, optional, default=0 If true, the axis where we pick the elements is left

in the result as dimension with size one.

mode 'clip', 'wrap', optional, default='clip' Specify how out-of-bound indices behave.

Default is "clip". "clip" means clip to the range. So, if all indices mentioned are too large, they are replaced by the index that addresses the last element along an

axis. "wrap" means to wrap around.

mx.nd.clip 99

Details

```
output[i] = input[i, indices[i]]
```

By default, if any index mentioned is too large, it is replaced by the index that addresses the last element along an axis (the 'clip' mode).

This function supports n-dimensional input and (n-1)-dimensional indices arrays.

Examples::

```
x = [[1., 2.], [3., 4.], [5., 6.]]
```

// picks elements with specified indices along axis 0 pick(x, y=[0,1], 0) = [1., 4.]

// picks elements with specified indices along axis 1 pick(x, y=[0,1,0], 1) = [1., 4., 5.]

$$y = [[1.], [0.], [2.]]$$

// picks elements with specified indices along axis 1 using 'wrap' mode // to place indicies that would normally be out of bounds pick(x, y=[2,-1,-2], 1, mode='wrap') = [1,, 4,, 5]

$$y = [[1.], [0.], [2.]]$$

// picks elements with specified indices along axis 1 and dims are maintained pick(x,y, 1, keep-dims=True) = [[2.], [3.], [6.]]

Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L155

Value

out The result mx.ndarray

mx.nd.clip

Clips (limits) the values in an array. Given an interval, values outside the interval are clipped to the interval edges. Clipping "x" between 'a_min' and 'a_max' would be:: .. math:: $clip(x, a_min, a_max) = \max(\min(x, a_max), a_min)$) Example:: x = [0, 1, 2, 3, 4, 5, 6, 7, 8, 9] clip(x,1,8) = [1, 1, 2, 3, 4, 5, 6, 7, 8, 8.] The storage type of "clip" output depends on storage types of inputs and the a_min, $a_max \cdot parameter \ values: - clip(default) = default - clip(row_sparse, a_min <= 0, a_max >= 0) = row_sparse - clip(csr, a_min <= 0, a_max >= 0) = csr - clip(row_sparse, a_min < 0, a_max < 0) = default - clip(csr, a_min < 0, a_max > 0) = csr - clip(csr, a_min > 0, a_max > 0) = csr$

Description

Defined in src/operator/tensor/matrix_op.cc:L671

Arguments

data	NDArray-or-Symbol Input array.
a.min	float, required Minimum value
a.max	float, required Maximum value

100 mx.nd.Concat

Value

out The result mx.ndarray

mx.nd.Concat

Joins input arrays along a given axis.

Description

.. note:: 'Concat' is deprecated. Use 'concat' instead.

Arguments

data NDArray-or-Symbol[] List of arrays to concatenate num.args int, required Number of inputs to be concated.

----, --- **1**----- ----**-- 1**-------

dim int, optional, default='1' the dimension to be concated.

Details

The dimensions of the input arrays should be the same except the axis along which they will be concatenated. The dimension of the output array along the concatenated axis will be equal to the sum of the corresponding dimensions of the input arrays.

The storage type of "concat" output depends on storage types of inputs

- concat(csr, csr, ..., csr, dim=0) = csr - otherwise, "concat" generates output with default storage

Example::

```
\mathbf{x} = [[1,1],[2,2]] \; \mathbf{y} = [[3,3],[4,4],[5,5]] \; \mathbf{z} = [[6,6],[7,7],[8,8]]
```

$$concat(x,y,z,dim=0) = [[1., 1.], [2., 2.], [3., 3.], [4., 4.], [5., 5.], [6., 6.], [7., 7.], [8., 8.]]$$

Note that you cannot concat x,y,z along dimension 1 since dimension 0 is not the same for all the input arrays.

```
concat(y,z,dim=1) = [[3., 3., 6., 6.], [4., 4., 7., 7.], [5., 5., 8., 8.]]
```

Defined in src/operator/nn/concat.cc:L383

Value

mx.nd.concat 101

mx.nd.concat	Joins input arrays along a given axis.

Description

.. note:: 'Concat' is deprecated. Use 'concat' instead.

Arguments

data NDArray-or-Symbol[] List of arrays to concatenate
num.args int, required Number of inputs to be concated.
dim int, optional, default='1' the dimension to be concated.

Details

The dimensions of the input arrays should be the same except the axis along which they will be concatenated. The dimension of the output array along the concatenated axis will be equal to the sum of the corresponding dimensions of the input arrays.

The storage type of "concat" output depends on storage types of inputs

- concat(csr, csr, ..., csr, dim=0) = csr - otherwise, "concat" generates output with default storage Example::

```
x = [[1,1],[2,2]] y = [[3,3],[4,4],[5,5]] z = [[6,6], [7,7],[8,8]]

concat(x,y,z,dim=0) = [[1,1,1],[2,2,1],[3,3,1],[4,4,1],[5,5,1],[6,6,1],[7,7,1],[8,8]]
```

Note that you cannot concat x,y,z along dimension 1 since dimension 0 is not the same for all the input arrays.

```
concat(y,z,dim=1) = [[3., 3., 6., 6.], [4., 4., 7., 7.], [5., 5., 8., 8.]]
```

Defined in src/operator/nn/concat.cc:L383

Value

out The result mx.ndarray

mx.nd.Convolution Compute *N*-D convolution on *(N+2)*-D input.

Description

In the 2-D convolution, given input data with shape *(batch_size, channel, height, width)*, the output is computed by

102 mx.nd.Convolution

Arguments

data NDArray-or-Symbol Input data to the ConvolutionOp. NDArray-or-Symbol Weight matrix. weight bias NDArray-or-Symbol Bias parameter. kernel Shape(tuple), required Convolution kernel size: (w,), (h, w) or (d, h, w) stride Shape(tuple), optional, default=[] Convolution stride: (w,), (h, w) or (d, h, w). Defaults to 1 for each dimension. dilate Shape(tuple), optional, default=[] Convolution dilate: (w,), (h, w) or (d, h, w). Defaults to 1 for each dimension. pad Shape(tuple), optional, default=[] Zero pad for convolution: (w,), (h, w) or (d, h, w). Defaults to no padding. num.filter int (non-negative), required Convolution filter(channel) number num.group int (non-negative), optional, default=1 Number of group partitions. long (non-negative), optional, default=1024 Maximum temporary workspace alworkspace lowed (MB) in convolution. This parameter has two usages. When CUDNN is not used, it determines the effective batch size of the convolution kernel. When CUDNN is used, it controls the maximum temporary storage used for tuning the best CUDNN kernel when 'limited_workspace' strategy is used. no.bias boolean, optional, default=0 Whether to disable bias parameter. cudnn.tune None, 'fastest', 'limited_workspace', 'off',optional, default='None' Whether to pick convolution algo by running performance test. cudnn.off boolean, optional, default=0 Turn off cudnn for this layer. layout None, 'NCDHW', 'NCHW', 'NCW', 'NDHWC', 'NHWC', optional, default='None' Set layout for input, output and weight. Empty for default layout: NCW for 1d, NCHW for 2d and NCDHW for 3d.NHWC and NDHWC are only supported on

Details

GPU.

```
.. math::
out[n,i,:,:] = bias[i] + \sum_j=0^channel data[n,j,:,:] \star weight[i,j,:,:]
where :math: '\star' is the 2-D cross-correlation operator.
For general 2-D convolution, the shapes are
   - **data**: *(batch_size, channel, height, width)* - **weight**: *(num_filter, channel, kernel[0], kernel[1])* - **bias**: *(num_filter,)* - **out**: *(batch_size, num_filter, out_height, out_width)*.
Define::
f(x,k,p,s,d) = floor((x+2*p-d*(k-1)-1)/s)+1
then we have::
out_height=f(height, kernel[0], pad[0], stride[0], dilate[0]) out_width=f(width, kernel[1], pad[1], stride[1], dilate[1])
If "no_bias" is set to be true, then the "bias" term is ignored.
```

mx.nd.Convolution.v1 103

The default data "layout" is *NCHW*, namely *(batch_size, channel, height, width)*. We can choose other layouts such as *NWC*.

If "num_group" is larger than 1, denoted by *g*, then split the input "data" evenly into *g* parts along the channel axis, and also evenly split "weight" along the first dimension. Next compute the convolution on the *i*-th part of the data with the *i*-th weight part. The output is obtained by concatenating all the *g* results.

1-D convolution does not have *height* dimension but only *width* in space.

- **data**: *(batch_size, channel, width)* **weight**: *(num_filter, channel, kernel[0])* **bias**: *(num_filter,)* **out**: *(batch_size, num_filter, out_width)*.
- 3-D convolution adds an additional *depth* dimension besides *height* and *width*. The shapes are
- **data**: *(batch_size, channel, depth, height, width)* **weight**: *(num_filter, channel, kernel[0], kernel[1], kernel[2])* **bias**: *(num_filter,)* **out**: *(batch_size, num_filter, out_depth, out_height, out_width)*.

Both "weight" and "bias" are learnable parameters.

There are other options to tune the performance.

- **cudnn_tune**: enable this option leads to higher startup time but may give faster speed. Options are
- **off**: no tuning **limited_workspace**:run test and pick the fastest algorithm that doesn't exceed workspace limit. **fastest**: pick the fastest algorithm and ignore workspace limit. **None** (default): the behavior is determined by environment variable "MXNET_CUDNN_AUTOTUNE_DEFAULT". 0 for off, 1 for limited workspace (default), 2 for fastest.
- **workspace**: A large number leads to more (GPU) memory usage but may improve the performance.

Defined in src/operator/nn/convolution.cc:L473

Value

out The result mx.ndarray

mx.nd.Convolution.v1 This operator is DEPRECATED. Apply convolution to input then add a bias.

Description

This operator is DEPRECATED. Apply convolution to input then add a bias.

Arguments

data NDArray-or-Symbol Input data to the ConvolutionV1Op.

weight NDArray-or-Symbol Weight matrix. bias NDArray-or-Symbol Bias parameter. 104 mx.nd.copyto

kernel Shape(tuple), required convolution kernel size: (h, w) or (d, h, w) stride Shape(tuple), optional, default=[] convolution stride: (h, w) or (d, h, w) dilate Shape(tuple), optional, default=[] convolution dilate: (h, w) or (d, h, w) pad Shape(tuple), optional, default=[] pad for convolution: (h, w) or (d, h, w)

num. filter int (non-negative), required convolution filter(channel) number

num.group int (non-negative), optional, default=1 Number of group partitions. Equivalent

to slicing input into num_group partitions, apply convolution on each, then con-

catenate the results

workspace long (non-negative), optional, default=1024 Maximum temporary workspace al-

lowed for convolution (MB). This parameter determines the effective batch size of the convolution kernel, which may be smaller than the given batch size. Also, the workspace will be automatically enlarged to make sure that we can run the

kernel with batch size=1

no.bias boolean, optional, default=0 Whether to disable bias parameter.

cudnn.tune None, 'fastest', 'limited_workspace', 'off',optional, default='None' Whether to

pick convolution algo by running performance test. Leads to higher startup time but may give faster speed. Options are: 'off': no tuning 'limited_workspace': run test and pick the fastest algorithm that doesn't exceed workspace limit. 'fastest': pick the fastest algorithm and ignore workspace limit. If set to None

(default), behavior is determined by environment variable MXNET_CUDNN_AUTOTUNE_DEFAULT:

0 for off, 1 for limited workspace (default), 2 for fastest.

cudnn.off boolean, optional, default=0 Turn off cudnn for this layer.

layout None, 'NCDHW', 'NCHW', 'NDHWC', 'NHWC', optional, default='None' Set

layout for input, output and weight. Empty for default layout: NCHW for 2d

and NCDHW for 3d.

Value

out The result mx.ndarray

mx.nd.copyto Generate an mx.ndarray object on ctx, with data copied from src

Description

Generate an mx.ndarray object on ctx, with data copied from src

Usage

```
mx.nd.copyto(src, ctx)
```

Arguments

src The source mx.ndarray object.

ctx The target context.

mx.nd.Correlation 105

Applies correlation to inputs.

Description

The correlation layer performs multiplicative patch comparisons between two feature maps.

Arguments

data1	NDArray-or-Symbol Input data1 to the correlation.
data2	NDArray-or-Symbol Input data2 to the correlation.
kernel.size	int (non-negative), optional, default=1 kernel size for Correlation must be an odd number
max.displacemer	t .
	int (non-negative), optional, default=1 Max displacement of Correlation
stride1	int (non-negative), optional, default=1 stride1 quantize data1 globally
stride2	int (non-negative), optional, default=1 stride2 quantize data2 within the neighborhood centered around data1 $$
pad.size	int (non-negative), optional, default=0 pad for Correlation
is.multiply	boolean, optional, default=1 operation type is either multiplication or subduction

Details

Given two multi-channel feature maps :math:'f_1, f_2', with :math:'w', :math:'h', and :math:'c' being their width, height, and number of channels, the correlation layer lets the network compare each patch from :math:'f_1' with each patch from :math:'f_2'.

For now we consider only a single comparison of two patches. The 'correlation' of two patches centered at :math: 'x_1' in the first map and :math: 'x_2' in the second map is then defined as:

.. math::

```
c(x_1, x_2) = \sum_{k=0}^{\infty} [-k,k] \le [-k,k] \le [-k,k] \le f_1(x_1 + o), f_2(x_2 + o) \le f_1(x_1 + o)
```

for a square patch of size :math: 'K:=2k+1'.

Note that the equation above is identical to one step of a convolution in neural networks, but instead of convolving data with a filter, it convolves data with other data. For this reason, it has no training weights.

Computing :math: $c(x_1, x_2)$ involves :math: k^2 multiplications. Comparing all patch combinations involves :math: k^2 such computations.

Given a maximum displacement :math: 'd', for each location :math: ' x_1 ' it computes correlations :math: ' (x_1, x_2) ' only in a neighborhood of size :math: ' (x_1, x_2) ' by limiting the range of :math: ' (x_2) '. We use strides :math: ' (x_1, x_2) ', to quantize :math: ' (x_1, x_2) ' within the neighborhood centered around :math: ' (x_1, x_2) '.

The final output is defined by the following expression:

```
.. math:: out[n, q, i, j] = c(x_i, j, x_q)
```

mx.nd.cosh

where :math:'i' and :math:'j' enumerate spatial locations in :math:'f_1', and :math:'q' denotes the :math:'q^th' neighborhood of :math:'x_i,j'.

Defined in src/operator/correlation.cc:L198

Value

out The result mx.ndarray

mx.nd.cos

Computes the element-wise cosine of the input array.

Description

The input should be in radians (:math: '2\pi' rad equals 360 degrees).

Arguments

data

NDArray-or-Symbol The input array.

Details

```
.. math:: cos([0, \pi/4, \pi/2]) = [1, 0.707, 0]
```

The storage type of "cos" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L90

Value

out The result mx.ndarray

mx.nd.cosh

Returns the hyperbolic cosine of the input array, computed elementwise.

Description

```
.. math:: cosh(x) = 0.5 \times (exp(x) + exp(-x))
```

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "cosh" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L351

mx.nd.Crop 107

Value

out The result mx.ndarray

mx.nd.Crop	note:: 'Crop' is deprecated. Use 'slice' instead.	

Description

Crop the 2nd and 3rd dim of input data, with the corresponding size of h_w or with width and height of the second input symbol, i.e., with one input, we need h_w to specify the crop height and width, otherwise the second input symbol's size will be used

Arguments

data	Symbol or Symbol[] Tensor or List of Tensors, the second input will be used as crop_like shape reference
num.args	int, required Number of inputs for crop, if equals one, then we will use the h_wfor crop height and width, else if equals two, then we will use the heightand width of the second input symbol, we name crop_like here
offset	Shape(tuple), optional, default= $[0,0]$ crop offset coordinate: (y, x)
h.w	Shape(tuple), optional, default=[0,0] crop height and width: (h, w)
center.crop	boolean, optional, default=0 If set to true, then it will use be the center_crop,or it will crop using the shape of crop_like

Details

Defined in src/operator/crop.cc:L50

Value

108 mx.nd.crop

mx.nd.crop

Slices a region of the array. .. note:: "crop" is deprecated. Use "slice" instead. This function returns a sliced array between the indices given by 'begin' and 'end' with the corresponding 'step'. For an input array of "shape=(d_0, d_1, ..., d_n-1)", slice operation with "begin=(b_0, b_1...b_m-1)", "end=(e_0, e_1, ..., e_m-1)", and " $step=(s_0, s_1, ..., s_{m-1})$ ", where $m \le n$, results in an array with the shape "(|e_0-b_0|/|s_0|, ..., |e_m-1-b_m-1|/|s_m-1|, d_m, ..., d_n-1)". The resulting array's *k*-th dimension contains elements from the *k*-th dimension of the input array starting from index "b_k" (inclusive) with step "s_k" until reaching "e_k" (exclusive). If the *k*-th elements are 'None' in the sequence of 'begin', 'end', and 'step', the following rule will be used to set default values. If 's_k' is 'None', set $s_k=1$. If $s_k>0$, set $b_k=0$, $e_k=d_k$; else, set $b_k=d_k-1$, 'e_k=-1'. The storage type of "slice" output depends on storage types of inputs - slice(csr) = csr - otherwise, "slice" generates output with default storage .. note:: When input data storage type is csr, it only supports step=(), or step=(None,), or step=(1,) to generate a csr output. For other step parameter values, it falls back to slicing a dense tensor. Example:: x = [[1., 2., 3., 4.], [5., 6., 7., 8.], [9., 10., 11.]12.]] slice(x, begin=(0,1), end=(2,4)) = [[2., 3., 4.], [6., 7., 8.]]slice(x, begin=(None, 0), end=(None, 3), step=(-1, 2)) = [[9., 11.],[5., 7.], [1., 3.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L477

Arguments

data	NDArray-or-Symbol Source input
begin	Shape(tuple), required starting indices for the slice operation, supports negative indices.
end	Shape(tuple), required ending indices for the slice operation, supports negative indices.
step	Shape(tuple), optional, default=[] step for the slice operation, supports negative values.

Value

mx.nd.ctc.loss

Description

.. note:: The existing alias "contrib_CTCLoss" is deprecated.

Arguments

data NDArray-or-Symbol Input ndarray

label NDArray-or-Symbol Ground-truth labels for the loss.

data.lengths NDArray-or-Symbol Lengths of data for each of the samples. Only required

when use_data_lengths is true.

label.lengths NDArray-or-Symbol Lengths of labels for each of the samples. Only required

when use_label_lengths is true.

use.data.lengths

boolean, optional, default=0 Whether the data lenghts are decided by 'data_lengths'.

If false, the lengths are equal to the max sequence length.

use.label.lengths

boolean, optional, default=0 Whether the label lengths are decided by 'label_lengths', or derived from 'padding_mask'. If false, the lengths are derived from the first occurrence of the value of 'padding_mask'. The value of 'padding_mask' is "0" when first CTC label is reserved for blank, and "-1" when last label is reserved

for blank. See 'blank_label'.

blank.label 'first', 'last', optional, default='first' Set the label that is reserved for blank la-

bel.If "first", 0-th label is reserved, and label values for tokens in the vocabulary are between "1" and "alphabet_size-1", and the padding mask is "-1". If "last", last label value "alphabet_size-1" is reserved for blank label instead, and label values for tokens in the vocabulary are between "0" and "alphabet_size-2", and

the padding mask is "0".

Details

The shapes of the inputs and outputs:

```
- **data**: '(sequence_length, batch_size, alphabet_size)' - **label**: '(batch_size, label_sequence_length)' - **out**: '(batch_size)'
```

The 'data' tensor consists of sequences of activation vectors (without applying softmax), with ith channel in the last dimension corresponding to i-th label for i between 0 and alphabet_size-1 (i.e always 0-indexed). Alphabet size should include one additional value reserved for blank label. When 'blank_label' is ""first"", the "0"-th channel is be reserved for activation of blank label, or otherwise if it is "last", "(alphabet_size-1)"-th channel should be reserved for blank label.

"label" is an index matrix of integers. When 'blank_label' is ""first"", the value 0 is then reserved for blank label, and should not be passed in this matrix. Otherwise, when 'blank_label' is ""last"", the value '(alphabet_size-1)' is reserved for blank label.

110 mx.nd.CTCLoss

If a sequence of labels is shorter than *label_sequence_length*, use the special padding value at the end of the sequence to conform it to the correct length. The padding value is '0' when 'blank_label' is ""first"", and '-1' otherwise.

For example, suppose the vocabulary is '[a, b, c]', and in one batch we have three sequences 'ba', 'cbb', and 'abac'. When 'blank_label' is ""first"", we can index the labels as 'a': 1, 'b': 2, 'c': 3', and we reserve the 0-th channel for blank label in data tensor. The resulting 'label' tensor should be padded to be::

[[2, 1, 0, 0], [3, 2, 2, 0], [1, 2, 1, 3]]

When 'blank_label' is ""last"", we can index the labels as 'a': 0, 'b': 1, 'c': 2', and we reserve the channel index 3 for blank label in data tensor. The resulting 'label' tensor should be padded to be::

[[1, 0, -1, -1], [2, 1, 1, -1], [0, 1, 0, 2]]

"out" is a list of CTC loss values, one per example in the batch.

See *Connectionist Temporal Classification: Labelling Unsegmented Sequence Data with Recurrent Neural Networks*, A. Graves *et al*. for more information on the definition and the algorithm.

Defined in src/operator/nn/ctc_loss.cc:L100

Value

out The result mx.ndarray

mx.nd.CTCLoss Connectionist Temporal Classification Loss.

Description

.. note:: The existing alias "contrib_CTCLoss" is deprecated.

Arguments

data NDArray-or-Symbol Input ndarray

label NDArray-or-Symbol Ground-truth labels for the loss.

data.lengths NDArray-or-Symbol Lengths of data for each of the samples. Only required

when use_data_lengths is true.

label.lengths NDArray-or-Symbol Lengths of labels for each of the samples. Only required

when use_label_lengths is true.

use.data.lengths

boolean, optional, default=0 Whether the data lengths are decided by 'data_lengths'.

If false, the lengths are equal to the max sequence length.

use.label.lengths

boolean, optional, default=0 Whether the label lengths are decided by 'label_lengths', or derived from 'padding_mask'. If false, the lengths are derived from the first occurrence of the value of 'padding_mask'. The value of 'padding_mask' is "0" when first CTC label is reserved for blank, and "-1" when last label is reserved for blank. See 'blank_label'.

mx.nd.CTCLoss 111

blank.label

'first', 'last', optional, default='first' Set the label that is reserved for blank label.If "first", 0-th label is reserved, and label values for tokens in the vocabulary are between "1" and "alphabet_size-1", and the padding mask is "-1". If "last", last label value "alphabet_size-1" is reserved for blank label instead, and label values for tokens in the vocabulary are between "0" and "alphabet_size-2", and the padding mask is "0".

Details

The shapes of the inputs and outputs:

```
- **data**: '(sequence_length, batch_size, alphabet_size)' - **label**: '(batch_size, label_sequence_length)' - **out**: '(batch_size)'
```

The 'data' tensor consists of sequences of activation vectors (without applying softmax), with ith channel in the last dimension corresponding to i-th label for i between 0 and alphabet_size-1 (i.e always 0-indexed). Alphabet size should include one additional value reserved for blank label. When 'blank_label' is ""first"", the "0"-th channel is be reserved for activation of blank label, or otherwise if it is "last", "(alphabet_size-1)"-th channel should be reserved for blank label.

"label" is an index matrix of integers. When 'blank_label' is ""first"", the value 0 is then reserved for blank label, and should not be passed in this matrix. Otherwise, when 'blank_label' is ""last"", the value '(alphabet_size-1)' is reserved for blank label.

If a sequence of labels is shorter than *label_sequence_length*, use the special padding value at the end of the sequence to conform it to the correct length. The padding value is '0' when 'blank_label' is ""first"", and '-1' otherwise.

For example, suppose the vocabulary is '[a, b, c]', and in one batch we have three sequences 'ba', 'cbb', and 'abac'. When 'blank_label' is ""first"", we can index the labels as 'a': 1, 'b': 2, 'c': 3', and we reserve the 0-th channel for blank label in data tensor. The resulting 'label' tensor should be padded to be::

```
[[2, 1, 0, 0], [3, 2, 2, 0], [1, 2, 1, 3]]
```

When 'blank_label' is ""last"", we can index the labels as "a': 0, 'b': 1, 'c': 2', and we reserve the channel index 3 for blank label in data tensor. The resulting 'label' tensor should be padded to be::

```
[[1, 0, -1, -1], [2, 1, 1, -1], [0, 1, 0, 2]]
```

"out" is a list of CTC loss values, one per example in the batch.

See *Connectionist Temporal Classification: Labelling Unsegmented Sequence Data with Recurrent Neural Networks*, A. Graves *et al*. for more information on the definition and the algorithm.

Defined in src/operator/nn/ctc_loss.cc:L100

Value

112 mx.nd.Custom

mx.nd.cumsum Return the cumulative sum of the elements along a given axis.	mx.nd.cumsum	Return the cumulative sum of the elements along a given axis.
--	--------------	---

Description

Defined in src/operator/numpy/np_cumsum.cc:L70

Arguments

a NDArray-or-Symbol Input ndarray

axis int or None, optional, default='None' Axis along which the cumulative sum is

computed. The default (None) is to compute the cumsum over the flattened

array.

dtype None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', optional, default='None'

Type of the returned array and of the accumulator in which the elements are summed. If dtype is not specified, it defaults to the dtype of a, unless a has an integer dtype with a precision less than that of the default platform integer. In

that case, the default platform integer is used.

Value

out The result mx.ndarray

mx.nd.Custom	Apply a custom operator implemented in a frontend language (like
	Python).

Description

Custom operators should override required methods like 'forward' and 'backward'. The custom operator must be registered before it can be used. Please check the tutorial here: https://mxnet.incubator.apache.org/api/faq/new_

Arguments

data NDArray-or-Symbol[] Input data for the custom operator.

op. type string Name of the custom operator. This is the name that is passed to 'mx.operator.register'

to register the operator.

Details

Defined in src/operator/custom/custom.cc:L546

Value

mx.nd.Deconvolution 113

mx.nd.Deconvolution

Computes 1D or 2D transposed convolution (aka fractionally strided convolution) of the input tensor. This operation can be seen as the gradient of Convolution operation with respect to its input. Convolution usually reduces the size of the input. Transposed convolution works the other way, going from a smaller input to a larger output while preserving the connectivity pattern.

Description

Computes 1D or 2D transposed convolution (aka fractionally strided convolution) of the input tensor. This operation can be seen as the gradient of Convolution operation with respect to its input. Convolution usually reduces the size of the input. Transposed convolution works the other way, going from a smaller input to a larger output while preserving the connectivity pattern.

Arguments

_	
data	NDArray-or-Symbol Input tensor to the deconvolution operation.
weight	NDArray-or-Symbol Weights representing the kernel.
bias	NDArray-or-Symbol Bias added to the result after the deconvolution operation.
kernel	Shape(tuple), required Deconvolution kernel size: (w,), (h, w) or (d, h, w). This is same as the kernel size used for the corresponding convolution
stride	Shape(tuple), optional, default=[] The stride used for the corresponding convolution: (w,), (h, w) or (d, h, w). Defaults to 1 for each dimension.
dilate	Shape(tuple), optional, default=[] Dilation factor for each dimension of the input: (w,), (h, w) or (d, h, w). Defaults to 1 for each dimension.
pad	Shape(tuple), optional, default=[] The amount of implicit zero padding added during convolution for each dimension of the input: (w,), (h, w) or (d, h, w). "(kernel-1)/2" is usually a good choice. If 'target_shape' is set, 'pad' will be ignored and a padding that will generate the target shape will be used. Defaults to no padding.
adj	Shape(tuple), optional, default=[] Adjustment for output shape: (w,), (h, w) or (d, h, w). If 'target_shape' is set, 'adj' will be ignored and computed accordingly.
target.shape	Shape(tuple), optional, default=[] Shape of the output tensor: $(w,)$, (h, w) or (d, h, w) .
num.filter	int (non-negative), required Number of output filters.
num.group	int (non-negative), optional, default=1 Number of groups partition.
workspace	long (non-negative), optional, default=512 Maximum temporary workspace allowed (MB) in deconvolution. This parameter has two usages. When CUDNN is not used, it determines the effective batch size of the deconvolution kernel. When CUDNN is used, it controls the maximum temporary storage used for

tuning the best CUDNN kernel when 'limited_workspace' strategy is used.

114 mx.nd.degrees

no.bias boolean, optional, default=1 Whether to disable bias parameter.

cudnn.tune None, 'fastest', 'limited_workspace', 'off',optional, default='None' Whether to

pick convolution algorithm by running performance test.

cudnn.off boolean, optional, default=0 Turn off cudnn for this layer.

layout None, 'NCDHW', 'NCHW', 'NCW', 'NDHWC', 'NHWC', optional, default='None'

Set layout for input, output and weight. Empty for default layout, NCW for 1d, NCHW for 2d and NCDHW for 3d.NHWC and NDHWC are only supported on

GPU.

Value

out The result mx.ndarray

mx.nd.degrees

Converts each element of the input array from radians to degrees.

Description

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "degrees" output depends upon the input storage type:

- degrees(default) = default - degrees(row_sparse) = row_sparse - degrees(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L274

Value

mx.nd.depth.to.space 115

mx.nd.depth.to.space

Rearranges(permutes) data from depth into blocks of spa-Similar to ONNX DepthToSpace operator: https://github.com/onnx/onnx/blob/master/docs/Operators.md#DepthToSpace.The output is a new tensor where the values from depth dimension are moved in spatial blocks to height and width dimension. The reverse of this operation is "space to depth". .. math:: \begingather* x \prime = $reshape(x, [N, block_size, block_size, C / (block_size ^ 2), H *$ $block \leq v + block \leq v + bloc$ [0, 3, 4, 1, 5, 2]\\\\\y = reshape(x \prime \prime, [N, C / (block_size \^ 2), $H * block \land size$, $W * block \land size$) $\land endgather * where :math: 'x' is$ an input tensor with default layout as :math: '[N, C, H, W]': [batch, channels, height, width] and :math: 'y' is the output tensor of layout :math: '[N, C / ($block \le ^ 2$), $H * block \le W * block \le '$ Example:: x = [[[0, 1, 2], [3, 4, 5]], [[6, 7, 8], [9, 10, 11]], [[12, 13, 1]]14], [15, 16, 17]], [[18, 19, 20], [21, 22, 23]]]] depth_to_space(x, 2) = [[[0, 6, 1, 7, 2, 8], [12, 18, 13, 19, 14, 20], [3, 9, 4, 10, 5, 11], [15, 12]]21, 16, 22, 17, 23]]]]

Description

Defined in src/operator/tensor/matrix_op.cc:L965

Arguments

data NDArray-or-Symbol Input ndarray

block.size int, required Blocks of [block_size. block_size] are moved

Value

out The result mx.ndarray

mx.nd.diag

Extracts a diagonal or constructs a diagonal array.

Description

"diag"'s behavior depends on the input array dimensions:

Arguments

data NDArray-or-Symbol Input ndarray

k int, optional, default='0' Diagonal in question. The default is 0. Use k>0 for diagonals above the main diagonal, and k<0 for diagonals below the main diagonal.

onal. If input has shape (S0 S1) k must be between -S0 and S1

116 mx.nd.dot

axis1	int, optional, default='0' The first axis of the sub-arrays of interest. Ignored when the input is a 1-D array.
axis2	int, optional, default='1' The second axis of the sub-arrays of interest. Ignored when the input is a 1-D array.

Details

- 1-D arrays: constructs a 2-D array with the input as its diagonal, all other elements are zero. - N-D arrays: extracts the diagonals of the sub-arrays with axes specified by "axis1" and "axis2". The output shape would be decided by removing the axes numbered "axis1" and "axis2" from the input shape and appending to the result a new axis with the size of the diagonals in question.

For example, when the input shape is '(2, 3, 4, 5)', "axis1" and "axis2" are 0 and 2 respectively and "k" is 0, the resulting shape would be '(3, 5, 2)'.

Examples::

```
x = [[1, 2, 3], [4, 5, 6]]
diag(x) = [1, 5]
diag(x, k=1) = [2, 6]
diag(x, k=-1) = [4]
x = [1, 2, 3]
diag(x) = [[1, 0, 0], [0, 2, 0], [0, 0, 3]]
diag(x, k=1) = [[0, 1, 0], [0, 0, 2], [0, 0, 0]]
diag(x, k=-1) = [[0, 0, 0], [1, 0, 0], [0, 2, 0]]
x = [[[1, 2], [3, 4]],
[[5, 6], [7, 8]]]
diag(x) = [[1, 7], [2, 8]]
diag(x, axis1=-2, axis2=-1) = [[1, 4], [5, 8]]
Defined in src/operator/tensor/diag_op.cc:L87
```

Value

out The result mx.ndarray

mx.nd.dot

Dot product of two arrays.

Description

"dot"'s behavior depends on the input array dimensions:

mx.nd.dot

Arguments

1hs NDArray-or-Symbol The first inputrhs NDArray-or-Symbol The second input

transpose.a boolean, optional, default=0 If true then transpose the first input before dot.

transpose.b boolean, optional, default=0 If true then transpose the second input before dot.

forward.stype None, 'csr', 'default', 'row_sparse', optional, default='None' The desired stor-

age type of the forward output given by user, if the combination of input storage types and this hint does not matchany implemented ones, the dot operator will perform fallback operation and still produce an output of the desired storage type.

Details

- 1-D arrays: inner product of vectors - 2-D arrays: matrix multiplication - N-D arrays: a sum product over the last axis of the first input and the first axis of the second input

For example, given 3-D "x" with shape '(n,m,k)' and "y" with shape '(k,r,s)', the result array will have shape '(n,m,r,s)'. It is computed by::

```
dot(x,y)[i,j,a,b] = sum(x[i,j,:]*y[:,a,b])
```

Example::

```
x = reshape([0,1,2,3,4,5,6,7], shape=(2,2,2)) y = reshape([7,6,5,4,3,2,1,0], shape=(2,2,2)) dot(x,y)[0,0,1,1] = 0 sum(x[0,0,:]*y[:,1,1]) = 0
```

The storage type of "dot" output depends on storage types of inputs, transpose option and forward_stype option for output storage type. Implemented sparse operations include:

- dot(default, default, transpose_a=True/False, transpose_b=True/False) = default - dot(csr, default, transpose_a=True) = default - dot(csr, default, transpose_a=True) = row_sparse - dot(csr, default)
 = default - dot(csr, row_sparse) = default - dot(default, csr) = csr (CPU only) - dot(default, csr, forward_stype='default') = default - dot(default, csr, transpose_b=True, forward_stype='default')
 = default

If the combination of input storage types and forward_stype does not match any of the above patterns, "dot" will fallback and generate output with default storage.

.. Note::

If the storage type of the lhs is "csr", the storage type of gradient w.r.t rhs will be "row_sparse". Only a subset of optimizers support sparse gradients, including SGD, AdaGrad and Adam. Note that by default lazy updates is turned on, which may perform differently from standard updates. For more details, please check the Optimization API at: https://mxnet.incubator.apache.org/api/python/optimization/optimization.html

Defined in src/operator/tensor/dot.cc:L77

Value

118 mx.nd.Dropout

|--|

Description

- During training, each element of the input is set to zero with probability p. The whole array is rescaled by :math: $\frac{1}{1-p}$ to keep the expected sum of the input unchanged.

Arguments

data	NDArray-or-Symbol Input array to which dropout will be applied.
p	float, optional, default=0.5 Fraction of the input that gets dropped out during training time.
mode	'always', 'training',optional, default='training' Whether to only turn on dropout during training or to also turn on for inference.
axes	Shape(tuple), optional, default=[] Axes for variational dropout kernel.
cudnn.off	boolean or None, optional, default=0 Whether to turn off cudnn in dropout operator. This option is ignored if axes is specified.

Details

- During testing, this operator does not change the input if mode is 'training'. If mode is 'always', the same computation as during training will be applied.

Example::

```
random.seed(998) input_array = array([[3., 0.5, -0.5, 2., 7.], [2., -0.4, 7., 3., 0.2]]) a = symbol.Variable('a') dropout = symbol.Dropout(a, p = 0.2) executor = dropout.simple_bind(a = input_array.shape)
```

If training executor.forward(is_train = True, a = input_array) executor.outputs [[3.75 0.625 -0. 2.5 8.75] [2.5 -0.5 8.75 3.75 0.]]

If testing executor.forward(is_train = False, a = input_array) executor.outputs [[3. 0.5 -0.5 2. 7.] [2. -0.4 7. 3. 0.2]]

Defined in src/operator/nn/dropout.cc:L96

Value

mx.nd.ElementWiseSum 119

mx.nd.ElementWiseSum

Adds all input arguments element-wise.

Description

```
.. math:: add\_n(a_1, a_2, ..., a_n) = a_1 + a_2 + ... + a_n
```

Arguments

args

NDArray-or-Symbol[] Positional input arguments

Details

"add_n" is potentially more efficient than calling "add" by 'n' times.

The storage type of "add_n" output depends on storage types of inputs

- add_n(row_sparse, row_sparse, ..) = row_sparse - add_n(default, csr, default) = default - add_n(any input combinations longer than 4 (>4) with at least one default type) = default - otherwise, "add_n" falls all inputs back to default storage and generates default storage

Defined in src/operator/tensor/elemwise_sum.cc:L155

Value

out The result mx.ndarray

mx.nd.elemwise.add

Adds arguments element-wise.

Description

The storage type of "elemwise_add" output depends on storage types of inputs

Arguments

1hs NDArray-or-Symbol first inputrhs NDArray-or-Symbol second input

Details

- elemwise_add(row_sparse, row_sparse) = row_sparse - elemwise_add(csr, csr) = csr - elemwise_add(default, csr) = default - elemwise_add(csr, default) = default - elemwise_add(default, rsp) = default - elemwise_add(rsp, default) = default - otherwise, "elemwise_add" generates output with default storage

Value

120 mx.nd.elemwise.mul

mx.nd.elemwise.div Divides arguments element-wise.

Description

The storage type of "elemwise_div" output is always dense

Arguments

lhs NDArray-or-Symbol first input rhs NDArray-or-Symbol second input

Value

out The result mx.ndarray

mx.nd.elemwise.mul Multiplies arguments element-wise.

Description

The storage type of "elemwise_mul" output depends on storage types of inputs

Arguments

lhs NDArray-or-Symbol first input NDArray-or-Symbol second input rhs

Details

- elemwise_mul(default, default) = default elemwise_mul(row_sparse, row_sparse) = row_sparse elemwise_mul(default, row_sparse) = row_sparse - elemwise_mul(row_sparse, default) = row_sparse
- elemwise_mul(csr, csr) = csr otherwise, "elemwise_mul" generates output with default storage

Value

mx.nd.elemwise.sub

mx.nd.elemwise.sub	Subtracts arguments element-wise.	
--------------------	-----------------------------------	--

Description

The storage type of "elemwise_sub" output depends on storage types of inputs

Arguments

lhs	NDArray-or-Symbol first input
rhs	NDArray-or-Symbol second input

Details

- elemwise_sub(row_sparse, row_sparse) = row_sparse - elemwise_sub(csr, csr) = csr - elemwise_sub(default, csr) = default - elemwise_sub(csr, default) = default - elemwise_sub(default, rsp) = default - elemwise_sub(rsp, default) = default - otherwise, "elemwise_sub" generates output with default storage

Value

out The result mx.ndarray

mx.nd.Embedding Maps integer indices to vector representations (embeddings).
--

Description

This operator maps words to real-valued vectors in a high-dimensional space, called word embeddings. These embeddings can capture semantic and syntactic properties of the words. For example, it has been noted that in the learned embedding spaces, similar words tend to be close to each other and dissimilar words far apart.

Arguments

data	NDArray-or-Symbol The input array to the embedding operator.
weight	NDArray-or-Symbol The embedding weight matrix.
input.dim	int, required Vocabulary size of the input indices.
output.dim	int, required Dimension of the embedding vectors.
dtype	'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, default='float32' Data type of weight.
sparse.grad	boolean, optional, default=0 Compute row sparse gradient in the backward calculation. If set to True, the grad's storage type is row_sparse.

122 mx.nd.erf

Details

For an input array of shape (d1, ..., dK), the shape of an output array is (d1, ..., dK, output_dim). All the input values should be integers in the range [0, input_dim).

If the input_dim is ip0 and output_dim is op0, then shape of the embedding weight matrix must be (ip0, op0).

When "sparse_grad" is False, if any index mentioned is too large, it is replaced by the index that addresses the last vector in an embedding matrix. When "sparse_grad" is True, an error will be raised if invalid indices are found.

Examples::

 $input_dim = 4 output_dim = 5$

// Each row in weight matrix y represents a word. So, y = (w0,w1,w2,w3) y = [[0., 1., 2., 3., 4.], [5., 6., 7., 8., 9.], [10., 11., 12., 13., 14.], [15., 16., 17., 18., 19.]]

// Input array x represents n-grams(2-gram). So, $x = [(w_1, w_3), (w_0, w_2)] x = [[1, 3, 3], [0, 2, 2]]$

// Mapped input x to its vector representation y. Embedding(x, y, 4, 5) = [[[5., 6., 7., 8., 9.], [15., 16., 17., 18., 19.]],

The storage type of weight can be either row_sparse or default.

.. Note:

If "sparse_grad" is set to True, the storage type of gradient w.r.t weights will be "row_sparse". Only a subset of optimizers support sparse gradients, including SGD, AdaGrad and Adam. Note that by default lazy updates is turned on, which may perform differently from standard updates. For more details, please check the Optimization API at: https://mxnet.incubator.apache.org/api/python/optimization/optimization.html Defined in src/operator/tensor/indexing_op.cc:L539

Value

out The result mx.ndarray

mx.nd.erf

Returns element-wise gauss error function of the input.

Description

Example::

Arguments

data

NDArray-or-Symbol The input array.

Details

```
erf([0, -1., 10.]) = [0., -0.8427, 1.]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L886

mx.nd.erfinv 123

Value

out The result mx.ndarray

mx.nd.erfinv

Returns element-wise inverse gauss error function of the input.

Description

Example::

Arguments

data

NDArray-or-Symbol The input array.

Details

```
erfinv([0, 0.5., -1.]) = [0., 0.4769, -inf]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L907

Value

out The result mx.ndarray

mx.nd.exp

Returns element-wise exponential value of the input.

Description

```
.. math:: exp(x) = e^x \cdot approx 2.718^x
```

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

```
\exp([0, 1, 2]) = [1., 2.71828175, 7.38905621]
```

The storage type of "exp" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L63

Value

124 mx.nd.expm1

mx.nd.expand.dims	Inserts a new axis of size 1 into the array shape For example, given " x " with shape " $(2,3,4)$ ", then "expand_dims $(x, axis=1)$ " will return
	a new array with shape "(2,1,3,4)".

Description

Defined in src/operator/tensor/matrix_op.cc:L390

Arguments

data NDArray-or-Symbol Source input

axis int, required Position where new axis is to be inserted. Suppose that the in-

put 'NDArray''s dimension is 'ndim', the range of the inserted axis is '[-ndim,

ndim]'

Value

out The result mx.ndarray

mx.nd.expm1 Returns "exp(x) - 1" computed element-wise on the input.

Description

This function provides greater precision than "exp(x) - 1" for small values of "x".

Arguments

data NDArray-or-Symbol The input array.

Details

The storage type of "expm1" output depends upon the input storage type:

- expm1(default) = default - expm1(row_sparse) = row_sparse - expm1(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L224

Value

mx.nd.fill.element.0index 125

mx.nd.fill.element.0index

Fill one element of each line(row for python, column for R/Julia) in lhs according to index indicated by rhs and values indicated by mhs. This function assume rhs uses 0-based index.

Description

Fill one element of each line(row for python, column for R/Julia) in lhs according to index indicated by rhs and values indicated by mhs. This function assume rhs uses 0-based index.

Arguments

1hs NDArray Left operand to the function.mhs NDArray Middle operand to the function.rhs NDArray Right operand to the function.

Value

out The result mx.ndarray

mx.nd.fix

Returns element-wise rounded value to the nearest \ integer towards zero of the input.

Description

Example::

Arguments

data

NDArray-or-Symbol The input array.

Details

```
fix([-2.1, -1.9, 1.9, 2.1]) = [-2., -1., 1., 2.]
```

The storage type of "fix" output depends upon the input storage type:

- fix(default) = default - fix(row_sparse) = row_sparse - fix(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L875

Value

mx.nd.flatten

mx.nd.Flatten

Flattens the input array into a 2-D array by collapsing the higher dimensions. .. note:: 'Flatten' is deprecated. Use 'flatten' instead. For an input array with shape "(d1, d2, ..., dk)", 'flatten' operation reshapes the input array into an output array of shape "(d1, d2*...*dk)". Note that the behavior of this function is different from numpy.ndarray.flatten, which behaves similar to mxnet.ndarray.reshape((-1, 1)). Example:: x = [[1,2,3], [4,5,6], [7,8,9]], [1,2,3], [4,5,6], [7,8,9]], flatten(x = [1,2,3], [4,5,6], [7,8,9]], flatten(x = [1,2,3], [4,5,6], [7,8,9]]

Description

Defined in src/operator/tensor/matrix_op.cc:L249

Arguments

data

NDArray-or-Symbol Input array.

Value

out The result mx.ndarray

mx.nd.flatten

Flattens the input array into a 2-D array by collapsing the higher dimensions. .. note:: 'Flatten' is deprecated. Use 'flatten' instead. For an input array with shape "(d1, d2, ..., dk)", 'flatten' operation reshapes the input array into an output array of shape "(d1, d2*...*dk)". Note that the behavior of this function is different from numpy.ndarray.flatten, which behaves similar to mxnet.ndarray.reshape((-1,)). Example:: x = [[1,2,3], [4,5,6], [7,8,9]], [1,2,3], [4,5,6], [7,8,9]], flatten(x) = x0 = x1 = x3 = x4 = x5 = x5 = x6 = x7 = x7 = x8 = x9 =

Description

Defined in src/operator/tensor/matrix_op.cc:L249

Arguments

data

NDArray-or-Symbol Input array.

Value

mx.nd.flip

mx.nd.flip Reve

Reverses the order of elements along given axis while preserving array shape. Note: reverse and flip are equivalent. We use reverse in the following examples. Examples:: x = [[0, 1, 2, 3, 4], [5, 6, 7, 8, 9]] reverse(x, axis=0) = [[5, 6, 7, 8, 9], [0, 1, 2, 3, 4]] reverse(x, axis=1) = [[4, 3, 2, 1, 0], [9, 8, 7, 6, 5]]

Description

Defined in src/operator/tensor/matrix_op.cc:L826

Arguments

data NDArray-or-Symbol Input data array

axis Shape(tuple), required The axis which to reverse elements.

Value

out The result mx.ndarray

mx.nd.floor

Returns element-wise floor of the input.

Description

The floor of the scalar x is the largest integer i, such that $i \le x$.

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

```
floor([-2.1, -1.9, 1.5, 1.9, 2.1]) = [-3., -2., 1., 1., 2.]
```

The storage type of "floor" output depends upon the input storage type:

- floor(default) = default - floor(row_sparse) = row_sparse - floor(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L837

Value

128 mx.nd.ftml.update

mx.nd.ftml.update	The	FTML	optimizer	described	in	*FTM	'L -	Follow
	the	Moving	Leader i	n Deep	Learn	ing*,	availa	ble at
	http:	//proceedii	ngs.mlr.press	/v70/zheng1	7a/zhe	ng17a. _l	odf.	

Description

.. math::

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
d	NDArray-or-Symbol Internal state "d_t"
V	NDArray-or-Symbol Internal state "v_t"
Z	NDArray-or-Symbol Internal state "z_t"
lr	float, required Learning rate.
beta1	float, optional, default=0.600000024 Generally close to 0.5.
beta2	float, optional, default=0.999000013 Generally close to 1.
epsilon	double, optional, default=9.9999999392252903e-09 Epsilon to prevent div 0.
t	int, required Number of update.
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.grad	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).

Details

```
 g_t = \addit J(W_t-1) \ v_t = \beta_2 \ v_t-1 + (1 - \beta_2) \ g_t^2 \ d_t = \frac \ 1 - \beta_1^t \ (\sqrt \ \frac \ v_t \ 1 - \beta_2^t + \ensilon) \ sigma_t = d_t - \beta_1 \ d_t-1 \ z_t = \beta_1 \ z_t-1 + (1 - \beta_1^t) \ g_t - \sigma_t \ W_t-1 \ W_t = - \frac \ z_t \ d_t
```

Defined in src/operator/optimizer_op.cc:L638

Value

mx.nd.ftrl.update 129

mx.nd.ftrl.update	Update function for Ftrl optimizer. Referenced from *Ad
	Click Prediction: a View from the Trenches*, available at
	http://dl.acm.org/citation.cfm?id=2488200.

Description

It updates the weights using::

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
z	NDArray-or-Symbol z
n	NDArray-or-Symbol Square of grad
lr	float, required Learning rate
lamda1	float, optional, default=0.00999999978 The L1 regularization coefficient.
beta	float, optional, default=1 Per-Coordinate Learning Rate beta.
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).

Details

```
rescaled_grad = clip(grad * rescale_grad, clip_gradient) z += rescaled_grad - (sqrt(n + rescaled_grad**2) - sqrt(n)) * weight / learning_rate n += rescaled_grad**2 w = (sign(z) * lamda1 - z) / ((beta + sqrt(n)) / learning_rate + wd) * (abs(z) > lamda1)
```

If w, z and n are all of "row_sparse" storage type, only the row slices whose indices appear in grad.indices are updated (for w, z and n)::

for row in grad.indices: rescaled_grad[row] = clip(grad[row] * rescale_grad, clip_gradient) z[row] += rescaled_grad[row] - (sqrt(n[row] + rescaled_grad[row]**2) - sqrt(n[row])) * weight[row] / learning_rate n[row] += rescaled_grad[row]**2 w[row] = (sign(z[row]) * lamda1 - z[row]) / ((beta + sqrt(n[row])) / learning_rate + wd) * (abs(z[row]) > lamda1)

Defined in src/operator/optimizer_op.cc:L874

Value

mx.nd.FullyConnected Applies a linear transformation: :math: $Y = XW^T + b'$.

Description

If "flatten" is set to be true, then the shapes are:

Arguments

data NDArray-or-Symbol Input data.
weight NDArray-or-Symbol Weight matrix.
bias NDArray-or-Symbol Bias parameter.

num. hidden int, required Number of hidden nodes of the output.

no.bias boolean, optional, default=0 Whether to disable bias parameter.

flatten boolean, optional, default=1 Whether to collapse all but the first axis of the input

data tensor.

Details

```
- **data**: '(batch_size, x1, x2, ..., xn)' - **weight**: '(num_hidden, x1 * x2 * ... * xn)' - **bias**: '(num_hidden,)' - **out**: '(batch_size, num_hidden)'
```

If "flatten" is set to be false, then the shapes are:

```
- **data**: '(x1, x2, ..., xn, input_dim)' - **weight**: '(num_hidden, input_dim)' - **bias**: '(num_hidden,)' - **out**: '(x1, x2, ..., xn, num_hidden)'
```

The learnable parameters include both "weight" and "bias".

If "no_bias" is set to be true, then the "bias" term is ignored.

.. Note::

The sparse support for FullyConnected is limited to forward evaluation with 'row_sparse' weight and bias, where the length of 'weight.indices' and 'bias.indices' must be equal to 'num_hidden'. This could be useful for model inference with 'row_sparse' weights trained with importance sampling or noise contrastive estimation.

To compute linear transformation with 'csr' sparse data, sparse.dot is recommended instead of sparse.FullyConnected.

Defined in src/operator/nn/fully_connected.cc:L291

Value

mx.nd.gamma 131

mx.nd.gamma	Returns the gamma function (extension of the factorial function \ to
	the reals), computed element-wise on the input array.

Description

The storage type of "gamma" output is always dense

Arguments

data

NDArray-or-Symbol The input array.

Value

out The result mx.ndarray

 ${\sf mx.nd.gammaln}$

Returns element-wise log of the absolute value of the gamma function \ of the input.

Description

The storage type of "gammaln" output is always dense

Arguments

data

NDArray-or-Symbol The input array.

Value

mx.nd.GridGenerator

mx.nd.gather.nd	Gather elements or slices from 'data' and store to a tensor whose
	shape is defined by 'indices'.

Description

Given 'data' with shape ' $(X_0, X_1, ..., X_{N-1})$ ' and indices with shape ' $(M, Y_0, ..., Y_{K-1})$ ', the output will have shape ' $(Y_0, ..., Y_{K-1}, X_M, ..., X_{N-1})$ ', where ' $M \le N$ '. If 'M = N', output shape will simply be ' $(Y_0, ..., Y_{K-1})$ '.

Arguments

data NDArray-or-Symbol data indices NDArray-or-Symbol indices

Details

The elements in output is defined as follows::

```
output[y_0, ..., y_K-1, x_M, ..., x_N-1] = data[indices[0, y_0, ..., y_K-1], ..., indices[M-1, y_0, ..., y_K-1], x_M, ..., x_N-1]
```

Examples::

```
data = [[0, 1], [2, 3]] indices = [[1, 1, 0], [0, 1, 0]] gather_nd(data, indices) = [2, 3, 0]
data = [[[1, 2], [3, 4]], [[5, 6], [7, 8]]] indices = [[0, 1], [1, 0]] gather_nd(data, indices) = [[3, 4], [5, 6]]
```

Value

out The result mx.ndarray

mx.nd.GridGenerator Generates 2D sampling grid for bilinear sampling.

Description

Generates 2D sampling grid for bilinear sampling.

Arguments

data	NDArray-or-Symbol Input data to the function.

transform.type 'affine', 'warp', required The type of transformation. For 'affine', input data

should be an affine matrix of size (batch, 6). For 'warp', input data should be an

optical flow of size (batch, 2, h, w).

target.shape Shape(tuple), optional, default=[0,0] Specifies the output shape (H, W). This is

required if transformation type is 'affine'. If transformation type is 'warp', this

parameter is ignored.

mx.nd.GroupNorm 133

Value

out The result mx.ndarray

mx.nd.GroupNorm

Group normalization.

Description

The input channels are separated into "num_groups" groups, each containing "num_channels / num_groups" channels. The mean and standard-deviation are calculated separately over the each group.

Arguments

data NDArray-or-Symbol Input data

gamma NDArray-or-Symbol gamma array

beta NDArray-or-Symbol beta array

num.groups int, optional, default='1' Total number of groups.

eps float, optional, default=9.99999975e-06 An 'epsilon' parameter to prevent divi-

sion by 0.

output.mean.var

boolean, optional, default=0 Output the mean and std calculated along the given

axis.

Details

.. math::

 $\label{eq:data} $$ data = data.reshape((N, num_groups, C // num_groups, ...)) out = \frac{a - mean(data, axis)}{qata - mean(data, axis)} $$ axis) + epsilon * gamma + beta $$ axis) + constant $$ axis + cons$

Both "gamma" and "beta" are learnable parameters.

Defined in src/operator/nn/group_norm.cc:L77

Value

mx.nd.identity

mx.nd.hard.sigmoid

Computes hard sigmoid of x element-wise.

Description

```
.. math:: y = max(0, min(1, alpha * x + beta))
```

Arguments

data NDArray-or-Symbol The input array.

alpha float, optional, default=0.200000003 Slope of hard sigmoid

beta float, optional, default=0.5 Bias of hard sigmoid.

Details

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L161

Value

out The result mx.ndarray

mx.nd.identity

Returns a copy of the input.

Description

From:src/operator/tensor/elemwise_unary_op_basic.cc:246

Arguments

data

NDArray-or-Symbol The input array.

Value

mx.nd.IdentityAttachKLSparseReg

Apply a sparse regularization to the output a sigmoid activation function.

Description

Apply a sparse regularization to the output a sigmoid activation function.

Arguments

data NDArray-or-Symbol Input data.

sparseness.target

float, optional, default=0.100000001 The sparseness target

penalty float, optional, default=0.00100000005 The tradeoff parameter for the sparse-

ness penalty

momentum float, optional, default=0.899999976 The momentum for running average

Value

out The result mx.ndarray

mx.nd.InstanceNorm Applies instance normalization to the n-dimensional input array.

Description

This operator takes an n-dimensional input array where (n>2) and normalizes the input using the following formula:

Arguments

data	NDArray-or-Symbol An n-dimensional input array $(n > 2)$ of the form [batch, channel, spatial_dim1, spatial_dim2,].
gamma	NDArray-or-Symbol A vector of length 'channel', which multiplies the normalized input.
beta	NDArray-or-Symbol A vector of length 'channel', which is added to the product of the normalized input and the weight.
eps	float, optional, default=0.00100000005 An 'epsilon' parameter to prevent division by 0.

mx.nd.khatri.rao

Details

.. math::

```
out = \fracx - mean[data] \sqrtVar[data] + \epsilon * gamma + beta
```

This layer is similar to batch normalization layer ('BatchNorm') with two differences: first, the normalization is carried out per example (instance), not over a batch. Second, the same normalization is applied both at test and train time. This operation is also known as 'contrast normalization'.

If the input data is of shape [batch, channel, spacial_dim1, spacial_dim2, ...], 'gamma' and 'beta' parameters must be vectors of shape [channel].

This implementation is based on this paper [1]_

.. [1] Instance Normalization: The Missing Ingredient for Fast Stylization, D. Ulyanov, A. Vedaldi, V. Lempitsky, 2016 (arXiv:1607.08022v2).

Examples::

```
// Input of shape (2,1,2) x = [[[ 1.1, 2.2]], [[ 3.3, 4.4]]]
```

// gamma parameter of length 1 gamma = [1.5]

// beta parameter of length 1 beta = [0.5]

// Instance normalization is calculated with the above formula InstanceNorm(x,gamma,beta) = [[[-0.997527, 1.99752665]], [[-0.99752653, 1.99752724]]]

Defined in src/operator/instance_norm.cc:L95

Value

out The result mx.ndarray

mx.nd.khatri.rao

Computes the Khatri-Rao product of the input matrices.

Description

Given a collection of :math: 'n' input matrices,

Arguments

args

NDArray-or-Symbol[] Positional input matrices

Details

```
.. math:: A 1 \in \mathbbR^M 1 \times M, ..., A n \in \mathbbR^M n \times N,
```

the (column-wise) Khatri-Rao product is defined as the matrix,

.. math:: $X = A_1 \cdot A_1 \cdot A_n \cdot A_$

where the :math:'k' th column is equal to the column-wise outer product :math:'A_1_k \otimes \cdots \otimes A_n_k' where :math:'A_i_k' is the kth column of the ith matrix.

Example::

mx.nd.L2Normalization 137

```
»> A = mx.nd.array([[1, -1], »> [2, -3]]) »> B = mx.nd.array([[1, 4], »> [2, 5], »> [3, 6]]) »> C =
mx.nd.khatri_rao(A, B) »> print(C.asnumpy()) [[ 1. -4.] [ 2. -5.] [ 3. -6.] [ 2. -12.] [ 4. -15.] [ 6.
-18.]]
```

Defined in src/operator/contrib/krprod.cc:L108

Value

out The result mx.ndarray

mx.nd.L2Normalization Normalize the input array using the L2 norm.

Description

For 1-D NDArray, it computes::

Arguments

data NDArray-or-Symbol Input array to normalize.

eps float, optional, default=1.00000001e-10 A small constant for numerical stability.

mode 'channel', 'instance', 'spatial',optional, default='instance' Specify the dimen-

sion along which to compute L2 norm.

Details

```
out = data / sqrt(sum(data ** 2) + eps)
```

For N-D NDArray, if the input array has shape (N, N, ..., N),

with "mode" = "instance", it normalizes each instance in the multidimensional array by its L2 norm.::

```
for i in 0...N out[i,:,:,...,:] = data[i,:,:,...,:] / sqrt(sum(data[i,:,:,...,:] ** 2) + eps)
```

with "mode" = "channel", it normalizes each channel in the array by its L2 norm.::

```
for i in 0...N out[:,i,:,...,:] = data[:,i,:,...,:] / sqrt(sum(data[:,i,:,...,:] ** 2) + eps)
```

with "mode" = "spatial", it normalizes the cross channel norm for each position in the array by its L2 norm.::

for dim in 2...N for i in 0...N out[....,i,...] = take(out, indices=i, axis=dim) / sqrt(sum(take(out, indices=i, axis=dim) ** 2) + eps) -dim-

Example::

```
x = [[[1,2], [3,4]], [[2,2], [5,6]]]
```

L2Normalization(x, mode='instance') =[[[0.18257418 0.36514837] [0.54772252 0.73029673]] [[0.24077171 0.24077171] [0.60192931 0.72231513]]]

L2Normalization(x, mode='channel') =[[[0.31622776 0.44721359] [0.94868326 0.89442718]] [[0.37139067 0.31622776] [0.92847669 0.94868326]]

L2Normalization(x, mode='spatial') =[[[0.44721359 0.89442718] [0.60000002 0.80000001]] [[0.70710677 0.70710677] [0.6401844 0.76822126]]]

Defined in src/operator/l2_normalization.cc:L196

138 mx.nd.LayerNorm

Value

out The result mx.ndarray

Description

Normalizes the channels of the input tensor by mean and variance, and applies a scale "gamma" as well as offset "beta".

Arguments

data	NDArray-or-Symbol Input data to layer normalization
gamma	NDArray-or-Symbol gamma array
beta	NDArray-or-Symbol beta array
axis	int, optional, default='-1' The axis to perform layer normalization. Usually, this should be be axis of the channel dimension. Negative values means indexing from right to left.
eps	float, optional, default=9.99999975e-06 An 'epsilon' parameter to prevent division by 0.
output.mean.var	
	boolean, optional, default=0 Output the mean and std calculated along the given axis.

Details

Assume the input has more than one dimension and we normalize along axis 1. We first compute the mean and variance along this axis and then compute the normalized output, which has the same shape as input, as following:

```
.. math:
```

out = \fracdata - mean(data, axis)\sqrtvar(data, axis) + \epsilon * gamma + beta

Both "gamma" and "beta" are learnable parameters.

Unlike BatchNorm and InstanceNorm, the *mean* and *var* are computed along the channel dimension.

Assume the input has size k^* on axis 1, then both "gamma" and "beta" have shape k,k. If "output_mean_var" is set to be true, then outputs both "data_mean" and "data_std". Note that no gradient will be passed through these two outputs.

The parameter "axis" specifies which axis of the input shape denotes the 'channel' (separately normalized groups). The default is -1, which sets the channel axis to be the last item in the input shape.

Defined in src/operator/nn/layer_norm.cc:L156

mx.nd.LeakyReLU 139

Value

out The result mx.ndarray

mx.nd.LeakyReLU Applies Leaky rectified linear unit activation element-wise to the input.	mx.nd.LeakyReLU	Applies Leaky rectified linear unit activation element-wise to the input.
---	-----------------	---

Description

Leaky ReLUs attempt to fix the "dying ReLU" problem by allowing a small 'slope' when the input is negative and has a slope of one when input is positive.

Arguments

data	NDArray-or-Symbol Input data to activation function.
gamma	NDArray-or-Symbol Input data to activation function.
act.type	'elu', 'gelu', 'leaky', 'prelu', 'rrelu', 'selu',optional, default='leaky' Activation function to be applied.
slope	float, optional, default=0.25 Init slope for the activation. (For leaky and elu only)
lower.bound	float, optional, default=0.125 Lower bound of random slope. (For rrelu only)
upper.bound	float, optional, default=0.333999991 Upper bound of random slope. (For rrelu only)

Details

The following modified ReLU Activation functions are supported:

```
- *elu*: Exponential Linear Unit. 'y = x > 0 ? x : slope * (exp(x)-1)' - *selu*: Scaled Exponential Linear Unit. 'y = lambda * (x > 0 ? x : alpha * (exp(x) - 1))' where *lambda = 1.0507009873554804934193349852946* and *alpha = 1.6732632423543772848170429916717*. - *leaky*: Leaky ReLU. 'y = x > 0 ? x : slope * x' - *prelu*: Parametric ReLU. This is same as *leaky* except that 'slope' is learnt during training. - *rrelu*: Randomized ReLU. same as *leaky* but the 'slope' is uniformly and randomly chosen from *[lower_bound, upper_bound)* for training, while fixed to be *(lower_bound+upper_bound)/2* for inference.
```

Defined in src/operator/leaky_relu.cc:L161

Value

mx.nd.linalg.det

Compute the determinant of a matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, *A* is a square matrix. We compute:

Arguments

Α

NDArray-or-Symbol Tensor of square matrix

Details

```
*out* = *det(A)*
```

If *n>2*, *det* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only. .. note:: There is no gradient backwarded when A is non-invertible (which is equivalent to det(A) = 0) because zero is rarely hit upon in float point computation and the Jacobi's formula on determinant gradient is not computationally efficient when A is non-invertible.

Examples::

Single matrix determinant A = [[1., 4.], [2., 3.]] det(A) = [-5.]

Batch matrix determinant A = [[[1., 4.], [2., 3.]], [[2., 3.], [1., 4.]]] det(A) = [-5., 5.]

Defined in src/operator/tensor/la_op.cc:L970

Value

out The result mx.ndarray

```
mx.nd.linalg.extractdiag
```

Extracts the diagonal entries of a square matrix. Input is a tensor A^* of dimension $n \ge 2$.

Description

If *n=2*, then *A* represents a single square matrix which diagonal elements get extracted as a 1-dimensional tensor.

Arguments

Α

NDArray-or-Symbol Tensor of square matrices

offset

int, optional, default='0' Offset of the diagonal versus the main diagonal. 0 corresponds to the main diagonal, a negative/positive value to diagonals below/above the main diagonal.

Details

If *n>2*, then *A* represents a batch of square matrices on the trailing two dimensions. The extracted diagonals are returned as an *n-1*-dimensional tensor.

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix diagonal extraction A = [[1.0, 2.0], [3.0, 4.0]]

extractdiag(A) = [1.0, 4.0]

extractdiag(A, 1) = [2.0]

Batch matrix diagonal extraction A = [[[1.0, 2.0], [3.0, 4.0]], [[5.0, 6.0], [7.0, 8.0]]]

extractdiag(A) = [[1.0, 4.0], [5.0, 8.0]]

Defined in src/operator/tensor/la_op.cc:L495

Value

out The result mx.ndarray

mx.nd.linalg.extracttrian

Extracts a triangular sub-matrix from a square matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, then *A* represents a single square matrix from which a triangular sub-matrix is extracted as a 1-dimensional tensor.

Arguments

A NDArray-or-Symbol Tensor of square matrices

offset int, optional, default='0' Offset of the diagonal versus the main diagonal. 0

corresponds to the main diagonal, a negative/positive value to diagonals be-

low/above the main diagonal.

lower boolean, optional, default=1 Refer to the lower triangular matrix if lower=true,

refer to the upper otherwise. Only relevant when offset=0

Details

If *n>2*, then *A* represents a batch of square matrices on the trailing two dimensions. The extracted triangular sub-matrices are returned as an *n-1*-dimensional tensor.

The *offset* and *lower* parameters determine the triangle to be extracted:

- When *offset = 0* either the lower or upper triangle with respect to the main diagonal is extracted depending on the value of parameter *lower*. - When *offset = k > 0* the upper triangle with

mx.nd.linalg.gelqf

respect to the k-th diagonal above the main diagonal is extracted. - When *offset = k < 0* the lower triangle with respect to the k-th diagonal below the main diagonal is extracted.

.. note:: The operator supports float32 and float64 data types only.

Examples::

```
Single triagonal extraction A = [[1.0, 2.0], [3.0, 4.0]]
```

extracttrian(A) = [1.0, 3.0, 4.0] extracttrian(A, lower=False) = [1.0, 2.0, 4.0] extracttrian(A, 1) = [2.0] extracttrian(A, -1) = [3.0]

Batch triagonal extraction A = [[[1.0, 2.0], [3.0, 4.0]], [[5.0, 6.0], [7.0, 8.0]]]

extracttrian(A) = [[1.0, 3.0, 4.0], [5.0, 7.0, 8.0]]

Defined in src/operator/tensor/la_op.cc:L605

Value

out The result mx.ndarray

mx.nd.linalg.gelqf LQ factorization for general matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, we compute the LQ factorization (LAPACK *gelqf*, followed by *orglq*). *A* must have shape *(x, y)* with *x <= y*, and must have full rank *=x*. The LQ factorization consists of *L* with shape *(x, x)* and *Q* with shape *(x, y)*, so that:

Arguments

Α

NDArray-or-Symbol Tensor of input matrices to be factorized

Details

```
*A* = *L* \ **O*
```

Here, $^*L^*$ is lower triangular (upper triangle equal to zero) with nonzero diagonal, and $^*Q^*$ is row-orthonormal, meaning that

```
*Q* \* *Q*\ :sup:'T'
```

is equal to the identity matrix of shape *(x, x)*.

If *n>2*, *gelqf* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single LQ factorization A = [[1., 2., 3.], [4., 5., 6.]] Q, L = gelqf(A) Q = [[-0.26726124, -0.53452248, -0.80178373], [0.87287156, 0.21821789, -0.43643578]] L = [[-3.74165739, 0.], [-8.55235974, 1.96396101]]

mx.nd.linalg.gemm 143

Batch LQ factorization A = [[[1., 2., 3.], [4., 5., 6.]], [[7., 8., 9.], [10., 11., 12.]]] Q, L = gelqf(A) Q = [[[-0.26726124, -0.53452248, -0.80178373], [0.87287156, 0.21821789, -0.43643578]], [[-0.50257071, -0.57436653, -0.64616234], [0.7620735, 0.05862104, -0.64483142]]] L = [[[-3.74165739, 0.], [-8.55235974, 1.96396101]], [[-13.92838828, 0.], [-19.09768702, 0.52758934]]]

Defined in src/operator/tensor/la_op.cc:L798

Value

out The result mx.ndarray

mx.nd.linalg.gemm	Performs general matrix multiplication and accumulation. Input are tensors $*A*$, $*B*$, $*C*$, each of dimension $*n >= 2*$ and having the same shape on the leading $*n-2*$ dimensions.
	•

Description

If *n=2*, the BLAS3 function *gemm* is performed:

Arguments

A	NDArray-or-Symbol Tensor of input matrices
В	NDArray-or-Symbol Tensor of input matrices
С	NDArray-or-Symbol Tensor of input matrices
transpose.a	boolean, optional, default=0 Multiply with transposed of first input (A).
transpose.b	boolean, optional, default=0 Multiply with transposed of second input (B).
alpha	double, optional, default=1 Scalar factor multiplied with A*B.
beta	double, optional, default=1 Scalar factor multiplied with C.
axis	int, optional, default='-2' Axis corresponding to the matrix rows.

Details

```
*out* = *alpha* \ **op* \ (*A*) \ **op* \ (*B*) + *beta* \ **C*
```

Here, *alpha* and *beta* are scalar parameters, and *op()* is either the identity or matrix transposition (depending on *transpose_a*, *transpose_b*).

If *n>2*, *gemm* is performed separately for a batch of matrices. The column indices of the matrices are given by the last dimensions of the tensors, the row indices by the axis specified with the *axis* parameter. By default, the trailing two dimensions will be used for matrix encoding.

For a non-default axis parameter, the operation performed is equivalent to a series of swapaxes/gemm/swapaxes calls. For example let *A*, *B*, *C* be 5 dimensional tensors. Then gemm(*A*, *B*, *C*, axis=1) is equivalent to the following without the overhead of the additional swapaxis operations::

A1 = swapaxes(A, dim1=1, dim2=3) B1 = swapaxes(B, dim1=1, dim2=3) C = swapaxes(C, dim1=1, dim2=3) C = gemm(A1, B1, C) C = swapaxis(C, dim1=1, dim2=3)

144 mx.nd.linalg.gemm2

When the input data is of type float32 and the environment variables MXNET_CUDA_ALLOW_TENSOR_CORE and MXNET_CUDA_TENSOR_OP_MATH_ALLOW_CONVERSION are set to 1, this operator will try to use pseudo-float16 precision (float32 math with float16 I/O) precision in order to use Tensor Cores on suitable NVIDIA GPUs. This can sometimes give significant speedups.

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix multiply-add $A = [[1.0, 1.0], [1.0, 1.0]] B = [[1.0, 1.0], [1.0, 1.0], [1.0, 1.0]] C = [[1.0, 1.0, 1.0], [1.0, 1.0], [1.0, 1.0]] gemm(A, B, C, transpose_b=True, alpha=2.0, beta=10.0) = [[14.0, 14.0, 14.0], [14.0, 14.0, 14.0]]$

Batch matrix multiply-add $A = [[[1.0, 1.0]], [[0.1, 0.1]]] B = [[[1.0, 1.0]], [[0.1, 0.1]]] C = [[[10.0]], [[0.01]]] gemm(A, B, C, transpose_b=True, alpha=2.0, beta=10.0) = [[[104.0]], [[0.14]]]$

Defined in src/operator/tensor/la_op.cc:L89

Value

out The result mx.ndarray

mx.nd.linalg.gemm2 Performs general matrix multiplication. Input are tensors *A*, *B*, each of dimension *n >= 2* and having the same shape on the leading *n-2* dimensions.

Description

If *n=2*, the BLAS3 function *gemm* is performed:

Arguments

A NDArray-or-Symbol Tensor of input matrices

B NDArray-or-Symbol Tensor of input matrices

transpose.a boolean, optional, default=0 Multiply with transposed of first input (A). transpose.b boolean, optional, default=0 Multiply with transposed of second input (B).

alpha double, optional, default=1 Scalar factor multiplied with A*B.

axis int, optional, default='-2' Axis corresponding to the matrix row indices.

Details

```
*out* = *alpha* \ **op*\ (*A*) \ **op*\ (*B*)
```

Here *alpha* is a scalar parameter and *op()* is either the identity or the matrix transposition (depending on *transpose_a*, *transpose_b*).

If *n>2*, *gemm* is performed separately for a batch of matrices. The column indices of the matrices are given by the last dimensions of the tensors, the row indices by the axis specified with the *axis* parameter. By default, the trailing two dimensions will be used for matrix encoding.

mx.nd.linalg.inverse 145

For a non-default axis parameter, the operation performed is equivalent to a series of swapaxes/gemm/swapaxes calls. For example let *A*, *B* be 5 dimensional tensors. Then gemm(*A*, *B*, axis=1) is equivalent to the following without the overhead of the additional swapaxis operations::

```
A1 = swapaxes(A, dim1=1, dim2=3) B1 = swapaxes(B, dim1=1, dim2=3) C = gemm2(A1, B1) C = swapaxis(C, dim1=1, dim2=3)
```

When the input data is of type float32 and the environment variables MXNET_CUDA_ALLOW_TENSOR_CORE and MXNET_CUDA_TENSOR_OP_MATH_ALLOW_CONVERSION are set to 1, this operator will try to use pseudo-float16 precision (float32 math with float16 I/O) precision in order to use Tensor Cores on suitable NVIDIA GPUs. This can sometimes give significant speedups.

.. note:: The operator supports float32 and float64 data types only.

Examples::

```
Single matrix multiply A = [[1.0, 1.0], [1.0, 1.0]] B = [[1.0, 1.0], [1.0, 1.0], [1.0, 1.0]] gemm2(A, B, transpose_b=True, alpha=2.0) = [[4.0, 4.0, 4.0], [4.0, 4.0, 4.0]]
```

Batch matrix multiply $A = [[[1.0, 1.0]], [[0.1, 0.1]]] B = [[[1.0, 1.0]], [[0.1, 0.1]]] gemm2(A, B, transpose_b=True, alpha=<math>2.0$) = [[[4.0]], [[0.04]]]

Defined in src/operator/tensor/la_op.cc:L163

Value

out The result mx.ndarray

```
mx.nd.linalg.inverse Compute the inverse of a matrix. Input is a tensor *A* of dimension *n >= 2*.
```

Description

If *n=2*, *A* is a square matrix. We compute:

Arguments

A NDArray-or-Symbol Tensor of square matrix

Details

```
*out* = *A* \ :sup:'-1'
```

If *n>2*, *inverse* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

```
Single matrix inverse A = [[1., 4.], [2., 3.]] inverse(A) = [[-0.6, 0.8], [0.4, -0.2]] Batch matrix inverse A = [[[1., 4.], [2., 3.]], [[1., 3.], [2., 4.]]] inverse(A) = [[[-0.6, 0.8], [0.4, -0.2]], [[-2., 1.5], [1., -0.5]]]
```

Defined in src/operator/tensor/la_op.cc:L917

Value

out The result mx.ndarray

mx.nd.linalg.makediag Constructs a square matrix with the input as diagonal. Input is a tensor *A* of dimension *n >= 1*.

Description

If *n=1*, then *A* represents the diagonal entries of a single square matrix. This matrix will be returned as a 2-dimensional tensor. If *n>1*, then *A* represents a batch of diagonals of square matrices. The batch of diagonal matrices will be returned as an *n+1*-dimensional tensor.

Arguments

A NDArray-or-Symbol Tensor of diagonal entries

offset int, optional, default='0' Offset of the diagonal versus the main diagonal. 0

corresponds to the main diagonal, a negative/positive value to diagonals be-

low/above the main diagonal.

Details

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single diagonal matrix construction A = [1.0, 2.0]

makediag(A) = [[1.0, 0.0], [0.0, 2.0]]

makediag(A, 1) = [[0.0, 1.0, 0.0], [0.0, 0.0, 2.0], [0.0, 0.0, 0.0]]

Batch diagonal matrix construction A = [[1.0, 2.0], [3.0, 4.0]]

makediag(A) = [[[1.0, 0.0], [0.0, 2.0]], [[3.0, 0.0], [0.0, 4.0]]]

Defined in src/operator/tensor/la_op.cc:L547

Value

mx.nd.linalg.maketrian

mx.nd.linalg.maketrian

Constructs a square matrix with the input representing a specific triangular sub-matrix. This is basically the inverse of *linalg.extracttrian*. Input is a tensor *A* of dimension *n >= 1*.

147

Description

If *n=1*, then *A* represents the entries of a triangular matrix which is lower triangular if *off-set<0* or *offset=0*, *lower=true*. The resulting matrix is derived by first constructing the square matrix with the entries outside the triangle set to zero and then adding *offset*-times an additional diagonal with zero entries to the square matrix.

Arguments

A NDArray-or-Symbol Tensor of triangular matrices stored as vectors

offset int, optional, default='0' Offset of the diagonal versus the main diagonal. 0

corresponds to the main diagonal, a negative/positive value to diagonals be-

low/above the main diagonal.

lower boolean, optional, default=1 Refer to the lower triangular matrix if lower=true,

refer to the upper otherwise. Only relevant when offset=0

Details

If *n>1*, then *A* represents a batch of triangular sub-matrices. The batch of corresponding square matrices is returned as an *n+1*-dimensional tensor.

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix construction A = [1.0, 2.0, 3.0]

maketrian(A) = [[1.0, 0.0], [2.0, 3.0]]

maketrian(A, lower=false) = [[1.0, 2.0], [0.0, 3.0]]

maketrian(A, offset=1) = [[0.0, 1.0, 2.0], [0.0, 0.0, 3.0], [0.0, 0.0, 0.0]] maketrian(A, offset=-1) = [[0.0, 0.0, 0.0], [1.0, 0.0, 0.0], [2.0, 3.0, 0.0]]

Batch matrix construction A = [[1.0, 2.0, 3.0], [4.0, 5.0, 6.0]]

maketrian(A) = [[[1.0, 0.0], [2.0, 3.0]], [[4.0, 0.0], [5.0, 6.0]]]

maketrian(A, offset=1) = [[[0.0, 1.0, 2.0], [0.0, 0.0, 3.0], [0.0, 0.0, 0.0]], [[0.0, 4.0, 5.0], [0.0, 0.0, 6.0], [0.0, 0.0, 0.0]]]

Defined in src/operator/tensor/la_op.cc:L673

Value

148 mx.nd.linalg.potri

mx.nd.linalg.potrf	Performs Cholesky factorization of a symmetric positive-definite ma-
	trix. Input is a tensor A^* of dimension $n \ge 2$.

Description

If *n=2*, the Cholesky factor *B* of the symmetric, positive definite matrix *A* is computed. *B* is triangular (entries of upper or lower triangle are all zero), has positive diagonal entries, and:

Arguments

Α

NDArray-or-Symbol Tensor of input matrices to be decomposed

Details

```
*A* = *B* \* *B*\ :sup: 'T' if *lower* = *true* *A* = *B*\ :sup: 'T' \* *B* if *lower* = *false*
```

If *n>2*, *potrf* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix factorization A = [[4.0, 1.0], [1.0, 4.25]] potrf(A) = [[2.0, 0], [0.5, 2.0]]

Batch matrix factorization A = [[[4.0, 1.0], [1.0, 4.25]], [[16.0, 4.0], [4.0, 17.0]]] potrf(A) = [[[2.0, 0], [0.5, 2.0]], [[4.0, 0], [1.0, 4.0]]]

Defined in src/operator/tensor/la_op.cc:L214

Value

out The result mx.ndarray

mx.nd.linalg.potri	Performs matrix inversion from a Cholesky factorization.	Input is a
	tensor $*A*$ of dimension $*n \ge 2*$.	

Description

If *n=2*, *A* is a triangular matrix (entries of upper or lower triangle are all zero) with positive diagonal. We compute:

Arguments

A NDArray-or-Symbol Tensor of lower triangular matrices

mx.nd.linalg.slogdet 149

Details

```
*out* = *A*\ :sup:'-T' \* *A*\ :sup:'-1' if *lower* = *true* *out* = *A*\ :sup:'-1' \* *A*\ :sup:'-T' if *lower* = *false*
```

In other words, if *A* is the Cholesky factor of a symmetric positive definite matrix *B* (obtained by *potrf*), then

```
*out* = *B*\ :sup:'-1'
```

If *n>2*, *potri* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

.. note:: Use this operator only if you are certain you need the inverse of *B*, and cannot use the Cholesky factor *A* (*potrf*), together with backsubstitution (*trsm*). The latter is numerically much safer, and also cheaper.

Examples::

Single matrix inverse A = [[2.0, 0], [0.5, 2.0]] potri(A) = [[0.26563, -0.0625], [-0.0625, 0.25]]

Batch matrix inverse A = [[[2.0, 0], [0.5, 2.0]], [[4.0, 0], [1.0, 4.0]]] potri(A) = [[[0.26563, -0.0625], [-0.0625, 0.25]], [[0.06641, -0.01562], [-0.01562, 0.0625]]]

Defined in src/operator/tensor/la_op.cc:L275

Value

out The result mx.ndarray

mx.nd.linalg.slogdet Compute the sign and log of the determinant of a matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, *A* is a square matrix. We compute:

Arguments

Α

NDArray-or-Symbol Tensor of square matrix

Details

```
*sign* = *sign(det(A))* *logabsdet* = *log(abs(det(A)))*
```

If *n>2*, *slogdet* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only. .. note:: The gradient is not properly defined on sign, so the gradient of it is not backwarded. .. note:: No gradient is backwarded when A is non-invertible. Please see the docs of operator det for detail.

Examples::

Single matrix signed log determinant A = [[2., 3.], [1., 4.]] sign, logabsdet = slogdet(A) sign = [1.] logabsdet = [1.609438]

Batch matrix signed log determinant A = [[[2., 3.], [1., 4.]], [[1., 2.], [2., 4.]], [[1., 2.], [4., 3.]]] sign, logabsdet = slogdet(A) sign = [1., 0., -1.] logabsdet = [1.609438, -inf, 1.609438]

Defined in src/operator/tensor/la_op.cc:L1027

Value

out The result mx.ndarray

mx.nd.linalg.sumlogdiag

Computes the sum of the logarithms of the diagonal elements of a square matrix. Input is a tensor *A* of dimension $*n \ge 2*$.

Description

If *n=2*, *A* must be square with positive diagonal entries. We sum the natural logarithms of the diagonal elements, the result has shape (1,).

Arguments

A NDArray-or-Symbol Tensor of square matrices

Details

If *n>2*, *sumlogdiag* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix reduction A = [[1.0, 1.0], [1.0, 7.0]] sumlogdiag(A) = [1.9459]

Batch matrix reduction A = [[[1.0, 1.0], [1.0, 7.0]], [[3.0, 0], [0, 17.0]]] sumlogdiag(A) = [1.9459, 3.9318]

Defined in src/operator/tensor/la_op.cc:L445

Value

mx.nd.linalg.syrk 151

mx.nd.linalg.syrk Multiplication of matrix with its transpose. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, the operator performs the BLAS3 function *syrk*:

Arguments

A NDArray-or-Symbol Tensor of input matrices

transpose boolean, optional, default=0 Use transpose of input matrix.

alpha double, optional, default=1 Scalar factor to be applied to the result.

Details

```
*out* = *alpha* \* *A* \* *A*\ :sup:'T'
```

if *transpose=False*, or

out = *alpha* * *A*\ :sup: 'T' \ * *A*

if *transpose=True*.

If *n>2*, *syrk* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix multiply A = [[1., 2., 3.], [4., 5., 6.]] syrk(A, alpha=1., transpose=False) = [[14., 32.], [32., 77.]] syrk(A, alpha=1., transpose=True) = [[17., 22., 27.], [22., 29., 36.], [27., 36., 45.]]

Batch matrix multiply A = [[[1., 1.]], [[0.1, 0.1]]] syrk(A, alpha=2., transpose=False) = [[[4.]], [[0.04]]]

Defined in src/operator/tensor/la_op.cc:L730

Value

mx.nd.linalg.trmm

mx.nd.linalg.trmm	Performs multiplication with a lower triangular matrix. Input are tensors $*A*$, $*B*$, each of dimension $*n >= 2*$ and having the same shape on the leading $*n-2*$ dimensions.

Description

If *n=2*, *A* must be triangular. The operator performs the BLAS3 function *trmm*:

Arguments

A	NDArray-or-Symbol Tensor of lower triangular matrices
В	NDArray-or-Symbol Tensor of matrices
transpose	boolean, optional, default=0 Use transposed of the triangular matrix
rightside	boolean, optional, default=0 Multiply triangular matrix from the right to non-triangular one.
lower	boolean, optional, default=1 True if the triangular matrix is lower triangular, false if it is upper triangular.
alpha	double, optional, default=1 Scalar factor to be applied to the result.

Details

```
*out* = *alpha* \* *op*\ (*A*) \* *B*
if *rightside=False*, or
*out* = *alpha* \* *B* \* *op*\ (*A*)
```

if *rightside=True*. Here, *alpha* is a scalar parameter, and *op()* is either the identity or the matrix transposition (depending on *transpose*).

If *n>2*, *trmm* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single triangular matrix multiply A = [[1.0, 0], [1.0, 1.0]] B = [[1.0, 1.0, 1.0], [1.0, 1.0, 1.0]] trmm(A, B, alpha=2.0) = [[2.0, 2.0, 2.0], [4.0, 4.0, 4.0]]

Batch triangular matrix multiply A = [[[1.0, 0], [1.0, 1.0]], [[1.0, 0], [1.0, 1.0]]] B = [[[1.0, 1.0, 1.0], [1.0, 1.0]], [[0.5, 0.5, 0.5], [0.5, 0.5, 0.5]]] trmm(A, B, alpha=2.0) = [[[2.0, 2.0, 2.0], [4.0, 4.0, 4.0]], [[1.0, 1.0, 1.0], [2.0, 2.0, 2.0]]]

Defined in src/operator/tensor/la_op.cc:L333

Value

mx.nd.linalg.trsm 153

mx.nd.linalg.trsm	Solves matrix equation involving a lower triangular matrix. Input are tensors $*A*$, $*B*$, each of dimension $*n >= 2*$ and having the same shape on the leading $*n-2*$ dimensions.
	snape on the leading "n-2" aimensions.

Description

If *n=2*, *A* must be triangular. The operator performs the BLAS3 function *trsm*, solving for *out* in:

Arguments

Α	NDArray-or-Symbol Tensor of lower triangular matrices
В	NDArray-or-Symbol Tensor of matrices
transpose	boolean, optional, default=0 Use transposed of the triangular matrix
rightside	boolean, optional, default=0 Multiply triangular matrix from the right to non-triangular one.
lower	boolean, optional, default=1 True if the triangular matrix is lower triangular, false if it is upper triangular.

double, optional, default=1 Scalar factor to be applied to the result.

Details

alpha

```
*op*\(*A*)\* *out* = *alpha* \* *B*
if *rightside=False*, or
*out* \* *op*\(*A*) = *alpha* \* *B*
```

if *rightside=True*. Here, *alpha* is a scalar parameter, and *op()* is either the identity or the matrix transposition (depending on *transpose*).

If *n>2*, *trsm* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix solve A = [[1.0, 0], [1.0, 1.0]] B = [[2.0, 2.0, 2.0], [4.0, 4.0, 4.0]] trsm(A, B, alpha=0.5) = [[1.0, 1.0, 1.0], [1.0, 1.0, 1.0]]

Batch matrix solve A = [[[1.0, 0], [1.0, 1.0]], [[1.0, 0], [1.0, 1.0]]] B = [[[2.0, 2.0, 2.0], [4.0, 4.0, 4.0]], [[4.0, 4.0, 4.0], [8.0, 8.0, 8.0]]] trsm(A, B, alpha=0.5) = [[[1.0, 1.0, 1.0], [1.0, 1.0, 1.0]], [[2.0, 2.0, 2.0], [2.0, 2.0, 2.0]]]

Defined in src/operator/tensor/la_op.cc:L396

Value

mx.nd.load

mx.nd.LinearRegressionOutput

Computes and optimizes for squared loss during backward propagation. Just outputs "data" during forward propagation.

Description

If :math: '\haty_i' is the predicted value of the i-th sample, and :math: 'y_i' is the corresponding target value, then the squared loss estimated over :math: 'n' samples is defined as

Arguments

data NDArray-or-Symbol Input data to the function.

1abel NDArray-or-Symbol Input label to the function.

grad.scale float, optional, default=1 Scale the gradient by a float factor

Details

 $: math: `\text{textSquaredLoss}(\text{textbfY}, \text{hat}\text{textbfY}) = \frac{1n \sum_{i=0}^{n-1} \text{textbfy}_i - \text{hat}\text{textbfy}_i - \text{hat}\text{textbfy}_i$

.. note:: Use the LinearRegressionOutput as the final output layer of a net.

The storage type of "label" can be "default" or "csr"

 $- Linear Regression Output (default, \ default) = default - Linear Regression Output (default, \ csr) = default$

By default, gradients of this loss function are scaled by factor '1/m', where m is the number of regression outputs of a training example. The parameter 'grad_scale' can be used to change this scale to 'grad_scale/m'.

Defined in src/operator/regression_output.cc:L92

Value

out The result mx.ndarray

mx.nd.load

Load an mx.nd.array object on disk

Description

Load an mx.nd.array object on disk

Usage

mx.nd.load(filename)

mx.nd.log

Arguments

filename (including the path)

Examples

```
mat = mx.nd.array(1:3)
mx.nd.save(mat, 'temp.mat')
mat2 = mx.nd.load('temp.mat')
as.array(mat)
as.array(mat2)
```

mx.nd.log

Returns element-wise Natural logarithmic value of the input.

Description

The natural logarithm is logarithm in base e^* , so that "log(exp(x)) = x"

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "log" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L76

Value

out The result mx.ndarray

mx.nd.log.softmax

Computes the log softmax of the input. This is equivalent to computing softmax followed by log.

Description

Examples::

156 mx.nd.log10

Arguments

data NDArray-or-Symbol The input array.

axis int, optional, default='-1' The axis along which to compute softmax.

temperature double or None, optional, default=None Temperature parameter in softmax

dtype None, 'float16', 'float32', 'float64', optional, default='None' DType of the out-

put in case this can't be inferred. Defaults to the same as input's dtype if not

defined (dtype=None).

use.length boolean or None, optional, default=0 Whether to use the length input as a mask

over the data input.

Details

 $\gg x = mx.nd.array([1, 2, .1]) \gg mx.nd.log_softmax(x).asnumpy() array([-1.41702998, -0.41702995, -2.31702995], dtype=float32)$

»> x = mx.nd.array([[1, 2, .1],[.1, 2, 1]]) »> mx.nd.log_softmax(x, axis=0).asnumpy() array([[-0.34115392, -0.69314718, -1.24115396], [-1.24115396, -0.69314718, -0.34115392]], dtype=float32)

Value

out The result mx.ndarray

mx.nd.log10

Returns element-wise Base-10 logarithmic value of the input.

Description

```
10**log10(x) = x
```

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "log10" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L93

Value

mx.nd.log1p 157

mx.nd.log1p

Returns element-wise "log(1 + x)" value of the input.

Description

This function is more accurate than "log(1 + x)" for small "x" so that :math: '1+x\approx 1'

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "log1p" output depends upon the input storage type:

- $log1p(default) = default - log1p(row_sparse) = row_sparse - log1p(csr) = csr$

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L206

Value

out The result mx.ndarray

mx.nd.log2

Returns element-wise Base-2 logarithmic value of the input.

Description

$$2**log2(x) = x$$

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "log2" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L105

Value

mx.nd.logical.not

Returns the result of logical NOT (!) function

Description

Example: $logical_not([-2., 0., 1.]) = [0., 1., 0.]$

Arguments

data

NDArray-or-Symbol The input array.

Value

out The result mx.ndarray

mx.nd.LogisticRegressionOutput

Applies a logistic function to the input.

Description

The logistic function, also known as the sigmoid function, is computed as :math: \frac11+exp(-\textbfx)'.

Arguments

data NDArray-or-Symbol Input data to the function.

1abel NDArray-or-Symbol Input label to the function.

grad.scale float, optional, default=1 Scale the gradient by a float factor

Details

Commonly, the sigmoid is used to squash the real-valued output of a linear model :math:'wTx+b' into the [0,1] range so that it can be interpreted as a probability. It is suitable for binary classification or probability prediction tasks.

.. note:: Use the LogisticRegressionOutput as the final output layer of a net.

The storage type of "label" can be "default" or "csr"

- LogisticRegressionOutput(default, default) = default - LogisticRegressionOutput(default, csr) = default

The loss function used is the Binary Cross Entropy Loss:

```
:math: -(y\log(p) + (1 - y)\log(1 - p))
```

Where 'y' is the ground truth probability of positive outcome for a given example, and 'p' the probability predicted by the model. By default, gradients of this loss function are scaled by factor '1/m',

mx.nd.LRN 159

where m is the number of regression outputs of a training example. The parameter 'grad_scale' can be used to change this scale to 'grad_scale/m'.

Defined in src/operator/regression_output.cc:L152

Value

out The result mx.ndarray

mx.nd.LRN	Applies local response normalization to the input.	

Description

The local response normalization layer performs "lateral inhibition" by normalizing over local input regions.

Arguments

data	NDArray-or-Symbol Input data to LRN
alpha	float, optional, default=9.99999975e-05 The variance scaling parameter :math: '\alpha' in the LRN expression.
beta	float, optional, default=0.75 The power parameter :math: '\beta' in the LRN expression.
knorm	float, optional, default=2 The parameter :math: 'k' in the LRN expression.
nsize	int (non-negative), required normalization window width in elements.

Details

If :math: 'a_x,y^i' is the activity of a neuron computed by applying kernel :math: 'i' at position :math: '(x, y)' and then applying the ReLU nonlinearity, the response-normalized activity :math: 'b_x,y^i' is given by the expression:

```
.. math:: b_x,y^i = \fraca_x,y^i\Bigg(k + \frac\alphan \sum_j = max(0, i-\fracn2)^min(N-1, i+\fracn2) (a_x,y^j)^2\Bigg)^\beta
```

where the sum runs over :math: 'n' "adjacent" kernel maps at the same spatial position, and :math: 'N' is the total number of kernels in the layer.

Defined in src/operator/nn/lrn.cc:L164

Value

160 mx.nd.make.loss

mx.nd.MAERegressionOutput

Computes mean absolute error of the input.

Description

MAE is a risk metric corresponding to the expected value of the absolute error.

Arguments

data NDArray-or-Symbol Input data to the function.

1abel NDArray-or-Symbol Input label to the function.

grad.scale float, optional, default=1 Scale the gradient by a float factor

Details

If :math: '\haty_i' is the predicted value of the i-th sample, and :math: 'y_i' is the corresponding target value, then the mean absolute error (MAE) estimated over :math: 'n' samples is defined as :math: '\textMAE(\textbfY, \hat\textbfY) = \frac1n \sum_i=0^n-1 \lVert \textbfy_i - \hat\textbfy_i \rVert_1'

.. note:: Use the MAERegressionOutput as the final output layer of a net.

The storage type of "label" can be "default" or "csr"

- MAERegressionOutput(default, default) = default - MAERegressionOutput(default, csr) = default By default, gradients of this loss function are scaled by factor '1/m', where m is the number of regression outputs of a training example. The parameter 'grad_scale' can be used to change this scale to 'grad_scale/m'.

Defined in src/operator/regression_output.cc:L120

Value

out The result mx.ndarray

mx.nd.make.loss Make your own loss function in network construction.

Description

This operator accepts a customized loss function symbol as a terminal loss and the symbol should be an operator with no backward dependency. The output of this function is the gradient of loss with respect to the input data.

Arguments

data NDArray-or-Symbol The input array.

mx.nd.MakeLoss 161

Details

For example, if you are a making a cross entropy loss function. Assume "out" is the predicted output and "label" is the true label, then the cross entropy can be defined as::

```
cross\_entropy = label * log(out) + (1 - label) * log(1 - out) loss = make\_loss(cross\_entropy)
```

We will need to use "make_loss" when we are creating our own loss function or we want to combine multiple loss functions. Also we may want to stop some variables' gradients from backpropagation. See more detail in "BlockGrad" or "stop_gradient".

The storage type of "make_loss" output depends upon the input storage type:

- make_loss(default) = default - make_loss(row_sparse) = row_sparse

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L360

Value

out The result mx.ndarray

mx.nd.MakeLoss	Make your own loss function in network construction.

Description

This operator accepts a customized loss function symbol as a terminal loss and the symbol should be an operator with no backward dependency. The output of this function is the gradient of loss with respect to the input data.

Arguments

data	NDArray-or-Symbol Input array.
grad.scale	float, optional, default=1 Gradient scale as a supplement to unary and binary operators
valid.thresh	float, optional, default=0 clip each element in the array to 0 when it is less than "valid_thresh". This is used when "normalization" is set to "valid".
normalization	'batch', 'null', 'valid',optional, default='null' If this is set to null, the output gradient will not be normalized. If this is set to batch, the output gradient will be divided by the batch size. If this is set to valid, the output gradient will be divided by the number of valid input elements.

Details

For example, if you are a making a cross entropy loss function. Assume "out" is the predicted output and "label" is the true label, then the cross entropy can be defined as::

```
cross\_entropy = label * log(out) + (1 - label) * log(1 - out) loss = MakeLoss(cross\_entropy)
```

We will need to use "MakeLoss" when we are creating our own loss function or we want to combine multiple loss functions. Also we may want to stop some variables' gradients from backpropagation. See more detail in "BlockGrad" or "stop_gradient".

mx.nd.max

In addition, we can give a scale to the loss by setting "grad_scale", so that the gradient of the loss will be rescaled in the backpropagation.

.. note:: This operator should be used as a Symbol instead of NDArray.

Defined in src/operator/make_loss.cc:L71

Value

out The result mx.ndarray

mx.nd.max

Computes the max of array elements over given axes.

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L32

Arguments

data	NDArray-or-Symbol The input
axis	Shape or None, optional, default=None The axis or axes along which to perform the reduction.
	The default, 'axis=()', will compute over all elements into a scalar array with shape '(1,)'.
	If 'axis' is int, a reduction is performed on a particular axis.
	If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in the tuple.
	If 'exclude' is true, reduction will be performed on the axes that are NOT in axis instead.
	Negative values means indexing from right to left.
keepdims	boolean, optional, default=0 If this is set to 'True', the reduced axes are left in the result as dimension with size one.
exclude	boolean, optional, default=0 Whether to perform reduction on axis that are NOT in axis instead.

Value

mx.nd.max.axis 163

mx.nd.max.axis Computes the max of array elements over given axes.	
--	--

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L32

Arguments

data

NDArray-or-Symbol The input

Shape or None, optional, default=None The axis or axes along which to perform the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

Value

out The result mx.ndarray

mx.nd.mean	Computes the mean of array elements over given axes.	

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L83

Arguments

data NDArray-or-Symbol The input

164 mx.nd.min

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

Value

out The result mx.ndarray

mx.nd.min Computes the min of array elements over given axes.

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L46

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

Value

mx.nd.min.axis

mx.nd.min.axis	Computes the min of array elements over given axes.	
mx.nd.min.axis	Computes the min of array elements over given axes.	

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L46

Arguments

data	NDArray-or-Symbol The input
axis	Shape or None, optional, default=None The axis or axes along which to perform the reduction.
	The default, 'axis=()', will compute over all elements into a scalar array with shape '(1,)'.
	If 'axis' is int, a reduction is performed on a particular axis.
	If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in the tuple.
	If 'exclude' is true, reduction will be performed on the axes that are NOT in axis instead.
	Negative values means indexing from right to left.
keepdims	boolean, optional, default=0 If this is set to 'True', the reduced axes are left in the result as dimension with size one.
exclude	boolean, optional, default=0 Whether to perform reduction on axis that are NOT in axis instead.

Value

out The result mx.ndarray

mx.nd.moments	Calculate the mean and variance of 'data'.	

Description

The mean and variance are calculated by aggregating the contents of data across axes. If x is 1-D and axes = [0] this is just the mean and variance of a vector.

Arguments

data	NDArray-or-Symbol Input ndarray
axes	Shape or None, optional, default=None Array of ints. Axes along which to compute mean and variance.
keepdims	boolean, optional, default=0 produce moments with the same dimensionality as the input.

Details

Example:

x = [[1, 2, 3], [4, 5, 6]] mean, var = moments(data=x, axes=[0]) mean = [2.5, 3.5, 4.5] var = [2.25, 2.25, 2.25] mean, var = moments(data=x, axes=[1]) mean = [2.0, 5.0] var = [0.66666667], 0.66666667] mean, var = moments(data=x, axis=[0, 1]) mean = [3.5] var = [2.9166667]

Defined in src/operator/nn/moments.cc:L54

Value

out The result mx.ndarray

mx.nd.mp.nag.mom.update

Update function for multi-precision Nesterov Accelerated Gradient(NAG) optimizer.

Description

Defined in src/operator/optimizer_op.cc:L743

Arguments

weight NDArray-or-Symbol Weight
grad NDArray-or-Symbol Gradient
mom NDArray-or-Symbol Momentum
weight32 NDArray-or-Symbol Weight32
1r float, required Learning rate

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

Value

mx.nd.mp.sgd.mom.update

Updater function for multi-precision sgd optimizer

Description

Updater function for multi-precision sgd optimizer

Arguments

weight NDArray-or-Symbol Weight NDArray-or-Symbol Gradient grad NDArray-or-Symbol Momentum mom weight32 NDArray-or-Symbol Weight32 lr float, required Learning rate float, optional, default=0 The decay rate of momentum estimates at each epoch. momentum float, optional, default=0 Weight decay augments the objective function with a wd regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight. float, optional, default=1 Rescale gradient to grad = rescale_grad*grad. rescale.grad float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] clip.gradient If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

lazy.update boolean, optional, default=1 If true, lazy updates are applied if gradient's stype

is row_sparse and both weight and momentum have the same stype

Value

out The result mx.ndarray

Description

Updater function for multi-precision sgd optimizer

mx.nd.multi.all.finite

Arguments

weight NDArray-or-Symbol Weight grad NDArray-or-Symbol gradient weight32 NDArray-or-Symbol Weight32

1r float, required Learning rate

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

lazy.update boolean, optional, default=1 If true, lazy updates are applied if gradient's stype

is row_sparse.

Value

out The result mx.ndarray

mx.nd.multi.all.finite

Check if all the float numbers in all the arrays are finite (used for AMP)

Description

Defined in src/operator/contrib/all_finite.cc:L133

Arguments

data NDArray-or-Symbol[] Arrays

num. arrays int, optional, default='1' Number of arrays.

init.output boolean, optional, default=1 Initialize output to 1.

Value

mx.nd.multi.lars 169

mx.nd.multi.lars	Compute the LARS coefficients of multiple weights and grads from
	their sums of square"

Description

Defined in src/operator/contrib/multi_lars.cc:L37

Arguments

1rs NDArray-or-Symbol Learning rates to scale by LARS coefficient

weights.sum.sq NDArray-or-Symbol sum of square of weights arrays grads.sum.sq NDArray-or-Symbol sum of square of gradients arrays

wds NDArray-or-Symbol weight decays

eta float, required LARS eta eps float, required LARS eps

rescale.grad float, optional, default=1 Gradient rescaling factor

Value

out The result mx.ndarray

```
mx.nd.multi.mp.sgd.mom.update
```

Momentum update function for multi-precision Stochastic Gradient Descent (SGD) optimizer.

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Arguments

data	NDArray-or-Symbol[] Weights
lrs	tuple of <float>, required Learning rates.</float>
wds	tuple of <float>, required Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.</float>
momentum	float, optional, default=0 The decay rate of momentum estimates at each epoch.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
num.weights	int, optional, default='1' Number of updated weights.

Details

```
.. math:: v_1 = \alpha V_0 + \alpha V_1 - \alpha V_
```

Value

out The result mx.ndarray

```
mx.nd.multi.mp.sgd.update
```

Update function for multi-precision Stochastic Gradient Descent (SDG) optimizer.

Description

It updates the weights using::

Arguments

data	NDArray-or-Symbol[] Weights
lrs	tuple of <float>, required Learning rates.</float>
wds	tuple of <float>, required Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.</float>
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
num.weights	int, optional, default='1' Number of updated weights.

Details

```
weight = weight - learning_rate * (gradient + wd * weight)
Defined in src/operator/optimizer_op.cc:L415
```

Value

mx.nd.multi.sgd.mom.update

Momentum update function for Stochastic Gradient Descent (SGD) optimizer.

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Arguments

data	NDArray-or-Symbol[] Weights, gradients and momentum
lrs	tuple of <float>, required Learning rates.</float>
wds	tuple of <float>, required Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.</float>
momentum	float, optional, default=0 The decay rate of momentum estimates at each epoch.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
num.weights	int, optional, default='1' Number of updated weights.

Details

```
.. math::
```

```
 v_1 = \alpha V_0 + \alpha V_0 = \gamma V_1 - \alpha V_1
```

```
v = momentum * v - learning_rate * gradient weight += v
```

Where the parameter "momentum" is the decay rate of momentum estimates at each epoch.

Defined in src/operator/optimizer_op.cc:L372

Value

172 mx.nd.multi.sum.sq

mx.nd.multi.sgd.update

Update function for Stochastic Gradient Descent (SDG) optimizer.

Description

It updates the weights using::

Arguments

data NDArray-or-Symbol[] Weights

1rs tuple of <float>, required Learning rates.

wds tuple of <float>, required Weight decay augments the objective function with

a regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

Details

weight = weight - learning_rate * (gradient + wd * weight)
Defined in src/operator/optimizer_op.cc:L327

Value

out The result mx.ndarray

mx.nd.multi.sum.sq Compute the sums of squares of multiple arrays

Description

Defined in src/operator/contrib/multi_sum_sq.cc:L36

Arguments

data NDArray-or-Symbol[] Arrays num.arrays int, required number of input arrays.

Value

mx.nd.nag.mom.update 173

mx.nd.nag.mom.update Update function for Nesterov Accelerated Gradient(NAG) optimizer.

It updates the weights using the following formula,

Description

.. math:: $v_t = \gamma v_{t-1} + \epsilon * \beta J(W_{t-1} - \gamma v_t) W_t = W_{t-1} - v_t$

Arguments

weight NDArray-or-Symbol Weight

grad NDArray-or-Symbol Gradient

mom NDArray-or-Symbol Momentum

1r float, required Learning rate

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

Details

Where :math: '\eta' is the learning rate of the optimizer :math: '\gamma' is the decay rate of the momentum estimate :math: '\v_t' is the update vector at time step 't' :math: '\W_t' is the weight vector at time step 't'

Defined in src/operator/optimizer_op.cc:L724

Value

174 mx.nd.nansum

mx.nd.nanprod Computes the product of array elements over given axes treating Not a Numbers ("NaN") as one.	mx.nd.nanprod	Computes the product of array elements over given axes treating Not a Numbers ("NaN") as one.
---	---------------	---

Description

Computes the product of array elements over given axes treating Not a Numbers ("NaN") as one.

Arguments

data	NDArray-or-Symbol The input
axis	Shape or None, optional, default=None The axis or axes along which to perform the reduction.
	The default, 'axis=()', will compute over all elements into a scalar array with shape ' $(1,)$ '.
	If 'axis' is int, a reduction is performed on a particular axis.
	If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in the tuple.
	If 'exclude' is true, reduction will be performed on the axes that are NOT in axis instead.
	Negative values means indexing from right to left.
keepdims	boolean, optional, default=0 If this is set to 'True', the reduced axes are left in the result as dimension with size one.
exclude	boolean, optional, default=0 Whether to perform reduction on axis that are NOT in axis instead.

Details

Defined in src/operator/tensor/broadcast_reduce_prod_value.cc:L46

Value

out The result mx.ndarray

mx.nd.nansum	Computes the sum of array elements over given axes treating Not a Numbers ("NaN") as zero.
	Trumbers (Truit) as zero.

Description

Computes the sum of array elements over given axes treating Not a Numbers ("NaN") as zero.

mx.nd.negative 175

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

Details

Defined in src/operator/tensor/broadcast_reduce_sum_value.cc:L100

Value

out The result mx.ndarray

mx.nd.negative

Numerical negative of the argument, element-wise.

Description

The storage type of "negative" output depends upon the input storage type:

Arguments

data

NDArray-or-Symbol The input array.

Details

- negative(default) = default - negative(row_sparse) = row_sparse - negative(csr) = csr

Value

176 mx.nd.norm

mx.nd.norm Computes the norm on an NDArray.

Description

This operator computes the norm on an NDArray with the specified axis, depending on the value of the ord parameter. By default, it computes the L2 norm on the entire array. Currently only ord=2 supports sparse ndarrays.

Arguments

data	NDArray-or-Symbol The input
ord	int, optional, default='2' Order of the norm. Currently ord=1 and ord=2 is supported.
axis	Shape or None, optional, default=None The axis or axes along which to perform the reduction. The default, 'axis=()', will compute over all elements into a scalar array with shape '(1,)'. If 'axis' is int, a reduction is performed on a particular axis. If 'axis' is a 2-tuple, it specifies the axes that hold 2-D matrices, and the matrix norms of these matrices are computed.
out.dtype	None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', optional, default='None' The data type of the output.
keepdims	boolean, optional, default=0 If this is set to 'True', the reduced axis is left in the result as dimension with size one.

Details

```
Examples::
```

```
x = [[[1, 2], [3, 4]], [[2, 2], [5, 6]]]

norm(x, ord=2, axis=1) = [[3.1622777 4.472136] [5.3851647 6.3245554]]

norm(x, ord=1, axis=1) = [[4., 6.], [7., 8.]]

rsp = x.cast_storage('row_sparse')

norm(rsp) = [5.47722578]

csr = x.cast_storage('csr')

norm(csr) = [5.47722578]

Defined in src/operator/tensor/broadcast_reduce_norm_value.cc:L89
```

Value

```
out The result mx.ndarray
```

mx.nd.normal 177

mx.nd.normal	Draw random samples from a normal (Gaussian) distribution.

Description

.. note:: The existing alias "normal" is deprecated.

Arguments

loc	float, optional, default=0 Mean of the distribution.
scale	float, optional, default=1 Standard deviation of the distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

Details

Samples are distributed according to a normal distribution parametrized by *loc* (mean) and *scale* (standard deviation).

Example::

```
normal(loc=0, scale=1, shape=(2,2)) = \hbox{\tt [[1.89171135, -1.16881478], [-1.23474145, 1.55807114]]} Defined in src/operator/random/sample_op.cc:L113
```

Value

out The result mx.ndarray

Returns a one-hot array.

Description

The locations represented by 'indices' take value 'on_value', while all other locations take value 'off_value'.

mx.nd.ones

Arguments

indices NDArray-or-Symbol array of locations where to set on_value

depth int, required Depth of the one hot dimension.

on.value double, optional, default=1 The value assigned to the locations represented by

indices.

off.value double, optional, default=0 The value assigned to the locations not represented

by indices.

dtype 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, default='float32'

DType of the output

Details

'one_hot' operation with 'indices' of shape "(i0, i1)" and 'depth' of "d" would result in an output array of shape "(i0, i1, d)" with::

 $\operatorname{output}[i,j,:] = \operatorname{off_value} \operatorname{output}[i,j,\operatorname{indices}[i,j]] = \operatorname{on_value}$

Examples::

```
one_hot([1,0,2,0], 3) = [[0.1.0.] [1.0.0.] [0.0.1.] [1.0.0.]
```

one_hot([1,0,2,0], 3, on_value=8, off_value=1, dtype='int32') = [[1 8 1] [8 1 1] [1 1 8] [8 1 1]]

one_hot([[1,0],[1,0],[2,0]], 3) = [[[0.1.0.][1.0.0.]]

[[0. 1. 0.] [1. 0. 0.]]

[[0. 0. 1.] [1. 0. 0.]]]

Defined in src/operator/tensor/indexing_op.cc:L821

Value

out The result mx.ndarray

mx.nd.ones

Generate an mx.ndarray object with ones

Description

Generate an mx.ndarray object with ones

Usage

```
mx.nd.ones(shape, ctx = NULL)
```

Arguments

shape the dimension of the mx.ndarray

ctx optional The context device of the array. mx.ctx.default() will be used in default.

mx.nd.ones.like

Examples

```
mat = mx.nd.ones(10)
as.array(mat)
mat2 = mx.nd.ones(c(5,5))
as.array(mat)
mat3 = mx.nd.ones(c(3,3,3))
as.array(mat3)
```

mx.nd.ones.like

Return an array of ones with the same shape and type as the input array.

Description

Examples::

Arguments

data

NDArray-or-Symbol The input

Details

```
x = [[ 0., 0., 0.], [ 0., 0., 0.]]
ones_like(x) = [[ 1., 1., 1.], [ 1., 1., 1.]]
```

Value

out The result mx.ndarray

mx.nd.Pad

Pads an input array with a constant or edge values of the array.

Description

```
.. note:: 'Pad' is deprecated. Use 'pad' instead.
```

Arguments

data

NDArray-or-Symbol An n-dimensional input array.

mode

'constant', 'edge', 'reflect', required Padding type to use. "constant" pads with 'constant_value' "edge" pads using the edge values of the input array "reflect"

pads by reflecting values with respect to the edges.

mx.nd.Pad

pad.width

Shape(tuple), required Widths of the padding regions applied to the edges of each axis. It is a tuple of integer padding widths for each axis of the format "(before_1, after_1, ..., before_N, after_N)". It should be of length "2*N" where "N" is the number of dimensions of the array. This is equivalent to pad_width in numpy.pad, but flattened.

constant.value double, optional, default=0 The value used for padding when 'mode' is "constant".

Details

.. note:: Current implementation only supports 4D and 5D input arrays with padding applied only on axes 1, 2 and 3. Expects axes 4 and 5 in 'pad_width' to be zero.

This operation pads an input array with either a 'constant_value' or edge values along each axis of the input array. The amount of padding is specified by 'pad_width'.

'pad_width' is a tuple of integer padding widths for each axis of the format "(before_1, after_1, ..., before_N, after_N)". The 'pad_width' should be of length "2*N" where "N" is the number of dimensions of the array.

For dimension "N" of the input array, "before_N" and "after_N" indicates how many values to add before and after the elements of the array along dimension "N". The widths of the higher two dimensions "before_1", "after_1", "before_2", "after_2" must be 0.

Example::

```
 \begin{aligned} x &= [[[[\ 1.\ 2.\ 3.]\ [\ 4.\ 5.\ 6.]] \\ [[\ 7.\ 8.\ 9.]\ [\ 10.\ 11.\ 12.]]] \\ [[[\ 11.\ 12.\ 13.]\ [\ 14.\ 15.\ 16.]] \\ [[[\ 17.\ 18.\ 19.]\ [\ 20.\ 21.\ 22.]]]] \\ pad(x,mode="edge", pad_width=(0,0,0,0,1,1,1,1)) &= \\ [[[\ 1.\ 1.\ 2.\ 3.\ 3.]\ [\ 1.\ 1.\ 2.\ 3.\ 3.]\ [\ 4.\ 4.\ 5.\ 6.\ 6.]\ [\ 4.\ 4.\ 5.\ 6.\ 6.]] \\ [[\ 7.\ 7.\ 8.\ 9.\ 9.]\ [\ 7.\ 7.\ 8.\ 9.\ 9.]\ [\ 10.\ 10.\ 11.\ 12.\ 12.]\ [\ 10.\ 10.\ 11.\ 12.\ 12.]]] \\ [[[\ 11.\ 11.\ 12.\ 13.\ 13.]\ [\ 11.\ 11.\ 12.\ 13.\ 13.]\ [\ 14.\ 14.\ 15.\ 16.\ 16.]\ [\ 14.\ 14.\ 15.\ 16.\ 16.]] \\ [[\ 17.\ 17.\ 18.\ 19.\ 19.]\ [\ 17.\ 17.\ 18.\ 19.\ 19.]\ [\ 20.\ 20.\ 21.\ 22.\ 22.]\ [\ 20.\ 20.\ 21.\ 22.\ 22.]]]] \\ pad(x, mode="constant", constant_value=0, pad_width=(0,0,0,0,1,1,1,1)) = \\ [[[\ 0.\ 0.\ 0.\ 0.\ 0.]\ [\ 0.\ 1.\ 2.\ 3.\ 0.]\ [\ 0.\ 4.\ 5.\ 6.\ 0.]\ [\ 0.\ 0.\ 0.\ 0.\ 0.]] \\ [[\ 0.\ 0.\ 0.\ 0.\ 0.\ 0.]\ [\ 0.\ 11.\ 12.\ 13.\ 0.]\ [\ 0.\ 14.\ 15.\ 16.\ 0.]\ [\ 0.\ 0.\ 0.\ 0.\ 0.]]] \\ [[\ 0.\ 0.\ 0.\ 0.\ 0.\ 0.\ 0.]\ [\ 0.\ 11.\ 12.\ 13.\ 0.]\ [\ 0.\ 14.\ 15.\ 16.\ 0.]\ [\ 0.\ 0.\ 0.\ 0.\ 0.\ 0.]]]] \\ Defined in src/operator/pad.cc:L766 \end{aligned}
```

Value

mx.nd.pad 181

mx.nd.pad Pads an input array with a constant or edge values of the array.	mx.nd.pad	Pads an input array with a constant or edge values of the array.
--	-----------	--

Description

.. note:: 'Pad' is deprecated. Use 'pad' instead.

Arguments

data NDArray-or-Symbol An n-dimensional input array.

mode 'constant', 'edge', 'reflect', required Padding type to use. "constant" pads with

'constant_value' "edge" pads using the edge values of the input array "reflect"

pads by reflecting values with respect to the edges.

pad.width Shape(tuple), required Widths of the padding regions applied to the edges of

each axis. It is a tuple of integer padding widths for each axis of the format "(before_1, after_1, ..., before_N, after_N)". It should be of length "2*N" where "N" is the number of dimensions of the array. This is equivalent to pad_width in

numpy.pad, but flattened.

constant.value double, optional, default=0 The value used for padding when 'mode' is "con-

stant".

Details

.. note:: Current implementation only supports 4D and 5D input arrays with padding applied only on axes 1, 2 and 3. Expects axes 4 and 5 in 'pad_width' to be zero.

This operation pads an input array with either a 'constant_value' or edge values along each axis of the input array. The amount of padding is specified by 'pad_width'.

'pad_width' is a tuple of integer padding widths for each axis of the format "(before_1, after_1, ..., before_N, after_N)". The 'pad_width' should be of length "2*N" where "N" is the number of dimensions of the array.

For dimension "N" of the input array, "before_N" and "after_N" indicates how many values to add before and after the elements of the array along dimension "N". The widths of the higher two dimensions "before_1", "after_1", "before_2", "after_2" must be 0.

Example::

```
x = [[[[ 1. 2. 3.] [ 4. 5. 6.]]
[[ 7. 8. 9.] [ 10. 11. 12.]]]
[[[ 11. 12. 13.] [ 14. 15. 16.]]
[[ 17. 18. 19.] [ 20. 21. 22.]]]]
pad(x,mode="edge", pad_width=(0,0,0,0,1,1,1,1)) =
[[[[ 1. 1. 2. 3. 3.] [ 1. 1. 2. 3. 3.] [ 4. 4. 5. 6. 6.] [ 4. 4. 5. 6. 6.]]
[[ 7. 7. 8. 9. 9.] [ 7. 7. 8. 9. 9.] [ 10. 10. 11. 12. 12.] [ 10. 10. 11. 12. 12.]]]
[[[ 11. 11. 12. 13. 13.] [ 11. 11. 12. 13. 13.] [ 14. 14. 15. 16. 16.] [ 14. 14. 15. 16. 16.]]
```

182 mx.nd.pick

```
[[ 17. 17. 18. 19. 19.] [ 17. 17. 18. 19. 19.] [ 20. 20. 21. 22. 22.] [ 20. 20. 21. 22. 22.]]]]

pad(x, mode="constant", constant_value=0, pad_width=(0,0,0,0,1,1,1,1)) =

[[[[ 0. 0. 0. 0. 0. 0.] [ 0. 1. 2. 3. 0.] [ 0. 4. 5. 6. 0.] [ 0. 0. 0. 0. 0. 0.]]

[[ 0. 0. 0. 0. 0.] [ 0. 7. 8. 9. 0.] [ 0. 10. 11. 12. 0.] [ 0. 0. 0. 0. 0. 0.]]]

[[[ 0. 0. 0. 0. 0.] [ 0. 11. 12. 13. 0.] [ 0. 14. 15. 16. 0.] [ 0. 0. 0. 0. 0.]]

[[ 0. 0. 0. 0. 0.] [ 0. 17. 18. 19. 0.] [ 0. 20. 21. 22. 0.] [ 0. 0. 0. 0. 0.]]]]

Defined in src/operator/pad.cc:L766
```

Value

out The result mx.ndarray

mx.nd.pick	Picks elements from an input array according to the input indices along the given axis.
	atong the given axis.

Description

Given an input array of shape "(d0, d1)" and indices of shape "(i0,)", the result will be an output array of shape "(i0,)" with::

Arguments

data	NDArray-or-Symbol The input array
index	NDArray-or-Symbol The index array
axis	int or None, optional, default='-1' int or None. The axis to picking the elements. Negative values means indexing from right to left. If is 'None', the elements in the index w.r.t the flattened input will be picked.
keepdims	boolean, optional, default=0 If true, the axis where we pick the elements is left in the result as dimension with size one.
mode	'clip', 'wrap',optional, default='clip' Specify how out-of-bound indices behave. Default is "clip". "clip" means clip to the range. So, if all indices mentioned are too large, they are replaced by the index that addresses the last element along an axis. "wrap" means to wrap around.

Details

```
output[i] = input[i, indices[i]]
```

By default, if any index mentioned is too large, it is replaced by the index that addresses the last element along an axis (the 'clip' mode).

This function supports n-dimensional input and (n-1)-dimensional indices arrays.

Examples::

```
x = [[1., 2.], [3., 4.], [5., 6.]]
```

mx.nd.Pooling 183

```
// picks elements with specified indices along axis 0 pick(x, y=[0,1], 0) = [1., 4.] 
// picks elements with specified indices along axis 1 pick(x, y=[0,1,0], 1) = [1., 4., 5.] 
y = [[1.], [0.], [2.]]
```

// picks elements with specified indices along axis 1 using 'wrap' mode // to place indicies that would normally be out of bounds pick(x, y=[2,-1,-2], 1, mode='wrap') = [1., 4., 5.]

```
y = [[1.], [0.], [2.]]
```

// picks elements with specified indices along axis 1 and dims are maintained pick(x,y, 1, keep-dims=True) = [[2.], [3.], [6.]]

Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L155

Value

out The result mx.ndarray

mx.nd.Pooling	Performs pooling on the input.	

Description

The shapes for 1-D pooling are

Arguments

	data	NDArray-or-Symbol Input data to the pooling operator.
	kernel	Shape(tuple), optional, default=[] Pooling kernel size: (y, x) or (d, y, x)
	pool.type	'avg', 'lp', 'max', 'sum',optional, default='max' Pooling type to be applied.
	global.pool	boolean, optional, default=0 Ignore kernel size, do global pooling based on current input feature map.
	cudnn.off	boolean, optional, default=0 Turn off cudnn pooling and use MXNet pooling operator.
pooling.convention		
		'full', 'same', 'valid',optional, default='valid' Pooling convention to be applied.
	stride	Shape(tuple), optional, default=[] Stride: for pooling (y, x) or (d, y, x) . Defaults to 1 for each dimension.
	pad	Shape(tuple), optional, default=[] Pad for pooling: (y, x) or (d, y, x) . Defaults to no padding.
	p.value	int or None, optional, default='None' Value of p for Lp pooling, can be 1 or 2, required for Lp Pooling.
	count.include.p	pad

boolean or None, optional, default=None Only used for AvgPool, specify whether to count padding elements for average calculation. For example, with a 5*5 kernel on a 3*3 corner of a image, the sum of the 9 valid elements will be divided by 25 if this is set to true, or it will be divided by 9 if this is set to false. Defaults to true.

184 mx.nd.Pooling

layout

None, 'NCDHW', 'NCHW', 'NCW', 'NDHWC', 'NHWC', 'NWC', optional, default='None' Set layout for input and output. Empty for default layout: NCW for 1d, NCHW for 2d and NCDHW for 3d.

Details

- **data** and **out**: *(batch_size, channel, width)* (NCW layout) or *(batch_size, width, channel)* (NWC layout),

The shapes for 2-D pooling are

- **data** and **out**: *(batch_size, channel, height, width)* (NCHW layout) or *(batch_size, height, width, channel)* (NHWC layout),

out_height = f(height, kernel[0], pad[0], stride[0]) out_width = f(width, kernel[1], pad[1], stride[1])

The definition of *f* depends on "pooling_convention", which has two options:

- **valid** (default)::

f(x, k, p, s) = floor((x+2*p-k)/s)+1

- **full**, which is compatible with Caffe::

$$f(x, k, p, s) = ceil((x+2*p-k)/s)+1$$

When "global_pool" is set to be true, then global pooling is performed. It will reset "kernel=(height, width)" and set the appropriate padding to 0.

Three pooling options are supported by "pool_type":

```
- **avg**: average pooling - **max**: max pooling - **sum**: sum pooling - **lp**: Lp pooling
```

For 3-D pooling, an additional *depth* dimension is added before *height*. Namely the input data and output will have shape *(batch_size, channel, depth, height, width)* (NCDHW layout) or *(batch_size, depth, height, width, channel)* (NDHWC layout).

Notes on Lp pooling:

Lp pooling was first introduced by this paper: https://arxiv.org/pdf/1204.3968.pdf. L-1 pooling is simply sum pooling, while L-inf pooling is simply max pooling. We can see that Lp pooling stands between those two, in practice the most common value for p is 2.

For each window "X", the mathematical expression for Lp pooling is:

```
:math:'f(X) = \sqrt{p}\sum_x^X x^p'
```

Defined in src/operator/nn/pooling.cc:L417

Value

mx.nd.Pooling.v1

mx.	nd.	Poo1	ing	. v1	

This operator is DEPRECATED. Perform pooling on the input.

Description

The shapes for 2-D pooling is

Arguments

data NDArray-or-Symbol Input data to the pooling operator.

kernel Shape(tuple), optional, default=[] pooling kernel size: (y, x) or (d, y, x) pool. type 'avg', 'max', 'sum', optional, default='max' Pooling type to be applied.

global.pool boolean, optional, default=0 Ignore kernel size, do global pooling based on cur-

rent input feature map.

pooling.convention

'full', 'valid', optional, default='valid' Pooling convention to be applied.

stride Shape(tuple), optional, default=[] stride: for pooling (y, x) or (d, y, x) pad Shape(tuple), optional, default=[] pad for pooling: (y, x) or (d, y, x)

Details

- **data**: *(batch_size, channel, height, width)* - **out**: *(batch_size, num_filter, out_height, out_width)*, with::

out_height = f(height, kernel[0], pad[0], stride[0]) out_width = f(width, kernel[1], pad[1], stride[1])

The definition of *f* depends on "pooling_convention", which has two options:

- **valid** (default)::

f(x, k, p, s) = floor((x+2*p-k)/s)+1

- **full**, which is compatible with Caffe::

f(x, k, p, s) = ceil((x+2*p-k)/s)+1

But "global_pool" is set to be true, then do a global pooling, namely reset "kernel=(height, width)".

Three pooling options are supported by "pool_type":

- **avg**: average pooling - **max**: max pooling - **sum**: sum pooling

1-D pooling is special case of 2-D pooling with *weight=1* and *kernel[1]=1*.

For 3-D pooling, an additional *depth* dimension is added before *height*. Namely the input data will have shape *(batch_size, channel, depth, height, width)*.

Defined in src/operator/pooling_v1.cc:L104

Value

mx.nd.preloaded.multi.mp.sgd.mom.update

Momentum update function for multi-precision Stochastic Gradient Descent (SGD) optimizer.

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Arguments

data NDArray-or-Symbol[] Weights, gradients, momentums, learning rates and weight

decays

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

Details

.. math::

 $v_1 = \alpha + \alpha + \alpha + \beta J(W_0)$

It updates the weights using::

v = momentum * v - learning_rate * gradient weight += v

Where the parameter "momentum" is the decay rate of momentum estimates at each epoch.

Defined in src/operator/contrib/preloaded_multi_sgd.cc:L200

Value

mx.nd.preloaded.multi.mp.sgd.update

Update function for multi-precision Stochastic Gradient Descent (SDG) optimizer.

Description

It updates the weights using::

Arguments

data NDArray-or-Symbol[] Weights, gradients, learning rates and weight decays

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

Details

```
weight = weight - learning_rate * (gradient + wd * weight)
```

Defined in src/operator/contrib/preloaded_multi_sgd.cc:L140

Value

out The result mx.ndarray

mx.nd.preloaded.multi.sgd.mom.update

Momentum update function for Stochastic Gradient Descent (SGD) optimizer.

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Arguments

data NDArray-or-Symbol[] Weights, gradients, momentum, learning rates and weight

decays

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

Details

.. math::

 $v_1 = \alpha V_t - 1 - \alpha V_t - \Omega V_t = \gamma V_t - 1 - \alpha V_t$

It updates the weights using::

v = momentum * v - learning_rate * gradient weight += v

Where the parameter "momentum" is the decay rate of momentum estimates at each epoch.

Defined in src/operator/contrib/preloaded_multi_sgd.cc:L91

Value

out The result mx.ndarray

mx.nd.preloaded.multi.sgd.update

Update function for Stochastic Gradient Descent (SDG) optimizer.

Description

It updates the weights using::

Arguments

data NDArray-or-Symbol[] Weights, gradients, learning rates and weight decays

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

Details

weight = weight - learning_rate * (gradient + wd * weight)

Defined in src/operator/contrib/preloaded_multi_sgd.cc:L42

mx.nd.prod 189

Value

out The result mx.ndarray

mx.nd.prod

Computes the product of array elements over given axes.

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L31

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

Value

out The result mx.ndarray

mx.nd.radians

Converts each element of the input array from degrees to radians.

Description

```
.. math:: radians([0, 90, 180, 270, 360]) = [0, \pi/2, \pi/2, 2\pi]
```

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "radians" output depends upon the input storage type:

- radians(default) = default - radians(row_sparse) = row_sparse - radians(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L293

Value

out The result mx.ndarray

mx.nd.random.exponential

Draw random samples from an exponential distribution.

Description

Samples are distributed according to an exponential distribution parametrized by *lambda* (rate).

Arguments

lam	float, optional, default=1 Lambda parameter (rate) of the exponential distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

Details

```
Example::
```

```
exponential(lam=4, shape=(2,2)) = [[ 0.0097189 , 0.08999364], [ 0.04146638, 0.31715935]] Defined in src/operator/random/sample_op.cc:L137
```

Value

mx.nd.random.gamma 191

mx.nd.random.gam	ma

Draw random samples from a gamma distribution.

Description

Samples are distributed according to a gamma distribution parametrized by *alpha* (shape) and *beta* (scale).

Arguments

alpha	float, optional, default=1 Alpha parameter (shape) of the gamma distribution.
beta	float, optional, default=1 Beta parameter (scale) of the gamma distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

Details

Example::

```
gamma(alpha=9, beta=0.5, shape=(2,2)) = [[ 7.10486984, 3.37695289], [ 3.91697288, 3.65933681]] Defined in src/operator/random/sample_op.cc:L125
```

Value

out The result mx.ndarray

```
mx.nd.random.generalized.negative.binomial
```

Draw random samples from a generalized negative binomial distribution.

Description

Samples are distributed according to a generalized negative binomial distribution parametrized by *mu* (mean) and *alpha* (dispersion). *alpha* is defined as *1/k* where *k* is the failure limit of the number of unsuccessful experiments (generalized to real numbers). Samples will always be returned as a floating point data type.

Arguments

mu	float, optional, default=1 Mean of the negative binomial distribution.
mu	float, optional, default=1 Mean of the negative binomial distribution.

alpha float, optional, default=1 Alpha (dispersion) parameter of the negative binomial

distribution.

shape Shape(tuple), optional, default=None Shape of the output.

ctx string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n).

Only used for imperative calls.

dtype 'None', 'float16', 'float32', 'float64', optional, default='None' DType of the out-

put in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

Details

Example::

generalized_negative_binomial(mu=2.0, alpha=0.3, shape=(2,2)) = [[2., 1.], [6., 4.]]

Defined in src/operator/random/sample_op.cc:L179

Value

out The result mx.ndarray

mx.nd.random.negative.binomial

Draw random samples from a negative binomial distribution.

Description

Samples are distributed according to a negative binomial distribution parametrized by *k* (limit of unsuccessful experiments) and *p* (failure probability in each experiment). Samples will always be returned as a floating point data type.

Arguments

k int, optional, default='1' Limit of unsuccessful experiments.

p float, optional, default=1 Failure probability in each experiment.

shape Shape(tuple), optional, default=None Shape of the output.

ctx string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n).

Only used for imperative calls.

dtype 'None', 'float16', 'float32', 'float64', optional, default='None' DType of the out-

put in case this can't be inferred. Defaults to float 32 if not defined (dtype=None).

Details

Example::

negative_binomial(k=3, p=0.4, shape=(2,2)) = [[4., 7.], [2., 5.]]

Defined in src/operator/random/sample_op.cc:L164

mx.nd.random.normal

Value

out The result mx.ndarray

mx.nd.random.normal

Draw random samples from a normal (Gaussian) distribution.

Description

.. note:: The existing alias "normal" is deprecated.

Arguments

loc	float, optional, default=0 Mean of the distribution.
scale	float, optional, default=1 Standard deviation of the distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

Details

Samples are distributed according to a normal distribution parametrized by *loc* (mean) and *scale* (standard deviation).

Example::

```
normal(loc=0, scale=1, shape=(2,2)) = [[ 1.89171135, -1.16881478], [-1.23474145, 1.55807114]]
Defined in src/operator/random/sample_op.cc:L113
```

Value

mx.nd.random.pdf.dirichlet

Computes the value of the PDF of *sample* of Dirichlet distributions with parameter *alpha*.

Description

The shape of *alpha* must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *alpha*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the value of *alpha* at index *i*.

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
alpha	NDArray-or-Symbol Concentration parameters of the distributions.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.

Details

Examples::

```
random_pdf_dirichlet(sample=[[1,2],[2,3],[3,4]], alpha=[2.5, 2.5]) = [38.413498, 199.60245, 564.56085] sample = [[[1, 2, 3], [10, 20, 30], [100, 200, 300]], [[0.1, 0.2, 0.3], [0.01, 0.02, 0.03], [0.001, 0.002, 0.003]]] random_pdf_dirichlet(sample=sample, alpha=[0.1, 0.4, 0.9]) = [[2.3257459e-02, 5.8420084e-04, 1.4674458e-05], [9.2589635e-01, 3.6860607e+01, 1.4674468e+03]] Defined in src/operator/random/pdf_op.cc:L316
```

Value

out The result mx.ndarray

```
mx.nd.random.pdf.exponential
```

Computes the value of the PDF of *sample* of exponential distributions with parameters *lam* (rate).

Description

The shape of *lam* must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *lam*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the value of *lam* at index *i*.

Arguments

sample NDArray-or-Symbol Samples from the distributions.

lam NDArray-or-Symbol Lambda (rate) parameters of the distributions.

is.log boolean, optional, default=0 If set, compute the density of the log-probability

instead of the probability.

Details

Examples::

```
random_pdf_exponential(sample=[[1, 2, 3]], lam=[1]) = [[0.36787945, 0.13533528, 0.04978707]] sample = [[1,2,3], [1,2,3], [1,2,3]]
```

random_pdf_exponential(sample=sample, lam=[1,0.5,0.25]) = [[0.36787945, 0.13533528, 0.04978707], [0.30326533, 0.18393973, 0.11156508], [0.1947002, 0.15163267, 0.11809164]]

Defined in src/operator/random/pdf_op.cc:L305

Value

out The result mx.ndarray

```
mx.nd.random.pdf.gamma
```

Computes the value of the PDF of *sample* of gamma distributions with parameters *alpha* (shape) and *beta* (rate).

Description

alpha and *beta* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *alpha* and *beta*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *alpha* and *beta* at index *i*.

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
alpha	NDArray-or-Symbol Alpha (shape) parameters of the distributions.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.
beta	NDArray-or-Symbol Beta (scale) parameters of the distributions.

Details

Value

Examples::

```
\begin{aligned} & \text{random\_pdf\_gamma}(\text{sample=}[[1,2,3,4,5]], \text{alpha=}[5], \text{beta=}[1]) = [[0.01532831, 0.09022352, 0.16803136, 0.19536681, 0.17546739]] \\ & \text{sample} = [[1,2,3,4,5], [2,3,4,5,6], [3,4,5,6,7]] \\ & \text{random\_pdf\_gamma}(\text{sample=sample}, \text{alpha=}[5,6,7], \text{beta=}[1,1,1]) = [[0.01532831, 0.09022352, 0.16803136, 0.19536681, 0.17546739], [0.03608941, 0.10081882, 0.15629345, 0.17546739, 0.16062315], [0.05040941, 0.10419563, 0.14622283, 0.16062315, 0.14900276]] \end{aligned}
```

out The result mx.ndarray

```
mx.nd.random.pdf.generalized.negative.binomial
```

Defined in src/operator/random/pdf_op.cc:L303

Computes the value of the PDF of *sample* of generalized negative binomial distributions with parameters *mu* (mean) and *alpha* (dispersion). This can be understood as a reparameterization of the negative binomial, where *k* = *1 / alpha* and $*p* = *1 / (mu \setminus *alpha + 1)*$.

Description

mu and *alpha* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *mu* and *alpha*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *mu* and *alpha* at index *i*.

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
mu	NDArray-or-Symbol Means of the distributions.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.
alpha	NDArray-or-Symbol Alpha (dispersion) parameters of the distributions.

Details

Examples::

random_pdf_generalized_negative_binomial(sample=[[1, 2, 3, 4]], alpha=[1], mu=[1]) = [[0.25, 0.125, 0.0625, 0.03125]]

sample = [[1,2,3,4], [1,2,3,4]] random_pdf_generalized_negative_binomial(sample=sample, alpha=[1, 0.6666], mu=[1, 1.5]) = [[0.25, 0.125, 0.0625, 0.03125], [0.26517063, 0.16573331, 0.09667706, 0.05437994]]

Defined in src/operator/random/pdf_op.cc:L314

Value

out The result mx.ndarray

mx.nd.random.pdf.negative.binomial

Computes the value of the PDF of samples of negative binomial distributions with parameters *k* (failure limit) and *p* (failure probability).

Description

k and *p* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *k* and *p*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *k* and *p* at index *i*.

Arguments

sample NDArray-or-Symbol Samples from the distributions.

k NDArray-or-Symbol Limits of unsuccessful experiments.

is.log boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.

p NDArray-or-Symbol Failure probabilities in each experiment.

Details

Examples::

```
 \begin{array}{l} {\rm random\_pdf\_negative\_binomial(sample=[[1,2,3,4]], k=[1], p=a[0.5])=[[0.25, 0.125, 0.0625, 0.03125]]} \\ {\rm \#\,Note\,that\,k\,may\,be\,real\_valued\,sample=[[1,2,3,4], [1,2,3,4]]\,random\_pdf\_negative\_binomial(sample=sample, k=[1, 1.5], p=[0.5, 0.5])=[[0.25, 0.125, 0.0625, 0.03125], [0.26516506, 0.16572815, 0.09667476, 0.05437956]]} \\ \end{array}
```

Defined in src/operator/random/pdf_op.cc:L310

Value

out The result mx.ndarray

mx.nd.random.pdf.normal

Computes the value of the PDF of *sample* of normal distributions with parameters *mu* (mean) and *sigma* (standard deviation).

Description

mu and *sigma* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *mu* and *sigma*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *mu* and *sigma* at index *i*.

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
mu	NDArray-or-Symbol Means of the distributions.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.
sigma	NDArray-or-Symbol Standard deviations of the distributions.

Details

Examples::

```
sample = [[-2, -1, 0, 1, 2]] random_pdf_normal(sample=sample, mu=[0], sigma=[1]) = [[0.05399097, 0.24197073, 0.3989423, 0.24197073, 0.05399097]]
```

random_pdf_normal(sample=sample*2, mu=[0,0], sigma=[1,2]) = [[0.05399097, 0.24197073, 0.3989423, 0.24197073, 0.05399097], [0.12098537, 0.17603266, 0.19947115, 0.17603266, 0.12098537]]

Defined in src/operator/random/pdf_op.cc:L300

Value

mx.nd.random.pdf.poisson

Computes the value of the PDF of *sample* of Poisson distributions with parameters *lam* (rate).

Description

The shape of *lam* must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *lam*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the value of *lam* at index *i*.

Arguments

sample NDArray-or-Symbol Samples from the distributions.

lam NDArray-or-Symbol Lambda (rate) parameters of the distributions.

is.log boolean, optional, default=0 If set, compute the density of the log-probability

instead of the probability.

Details

Examples::

```
\begin{split} & \text{random\_pdf\_poisson}(\text{sample=}[[0,1,2,3]], \text{lam=}[1]) = [[0.36787945, 0.36787945, 0.18393973, 0.06131324]] \\ & \text{sample=}[[0,1,2,3], [0,1,2,3], [0,1,2,3]] \end{split}
```

random_pdf_poisson(sample=sample, lam=[1,2,3]) = [[0.36787945, 0.36787945, 0.18393973, 0.06131324], [0.13533528, 0.27067056, 0.27067056, 0.18044704], [0.04978707, 0.14936121, 0.22404182, 0.22404182]]

Defined in src/operator/random/pdf_op.cc:L307

Value

out The result mx.ndarray

mx.nd.random.pdf.uniform

Computes the value of the PDF of *sample* of uniform distributions on the intervals given by *[low,high)*.

Description

low and *high* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *low* and *high*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *low* and *high* at index *i*.

200 mx.nd.random.poisson

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
low	NDArray-or-Symbol Lower bounds of the distributions.

is.log boolean, optional, default=0 If set, compute the density of the log-probability

instead of the probability.

high NDArray-or-Symbol Upper bounds of the distributions.

Details

Examples::

```
 \begin{array}{l} {\rm random\_pdf\_uniform(sample=[[1,2,3,4]],\ low=[0],\ high=[10])=[0.1,\ 0.1,\ 0.1,\ 0.1]} \\ {\rm sample=[[[1,2,3],\ [1,2,3]],\ [[1,2,3],\ [1,2,3]]]\ low=[[0,0],\ [0,0]]\ high=[[5,10],\ [15,20]]\ random\_pdf\_uniform(sample=sample,\ low=low,\ high=high)=[[[0.2,\ 0.2,\ 0.2],\ [0.1,\ 0.1,\ 0.1]],\ [[0.06667,\ 0.06667,\ 0.06667],\ [0.05,\ 0.05,\ 0.05]]] \\ {\rm Defined\ in\ src/operator/random/pdf\_op.cc:L298} \\ \end{array}
```

Value

out The result mx.ndarray

mx.nd.random.poisson Draw random samples from a Poisson distribution.

Description

Samples are distributed according to a Poisson distribution parametrized by *lambda* (rate). Samples will always be returned as a floating point data type.

Arguments

lam	float, optional, default=1 Lambda parameter (rate) of the Poisson distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n).
	Only used for imperative calls.

'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

Details

Example::

```
poisson(lam=4, shape=(2,2)) = [[ 5., 2.], [ 4., 6.]]
Defined in src/operator/random/sample_op.cc:L150
```

Value

mx.nd.random.randint 201

mx.nd.random.randint Draw random samples from a discrete uniform distribution.

Description

Samples are uniformly distributed over the half-open interval *[low, high)* (includes *low*, but excludes *high*).

Arguments

low long, required Lower bound of the distribution.high long, required Upper bound of the distribution.

shape Shape(tuple), optional, default=None Shape of the output.

ctx string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n).

Only used for imperative calls.

dtype 'None', 'int32', 'int64', optional, default='None' DType of the output in case

this can't be inferred. Defaults to int32 if not defined (dtype=None).

Details

Example::

randint(low=0, high=5, shape=(2,2)) = [[0, 2], [3, 1]] Defined in src/operator/random/sample_op.cc:L194

Value

out The result mx.ndarray

 $\verb|mx.nd.random.uniform|| \textit{Draw random samples from a uniform distribution}.$

Description

.. note:: The existing alias "uniform" is deprecated.

Arguments

low	float, optional, default=0 Lower bound of the distribution.
high	float, optional, default=1 Upper bound of the distribution.
shape	Shape(tuple), optional, default=None Shape of the output.

ctx string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n).

Only used for imperative calls.

dtype 'None', 'float16', 'float32', 'float64', optional, default='None' DType of the out-

put in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

202 mx.nd.ravel.multi.index

Details

Samples are uniformly distributed over the half-open interval *[low, high)* (includes *low*, but excludes *high*).

Example::

uniform(low=0, high=1, shape=(2,2)) = [[0.60276335, 0.85794562], [0.54488319, 0.84725171]]

Defined in src/operator/random/sample_op.cc:L96

Value

out The result mx.ndarray

mx.nd.ravel.multi.index

Converts a batch of index arrays into an array of flat indices. The operator follows numpy conventions so a single multi index is given by a column of the input matrix. The leading dimension may be left unspecified by using -1 as placeholder.

Description

Examples::

A = [[3,6,6],[4,5,1]] ravel(A, shape=(7,6)) = [22,41,37] ravel(A, shape=(-1,6)) = [22,41,37]

Arguments

data NDArray-or-Symbol Batch of multi-indices

shape Shape(tuple), optional, default=None Shape of the array into which the multi-

indices apply.

Details

Defined in src/operator/tensor/ravel.cc:L42

Value

mx.nd.rcbrt 203

mx.nd.rcbrt

Returns element-wise inverse cube-root value of the input.

Description

```
.. math:: rcbrt(x) = 1 \land sqrt[3]x
```

Arguments

data

NDArray-or-Symbol The input array.

Details

```
Example::
```

```
rcbrt([1,8,-125]) = [1.0, 0.5, -0.2]
```

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L269

Value

out The result mx.ndarray

mx.nd.reciprocal

Returns the reciprocal of the argument, element-wise.

Description

Calculates 1/x.

Arguments

data

NDArray-or-Symbol The input array.

Details

```
Example::
```

```
reciprocal([-2, 1, 3, 1.6, 0.2]) = [-0.5, 1.0, 0.33333334, 0.625, 5.0]
```

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L42

Value

204 mx.nd.repeat

mx.nd.relu

Computes rectified linear activation.

Description

.. math:: max(features, 0)

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "relu" output depends upon the input storage type:

- relu(default) = default - relu(row_sparse) = row_sparse - relu(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L85

Value

out The result mx.ndarray

mx.nd.repeat

Repeats elements of an array. By default, "repeat" flattens the input array into 1-D and then repeats the elements:: x = [[1, 2], [3, 4]] repeat(x, repeats=2) = [1, 1, 2, 2, 3, 3, 4, 4] The parameter "axis" specifies the axis along which to perform repeat:: repeat(x, repeats=2, axis=1) = [[1, 1, 2, 2, 2], [3, 3, 4, 4, 4]] repeat(x, repeats=2, axis=0) = [[1, 2, 2], [1, 2, 2], [3, 4, 4, 4]] repeat(x, repeats=2, axis=-1) = [[1, 1, 2, 2, 2], [3, 3, 4, 4, 4]]

Description

Defined in src/operator/tensor/matrix_op.cc:L738

Arguments

data NDArray-or-Symbol Input data array

repeats int, required The number of repetitions for each element.

axis int or None, optional, default='None' The axis along which to repeat values.

The negative numbers are interpreted counting from the backward. By default,

use the flattened input array, and return a flat output array.

Value

mx.nd.reset.arrays 205

mx.nd.reset.arrays
Set to zero multiple arrays

Description

Defined in src/operator/contrib/reset_arrays.cc:L36

Arguments

data NDArray-or-Symbol[] Arrays

num.arrays int, required number of input arrays.

Value

206 mx.nd.Reshape

mx.nd.Reshape

Reshapes the input array. .. note:: "Reshape" is deprecated, use "reshape" Given an array and a shape, this function returns a copy of the array in the new shape. The shape is a tuple of integers such as (2,3,4). The size of the new shape should be same as the size of the input array. Example:: reshape([1,2,3,4], shape=(2,2)) = [[1,2],[3,4]] Some dimensions of the shape can take special values from the set 0, -1, -2, -3, -4. The significance of each is explained below: - "0" copy this dimension from the input to the output shape. Example:: input shape = (2,3,4), shape = (4,0,2), output shape = (4,3,2) - input shape = (2,3,4), shape = (2,0,0), output shape = (2,3,4) - "-1" infers the dimension of the output shape by using the remainder of the input dimensions keeping the size of the new array same as that of the input array. At most one dimension of shape can be -1. Example:: - input shape = (2,3,4), shape = (6,1,-1), output shape = (6,1,4) - input shape= (2,3,4), shape = (3,-1,8), output shape = (3,1,8) - input shape =(2,3,4), shape=(-1,), output shape = (24,) - "-2" copy all/remainderof the input dimensions to the output shape. Example:: - input shape = (2,3,4), shape = (-2,), output shape = (2,3,4) - input shape = (2,3,4), shape = (2,-2), output shape = (2,3,4) - input shape = (2,3,4), shape = (-2,1,1), output shape = (2,3,4,1,1) - "-3" use the product of two consecutive dimensions of the input shape as the output dimension. Example:: - input shape = (2,3,4), shape = (-3,4), output shape = (6,4) - input shape = (2,3,4,5), shape = (-3,-3), output shape = (6,20)- input shape = (2,3,4), shape = (0,-3), output shape = (2,12) - input shape = (2,3,4), shape = (-3,-2), output shape = (6,4) - "-4" split one dimension of the input into two dimensions passed subsequent to -4 in shape (can contain -1). Example:: - input shape = (2,3,4), shape = (-4,1,2,-2), output shape = (1,2,3,4) - input shape = (2,3,4), shape = (2,-4,-1,3,-2), output shape = (2,1,3,4) If the argument 'reverse' is set to 1, then the special values are inferred from right to left. Example:: - without reverse=1, for input shape = (10,5,4), shape = (-1,0), output shape would be (40,5) - with reverse=1, output shape will be (50,4).

Description

Defined in src/operator/tensor/matrix_op.cc:L175

Arguments

data NDArray-or-Symbol Input data to reshape.

shape Shape(tuple), optional, default=[] The target shape

reverse boolean, optional, default=0 If true then the special values are inferred from

right to left

target.shape Shape(tuple), optional, default=[] (Deprecated! Use "shape" instead.) Target

new shape. One and only one dim can be 0, in which case it will be inferred

from the rest of dims

mx.nd.reshape 207

keep.highest

boolean, optional, default=0 (Deprecated! Use "shape" instead.) Whether keep the highest dim unchanged. If set to true, then the first dim in target_shape is ignored, and always fixed as input

Value

out The result mx.ndarray

mx.nd.reshape

Reshapes the input array. .. note:: "Reshape" is deprecated, use "reshape" Given an array and a shape, this function returns a copy of the array in the new shape. The shape is a tuple of integers such as (2,3,4). The size of the new shape should be same as the size of the input array. Example:: reshape([1,2,3,4], shape=(2,2)) = [[1,2],[3,4]] Some dimensions of the shape can take special values from the set 0, -1, -2, -3, -4. The significance of each is explained below: - "0" copy this dimension from the input to the output shape. Example:: input shape = (2,3,4), shape = (4,0,2), output shape = (4,3,2) - input shape = (2,3,4), shape = (2,0,0), output shape = (2,3,4) - "-1" infers the dimension of the output shape by using the remainder of the input dimensions keeping the size of the new array same as that of the input array. At most one dimension of shape can be -1. Example:: - input shape = (2,3,4), shape = (6,1,-1), output shape = (6,1,4) - input shape= (2,3,4), shape = (3,-1,8), output shape = (3,1,8) - input shape =(2,3,4), shape=(-1,), output shape=(24,) - "-2" copy all/remainder of the input dimensions to the output shape. Example:: - input shape =(2,3,4), shape =(-2,), output shape =(2,3,4) - input shape =(2,3,4), shape = (2,-2), output shape = (2,3,4) - input shape = (2,3,4), shape= (-2,1,1), output shape = (2,3,4,1,1) - "-3" use the product of two consecutive dimensions of the input shape as the output dimension. Example:: - input shape = (2,3,4), shape = (-3,4), output shape = (6,4) - input shape = (2,3,4,5), shape = (-3,-3), output shape = (6,20)- input shape = (2,3,4), shape = (0,-3), output shape = (2,12) - input shape = (2,3,4), shape = (-3,-2), output shape = (6,4) - "-4" split one dimension of the input into two dimensions passed subsequent to -4 in shape (can contain -1). Example:: - input shape = (2,3,4), shape = (-4,1,2,-2), output shape = (1,2,3,4) - input shape = (2,3,4), shape = (2,-4,-1,3,-2), output shape = (2,1,3,4) If the argument 'reverse' is set to 1, then the special values are inferred from right to left. Example:: - without reverse=1, for input shape = (10,5,4), shape = (-1,0), output shape would be (40,5) - with reverse=1, output shape will be (50,4).

Description

Defined in src/operator/tensor/matrix_op.cc:L175

208 mx.nd.reshape.like

Arguments

data NDArray-or-Symbol Input data to reshape.

shape Shape(tuple), optional, default=[] The target shape

reverse boolean, optional, default=0 If true then the special values are inferred from

right to left

target.shape Shape(tuple), optional, default=[] (Deprecated! Use "shape" instead.) Target

new shape. One and only one dim can be 0, in which case it will be inferred

from the rest of dims

keep.highest boolean, optional, default=0 (Deprecated! Use "shape" instead.) Whether keep

the highest dim unchanged. If set to true, then the first dim in target shape is

ignored, and always fixed as input

Value

out The result mx.ndarray

mx.nd.reshape.like Reshape some or all dimensions of 'lhs' to have the same shape as

some or all dimensions of 'rhs'.

Description

Returns a **view** of the 'lhs' array with a new shape without altering any data.

Arguments

1hs NDArray-or-Symbol First input.

rhs NDArray-or-Symbol Second input.

lhs.begin int or None, optional, default='None' Defaults to 0. The beginning index along

which the lhs dimensions are to be reshaped. Supports negative indices.

1hs. end int or None, optional, default='None' Defaults to None. The ending index along

which the lhs dimensions are to be used for reshaping. Supports negative in-

dices.

rhs.begin int or None, optional, default='None' Defaults to 0. The beginning index along

which the rhs dimensions are to be used for reshaping. Supports negative in-

dices.

rhs.end int or None, optional, default='None' Defaults to None. The ending index along

which the rhs dimensions are to be used for reshaping. Supports negative in-

dices.

mx.nd.reverse 209

Details

Example::

```
x = [1, 2, 3, 4, 5, 6] y = [[0, -4], [3, 2], [2, 2]] reshape_like(x, y) = [[1, 2], [3, 4], [5, 6]]
```

More precise control over how dimensions are inherited is achieved by specifying \ slices over the 'lhs' and 'rhs' array dimensions. Only the sliced 'lhs' dimensions \ are reshaped to the 'rhs' sliced dimensions, with the non-sliced 'lhs' dimensions staying the same.

Examples::

- lhs shape = (30.7), rhs shape = (15.2.4), lhs_begin=0, lhs_end=1, rhs_begin=0, rhs_end=2, output shape = (15.2.7) - lhs shape = (3.5), rhs shape = (1.15.4), lhs_begin=0, lhs_end=2, rhs_begin=1, rhs_end=2, output shape = (15)

Negative indices are supported, and 'None' can be used for either 'lhs_end' or 'rhs_end' to indicate the end of the range.

Example::

- lhs shape = (30, 12), rhs shape = (4, 2, 2, 3), lhs_begin=-1, lhs_end=None, rhs_begin=1, rhs_end=None, output shape = (30, 2, 2, 3)

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L513

Value

out The result mx.ndarray

mx.	nd.	rev	er	se

Reverses the order of elements along given axis while preserving array shape. Note: reverse and flip are equivalent. We use reverse in the following examples. Examples:: x = [[0., 1., 2., 3., 4.], [5., 6., 7., 8., 9.]] reverse(x, axis=0) = [[5., 6., 7., 8., 9.], [0., 1., 2., 3., 4.]] reverse(x, axis=1) = [[4., 3., 2., 1., 0.], [9., 8., 7., 6., 5.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L826

Arguments

data NDArray-or-Symbol Input data array

axis Shape(tuple), required The axis which to reverse elements.

Value

210 mx.nd.rmsprop.update

mx.nd.rint

Returns element-wise rounded value to the nearest integer of the input.

Description

.. note:: - For input "n.5" "rint" returns "n" while "round" returns "n+1". - For input "-n.5" both "rint" and "round" returns "-n-1".

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

```
rint([-1.5, 1.5, -1.9, 1.9, 2.1]) = [-2., 1., -2., 2., 2.]
```

The storage type of "rint" output depends upon the input storage type:

- rint(default) = default - rint(row_sparse) = row_sparse - rint(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L799

Value

out The result mx.ndarray

Update function for 'RMSProp' optimizer.

Description

'RMSprop' is a variant of stochastic gradient descent where the gradients are divided by a cache which grows with the sum of squares of recent gradients?

Arguments

wd

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
n	NDArray-or-Symbol n
lr	float, required Learning rate

gamma1 float, optional, default=0.949999988 The decay rate of momentum estimates.
epsilon float, optional, default=9.99999994e-09 A small constant for numerical stability.

float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

clip.weights float, optional, default=-1 Clip weights to the range of [-clip_weights, clip_weights]

If clip_weights <= 0, weight clipping is turned off. weights = max(min(weights,

clip_weights), -clip_weights).

Details

'RMSProp' is similar to 'AdaGrad', a popular variant of 'SGD' which adaptively tunes the learning rate of each parameter. 'AdaGrad' lowers the learning rate for each parameter monotonically over the course of training. While this is analytically motivated for convex optimizations, it may not be ideal for non-convex problems. 'RMSProp' deals with this heuristically by allowing the learning rates to rebound as the denominator decays over time.

Define the Root Mean Square (RMS) error criterion of the gradient as :math: 'RMS[g]_t = \sqrtE[g^2]_t + \epsilon', where :math: 'g' represents gradient and :math: 'E[g^2]_t' is the decaying average over past squared gradient.

The :math: $E[g^2]_t$ is given by:

.. math:: $E[g^2]_t = \gamma * E[g^2]_{t-1} + (1-\gamma) * g_t^2$

The update step is

.. math:: $\theta_t = \theta_t - \frac{r}{g} g_t$

The RMSProp code follows the version in http://www.cs.toronto.edu/~tijmen/csc321/slides/lecture_slides_lec6.pdf Tieleman & Hinton, 2012.

Hinton suggests the momentum term :math:'\gamma' to be 0.9 and the learning rate :math:'\eta' to be 0.001.

Defined in src/operator/optimizer_op.cc:L795

Value

out The result mx.ndarray

mx.nd.rmspropalex.update

Update function for RMSPropAlex optimizer.

Description

'RMSPropAlex' is non-centered version of 'RMSProp'.

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
n	NDArray-or-Symbol n
g	NDArray-or-Symbol g
delta	NDArray-or-Symbol delta
lr	float, required Learning rate
gamma1	float, optional, default=0.949999988 Decay rate.
gamma2	float, optional, default=0.899999976 Decay rate.
epsilon	float, optional, default=9.99999994e-09 A small constant for numerical stability.
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
clip.weights	float, optional, default=-1 Clip weights to the range of [-clip_weights, clip_weights] If clip_weights <= 0, weight clipping is turned off. weights = max(min(weights, clip_weights), -clip_weights).

Details

Define :math: $E[g^2]_t$ is the decaying average over past squared gradient and :math: $E[g]_t$ is the decaying average over past gradient.

```
.. math:: E[g^2]_t = \gamma_1 * E[g^2]_t-1 + (1 - \gamma_1) * g_t^2\ E[g]_t = \gamma_1 * E[g]_t-1 + (1 - \gamma_1) * g_t\ \Delta_t = \gamma_2 * \Delta_t-1 - \frac\eta\sqrtE[g^2]_t - E[g]_t^2 + \epsilon g_t\
```

The update step is

```
.. math:: \theta_t = \theta_t + \theta_t + \theta_t
```

The RMSPropAlex code follows the version in http://arxiv.org/pdf/1308.0850v5.pdf Eq(38) - Eq(45) by Alex Graves, 2013.

Graves suggests the momentum term :math: \gamma_1' to be 0.95, :math: \gamma_2' to be 0.9 and the learning rate :math: \eta' to be 0.0001.

Defined in src/operator/optimizer_op.cc:L834

Value

mx.nd.RNN 213

mx.nd.RNN	Applies recurrent layers to input data. Currently, vanilla RNN, LSTM and GRU are implemented, with both multi-layer and bidirectional support.

Description

When the input data is of type float32 and the environment variables MXNET_CUDA_ALLOW_TENSOR_CORE and MXNET_CUDA_TENSOR_OP_MATH_ALLOW_CONVERSION are set to 1, this operator will try to use pseudo-float16 precision (float32 math with float16 I/O) precision in order to use Tensor Cores on suitable NVIDIA GPUs. This can sometimes give significant speedups.

Arguments

data	NDArray-or-Symbol Input data to RNN
parameters	NDArray-or-Symbol Vector of all RNN trainable parameters concatenated
state	NDArray-or-Symbol initial hidden state of the RNN
state.cell	NDArray-or-Symbol initial cell state for LSTM networks (only for LSTM)
sequence.length	ı
	NDArray-or-Symbol Vector of valid sequence lengths for each element in batch. (Only used if use_sequence_length kwarg is True)
state.size	int (non-negative), required size of the state for each layer
num.layers	int (non-negative), required number of stacked layers
bidirectional	boolean, optional, default=0 whether to use bidirectional recurrent layers
mode	'gru', 'lstm', 'rnn_relu', 'rnn_tanh', required the type of RNN to compute
p	float, optional, default=0 drop rate of the dropout on the outputs of each RNN layer, except the last layer.
state.outputs	boolean, optional, default=0 Whether to have the states as symbol outputs.
projection.size	
	int or None, optional, default='None' size of project size
lstm.state.clip	o.min
	double or None, optional, default=None Minimum clip value of LSTM states. This option must be used together with lstm_state_clip_max.
3 3 .	

lstm.state.clip.max

double or None, optional, default=None Maximum clip value of LSTM states. This option must be used together with lstm_state_clip_min.

lstm.state.clip.nan

boolean, optional, default=0 Whether to stop NaN from propagating in state by clipping it to min/max. If clipping range is not specified, this option is ignored.

use.sequence.length

boolean, optional, default=0 If set to true, this layer takes in an extra input parameter 'sequence_length' to specify variable length sequence

214 mx.nd.ROIPooling

Details

```
**Vanilla RNN**
```

Applies a single-gate recurrent layer to input X. Two kinds of activation function are supported: ReLU and Tanh.

With ReLU activation function:

```
.. math:: h_t = relu(W_ih * x_t + b_ih + W_hh * h_(t-1) + b_hh)
```

With Tanh activtion function:

```
.. math:: h_t = \tanh(W_ih * x_t + b_ih + W_hh * h_(t-1) + b_hh)
```

Reference paper: Finding structure in time - Elman, 1988. https://crl.ucsd.edu/~elman/Papers/fsit.pdf **LSTM**

Long Short-Term Memory - Hochreiter, 1997. http://www.bioinf.jku.at/publications/older/2604.pdf

Gated Recurrent Unit - Cho et al. 2014. http://arxiv.org/abs/1406.1078

The definition of GRU here is slightly different from paper but compatible with CUDNN.

```
.. math:: \beginarrayll r_t = \mathrmsigmoid(W_ir x_t + b_ir + W_hr h_(t-1) + b_hr) \ z_t = \mathrmsigmoid(W_iz x_t + b_iz + W_hz h_(t-1) + b_hz) \ n_t = \tanh(W_in x_t + b_in + r_t * (W_hn h_(t-1) + b_hn)) \ h_t = (1 - z_t) * n_t + z_t * h_(t-1) \ \endarray
```

Defined in src/operator/rnn.cc:L351

Value

out The result mx.ndarray

mx.nd.ROIPooling

Performs region of interest(ROI) pooling on the input array.

Description

ROI pooling is a variant of a max pooling layer, in which the output size is fixed and region of interest is a parameter. Its purpose is to perform max pooling on the inputs of non-uniform sizes to obtain fixed-size feature maps. ROI pooling is a neural-net layer mostly used in training a 'Fast R-CNN' network for object detection.

mx.nd.ROIPooling 215

Arguments

data	NDArray-or-Symbol The input array to the pooling operator, a 4D Feature maps	
rois	NDArray-or-Symbol Bounding box coordinates, a 2D array of [[batch_index, x1, y1, x2, y2]], where (x1, y1) and (x2, y2) are top left and bottom right corners of designated region of interest. 'batch_index' indicates the index of corresponding image in the input array	
pooled.size	Shape(tuple), required ROI pooling output shape (h,w)	
spatial.scale	float, required Ratio of input feature map height (or w) to raw image height (or w). Equals the reciprocal of total stride in convolutional layers	

Details

This operator takes a 4D feature map as an input array and region proposals as 'rois', then it pools over sub-regions of input and produces a fixed-sized output array regardless of the ROI size.

To crop the feature map accordingly, you can resize the bounding box coordinates by changing the parameters 'rois' and 'spatial_scale'.

The cropped feature maps are pooled by standard max pooling operation to a fixed size output indicated by a 'pooled_size' parameter. batch_size will change to the number of region bounding boxes after 'ROIPooling'.

The size of each region of interest doesn't have to be perfectly divisible by the number of pooling sections ('pooled_size').

Example::

```
x = [[[[0., 1., 2., 3., 4., 5.], [6., 7., 8., 9., 10., 11.], [12., 13., 14., 15., 16., 17.], [18., 19., 20., 21., 22., 23.], [24., 25., 26., 27., 28., 29.], [30., 31., 32., 33., 34., 35.], [36., 37., 38., 39., 40., 41.], [42., 43., 44., 45., 46., 47.]]]]
```

// region of interest i.e. bounding box coordinates. y = [[0,0,0,4,4]]

// returns array of shape (2,2) according to the given roi with max pooling. ROIPooling(x, y, (2,2), 1.0) = [[[[14., 16.], [26., 28.]]]]

// region of interest is changed due to the change in 'spacial_scale' parameter. ROIPooling(x, y, (2,2), 0.7) = [[[[7., 9.], [19., 21.]]]]

Defined in src/operator/roi_pooling.cc:L225

Value

216 mx.nd.rsqrt

mx.nd.round

Returns element-wise rounded value to the nearest integer of the input.

Description

Example::

Arguments

data

NDArray-or-Symbol The input array.

Details

```
round([-1.5, 1.5, -1.9, 1.9, 2.1]) = [-2., 2., -2., 2., 2.]
```

The storage type of "round" output depends upon the input storage type:

- round(default) = default - round(row_sparse) = row_sparse - round(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L778

Value

out The result mx.ndarray

mx.nd.rsqrt

Returns element-wise inverse square-root value of the input.

Description

```
.. math:: rsqrt(x) = 1 \land sqrtx
```

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

```
rsqrt([4,9,16]) = [0.5, 0.33333334, 0.25]
```

The storage type of "rsqrt" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L193

Value

mx.nd.sample.exponential

Concurrent sampling from multiple exponential distributions with parameters lambda (rate).

Description

The parameters of the distributions are provided as an input array. Let *[s]* be the shape of the input array, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

Arguments

lam	NDArray-or-Symbol Lambda (rate) parameters of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

Details

For any valid *n*-dimensional index *i* with respect to the input array, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input value at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input array.

Examples::

```
lam = [1.0, 8.5]
```

// Draw a single sample for each distribution sample_exponential(lam) = [0.51837951, 0.09994757]

// Draw a vector containing two samples for each distribution sample_exponential(lam, shape=(2)) = [[0.51837951, 0.19866663], [0.09994757, 0.50447971]]

Defined in src/operator/random/multisample_op.cc:L284

Value

218 mx.nd.sample.gamma

mx.nd.sample.gamma	Concurrent sampling from multiple gamma distributions with parameters *alpha* (shape) and *beta* (scale).

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

Arguments

alpha	NDArray-or-Symbol Alpha (shape) parameters of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
beta	NDArray-or-Symbol Beta (scale) parameters of the distributions.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Examples::

```
alpha = [ 0.0, 2.5 ] beta = [ 1.0, 0.7 ]

// Draw a single sample for each distribution sample_gamma(alpha, beta) = [ 0. , 2.25797319]

// Draw a vector containing two samples for each distribution sample_gamma(alpha, beta, shape=(2)) = [[ 0. , 0. ], [ 2.25797319, 1.70734084]]

Defined in src/operator/random/multisample_op.cc:L282
```

Value

```
mx.nd.sample.generalized.negative.binomial
```

Concurrent sampling from multiple generalized negative binomial distributions with parameters *mu* (mean) and *alpha* (dispersion).

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

Arguments

mu	NDArray-or-Symbol Means of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
alpha	NDArray-or-Symbol Alpha (dispersion) parameters of the distributions.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Samples will always be returned as a floating point data type.

Examples::

```
mu = [2.0, 2.5] alpha = [1.0, 0.1]
```

// Draw a single sample for each distribution sample_generalized_negative_binomial(mu, alpha) = [0., 3.]

// Draw a vector containing two samples for each distribution sample_generalized_negative_binomial(mu, alpha, shape=(2)) = [[0., 3.], [3., 1.]]

Defined in src/operator/random/multisample_op.cc:L293

Value

```
mx.nd.sample.multinomial
```

Concurrent sampling from multiple multinomial distributions.

Description

data is an *n* dimensional array whose last dimension has length *k*, where *k* is the number of possible outcomes of each multinomial distribution. This operator will draw *shape* samples from each distribution. If shape is empty one sample will be drawn from each distribution.

Arguments

data	NDArray-or-Symbol Distribution probabilities. Must sum to one on the last axis.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
get.prob	boolean, optional, default=0 Whether to also return the log probability of sampled result. This is usually used for differentiating through stochastic variables, e.g. in reinforcement learning.
dtype	'float16', 'float32', 'float64', 'int32', 'uint8', optional, default='int32' DType of the output in case this can't be inferred.

Details

If *get_prob* is true, a second array containing log likelihood of the drawn samples will also be returned. This is usually used for reinforcement learning where you can provide reward as head gradient for this array to estimate gradient.

Note that the input distribution must be normalized, i.e. *data* must sum to 1 along its last axis.

Examples::

```
probs = [[0, 0.1, 0.2, 0.3, 0.4], [0.4, 0.3, 0.2, 0.1, 0]]

// Draw a single sample for each distribution sample_multinomial(probs) = [3, 0]

// Draw a vector containing two samples for each distribution sample_multinomial(probs, shape=(2)) = [[4, 2], [0, 0]]

// requests log likelihood sample_multinomial(probs, get_prob=True) = [2, 1], [0.2, 0.3]
```

Value

```
mx.nd.sample.negative.binomial
```

Concurrent sampling from multiple negative binomial distributions with parameters *k* (failure limit) and *p* (failure probability).

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

Arguments

k	NDArray-or-Symbol Limits of unsuccessful experiments.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
р	NDArray-or-Symbol Failure probabilities in each experiment.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Samples will always be returned as a floating point data type.

Examples::

```
k = [20, 49] p = [0.4, 0.77]
```

// Draw a single sample for each distribution sample_negative_binomial(k, p) = [15., 16.]

// Draw a vector containing two samples for each distribution sample_negative_binomial(k, p, shape=(2)) = [[15., 50.], [16., 12.]]

Defined in src/operator/random/multisample_op.cc:L289

Value

222 mx.nd.sample.normal

mx.nd.sample.normal	Concurrent sampling from multiple normal distributions with param-
	eters *mu* (mean) and *sigma* (standard deviation).

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

Arguments

mu	NDArray-or-Symbol Means of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
sigma	NDArray-or-Symbol Standard deviations of the distributions.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Examples::

```
mu = [0.0, 2.5] sigma = [1.0, 3.7]
```

// Draw a single sample for each distribution sample_normal(mu, sigma) = [-0.56410581, 0.95934606]

// Draw a vector containing two samples for each distribution sample_normal(mu, sigma, shape=(2)) = [[-0.56410581, 0.2928229], [0.95934606, 4.48287058]]

Defined in src/operator/random/multisample_op.cc:L279

Value

mx.nd.sample.poisson 223

mx.nd.sample.poisson Concurrent sampling from multiple Poisson distributions with parameters lambda (rate).

Description

The parameters of the distributions are provided as an input array. Let *[s]* be the shape of the input array, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

Arguments

lam	NDArray-or-Symbol Lambda (rate) parameters of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

Details

For any valid *n*-dimensional index *i* with respect to the input array, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input value at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input array.

Samples will always be returned as a floating point data type.

Examples::

```
lam = [1.0, 8.5]
```

// Draw a single sample for each distribution sample_poisson(lam) = [0., 13.]

// Draw a vector containing two samples for each distribution sample_poisson(lam, shape=(2)) = [[0., 4.], [13., 8.]]

Defined in src/operator/random/multisample_op.cc:L286

Value

224 mx.nd.sample.uniform

 $\begin{tabular}{ll} mx.nd.sample.uniform & Concurrent sampling from multiple uniform distributions on the intervals given by $$\{low,high)$*. \end{tabular}$

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

Arguments

low	NDArray-or-Symbol Lower bounds of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
high	NDArray-or-Symbol Upper bounds of the distributions.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Examples::

```
low = [0.0, 2.5] high = [1.0, 3.7]
```

// Draw a single sample for each distribution sample_uniform(low, high) = [0.40451524, 3.18687344]

// Draw a vector containing two samples for each distribution sample_uniform(low, high, shape=(2)) = [[0.40451524, 0.18017688], [3.18687344, 3.68352246]]

Defined in src/operator/random/multisample_op.cc:L277

Value

mx.nd.save 225

mx.nd.save

Save an mx.nd.array object

Description

Save an mx.nd.array object

Usage

```
mx.nd.save(ndarray, filename)
```

Arguments

ndarray the mx.nd.array object

filename (including the path)

Examples

```
mat = mx.nd.array(1:3)
mx.nd.save(mat, 'temp.mat')
mat2 = mx.nd.load('temp.mat')
as.array(mat)
as.array(mat2[[1]])
```

mx.nd.scatter.nd

Scatters data into a new tensor according to indices.

Description

Given 'data' with shape ' $(Y_0, ..., Y_{K-1}, X_M, ..., X_{N-1})$ ' and indices with shape ' $(M, Y_0, ..., Y_{K-1})$ ', the output will have shape ' $(X_0, X_1, ..., X_{N-1})$ ', where ' $M \le N$ '. If 'M == N', data shape should simply be ' $(Y_0, ..., Y_{K-1})$ '.

Arguments

data	NDArray-or-Symbol data
indices	NDArray-or-Symbol indices

shape Shape(tuple), required Shape of output.

226 mx.nd.SequenceLast

Details

The elements in output is defined as follows::

```
output[indices[0, y_0, ..., y_K-1], ..., indices[M-1, y_0, ..., y_K-1], x_M, ..., x_N-1] = data[y_0, ..., y_K-1, x_M, ..., x_N-1]
```

all other entries in output are 0.

.. warning::

If the indices have duplicates, the result will be non-deterministic and the gradient of 'scatter_nd' will not be correct!!

Examples::

```
data = [2, 3, 0] indices = [[1, 1, 0], [0, 1, 0]] shape = (2, 2) scatter_nd(data, indices, shape) = [[0, 0], [2, 3]]
```

data = [[[1, 2], [3, 4]], [[5, 6], [7, 8]]] indices = [[0, 1], [1, 1]] shape = (2, 2, 2, 2) scatter_nd(data, indices, shape) = [[[[0, 0], [0, 0]],

[[1, 2], [3, 4]]],

[[[0, 0], [0, 0]],

[[5, 6], [7, 8]]]

Value

out The result mx.ndarray

mx.nd.SequenceLast

Takes the last element of a sequence.

Description

This function takes an n-dimensional input array of the form [max_sequence_length, batch_size, other_feature_dims] and returns a (n-1)-dimensional array of the form [batch_size, other_feature_dims].

Arguments

data NDArray-or-Symbol n-dimensional input array of the form [max_sequence_length,

batch_size, other_feature_dims] where n>2

sequence.length

NDArray-or-Symbol vector of sequence lengths of the form [batch_size]

use.sequence.length

boolean, optional, default=0 If set to true, this layer takes in an extra input pa-

rameter 'sequence_length' to specify variable length sequence

axis int, optional, default='0' The sequence axis. Only values of 0 and 1 are currently

supported.

mx.nd.SequenceMask 227

Details

Parameter 'sequence_length' is used to handle variable-length sequences. 'sequence_length' should be an input array of positive ints of dimension [batch_size]. To use this parameter, set 'use_sequence_length' to 'True', otherwise each example in the batch is assumed to have the max sequence length.

.. note:: Alternatively, you can also use 'take' operator.

Example::

```
x = [[[ 1., 2., 3.], [ 4., 5., 6.], [ 7., 8., 9.]],

[[ 10., 11., 12.], [ 13., 14., 15.], [ 16., 17., 18.]],

[[ 19., 20., 21.], [ 22., 23., 24.], [ 25., 26., 27.]]]

// returns last sequence when sequence_length parameter is not used SequenceLast(x) = [[ 19., 20., 21.], [ 22., 23., 24.], [ 25., 26., 27.]]

// sequence_length is used SequenceLast(x, sequence_length=[1,1,1], use_sequence_length=True)

= [[ 1., 2., 3.], [ 4., 5., 6.], [ 7., 8., 9.]]

// sequence_length is used SequenceLast(x, sequence_length=[1,2,3], use_sequence_length=True)

= [[ 1., 2., 3.], [ 13., 14., 15.], [ 25., 26., 27.]]

Defined in src/operator/sequence_last.cc:L106
```

Value

out The result mx.ndarray

mx.nd.SequenceMask

Sets all elements outside the sequence to a constant value.

Description

This function takes an n-dimensional input array of the form [max_sequence_length, batch_size, other_feature_dims] and returns an array of the same shape.

Arguments

data	NDArray-or-Symbol n-dimensional input array of the form [max_sequence_length, batch_size, other_feature_dims] where n>2	
sequence.length	1	
	NDArray-or-Symbol vector of sequence lengths of the form [batch_size]	
use.sequence.length		
	boolean, optional, default=0 If set to true, this layer takes in an extra input parameter 'sequence_length' to specify variable length sequence	
value	float, optional, default=0 The value to be used as a mask.	
axis	int, optional, default='0' The sequence axis. Only values of 0 and 1 are currently supported.	

Details

Parameter 'sequence_length' is used to handle variable-length sequences. 'sequence_length' should be an input array of positive ints of dimension [batch_size]. To use this parameter, set 'use_sequence_length' to 'True', otherwise each example in the batch is assumed to have the max sequence length and this operator works as the 'identity' operator.

Example::

```
x = [[[ 1., 2., 3.], [ 4., 5., 6.]],

[[ 7., 8., 9.], [ 10., 11., 12.]],

[[ 13., 14., 15.], [ 16., 17., 18.]]]

// Batch 1 B1 = [[ 1., 2., 3.], [ 7., 8., 9.], [ 13., 14., 15.]]

// Batch 2 B2 = [[ 4., 5., 6.], [ 10., 11., 12.], [ 16., 17., 18.]]
```

// works as identity operator when sequence_length parameter is not used SequenceMask(x) = [[[1., 2., 3.], [4., 5., 6.]],

```
[[ 7., 8., 9.], [ 10., 11., 12.]],
[[ 13., 14., 15.], [ 16., 17., 18.]]]
```

// sequence_length [1,1] means 1 of each batch will be kept // and other rows are masked with default mask value = 0 SequenceMask(x, sequence_length=[1,1], use_sequence_length=True) = [[[1., 2., 3.], [4., 5., 6.]],

```
[[0., 0., 0.], [0., 0., 0.]],
[[0., 0., 0.], [0., 0., 0.]]]
```

// sequence_length [2,3] means 2 of batch B1 and 3 of batch B2 will be kept // and other rows are masked with value = 1 SequenceMask(x, sequence_length=[2,3], use_sequence_length=True, value=1) = [[[1., 2., 3.], [4., 5., 6.]],

```
[[ 7., 8., 9.], [ 10., 11., 12.]],
[[ 1., 1., 1.], [ 16., 17., 18.]]]
```

Defined in src/operator/sequence_mask.cc:L186

Value

out The result mx.ndarray

mx.nd.SequenceReverse Reverses the elements of each sequence.

Description

This function takes an n-dimensional input array of the form [max_sequence_length, batch_size, other_feature_dims] and returns an array of the same shape.

Arguments

data NDArray-or-Symbol n-dimensional input array of the form [max_sequence_length, batch_size, other dims] where n>2

sequence.length

NDArray-or-Symbol vector of sequence lengths of the form [batch_size]

use.sequence.length

boolean, optional, default=0 If set to true, this layer takes in an extra input parameter 'sequence_length' to specify variable length sequence

axis int, optional, default='0' The sequence axis. Only 0 is currently supported.

Details

Parameter 'sequence_length' is used to handle variable-length sequences. 'sequence_length' should be an input array of positive ints of dimension [batch_size]. To use this parameter, set 'use_sequence_length' to 'True', otherwise each example in the batch is assumed to have the max sequence length.

Example::

```
x = [[[ 1., 2., 3.], [ 4., 5., 6.]],

[[ 7., 8., 9.], [ 10., 11., 12.]],

[[ 13., 14., 15.], [ 16., 17., 18.]]]

// Batch 1 B1 = [[ 1., 2., 3.], [ 7., 8., 9.], [ 13., 14., 15.]]
```

// Batch 2 B2 = [[4., 5., 6.], [10., 11., 12.], [16., 17., 18.]]

// returns reverse sequence when sequence_length parameter is not used SequenceReverse(x) = [[[13., 14., 15.], [16., 17., 18.]],

[[7., 8., 9.], [10., 11., 12.]],

[[1., 2., 3.], [4., 5., 6.]]]

// sequence_length [2,2] means 2 rows of // both batch B1 and B2 will be reversed. SequenceReverse(x, sequence_length=[2,2], use_sequence_length=True) = [[[7., 8., 9.], [10., 11., 12.]],

[[1., 2., 3.], [4., 5., 6.]],

[[13., 14., 15.], [16., 17., 18.]]]

// sequence_length [2,3] means 2 of batch B2 and 3 of batch B3 // will be reversed. SequenceReverse(x, sequence_length=[2,3], use_sequence_length=True) = [[[7., 8., 9.], [16., 17., 18.]],

[[1., 2., 3.], [10., 11., 12.]],

[[13., 14, 15.], [4., 5., 6.]]]

Defined in src/operator/sequence_reverse.cc:L122

Value

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Arguments

weight NDArray-or-Symbol Weight grad NDArray-or-Symbol Gradient mom NDArray-or-Symbol Momentum 1r float, required Learning rate

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

lazy.update boolean, optional, default=1 If true, lazy updates are applied if gradient's stype

is row_sparse and both weight and momentum have the same stype

Details

.. math::

 $v_1 = \alpha v_t - 1 - \alpha v_t - 1$

v = momentum * v - learning_rate * gradient weight += v

Where the parameter "momentum" is the decay rate of momentum estimates at each epoch.

However, if grad's storage type is "row_sparse", "lazy_update" is True and weight's storage type is the same as momentum's storage type, only the row slices whose indices appear in grad.indices are updated (for both weight and momentum)::

for row in gradient.indices: v[row] = momentum[row] * v[row] - learning_rate * gradient[row] weight[row] += v[row]

Defined in src/operator/optimizer_op.cc:L563

Value

mx.nd.sgd.update 231

mx.nd.sgd.update	Update function for Stochastic Gradient Descent (SGD) optimizer.

Description

It updates the weights using::

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
lr	float, required Learning rate
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
lazy.update	boolean, optional, default=1 If true, lazy updates are applied if gradient's stype is row_sparse.

Details

```
weight = weight - learning_rate * (gradient + wd * weight)
```

However, if gradient is of "row_sparse" storage type and "lazy_update" is True, only the row slices whose indices appear in grad.indices are updated::

for row in gradient.indices: weight[row] = weight[row] - learning_rate * (gradient[row] + wd * weight[row])

Defined in src/operator/optimizer_op.cc:L522

Value

232 mx.nd.shuffle

mx.nd.shape.array

Returns a 1D int64 array containing the shape of data.

Description

Example::

Arguments

data

NDArray-or-Symbol Input Array.

Details

```
shape_array([[1,2,3,4], [5,6,7,8]]) = [2,4]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L574

Value

out The result mx.ndarray

mx.nd.shuffle

Randomly shuffle the elements.

Description

This shuffles the array along the first axis. The order of the elements in each subarray does not change. For example, if a 2D array is given, the order of the rows randomly changes, but the order of the elements in each row does not change.

Arguments

data

NDArray-or-Symbol Data to be shuffled.

Value

mx.nd.sigmoid 233

mx.nd.sigmoid

Computes sigmoid of x element-wise.

Description

```
.. math:: y = 1 / (1 + \exp(-x))
```

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "sigmoid" output is always dense
Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L119

Value

out The result mx.ndarray

mx.nd.sign

Returns element-wise sign of the input.

Description

Example::

Arguments

data

NDArray-or-Symbol The input array.

Details

```
sign([-2, 0, 3]) = [-1, 0, 1]
```

The storage type of "sign" output depends upon the input storage type:

- $sign(default) = default - sign(row_sparse) = row_sparse - sign(csr) = csr$

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L759

Value

234 mx.nd.signum.update

Description

.. math::

Arguments

weight NDArray-or-Symbol Weight grad NDArray-or-Symbol Gradient lr float, required Learning rate

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

Details

```
g_t = \Lambda J(W_{t-1})  W_t = W_{t-1} - \beta (g_t)
```

It updates the weights using::

weight = weight - learning_rate * sign(gradient)

.. note:: - sparse ndarray not supported for this optimizer yet.

Defined in src/operator/optimizer_op.cc:L61

Value

out The result mx.ndarray

mx.nd.signum.update SIGN momentUM (Signum) optimizer.

Description

.. math::

mx.nd.sin 235

Arguments

weight NDArray-or-Symbol Weight
grad NDArray-or-Symbol Gradient
mom NDArray-or-Symbol Momentum
lr float, required Learning rate

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

wd.1h float, optional, default=0 The amount of weight decay that does not go into gra-

dient/momentum calculationsotherwise do weight decay algorithmically only.

Details

 $g_t = \Lambda J(W_{t-1}) = \Delta m_t + (1 - \beta g_t) - (1 - \beta g_t) = M_t - (1 - \beta g_t) - (1 - \beta$

It updates the weights using:: state = momentum * state + (1-momentum) * gradient weight = weight - learning_rate * sign(state)

Where the parameter "momentum" is the decay rate of momentum estimates at each epoch.

.. note:: - sparse ndarray not supported for this optimizer yet.

Defined in src/operator/optimizer_op.cc:L90

Value

out The result mx.ndarray

mx.nd.sin

Computes the element-wise sine of the input array.

Description

The input should be in radians (:math: '2\pi' rad equals 360 degrees).

Arguments

data

NDArray-or-Symbol The input array.

236 mx.nd.size.array

Details

```
.. math:: \sin([0, \pi/4, \pi/2]) = [0, 0.707, 1]
```

The storage type of "sin" output depends upon the input storage type:

- sin(default) = default - sin(row_sparse) = row_sparse - sin(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L47

Value

out The result mx.ndarray

mx.nd.sinh

Returns the hyperbolic sine of the input array, computed element-wise.

Description

```
.. math:: sinh(x) = 0.5 \times (exp(x) - exp(-x))
```

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "sinh" output depends upon the input storage type:

- sinh(default) = default - sinh(row_sparse) = row_sparse - sinh(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L313

Value

out The result mx.ndarray

mx.nd.size.array

Returns a 1D int64 array containing the size of data.

Description

Example::

Arguments

data

NDArray-or-Symbol Input Array.

mx.nd.slice.axis 237

Details

```
size_array([[1,2,3,4], [5,6,7,8]]) = [8]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L625

Value

out The result mx.ndarray

mx.nd.slice.axis	Slices along a given axis. Returns an array slice along a given 'axis'
	starting from the 'begin' index to the 'end' index. Examples:: $x = [[$
	1., 2., 3., 4.], [5., 6., 7., 8.], [9., 10., 11., 12.]] slice_axis(x, axis=0,
	begin=1, end=3) = [[5., 6., 7., 8.], [9., 10., 11., 12.]] slice_axis(x,
	$axis=1, begin=0, end=2) = [[1., 2.], [5., 6.], [9., 10.]] slice_axis(x, x, x)$
	axis=1, begin=-3, end=-1) = [[2., 3.], [6., 7.], [10., 11.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L565

Arguments

data	NDArray-or-Symbol Source input
axis	int, required Axis along which to be sliced, supports negative indexes.
begin	int, required The beginning index along the axis to be sliced, supports negative indexes.
end	int or None, required The ending index along the axis to be sliced, supports negative indexes.

Value

238 mx.nd.slice.like

mx.nd.slice.like

Slices a region of the array like the shape of another array. This function is similar to "slice", however, the 'begin' are always '0's and 'end' of specific axes are inferred from the second input 'shape_like'. Given the second 'shape_like' input of "shape= $(d_0, d_1, ..., d_{n-1})$ ", a "slice like" operator with default empty 'axes', it performs the following operation: " out = $slice(input, begin=(0, 0, ..., 0), end=(d_0, 0, ..., 0)$ $d_1, ..., d_{n-1}$)". When 'axes' is not empty, it is used to speficy which axes are being sliced. Given a 4-d input data, "slice_like" operator with "axes=(0, 2, -1)" will perform the following operation: " out = $slice(input, begin=(0, 0, 0, 0), end=(d_0, None, d_2, d_3))$ ". Note that it is allowed to have first and second input with different dimensions, however, you have to make sure the 'axes' are specified and not exceeding the dimension limits. For example, given 'input 1' with "shape=(2,3,4,5)" and 'input_2' with "shape=(1,2,3)", it is not allowed to use: "out = slice_like(a, b)" because ndim of 'input_1' is 4, and ndim of 'input_2' is 3. The following is allowed in this situation: " $out = slice_like(a, b, axes=(0, 2))$ " Example:: x = [[1., 2., 3., 4.],[5., 6., 7., 8.], [9., 10., 11., 12.]] y = [[0., 0., 0.], [0., 0., 0.]] $slice_like(x, y) = [[1., 2., 3.] [5., 6., 7.]] slice_like(x, y, axes=(0, 1))$ = [[1., 2., 3.] [5., 6., 7.]] $slice_like(x, y, axes=(0)) = [[1., 2., 3., 4.]]$ [5., 6., 7., 8.] slice_like(x, y, axes=(-1)) = [[1., 2., 3.] [5., 6., 7.]9., 10., 11.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L619

Arguments

data NDArray-or-Symbol Source input

shape.like NDArray-or-Symbol Shape like input

axes Shape(tuple), optional, default=[] List of axes on which input data will be sliced

according to the corresponding size of the second input. By default will slice on

all axes. Negative axes are supported.

Value

mx.nd.SliceChannel 239

mx.nd.SliceChannel

Splits an array along a particular axis into multiple sub-arrays.

Description

.. note:: "SliceChannel" is deprecated. Use "split" instead.

Arguments

data NDArray-or-Symbol The input

num.outputs int, required Number of splits. Note that this should evenly divide the length of

the 'axis'.

axis int, optional, default='1' Axis along which to split.

squeeze.axis boolean, optional, default=0 If true, Removes the axis with length 1 from the

shapes of the output arrays. **Note** that setting 'squeeze_axis' to "true" removes axis with length 1 only along the 'axis' which it is split. Also 'squeeze_axis'

can be set to "true" only if "input.shape[axis] == num_outputs".

Details

Note that 'num_outputs' should evenly divide the length of the axis along which to split the array.

Example::

```
x = [[[ 1.] [ 2.]] [[ 3.] [ 4.]] [[ 5.] [ 6.]]] x.shape = (3, 2, 1)
y = split(x, axis=1, num_outputs=2) // a list of 2 arrays with shape (3, 1, 1) y = [[[ 1.]] [[ 3.]] [[ 5.]]]
[[[ 2.]] [[ 4.]] [[ 6.]]]
y[0].shape = (3, 1, 1)
z = split(x, axis=0, num_outputs=3) // a list of 3 arrays with shape (1, 2, 1) z = [[[ 1.] [ 2.]]]
[[[ 3.] [ 4.]]]
[[[ 5.] [ 6.]]]
```

'squeeze_axis=1' removes the axis with length 1 from the shapes of the output arrays. **Note** that setting 'squeeze_axis' to "1" removes axis with length 1 only along the 'axis' which it is split. Also 'squeeze_axis' can be set to true only if "input.shape[axis] == num_outputs".

Example::

z[0].shape = (1, 2, 1)

Defined in src/operator/slice_channel.cc:L107

```
z = split(x, axis=0, num_outputs=3, squeeze_axis=1) // a list of 3 arrays with shape (2, 1) z = [[ 1.]
[ 2.]]
[[ 3.] [ 4.]]
[[ 5.] [ 6.]] z[0].shape = (2,1)
```

240 mx.nd.Softmax

Value

out The result mx.ndarray

mx.nd.smooth.l1

Calculate Smooth L1 Loss(lhs, scalar) by summing

Description

.. math::

Arguments

data

NDArray-or-Symbol source input

scalar

float scalar input

Details

 $f(x) = \text{logincases (\sigma x)^2/2,\& \textif } x < 1/\text{sigma^2} |x|-0.5/\text{sigma^2,\& \textotherwise \end-cases}$

where :math: 'x' is an element of the tensor *lhs* and :math: '\sigma' is the scalar.

Example::

 $smooth_{11}([1, 2, 3, 4]) = [0.5, 1.5, 2.5, 3.5] smooth_{11}([1, 2, 3, 4], scalar=1) = [0.5, 1.5, 2.5, 3.5]$

Defined in src/operator/tensor/elemwise_binary_scalar_op_extended.cc:L108

Value

out The result mx.ndarray

 ${\sf mx.nd.Softmax}$

Computes the gradient of cross entropy loss with respect to softmax output.

Description

- This operator computes the gradient in two steps. The cross entropy loss does not actually need to be computed.

mx.nd.Softmax 241

Arguments

data NDArray-or-Symbol Input array.

label NDArray-or-Symbol Ground truth label.

grad. scale float, optional, default=1 Scales the gradient by a float factor.

ignore.label float, optional, default=-1 The instances whose 'labels' == 'ignore label' will

be ignored during backward, if 'use_ignore' is set to "true").

multi.output boolean, optional, default=0 If set to "true", the softmax function will be com-

puted along axis "1". This is applied when the shape of input array differs from

the shape of label array.

use.ignore boolean, optional, default=0 If set to "true", the 'ignore_label' value will not

contribute to the backward gradient.

preserve.shape boolean, optional, default=0 If set to "true", the softmax function will be com-

puted along the last axis ("-1").

normalization 'batch', 'null', 'valid', optional, default='null' Normalizes the gradient.

out.grad boolean, optional, default=0 Multiplies gradient with output gradient element-

wise.

smooth.alpha float, optional, default=0 Constant for computing a label smoothed version of

cross-entropyfor the backwards pass. This constant gets subtracted from theonehot encoding of the gold label and distributed uniformly to all other labels.

Details

- Applies softmax function on the input array. - Computes and returns the gradient of cross entropy loss w.r.t. the softmax output.

- The softmax function, cross entropy loss and gradient is given by:
- Softmax Function:
- .. math:: $\text{textsoftmax}(x)_i = \frac{x_i}{\sum_{i=1}^{n} \exp(x_i)}$
- Cross Entropy Function:
- .. math:: \textCE(label, output) = \sum_i \textlabel_i \log(\textoutput_i)
- The gradient of cross entropy loss w.r.t softmax output:
- .. math:: \textgradient = \textoutput \textlabel
- During forward propagation, the softmax function is computed for each instance in the input array.

For general *N*-D input arrays with shape :math: $(d_1, d_2, ..., d_n)$. The size is :math: $s=d_1 \cdot d_2 \cdot d_2 \cdot d_n$. We can use the parameters 'preserve_shape' and 'multi_output' to specify the way to compute softmax:

- By default, 'preserve_shape' is "false". This operator will reshape the input array into a 2-D array with shape :math: ' $(d_1, \frac{1}{n})$ ' and then compute the softmax function for each row in the reshaped array, and afterwards reshape it back to the original shape :math: ' $(d_1, d_2, ..., d_n)$ '.
- If 'preserve_shape' is "true", the softmax function will be computed along the last axis ('axis' = "-1"). If 'multi_output' is "true", the softmax function will be computed along the second axis ('axis' = "1").

242 mx.nd.softmax

- During backward propagation, the gradient of cross-entropy loss w.r.t softmax output array is computed. The provided label can be a one-hot label array or a probability label array.

- If the parameter 'use_ignore' is "true", 'ignore_label' can specify input instances with a particular label to be ignored during backward propagation. **This has no effect when softmax 'output' has same shape as 'label'**.

Example::

 $\begin{array}{l} data = [[1,2,3,4],[2,2,2,2],[3,3,3,3],[4,4,4,4]] \ label = [1,0,2,3] \ ignore_label = 1 \ SoftmaxOutput(data=data, label = label, multi_output=true, use_ignore=true, lignore_label=ignore_label) \ \# \ forward \ softmax \ output \ [[0.0320586\ 0.08714432\ 0.23688284\ 0.64391428]\ [0.25\ 0.25\ 0.25\ 0.25\ 0.25\]\ [0.25\ 0.$

- The parameter 'grad_scale' can be used to rescale the gradient, which is often used to give each loss function different weights.
- This operator also supports various ways to normalize the gradient by 'normalization', The 'normalization' is applied if softmax output has different shape than the labels. The 'normalization' mode can be set to the followings:
- "'null'": do nothing. "'batch'": divide the gradient by the batch size. "'valid'": divide the gradient by the number of instances which are not ignored.

Defined in src/operator/softmax_output.cc:L231

Value

out The result mx.ndarray

Description

The resulting array contains elements in the range (0,1) and the elements along the given axis sum up to 1.

Arguments

data	NDArray-or-Symbol The input array.
length	NDArray-or-Symbol The length array.
axis	int, optional, default='-1' The axis along which to compute softmax.
temperature	double or None, optional, default=None Temperature parameter in softmax
dtype	None, 'float16', 'float32', 'float64',optional, default='None' DType of the output in case this can't be inferred. Defaults to the same as input's dtype if not defined (dtype=None).
use.length	boolean or None, optional, default=0 Whether to use the length input as a mask over the data input.

Details

```
.. math:: softmax(\mathbfz/t)_j = \frace^z_j/t\sum_k=1^K e^z_k/t for :math: 'j = 1, ..., K' t is the temperature parameter in softmax function. By default, t equals 1.0 Example:: x = [[\ 1.\ 1.\ 1.]\ [\ 1.\ 1.\ 1.]] softmax(x,axis=0) = [[\ 0.5\ 0.5\ 0.5]\ [\ 0.5\ 0.5\ 0.5]] softmax(x,axis=1) = [[\ 0.33333334, 0.3333334, 0.3333334], [\ 0.33333334, 0.33333334], [\ 0.33333334, 0.33333334]] Defined in src/operator/nn/softmax.cc:L103
```

Value

out The result mx.ndarray

```
mx.nd.softmax.cross.entropy
```

Calculate cross entropy of softmax output and one-hot label.

Description

- This operator computes the cross entropy in two steps: - Applies softmax function on the input array. - Computes and returns the cross entropy loss between the softmax output and the labels.

Arguments

data NDArray-or-Symbol Input data label NDArray-or-Symbol Input label

Details

- The softmax function and cross entropy loss is given by:
- Softmax Function:
- .. math:: $\text{textsoftmax}(x)_i = \frac{x_i}{\sum_{i=1}^{n} \exp(x_i)}$
- Cross Entropy Function:
- .. math:: \textCE(label, output) = \sum_i \textlabel_i \log(\textoutput_i)

Example::

```
Example: x = [[1, 2, 3], [11, 7, 5]]  
label = [2, 0]  
softmax(x) = [[0.09003057, 0.24472848, 0.66524094], [0.97962922, 0.01794253, 0.00242826]]  
softmax_cross_entropy(data, label) = - log(0.66524084) - log(0.97962922) = 0.4281871  
Defined in src/operator/loss_binary_op.cc:L59
```

244 mx.nd.SoftmaxActivation

Value

out The result mx.ndarray

mx.nd.SoftmaxActivation

Applies softmax activation to input. This is intended for internal layers.

Description

.. note::

Arguments

data NDArray-or-Symbol The input array.

mode 'channel', 'instance', optional, default='instance' Specifies how to compute the

softmax. If set to "instance", it computes softmax for each instance. If set to "channel", It computes cross channel softmax for each position of each instance.

Details

This operator has been deprecated, please use 'softmax'.

If 'mode' = "instance", this operator will compute a softmax for each instance in the batch. This is the default mode.

If 'mode' = "channel", this operator will compute a k-class softmax at each position of each instance, where 'k' = "num_channel". This mode can only be used when the input array has at least 3 dimensions. This can be used for 'fully convolutional network', 'image segmentation', etc.

Example::

»> input_array = mx.nd.array([[3., 0.5, -0.5, 2., 7.], »> [2., -4, 7., 3., 0.2]]) »> softmax_act =
mx.nd.SoftmaxActivation(input_array) »> print softmax_act.asnumpy() [[1.78322066e-02 1.46375655e03 5.38485940e-04 6.56010211e-03 9.73605454e-01] [6.56221947e-03 5.95310994e-04 9.73919690e01 1.78379621e-02 1.08472735e-03]]

Defined in src/operator/nn/softmax_activation.cc:L59

Value

mx.nd.SoftmaxOutput 245

mx.nd.SoftmaxOutput Computes the gradient of cross entropy loss with respect to softmax output.

Description

- This operator computes the gradient in two steps. The cross entropy loss does not actually need to be computed.

Arguments

data	NDArray-or-Symbol Input array.
label	NDArray-or-Symbol Ground truth label.
grad.scale	float, optional, default=1 Scales the gradient by a float factor.
ignore.label	float, optional, default=-1 The instances whose 'labels' == 'ignore_label' will be ignored during backward, if 'use_ignore' is set to "true").
multi.output	boolean, optional, default=0 If set to "true", the softmax function will be computed along axis "1". This is applied when the shape of input array differs from the shape of label array.
use.ignore	boolean, optional, default=0 If set to "true", the 'ignore_label' value will not contribute to the backward gradient.
preserve.shape	boolean, optional, default=0 If set to "true", the softmax function will be computed along the last axis ("-1").
normalization	'batch', 'null', 'valid',optional, default='null' Normalizes the gradient.
out.grad	boolean, optional, default=0 Multiplies gradient with output gradient elementwise.
smooth.alpha	float, optional, default=0 Constant for computing a label smoothed version of cross-entropyfor the backwards pass. This constant gets subtracted from theonehot encoding of the gold label and distributed uniformly toall other labels.

Details

- Applies softmax function on the input array. Computes and returns the gradient of cross entropy loss w.r.t. the softmax output.
- The softmax function, cross entropy loss and gradient is given by:
- Softmax Function:
- .. math:: $\textsoftmax(x)_i = \textsoftmax(x_i) \textsoftmax(x_j)$
- Cross Entropy Function:
- .. math:: \textCE(label, output) = \sum_i \textlabel_i \log(\textoutput_i)
- The gradient of cross entropy loss w.r.t softmax output:
- .. math:: \textgradient = \textoutput \textlabel

246 mx.nd.softmin

- During forward propagation, the softmax function is computed for each instance in the input array. For general *N*-D input arrays with shape :math:'(d_1, d_2, ..., d_n)'. The size is :math:'s=d_1 \cdot d_2 \cdot \cdot \cdot \cdot d_n'. We can use the parameters 'preserve_shape' and 'multi_output' to specify the way to compute softmax:

- By default, 'preserve_shape' is "false". This operator will reshape the input array into a 2-D array with shape :math: ' $(d_1, \frac{1}{2}, \frac{1}{2})$ ' and then compute the softmax function for each row in the reshaped array, and afterwards reshape it back to the original shape :math: ' $(d_1, d_2, ..., d_n)$ '. If 'preserve_shape' is "true", the softmax function will be computed along the last axis ('axis' = "-1"). If 'multi_output' is "true", the softmax function will be computed along the second axis ('axis' = "1").
- During backward propagation, the gradient of cross-entropy loss w.r.t softmax output array is computed. The provided label can be a one-hot label array or a probability label array.
- If the parameter 'use_ignore' is "true", 'ignore_label' can specify input instances with a particular label to be ignored during backward propagation. **This has no effect when softmax 'output' has same shape as 'label'**.

Example::

- The parameter 'grad_scale' can be used to rescale the gradient, which is often used to give each loss function different weights.
- This operator also supports various ways to normalize the gradient by 'normalization', The 'normalization' is applied if softmax output has different shape than the labels. The 'normalization' mode can be set to the followings:
- "'null'": do nothing. "'batch'": divide the gradient by the batch size. "'valid'": divide the gradient by the number of instances which are not ignored.

Defined in src/operator/softmax output.cc:L231

Value

out The result mx.ndarray

mx.nd.softmin

Applies the softmin function.

Description

The resulting array contains elements in the range (0,1) and the elements along the given axis sum up to 1.

mx.nd.softsign 247

Arguments

data NDArray-or-Symbol The input array.

axis int, optional, default='-1' The axis along which to compute softmax.

temperature double or None, optional, default=None Temperature parameter in softmax

dtype None, 'float16', 'float32', 'float64',optional, default='None' DType of the out-

put in case this can't be inferred. Defaults to the same as input's dtype if not

defined (dtype=None).

use.length boolean or None, optional, default=0 Whether to use the length input as a mask

over the data input.

Details

```
.. math:: softmin(\mathbfz/t)_j = \frac{-z_j}{t\sum_{k=1}^{K} e^{-z_k/t}}
```

for :math: 'j = 1, ..., K'

t is the temperature parameter in softmax function. By default, t equals 1.0

Example::

$$x = [[1. 2. 3.] [3. 2. 1.]]$$

softmin(x,axis=0) = [[0.88079703, 0.5, 0.11920292], [0.11920292, 0.5, 0.88079703]]

softmin(x,axis=1) = [[0.66524094, 0.24472848, 0.09003057], [0.09003057, 0.24472848, 0.66524094]]

Defined in src/operator/nn/softmin.cc:L57

Value

out The result mx.ndarray

mx.nd.softsign

Computes softsign of x element-wise.

Description

```
.. math:: y = x / (1 + abs(x))
```

Arguments

data NDArray-or-Symbol The input array.

Details

The storage type of "softsign" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L191

Value

248 mx.nd.space.to.depth

mx.nd.sort

Returns a sorted copy of an input array along the given axis.

Description

Examples::

Arguments

data NDArray-or-Symbol The input array

axis int or None, optional, default='-1' Axis along which to choose sort the input

tensor. If not given, the flattened array is used. Default is -1.

is.ascend boolean, optional, default=1 Whether to sort in ascending or descending order.

Details

```
x = [[1, 4], [3, 1]]
// sorts along the last axis sort(x) = [[1., 4.], [1., 3.]]
// flattens and then sorts sort(x, axis=None) = [1., 1., 3., 4.]
// sorts along the first axis sort(x, axis=0) = [[1., 1.], [3., 4.]]
// in a descend order sort(x, is_ascend=0) = [[4., 1.], [3., 1.]]
Defined in src/operator/tensor/ordering_op.cc:L131
```

Value

out The result mx.ndarray

mx.nd.space.to.depth

Rearranges(permutes) blocks of spatial data into SpaceToDepth depth. ONNXSimilar tooperator: https://github.com/onnx/onnx/blob/master/docs/Operators.md#SpaceToDepth The output is a new tensor where the values from height and width dimension are moved to the depth dimension. The reverse of this operation is "depth_to_space". .. math:: \begingather* x \prime = reshape(x, [N, C, H / block size, block size, W / block size, $block_size$]) \ x \prime \prime = $transpose(x \prime, [0, 3, 5, 1,$ 2, 4]) $\ y = reshape(x \rangle prime \rangle prime, [N, C * (block size ^ 2), H / (block size ^ 2)$ $block \subseteq w / block \subseteq w / block \le where : math: `x` is an input$ tensor with default layout as :math: '[N, C, H, W]': [batch, channels, height, width] and :math: 'y' is the output tensor of layout :math: '[N, $C * (block \ size \ 2), H/block \ size, W/block \ size] `Example:: x =$ [[[0, 6, 1, 7, 2, 8], [12, 18, 13, 19, 14, 20], [3, 9, 4, 10, 5, 11], [15, 21, 16, 22, 17, 23]]]] $space_to_depth(x, 2) = [[[[0, 1, 2], [3, 4, 5]],$ [[6, 7, 8], [9, 10, 11]], [[12, 13, 14], [15, 16, 17]], [[18, 19, 20], [21, 22, 23]]]]

Description

Defined in src/operator/tensor/matrix_op.cc:L1011

Arguments

data NDArray-or-Symbol Input ndarray

block.size int, required Blocks of [block_size. block_size] are moved

Value

out The result mx.ndarray

mx.nd.SpatialTransformer

Applies a spatial transformer to input feature map.

Description

Applies a spatial transformer to input feature map.

Arguments

data NDArray-or-Symbol Input data to the SpatialTransformerOp.

loc NDArray-or-Symbol localisation net, the output dim should be 6 when trans-

form_type is affine. You shold initialize the weight and bias with identity tran-

form.

target.shape Shape(tuple), optional, default=[0,0] output shape(h, w) of spatial transformer:

(y, x)

transform.type 'affine', required transformation type

sampler.type 'bilinear', required sampling type

cudnn.off boolean or None, optional, default=None whether to turn cudnn off

Value

250 mx.nd.split

mx.nd.split	Splits an array along a particular axis into multiple sub-arrays.

Description

.. note:: "SliceChannel" is deprecated. Use "split" instead.

Arguments

data NDArray-or-Symbol The input

num.outputs int, required Number of splits. Note that this should evenly divide the length of

the 'axis'.

axis int, optional, default='1' Axis along which to split.

squeeze.axis boolean, optional, default=0 If true, Removes the axis with length 1 from the

shapes of the output arrays. **Note** that setting 'squeeze_axis' to "true" removes axis with length 1 only along the 'axis' which it is split. Also 'squeeze_axis'

can be set to "true" only if "input.shape[axis] == num_outputs".

Details

Note that 'num_outputs' should evenly divide the length of the axis along which to split the array.

Example::

```
 \begin{aligned} x &= \text{[[[ 1.] [ 2.]] [[ 3.] [ 4.]] [[ 5.] [ 6.]]] } x.shape &= (3, 2, 1) \\ y &= \text{split}(x, \text{axis=1}, \text{num\_outputs=2}) \text{// a list of 2 arrays with shape } (3, 1, 1) \text{ y} &= \text{[[[ 1.]] [[ 3.]] [[ 5.]]]} \\ \text{[[[ 2.]] [[ 4.]] [[ 6.]]]} \\ y &[0].\text{shape} &= (3, 1, 1) \\ z &= \text{split}(x, \text{axis=0}, \text{num\_outputs=3}) \text{// a list of 3 arrays with shape } (1, 2, 1) \text{ z} &= \text{[[[ 1.] [ 2.]]]} \\ \text{[[[ 3.] [ 4.]]]} \\ \text{[[[ 5.] [ 6.]]]} \\ z &[0].\text{shape} &= (1, 2, 1) \end{aligned}
```

'squeeze_axis=1' removes the axis with length 1 from the shapes of the output arrays. **Note** that setting 'squeeze_axis' to "1" removes axis with length 1 only along the 'axis' which it is split. Also 'squeeze_axis' can be set to true only if "input.shape[axis] == num_outputs".

Example::

```
z = split(x, axis=0, num_outputs=3, squeeze_axis=1) // a list of 3 arrays with shape (2, 1) z = [[ 1.]
[ 2.]]
[[ 3.] [ 4.]]
[[ 5.] [ 6.]] z[0].shape = (2,1)
```

Defined in src/operator/slice_channel.cc:L107

mx.nd.sqrt 251

Value

out The result mx.ndarray

mx.nd.sqrt

Returns element-wise square-root value of the input.

Description

```
.. math:: \text{textrmsqrt}(x) = \text{sqrt}x
```

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

```
sqrt([4, 9, 16]) = [2, 3, 4]
```

The storage type of "sqrt" output depends upon the input storage type:

- sqrt(default) = default - sqrt(row_sparse) = row_sparse - sqrt(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L142

Value

out The result mx.ndarray

mx.nd.square

Returns element-wise squared value of the input.

Description

```
.. math:: square(x) = x^2
```

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

$$square([2, 3, 4]) = [4, 9, 16]$$

The storage type of "square" output depends upon the input storage type:

- square(default) = default - square(row_sparse) = row_sparse - square(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L118

252 mx.nd.stack

Value

out The result mx.ndarray

mx.nd.squeeze

Remove single-dimensional entries from the shape of an array. Same behavior of defining the output tensor shape as numpy.squeeze for the most of cases. See the following note for exception. Examples:: data = [[0], [1], [2]]] squeeze(data) = [0, 1, 2] squeeze(data, axis=0) = [[0], [1], [2]] squeeze(data, axis=2) = [[0, 1, 2]] squeeze(data, axis=(0, 2)) = [0, 1, 2]. Note:: The output of this operator will keep at least one dimension not removed. For example, squeeze([[[4]]]) = [4], while in numpy.squeeze, the output will become a scalar.

Description

Remove single-dimensional entries from the shape of an array. Same behavior of defining the output tensor shape as numpy.squeeze for the most of cases. See the following note for exception. Examples:: data = [[0], [1], [2]] squeeze(data) = [0, 1, 2] squeeze(data, axis=0) = [[0], [1], [2]] squeeze(data, axis=0) = [0, 1, 2] squeeze(data, axis=0) = [0, 1, 2] squeeze(data, axis=0) = [0, 1, 2] squeeze([0, 1, 2]) squeeze(data, axis=0) = [0, 1, 2] squeeze([0, 1, 2]) squeeze(

Arguments

data NDArray-or-Symbol data to squeeze

axis Shape or None, optional, default=None Selects a subset of the single-dimensional

entries in the shape. If an axis is selected with shape entry greater than one, an

error is raised.

Value

out The result mx.ndarray

mx.nd.stack

Join a sequence of arrays along a new axis. The axis parameter specifies the index of the new axis in the dimensions of the result. For example, if axis=0 it will be the first dimension and if axis=-1 it will be the last dimension. Examples:: x = [1, 2] y = [3, 4] stack(x, y) = [1, 2], [3, 4] stack(x, y), [4, 4]

Description

Join a sequence of arrays along a new axis. The axis parameter specifies the index of the new axis in the dimensions of the result. For example, if axis=0 it will be the first dimension and if axis=-1 it will be the last dimension. Examples:: x = [1, 2] y = [3, 4] stack(x, y) = [[1, 2], [3, 4]] stack(x, y), axis=1) = [[1, 3], [2, 4]]

mx.nd.stop.gradient 253

Arguments

data NDArray-or-Symbol[] List of arrays to stack

axis int, optional, default='0' The axis in the result array along which the input arrays

are stacked.

num. args int, required Number of inputs to be stacked.

Value

out The result mx.ndarray

mx.nd.stop.gradient Stop

Stops gradient computation.

Description

Stops the accumulated gradient of the inputs from flowing through this operator in the backward direction. In other words, this operator prevents the contribution of its inputs to be taken into account for computing gradients.

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

```
v1 = [1, 2] v2 = [0, 1] a = Variable('a') b = Variable('b') b_stop_grad = stop_gradient(3 * b) loss = MakeLoss(b_stop_grad + a)
```

```
executor = loss.simple_bind(ctx=cpu(), a=(1,2), b=(1,2)) executor.forward(is_train=True, a=v1, b=v2) executor.outputs [ 1. 5.]
```

```
executor.backward() executor.grad_arrays [ 0. 0.] [ 1. 1.]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L327

Value

254 mx.nd.sum

mx.nd.sum	Computes the sum of array elements over given axes.

Description

.. Note::

Arguments

data	NDArray-or-Symbol The input
axis	Shape or None, optional, default=None The axis or axes along which to perform the reduction.
	The default, 'axis=()', will compute over all elements into a scalar array with shape ' $(1,)$ '.
	If 'axis' is int, a reduction is performed on a particular axis.
	If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in
	the tuple.
	If 'exclude' is true, reduction will be performed on the axes that are NOT in axis instead.
	Negative values means indexing from right to left.
keepdims	boolean, optional, default=0 If this is set to 'True', the reduced axes are left in the result as dimension with size one.
exclude	boolean, optional, default=0 Whether to perform reduction on axis that are NOT

Details

'sum' and 'sum_axis' are equivalent. For ndarray of csr storage type summation along axis 0 and axis 1 is supported. Setting keepdims or exclude to True will cause a fallback to dense operator.

Example::

```
data = [[[1, 2], [2, 3], [1, 3]], [[1, 4], [4, 3], [5, 2]], [[7, 1], [7, 2], [7, 3]]] sum(data, axis=1) [[ 4. 8.] [ 10. 9.] [ 21. 6.]] sum(data, axis=[1,2]) [ 12. 19. 27.] data = [[1, 2, 0], [3, 0, 1], [4, 1, 0]] csr = cast_storage(data, 'csr') sum(csr, axis=0) [ 8. 3. 1.] sum(csr, axis=1) [ 3. 4. 5.] Defined in src/operator/tensor/broadcast_reduce_sum_value.cc:L67
```

in axis instead.

Value

mx.nd.sum.axis 255

mx.nd.sum.axis	Computes the sum of array elements over given axes.
IIIX.IIG. Julii. UXIJ	computes the sum of array elements over given axes.

Description

.. Note::

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

Details

'sum' and 'sum_axis' are equivalent. For ndarray of csr storage type summation along axis 0 and axis 1 is supported. Setting keepdims or exclude to True will cause a fallback to dense operator.

Example::

```
data = [[[1, 2], [2, 3], [1, 3]], [[1, 4], [4, 3], [5, 2]], [[7, 1], [7, 2], [7, 3]]] sum(data, axis=1) [[ 4. 8.] [ 10. 9.] [ 21. 6.]] sum(data, axis=[1,2]) [ 12. 19. 27.] data = [[1, 2, 0], [3, 0, 1], [4, 1, 0]] csr = cast_storage(data, 'csr') sum(csr, axis=0) [ 8. 3. 1.] sum(csr, axis=1) [ 3. 4. 5.] Defined in src/operator/tensor/broadcast_reduce_sum_value.cc:L67
```

Value

256 mx.nd.swapaxes

|--|

Description

This tutorial demonstrates using SVM as output layer for classification instead of softmax: https://github.com/dmlc/mxnet/tre

Arguments

data NDArray-or-Symbol Input data for SVM transformation.

label NDArray-or-Symbol Class label for the input data.

margin float, optional, default=1 The loss function penalizes outputs that lie outside this margin. Default margin is 1.

regularization.coefficient

float, optional, default=1 Regularization parameter for the SVM. This balances

the tradeoff between coefficient size and error.

use.linear boolean, optional, default=0 Whether to use L1-SVM objective. L2-SVM ob-

jective is used by default.

Value

out The result mx.ndarray

mx.nd.swapaxes

Description

Examples::

Arguments

data	NDArray-or-Symbol Input array.
dim1	int, optional, default='0' the first axis to be swapped.
dim2	int, optional, default='0' the second axis to be swapped.

Details

```
x = [[1, 2, 3]]) swapaxes(x, 0, 1) = [[1], [2], [3]]

x = [[[0, 1], [2, 3]], [[4, 5], [6, 7]]] // (2,2,2) array

swapaxes(x, 0, 2) = [[[0, 4], [2, 6]], [[1, 5], [3, 7]]]

Defined in src/operator/swapaxis.cc:L70
```

Value

mx.nd.SwapAxis 257

ray.	Interchanges two axes	mx.nd.SwapAxis
------	-----------------------	----------------

Description

Examples::

Arguments

data NDArray-or-Symbol Input array.

dim1 int, optional, default='0' the first axis to be swapped.
dim2 int, optional, default='0' the second axis to be swapped.

Details

```
x = [[1, 2, 3]]) swapaxes(x, 0, 1) = [[1], [2], [3]]

x = [[[0, 1], [2, 3]], [[4, 5], [6, 7]]] // (2,2,2) array

swapaxes(x, 0, 2) = [[[0, 4], [2, 6]], [[1, 5], [3, 7]]]

Defined in src/operator/swapaxis.cc:L70
```

Value

out The result mx.ndarray

mx.nd.take	Takes elements from an input array along the given axis.	

Description

This function slices the input array along a particular axis with the provided indices.

Arguments

a	NDArray-or-Symbol The input array.
indices	NDArray-or-Symbol The indices of the values to be extracted.
axis	int, optional, default='0' The axis of input array to be taken. For input tensor of rank r , it could be in the range of $[-r, r-1]$
mode	'clip', 'raise', 'wrap',optional, default='clip' Specify how out-of-bound indices bahave. Default is "clip". "clip" means clip to the range. So, if all indices mentioned are too large, they are replaced by the index that addresses the last element along an axis. "wrap" means to wrap around. "raise" means to raise an error when index out of range.

258 mx.nd.tan

Details

Given data tensor of rank $r \ge 1$, and indices tensor of rank q, gather entries of the axis dimension of data (by default outer-most one as axis=0) indexed by indices, and concatenates them in an output tensor of rank q + (r - 1).

```
Examples::
```

```
x = [4. 5. 6.]
```

// Trivial case, take the second element along the first axis.

$$take(x, [1]) = [5.]$$

// The other trivial case, axis=-1, take the third element along the first axis

$$take(x, [3], axis=-1, mode='clip') = [6.]$$

$$x = [[1., 2.], [3., 4.], [5., 6.]]$$

// In this case we will get rows 0 and 1, then 1 and 2. Along axis 0

$$take(x, [[0,1],[1,2]]) = [[[1., 2.], [3., 4.]],$$

 ${\it //}$ In this case we will get rows 0 and 1, then 1 and 2 (calculated by wrapping around). ${\it //}$ Along axis 1

take(x, [[0, 3], [-1, -2]], axis=1, mode='wrap') = [[[1. 2.] [2. 1.]]

[[3. 4.] [4. 3.]]

[[5. 6.] [6. 5.]]]

The storage type of "take" output depends upon the input storage type:

- take(default, default) = default - take(csr, default, axis=0) = csr

Defined in src/operator/tensor/indexing_op.cc:L716

Value

out The result mx.ndarray

mx.nd.tan

Computes the element-wise tangent of the input array.

Description

The input should be in radians (:math: '2\pi' rad equals 360 degrees).

Arguments

data

NDArray-or-Symbol The input array.

mx.nd.tanh 259

Details

```
.. math:: tan([0, \pi/4, \pi/2]) = [0, 1, -inf]
```

The storage type of "tan" output depends upon the input storage type:

 $-\tan(default) = default - \tan(row_sparse) = row_sparse - \tan(csr) = csr$

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L140

Value

out The result mx.ndarray

mx.nd.tanh

Returns the hyperbolic tangent of the input array, computed elementwise.

Description

```
.. math:: tanh(x) = sinh(x) / cosh(x)
```

Arguments

data

NDArray-or-Symbol The input array.

Details

The storage type of "tanh" output depends upon the input storage type:

- tanh(default) = default - tanh(row_sparse) = row_sparse - tanh(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L393

Value

260 mx.nd.topk

mx.nd.tile

Repeats the whole array multiple times. If "reps" has length *d*, and input array has dimension of *n*. There are three cases: - **n=d**. Repeat *i*-th dimension of the input by "reps[i]" times:: x = [[1, 2], [3, 4]] tile(x, reps=(2,3)) = [[1, 2., 1., 2., 1., 2.], [3., 4., 3., 4., 3., 4.]] - **n>d**. "reps" is promoted to length *n* by pre-pending 1's to it. Thus for an input shape "(2,3)", "repos=(2,)" is treated as "(1,2)":: tile(x, reps=(2,)) = [[1., 2., 1., 2.], [3., 4., 3., 4.]] - **n<d**. The input is promoted to be d-dimensional by prepending new axes. So a shape "(2,2)" array is promoted to "(1,2,2)" for 3-D replication:: tile(x, reps=(2,2,3)) = [[[1., 2., 1., 2., 1., 2.], [3., 4., 3., 4.], [1., 2., 1., 2.], [3., 4., 3., 4.]], [[1., 2., 1., 2.], [3., 4., 3., 4.]], [1., 2., 1., 2.], [3., 4., 3., 4.]], [1., 2., 1., 2.], [3., 4., 3., 4.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L790

Arguments

data NDArray-or-Symbol Input data array

reps Shape(tuple), required The number of times for repeating the tensor a. Each dim

size of reps must be a positive integer. If reps has length d, the result will have dimension of $\max(d, a.ndim)$; If a.ndim < d, a is promoted to be d-dimensional by prepending new axes. If a.ndim > d, reps is promoted to a.ndim by pre-

pending 1's to it.

Value

out The result mx.ndarray

mx.nd.topk

Returns the indices of the top *k* elements in an input array along the given axis (by default). If ret_type is set to 'value' returns the value of top *k* elements (instead of indices). In case of ret_type = 'both', both value and index would be returned. The returned elements will be sorted.

Description

Examples::

mx.nd.transpose 261

Arguments

data	NDArray-or-Symbol The input array
axis	int or None, optional, default='-1' Axis along which to choose the top k indices. If not given, the flattened array is used. Default is -1.
k	int, optional, default='1' Number of top elements to select, should be always smaller than or equal to the element number in the given axis. A global sort is performed if set $k < 1$.
ret.typ	'both', 'indices', 'mask', 'value',optional, default='indices' The return type. "value" means to return the top k values, "indices" means to return the indices of the top k values, "mask" means to return a mask array containing 0 and 1. 1 means the top k values. "both" means to return a list of both values and indices of top k elements.
is.ascend	boolean, optional, default=0 Whether to choose k largest or k smallest elements. Top K largest elements will be chosen if set to false.
dtype	'float16', 'float32', 'float64', 'int32', 'int64', 'uint8', optional, default='float32' DType of the output indices when ret_typ is "indices" or "both". An error will be raised if the selected data type cannot precisely represent the indices.

Details

```
x = [[\ 0.3,\ 0.2,\ 0.4],\ [\ 0.1,\ 0.3,\ 0.2]] // returns an index of the largest element on last axis topk(x) = [[\ 2.],\ [\ 1.]]] // returns the value of top-2 largest elements on last axis topk(x, ret_typ='value', k=2) = [[\ 0.4,\ 0.3], [\ 0.3,\ 0.2]] // returns the value of top-2 smallest elements on last axis topk(x, ret_typ='value', k=2, is_ascend=1) = [[\ 0.2,\ 0.3], [\ 0.1,\ 0.2]] // returns the value of top-2 largest elements on axis 0 topk(x, axis=0, ret_typ='value', k=2) = [[\ 0.3,\ 0.3,\ 0.4], [\ 0.1,\ 0.2,\ 0.2]] // flattens and then returns list of both values and indices topk(x, ret_typ='both', k=2) = [[[\ 0.4,\ 0.3], [\ 0.3,\ 0.2]], [[\ 2.,\ 0.], [\ 1.,\ 2.]]] Defined in src/operator/tensor/ordering_op.cc:L68
```

Value

mx.nd.transpose	Permutes the dimensions of an array. Examples:: $x = [[1, 2], [3, 4]]$ $transpose(x) = [[1., 3.], [2., 4.]]$ $x = [[[1., 2.], [3., 4.]], [[5., 6.],$
	[7., 8.]] $transpose(x) = [[[1., 5.], [3., 7.]], [[2., 6.], [4., 8.]]]$ $transpose(x, axes=(1,0,2)) = [[[1., 2.], [5., 6.]], [[3., 4.], [7., 8.]]]$

262 mx.nd.trunc

Description

Defined in src/operator/tensor/matrix_op.cc:L325

Arguments

data NDArray-or-Symbol Source input

axes Shape(tuple), optional, default=[] Target axis order. By default the axes will be

inverted.

Value

out The result mx.ndarray

mx.nd.trunc

Return the element-wise truncated value of the input.

Description

The truncated value of the scalar x is the nearest integer i which is closer to zero than x is. In short, the fractional part of the signed number x is discarded.

Arguments

data

NDArray-or-Symbol The input array.

Details

Example::

```
trunc([-2.1, -1.9, 1.5, 1.9, 2.1]) = [-2., -1., 1., 1., 2.]
```

The storage type of "trunc" output depends upon the input storage type:

- trunc(default) = default - trunc(row_sparse) = row_sparse - trunc(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L857

Value

mx.nd.uniform 263

mx.nd.uniform Draw random samples from a uniform distribution.	
--	--

Description

.. note:: The existing alias "uniform" is deprecated.

Arguments

float, optional, default=0 Lower bound of the distribution.

float, optional, default=1 Upper bound of the distribution.

Shape (tuple), optional, default=None Shape of the output.

ctx string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n).

Only used for imperative calls.

dtype 'None', 'float16', 'float32', 'float64',optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

Details

Samples are uniformly distributed over the half-open interval *[low, high)* (includes *low*, but excludes *high*).

Example::

uniform(low=0, high=1, shape=(2,2)) = [[0.60276335, 0.85794562], [0.54488319, 0.84725171]] Defined in src/operator/random/sample_op.cc:L96

Value

out The result mx.ndarray

mx.nd.unravel.index Converts an array of flat indices into a batch of index arrays. The

operator follows numpy conventions so a single multi index is given by a column of the output matrix. The leading dimension may be left

unspecified by using -1 as placeholder.

Description

Examples::

Arguments

data NDArray-or-Symbol Array of flat indices

shape Shape(tuple), optional, default=None Shape of the array into which the multi-

indices apply.

264 mx.nd.UpSampling

Details

```
A = [22,41,37] \text{ unravel}(A, \text{shape}=(7,6)) = [[3,6,6],[4,5,1]] \text{ unravel}(A, \text{shape}=(-1,6)) = [[3,6,6],[4,5,1]]
Defined in src/operator/tensor/ravel.cc:L67
```

Value

out The result mx.ndarray

mx.nd.UpSampling

Upsamples the given input data.

Description

Two algorithms ("sample_type") are available for upsampling:

Arguments

data	NDArray-or-Symbol∏	Array of tensors to upsample.	For bilinear upsampling.

there should be 2 inputs - 1 data and 1 weight.

scale int, required Up sampling scale

num.filter int, optional, default='0' Input filter. Only used by bilinear sample type. Since

bilinear upsampling uses deconvolution, num_filters is set to the number of

channels.

sample.type 'bilinear', 'nearest', required upsampling method

multi.input.mode

'concat', 'sum',optional, default='concat' How to handle multiple input. concat means concatenate upsampled images along the channel dimension. sum means

add all images together, only available for nearest neighbor upsampling.

int, required Number of inputs to be upsampled. For nearest neighbor upsamnum.args

> pling, this can be 1-N; the size of output will be(scale*h_0,scale*w_0) and all other inputs will be upsampled to thesame size. For bilinear upsampling this

must be 2; 1 input and 1 weight.

long (non-negative), optional, default=512 Tmp workspace for deconvolution workspace

(MB)

Details

- Nearest Neighbor - Bilinear

Nearest Neighbor Upsampling

Input data is expected to be NCHW.

Example::

x = [[[[1. 1. 1.] [1. 1. 1.] [1. 1. 1.]]]]

mx.nd.where 265

```
UpSampling(x, scale=2, sample_type='nearest') = [[[[1. 1. 1. 1. 1. 1. 1. ] [1. 1. 1. 1. 1. ] [1. 1. 1. 1. 1. ] [1. 1. 1. 1. 1. ] [1. 1. 1. 1. ] [1. 1. 1. 1. ]]]]
```

Bilinear Upsampling

Uses 'deconvolution' algorithm under the hood. You need provide both input data and the kernel.

Input data is expected to be NCHW.

'num_filter' is expected to be same as the number of channels.

Example::

```
\mathbf{x} = [[[[1. \ 1. \ 1.] \ [1. \ 1. \ 1.] \ [1. \ 1. \ 1.]]]]
\mathbf{w} = [[[[1. \ 1. \ 1. \ 1.] \ [1. \ 1. \ 1. \ 1.] \ [1. \ 1. \ 1. \ 1.]]]]
```

UpSampling(x, w, scale=2, sample_type='bilinear', num_filter=1) = [[[[1. 2. 2. 2. 2. 2. 1.] [2. 4. 4. 4. 2.] [2. 4. 4. 4. 2.] [2. 4. 4. 4. 2.] [1. 2. 2. 2. 2. 1.]]]]

Defined in src/operator/nn/upsampling.cc:L173

Value

out The result mx.ndarray

mx.nd.where

Return the elements, either from x or y, depending on the condition.

Description

Given three ndarrays, condition, x, and y, return an ndarray with the elements from x or y, depending on the elements from condition are true or false. x and y must have the same shape. If condition has the same shape as x, each element in the output array is from x if the corresponding element in the condition is true, and from y if false.

Arguments

condition NDArray-or-Symbol condition array

x NDArray-or-Symbol y NDArray-or-Symbol

Details

If condition does not have the same shape as x, it must be a 1D array whose size is the same as x's first dimension size. Each row of the output array is from x's row if the corresponding element from condition is true, and from y's row if false.

Note that all non-zero values are interpreted as "True" in condition.

Examples::

```
x = [[1, 2], [3, 4]] y = [[5, 6], [7, 8]] cond = [[0, 1], [-1, 0]]
where(cond, x, y) = [[5, 2], [3, 8]]
```

266 mx.nd.zeros.like

```
csr_cond = cast_storage(cond, 'csr')
where(csr_cond, x, y) = [[5, 2], [3, 8]]
Defined in src/operator/tensor/control_flow_op.cc:L57
```

Value

out The result mx.ndarray

mx.nd.zeros

Generate an mx.nd.array object with zeros

Description

Generate an mx.nd.array object with zeros

Usage

```
mx.nd.zeros(shape, ctx = NULL)
```

Arguments

shape the dimension of the mx.nd.array

optional The context device of the array. mx.ctx.default() will be used in default.

Examples

```
mat = mx.nd.zeros(10)
as.array(mat)
mat2 = mx.nd.zeros(c(5,5))
as.array(mat)
mat3 = mx.nd.zeroes(c(3,3,3))
as.array(mat3)
```

mx.nd.zeros.like

Return an array of zeros with the same shape, type and storage type as the input array.

Description

The storage type of "zeros_like" output depends on the storage type of the input

Arguments

data

NDArray-or-Symbol The input

mx.opt.adadelta 267

Details

```
- zeros_like(row_sparse) = row_sparse - zeros_like(csr) = csr - zeros_like(default) = default Examples:: x = [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] zeros_like(x) = [[\ 0.,\ 0.,\ 0.],\ [\ 0.,\ 0.,\ 0.]]
```

Value

out The result mx.ndarray

mx.opt.adadelta

Create an AdaDelta optimizer with respective parameters.

Description

AdaDelta optimizer as described in Zeiler, M. D. (2012). *ADADELTA: An adaptive learning rate method.* http://arxiv.org/abs/1212.5701

Usage

```
mx.opt.adadelta(rho = 0.9, epsilon = 1e-05, wd = 0,
  rescale.grad = 1, clip_gradient = -1)
```

Arguments

rho float, default=0.90 Decay rate for both squared gradients and delta x.

epsilon float, default=1e-5 The constant as described in the thesis.

wd float, default=0.0 L2 regularization coefficient add to all the weights.

rescale.grad float, default=1 rescaling factor of gradient.

clip_gradient float, default=-1 (no clipping if < 0) clip gradient in range [-clip_gradient, clip_gradient].

mx.opt.adagrad Create an AdaGrad optimizer with respective parameters. AdaGrad

optimizer of Duchi et al., 2011,

Description

This code follows the version in http://arxiv.org/pdf/1212.5701v1.pdf Eq(5) by Matthew D. Zeiler, 2012. AdaGrad will help the network to converge faster in some cases.

Usage

```
mx.opt.adagrad(learning.rate = 0.05, epsilon = 1e-08, wd = 0,
  rescale.grad = 1, clip_gradient = -1, lr_scheduler = NULL)
```

268 mx.opt.adam

Arguments

learning.rate float, default=0.05 Step size.

epsilon float, default=1e-8

wd float, default=0.0 L2 regularization coefficient add to all the weights.

rescale.grad float, default=1.0 rescaling factor of gradient.

clip_gradient float, default=-1.0 (no clipping if < 0) clip gradient in range [-clip_gradient,

clip_gradient].

1r_scheduler function, optional The learning rate scheduler.

mx.opt.adam Create an Adam optimizer with respective parameters. Adam optimizer as described in [King2014].

Description

[King2014] Diederik Kingma, Jimmy Ba, Adam: A Method for Stochastic Optimization, http://arxiv.org/abs/1412.6980

Usage

```
mx.opt.adam(learning.rate = 0.001, beta1 = 0.9, beta2 = 0.999,
    epsilon = 1e-08, wd = 0, rescale.grad = 1, clip_gradient = -1,
    lr_scheduler = NULL)
```

Arguments

learning.rate float, default=1e-3 The initial learning rate.

beta1 float, default=0.9 Exponential decay rate for the first moment estimates.

beta2 float, default=0.999 Exponential decay rate for the second moment estimates.

epsilon float, default=1e-8

wd float, default=0.0 L2 regularization coefficient add to all the weights.

rescale.grad float, default=1.0 rescaling factor of gradient.

clip_gradient float, optional, default=-1 (no clipping if < 0) clip gradient in range [-clip_gradient,

clip_gradient].

1r_scheduler function, optional The learning rate scheduler.

mx.opt.create 269

mx.opt.create

Create an optimizer by name and parameters

Description

Create an optimizer by name and parameters

Usage

```
mx.opt.create(name, ...)
```

Arguments

name The name of the optimizer

... Additional arguments

mx.opt.get.updater

Get an updater closure that can take list of weight and gradient and return updated list of weight.

Description

Get an updater closure that can take list of weight and gradient and return updated list of weight.

Usage

```
mx.opt.get.updater(optimizer, weights, ctx)
```

Arguments

optimizer The optimizer

weights The weights to be optimized

270 mx.opt.rmsprop

mx.opt.nag	Create a Nesterov Accelerated SGD(NAG) optimizer.	

Description

NAG optimizer is described in Aleksandar Botev. et al (2016). *NAG: A Nesterov accelerated SGD.* https://arxiv.org/pdf/1607.01981.pdf

Usage

```
mx.opt.nag(learning.rate = 0.01, momentum = 0, wd = 0,
   rescale.grad = 1, clip_gradient = -1, lr_scheduler = NULL)
```

Arguments

learning.rate float, default=0.01 The initial learning rate.

momentum float, default=0 The momentum value

wd float, default=0.0 L2 regularization coefficient added to all the weights.

rescale.grad float, default=1.0 rescaling factor of gradient.

clip_gradient float, optional, default=-1 (no clipping if < 0) clip gradient in range [-clip_gradient,

clip_gradient].

1r_scheduler function, optional The learning rate scheduler.

mx.opt.rmsprop Create an RMSProp optimizer with respective parameters. Reference: Tieleman T, Hinton G. Lecture 6.5-rmsprop: Divide the gradient by a running average of its recent magnitude[J]. COURSERA: Neural Networks for Machine Learning, 2012, 4(2). The code follows: http://arxiv.org/pdf/1308.0850v5.pdf Eq(38) - Eq(45) by Alex Graves, 2013.

Description

Create an RMSProp optimizer with respective parameters. Reference: Tieleman T, Hinton G. Lecture 6.5-rmsprop: Divide the gradient by a running average of its recent magnitude[J]. COURSERA: Neural Networks for Machine Learning, 2012, 4(2). The code follows: http://arxiv.org/pdf/1308.0850v5.pdf Eq(38) - Eq(45) by Alex Graves, 2013.

Usage

```
mx.opt.rmsprop(learning.rate = 0.002, centered = TRUE, gamma1 = 0.95,
  gamma2 = 0.9, epsilon = 1e-04, wd = 0, rescale.grad = 1,
  clip_gradient = -1, lr_scheduler = NULL)
```

mx.opt.sgd 271

Arguments

learning.rate float, default=0.002 The initial learning rate.

gamma1 float, default=0.95 decay factor of moving average for gradient, gradient^2.

gamma2 float, default=0.9 "momentum" factor.

epsilon float, default=1e-4

wd float, default=0.0 L2 regularization coefficient add to all the weights.

rescale.grad float, default=1.0 rescaling factor of gradient.

clip_gradient float, optional, default=-1 (no clipping if < 0) clip gradient in range [-clip_gradient,

clip_gradient].

1r_scheduler function, optional The learning rate scheduler.

Description

Create an SGD optimizer with respective parameters. Perform SGD with momentum update

Usage

```
mx.opt.sgd(learning.rate = 0.01, momentum = 0, wd = 0,
  rescale.grad = 1, clip_gradient = -1, lr_scheduler = NULL)
```

Arguments

learning.rate float, default=0.01 The initial learning rate.

momentum float, default=0 The momentum value

wd float, default=0.0 L2 regularization coefficient add to all the weights.

rescale.grad float, default=1.0 rescaling factor of gradient.

clip_gradient float, optional, default=-1 (no clipping if < 0) clip gradient in range [-clip_gradient,

clip_gradient].

1r_scheduler function, optional The learning rate scheduler.

272 mx.profiler.state

mx.profiler.config

Set up the configuration of profiler.

Description

Set up the configuration of profiler.

Usage

```
mx.profiler.config(params)
```

Arguments

flags

list of key/value pair tuples. Indicates configuration parameters profile_symbolic : boolean, whether to profile symbolic operators profile_imperative : boolean, whether to profile imperative operators profile_memory : boolean, whether to profile memory usage profile_api : boolean, whether to profile the C API file_name : string, output file for profile data continuous_dump : boolean, whether to periodically dump profiling data to file dump_period : float, seconds between profile data dumps

mx.profiler.state

Set up the profiler state to record operator.

Description

Set up the profiler state to record operator.

Usage

```
mx.profiler.state(state = MX.PROF.STATE$STOP)
```

Arguments

state

Indicting whether to run the profiler, can be 'MX.PROF.STATE\$RUN' or 'MX.PROF.STATE\$STOP'.

Default is 'MX.PROF.STATE\$STOP'.

filename

The name of output trace file. Default is 'profile.json'

mx.rnorm 273

my	rnorm
IIIA .	1 1101 111

Generate nomal distribution with mean and sd.

Description

Generate nomal distribution with mean and sd.

Usage

```
mx.rnorm(shape, mean = 0, sd = 1, ctx = NULL)
```

Arguments

shape Dimension, The shape(dimension) of the result.

mean numeric, The mean of distribution.
sd numeric, The standard deviations.

ctx, optional The context device of the array. mx.ctx.default() will be used in default.

Examples

```
mx.set.seed(0)
as.array(mx.runif(2))
# 0.5488135 0.5928446
mx.set.seed(0)
as.array(mx.rnorm(2))
# 2.212206 1.163079
```

mx.runif

Generate uniform distribution in [low, high) with specified shape.

Description

Generate uniform distribution in [low, high) with specified shape.

Usage

```
mx.runif(shape, min = 0, max = 1, ctx = NULL)
```

Arguments

shape	Dimension, The shape(dimension) of the result.
min	numeric, The lower bound of distribution.
max	numeric, The upper bound of distribution.
ctx,	optional The context device of the array. mx.ctx.default() will be used in default.

274 mx.set.seed

Examples

```
mx.set.seed(0)
as.array(mx.runif(2))
# 0.5488135 0.5928446
mx.set.seed(0)
as.array(mx.rnorm(2))
# 2.212206 1.163079
```

mx.serialize

Serialize MXNet model into RData-compatiable format.

Description

Serialize MXNet model into RData-compatiable format.

Usage

```
mx.serialize(model)
```

Arguments

model

The mxnet model

mx.set.seed

Set the seed used by mxnet device-specific random number generators.

Description

Set the seed used by mxnet device-specific random number generators.

Usage

```
mx.set.seed(seed)
```

Arguments

seed

the seed value to the device random number generators.

Details

We have a specific reason why mx.set.seed is introduced, instead of simply use set.seed.

The reason that is that most of mxnet random number generator can run on different devices, such as GPU. We need to use massively parallel PRNG on GPU to get fast random number generations. It can also be quite costly to seed these PRNGs. So we introduced mx.set.seed for mxnet specific device random numbers.

mx.simple.bind 275

Examples

```
mx.set.seed(0)
as.array(mx.runif(2))
# 0.5488135 0.5928446
mx.set.seed(0)
as.array(mx.rnorm(2))
# 2.212206 1.163079
```

mx.simple.bind

Simple bind the symbol to executor, with information from input shapes.

Description

Simple bind the symbol to executor, with information from input shapes.

Usage

```
mx.simple.bind(symbol, ctx, grad.req = "null", fixed.param = NULL, ...)
```

mx.symbol.abs

abs:Returns element-wise absolute value of the input.

Description

Example::

Usage

```
mx.symbol.abs(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
abs([-2, 0, 3]) = [2, 0, 3]
```

The storage type of "abs" output depends upon the input storage type:

- abs(default) = default - abs(row_sparse) = row_sparse - abs(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L721

Value

out The result mx.symbol

Description

The following activation functions are supported:

Usage

```
mx.symbol.Activation(...)
```

Arguments

data NDArray-or-Symbol The input array.

act.type 'relu', 'sigmoid', 'softrelu', 'softsign', 'tanh', required Activation function to be

applied.

name string, optional Name of the resulting symbol.

Details

```
- 'relu': Rectified Linear Unit, :math: 'y = max(x, 0)' - 'sigmoid': :math: 'y = \frac{11 + exp(-x)}{exp(-x)}" - 'tanh': Hyperbolic tangent, :math: 'y = \frac{11 + exp(-x)}{exp(-x)}" - 'softrelu': Soft ReLU, or SoftPlus, :math: 'y = \log(1 + exp(x))' - 'softsign': :math: 'y = \frac{11 + exp(-x)}{exp(-x)}"
```

Defined in src/operator/nn/activation.cc:L168

Value

out The result mx.symbol

mx.symbol.adam_update adam_update:Update function for Adam optimizer. Adam is seen as a generalization of AdaGrad.

Description

Adam update consists of the following steps, where g represents gradient and m, v are 1st and 2nd order moment estimates (mean and variance).

Usage

```
mx.symbol.adam_update(...)
```

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
mean	NDArray-or-Symbol Moving mean
var	NDArray-or-Symbol Moving variance
lr	float, required Learning rate
beta1	float, optional, default=0.899999976 The decay rate for the 1st moment estimates.
beta2	float, optional, default=0.999000013 The decay rate for the 2nd moment estimates.
epsilon	float, optional, default=9.99999994e-09 A small constant for numerical stability.
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
lazy.update	boolean, optional, default=1 If true, lazy updates are applied if gradient's stype is row_sparse and all of w, m and v have the same stype

Details

```
.. math::
```

name

```
 g_t = \adjust{0.05} \ J(W_t-1) \ m_t = \beta_1 \ m_t-1 + (1 - \beta_1) \ g_t \ v_t = \beta_2 \ v_t-1 + (1 - \beta_2) \ g_t^2 \ W_t = W_t-1 - \alpha frac m_t \ r_t + epsilon
```

string, optional Name of the resulting symbol.

It updates the weights using::

```
 m = beta1*m + (1-beta1)*grad v = beta2*v + (1-beta2)*(grad**2) w += - learning\_rate * m / (sqrt(v) + epsilon)
```

However, if grad's storage type is "row_sparse", "lazy_update" is True and the storage type of weight is the same as those of m and v, only the row slices whose indices appear in grad.indices are updated (for w, m and v)::

for row in grad.indices: $m[row] = beta1*m[row] + (1-beta1)*grad[row] v[row] = beta2*v[row] + (1-beta2)*(grad[row]**2) w[row] += - learning_rate * m[row] / (sqrt(v[row]) + epsilon)$

Defined in src/operator/optimizer_op.cc:L686

Value

out The result mx.symbol

278 mx.symbol.all_finite

mx.symbol.add_n

add_n:Adds all input arguments element-wise.

Description

```
.. math:: add\_n(a_1, a_2, ..., a_n) = a_1 + a_2 + ... + a_n
```

Usage

```
mx.symbol.add_n(...)
```

Arguments

args NDArray-or-Symbol[] Positional input arguments string, optional Name of the resulting symbol.

Details

"add_n" is potentially more efficient than calling "add" by 'n' times.

The storage type of "add_n" output depends on storage types of inputs

- add_n(row_sparse, row_sparse, ..) = row_sparse - add_n(default, csr, default) = default - add_n(any input combinations longer than 4 (>4) with at least one default type) = default - otherwise, "add_n" falls all inputs back to default storage and generates default storage

Defined in src/operator/tensor/elemwise_sum.cc:L155

Value

out The result mx.symbol

```
mx.symbol.all\_finite all_finite: Check if all the float numbers in the array are finite (used for AMP)
```

Description

Defined in src/operator/contrib/all_finite.cc:L101

Usage

```
mx.symbol.all_finite(...)
```

Arguments

data NDArray Array

init.output boolean, optional, default=1 Initialize output to 1. string, optional Name of the resulting symbol.

mx.symbol.amp_cast 279

Value

out The result mx.symbol

mx.symbol.amp_cast

amp_cast:Cast function between low precision float/FP32 used by

AMP.

Description

It casts only between low precision float/FP32 and does not do anything for other types.

Usage

```
mx.symbol.amp_cast(...)
```

Arguments

data NDArray-or-Symbol The input.

dtype 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', required Output

data type.

name string, optional Name of the resulting symbol.

Details

Defined in src/operator/tensor/amp_cast.cc:L37

Value

out The result mx.symbol

```
mx.symbol.amp_multicast
```

amp_multicast: Cast function used by AMP, that casts its inputs to the common widest type.

Description

It casts only between low precision float/FP32 and does not do anything for other types.

Usage

```
mx.symbol.amp_multicast(...)
```

280 mx.symbol.arccos

Arguments

data NDArray-or-Symbol[] Weights

num.outputs int, required Number of input/output pairs to be casted to the widest type.

cast.narrow boolean, optional, default=0 Whether to cast to the narrowest type

name string, optional Name of the resulting symbol.

Details

Defined in src/operator/tensor/amp_cast.cc:L71

Value

out The result mx.symbol

mx.symbol.arccos

arccos:Returns element-wise inverse cosine of the input array.

Description

The input should be in range '[-1, 1]'. The output is in the closed interval :math: '[0, \pi]'

Usage

```
mx.symbol.arccos(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
.. math:: arccos([-1, -.707, 0, .707, 1]) = [\pi, 3\pi/4, \pi/2, \pi/4, 0]
```

The storage type of "arccos" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L206

Value

out The result mx.symbol

mx.symbol.arccosh 281

mx.symbol.arccosh

arccosh:Returns the element-wise inverse hyperbolic cosine of the input array, \computed element-wise.

Description

The storage type of "arccosh" output is always dense

Usage

```
mx.symbol.arccosh(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L474

Value

out The result mx.symbol

mx.symbol.arcsin

arcsin:Returns element-wise inverse sine of the input array.

Description

The input should be in the range '[-1, 1]'. The output is in the closed interval of [:math:'-\pi/2', :math:'\pi/2'].

Usage

```
mx.symbol.arcsin(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

282 mx.symbol.arcsinh

Details

```
.. math:: \arcsin([-1, -.707, 0, .707, 1]) = [-\pi/2, -\pi/4, 0, \pi/4, \pi/2]
```

The storage type of "arcsin" output depends upon the input storage type:

- arcsin(default) = default - arcsin(row_sparse) = row_sparse - arcsin(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L187

Value

out The result mx.symbol

mx.symbol.arcsinh

arcsinh:Returns the element-wise inverse hyperbolic sine of the input array, \computed element-wise.

Description

The storage type of "arcsinh" output depends upon the input storage type:

Usage

```
mx.symbol.arcsinh(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
- arcsinh(default) = default - arcsinh(row_sparse) = row_sparse - arcsinh(csr) = csr
Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L436
```

Value

out The result mx.symbol

mx.symbol.arctan 283

mx.symbol.arctan

arctan:Returns element-wise inverse tangent of the input array.

Description

The output is in the closed interval :math: '[-\pi/2, \pi/2]'

Usage

```
mx.symbol.arctan(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
.. math:: \arctan([-1, 0, 1]) = [-\pi/4, 0, \pi/4]
```

The storage type of "arctan" output depends upon the input storage type:

- arctan(default) = default - arctan(row_sparse) = row_sparse - arctan(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L227

Value

out The result mx.symbol

mx.symbol.arctanh

arctanh: Returns the element-wise inverse hyperbolic tangent of the input array, \computed element-wise.

Description

The storage type of "arctanh" output depends upon the input storage type:

Usage

```
mx.symbol.arctanh(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

284 mx.symbol.argmax

Details

```
- arctanh(default) = default - arctanh(row_sparse) = row_sparse - arctanh(csr) = csr
Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L515
```

Value

out The result mx.symbol

mx.symbol.argmax

argmax: Returns indices of the maximum values along an axis.

Description

In the case of multiple occurrences of maximum values, the indices corresponding to the first occurrence are returned.

Usage

```
mx.symbol.argmax(...)
```

Arguments

data NDArray-or-Symbol The input

axis int or None, optional, default='None' The axis along which to perform the re-

duction. Negative values means indexing from right to left. "Requires axis to be

set as int, because global reduction is not supported yet."

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axis is left in the

result as dimension with size one.

name string, optional Name of the resulting symbol.

Details

Examples::

```
x = [[0., 1., 2.], [3., 4., 5.]]
```

// argmax along axis 0 argmax(x, axis=0) = [1., 1., 1.]

// argmax along axis 1 argmax(x, axis=1) = [2., 2.]

// argmax along axis 1 keeping same dims as an input array argmax(x, axis=1, keepdims=True) = [[2.], [2.]]

Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L52

Value

out The result mx.symbol

```
mx.symbol.argmax_channel
```

argmax_channel:Returns argmax indices of each channel from the input array.

Description

The result will be an NDArray of shape (num_channel,).

Usage

```
mx.symbol.argmax_channel(...)
```

Arguments

data NDArray-or-Symbol The input array

name string, optional Name of the resulting symbol.

Details

In case of multiple occurrences of the maximum values, the indices corresponding to the first occurrence are returned.

Examples::

```
x = [[0., 1., 2.], [3., 4., 5.]]

argmax\_channel(x) = [2., 2.]
```

Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L97

Value

out The result mx.symbol

mx.symbol.argmin

argmin:Returns indices of the minimum values along an axis.

Description

In the case of multiple occurrences of minimum values, the indices corresponding to the first occurrence are returned.

Usage

```
mx.symbol.argmin(...)
```

286 mx.symbol.argsort

Arguments

data NDArray-or-Symbol The input

axis int or None, optional, default='None' The axis along which to perform the re-

duction. Negative values means indexing from right to left. "Requires axis to be

set as int, because global reduction is not supported yet."

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axis is left in the

result as dimension with size one.

name string, optional Name of the resulting symbol.

Details

Examples::

```
x = [[0., 1., 2.], [3., 4., 5.]]
```

// argmin along axis 0 argmin(x, axis=0) = [0., 0., 0.]

// argmin along axis 1 argmin(x, axis=1) = [0., 0.]

// argmin along axis 1 keeping same dims as an input array argmin(x, axis=1, keepdims=True) = [[0.], [0.]]

Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L77

Value

out The result mx.symbol

mx.symbol.argsort

argsort:Returns the indices that would sort an input array along the given axis.

Description

This function performs sorting along the given axis and returns an array of indices having same shape as an input array that index data in sorted order.

Usage

```
mx.symbol.argsort(...)
```

Arguments

data NDArray-or-Symbol	The input array
------------------------	-----------------

axis int or None, optional, default='-1' Axis along which to sort the input tensor. If

not given, the flattened array is used. Default is -1.

is.ascend boolean, optional, default=1 Whether to sort in ascending or descending order.

dtype 'float16', 'float32', 'float64', 'int32', 'int64', 'uint8', optional, default='float32'

DType of the output indices. It is only valid when ret_typ is "indices" or "both". An error will be raised if the selected data type cannot precisely represent the

indices.

name string, optional Name of the resulting symbol.

Details

Examples::

```
 \begin{aligned} x &= [[\ 0.3, 0.2, 0.4], [\ 0.1, 0.3, 0.2]] \\ \text{// sort along axis -1 argsort}(x) &= [[\ 1., 0., 2.], [\ 0., 2., 1.]] \\ \text{// sort along axis 0 argsort}(x, axis=0) &= [[\ 1., 0., 1.] [\ 0., 1., 0.]] \\ \text{// flatten and then sort argsort}(x, axis=None) &= [\ 3., 1., 5., 0., 4., 2.] \\ \text{Defined in src/operator/tensor/ordering\_op.cc:L181}  \end{aligned}
```

Value

out The result mx.symbol

mx.symbol.BatchNorm

BatchNorm:Batch normalization.

Description

Normalizes a data batch by mean and variance, and applies a scale "gamma" as well as offset "beta".

Usage

```
mx.symbol.BatchNorm(...)
```

Arguments

data NDArray-or-Symbol Input data to batch normalization

gamma NDArray-or-Symbol gamma array beta NDArray-or-Symbol beta array

moving.mean NDArray-or-Symbol running mean of input moving.var NDArray-or-Symbol running variance of input

eps double, optional, default=0.001000000474974513 Epsilon to prevent div 0.

Must be no less than CUDNN_BN_MIN_EPSILON defined in cudnn.h when

using cudnn (usually 1e-5)

momentum float, optional, default=0.899999976 Momentum for moving average

fix.gamma boolean, optional, default=1 Fix gamma while training

use.global.stats

boolean, optional, default=0 Whether use global moving statistics instead of local batch-norm. This will force change batch-norm into a scale shift operator.

output.mean.var

boolean, optional, default=0 Output the mean and inverse std

axis int, optional, default='1' Specify which shape axis the channel is specified

cudnn.off boolean, optional, default=0 Do not select CUDNN operator, if available

min.calib.range

float or None, optional, default=None The minimum scalar value in the form of float32 obtained through calibration. If present, it will be used to by quantized batch norm op to calculate primitive scale.Note: this calib_range is to calib bn output.

max.calib.range

float or None, optional, default=None The maximum scalar value in the form of float32 obtained through calibration. If present, it will be used to by quantized batch norm op to calculate primitive scale.Note: this calib_range is to calib bn output.

name string, optional Name of the resulting symbol.

Details

Assume the input has more than one dimension and we normalize along axis 1. We first compute the mean and variance along this axis:

.. math::

```
data\_mean[i] = mean(data[:,i,:,...]) \setminus data\_var[i] = var(data[:,i,:,...])
```

Then compute the normalized output, which has the same shape as input, as following:

.. math::

```
out[:,i,:,...] = \frac{(i,i,:,...] - data_mean[i] \cdot qrtdata_var[i] + epsilon * gamma[i] + beta[i]}
```

Both *mean* and *var* returns a scalar by treating the input as a vector.

Assume the input has size *k* on axis 1, then both "gamma" and "beta" have shape *(k,)*. If "output_mean_var" is set to be true, then outputs both "data_mean" and the inverse of "data_var", which are needed for the backward pass. Note that gradient of these two outputs are blocked.

Besides the inputs and the outputs, this operator accepts two auxiliary states, "moving_mean" and "moving_var", which are *k*-length vectors. They are global statistics for the whole dataset, which are updated by::

moving_mean = moving_mean * momentum + data_mean * (1 - momentum) moving_var = moving_var * momentum + data_var * (1 - momentum)

If "use_global_stats" is set to be true, then "moving_mean" and "moving_var" are used instead of "data mean" and "data var" to compute the output. It is often used during inference.

The parameter "axis" specifies which axis of the input shape denotes the 'channel' (separately normalized groups). The default is 1. Specifying -1 sets the channel axis to be the last item in the input shape.

Both "gamma" and "beta" are learnable parameters. But if "fix_gamma" is true, then set "gamma" to 1 and its gradient to 0.

.. Note:: When "fix_gamma" is set to True, no sparse support is provided. If "fix_gamma is" set to False, the sparse tensors will fallback.

Defined in src/operator/nn/batch_norm.cc:L571

Value

out The result mx.symbol

```
mx.symbol.BatchNorm_v1
```

BatchNorm_v1:Batch normalization.

Description

This operator is DEPRECATED. Perform BatchNorm on the input.

Usage

```
mx.symbol.BatchNorm_v1(...)
```

Arguments

data	NDArray-or-	-Symbol Int	out data to	batch norma	ilization
uata	INDAHay-or	-9 / 111001 1111	jui uaia io	valcii iioiiiia	mzanc

gamma NDArray-or-Symbol gamma array beta NDArray-or-Symbol beta array

eps float, optional, default=0.00100000005 Epsilon to prevent div 0

momentum float, optional, default=0.899999976 Momentum for moving average

fix.gamma boolean, optional, default=1 Fix gamma while training

use.global.stats

boolean, optional, default=0 Whether use global moving statistics instead of

local batch-norm. This will force change batch-norm into a scale shift operator.

output.mean.var

boolean, optional, default=0 Output All,normal mean and var

name string, optional Name of the resulting symbol.

Details

Normalizes a data batch by mean and variance, and applies a scale "gamma" as well as offset "beta".

Assume the input has more than one dimension and we normalize along axis 1. We first compute the mean and variance along this axis:

.. math::

```
data \ [i] = mean(data[:,i,:,...]) \ \ data \ \ [var[i] = var(data[:,i,:,...])
```

Then compute the normalized output, which has the same shape as input, as following:

290 mx.symbol.batch_dot

```
.. math::
```

```
out[:,i,:,...] = \frac{(i,i,:,...] - data\underline{mean[i]} \operatorname{var}[i] + \operatorname{epsilon} * \operatorname{gamma}[i] + \operatorname{beta}[i]}
```

Both *mean* and *var* returns a scalar by treating the input as a vector.

Assume the input has size *k* on axis 1, then both "gamma" and "beta" have shape *(k,)*. If "output_mean_var" is set to be true, then outputs both "data_mean" and "data_var" as well, which are needed for the backward pass.

Besides the inputs and the outputs, this operator accepts two auxiliary states, "moving_mean" and "moving_var", which are *k*-length vectors. They are global statistics for the whole dataset, which are updated by::

moving_mean = moving_mean * momentum + data_mean * (1 - momentum) moving_var = moving_var * momentum + data_var * (1 - momentum)

If "use_global_stats" is set to be true, then "moving_mean" and "moving_var" are used instead of "data_mean" and "data_var" to compute the output. It is often used during inference.

Both "gamma" and "beta" are learnable parameters. But if "fix_gamma" is true, then set "gamma" to 1 and its gradient to 0.

There's no sparse support for this operator, and it will exhibit problematic behavior if used with sparse tensors.

Defined in src/operator/batch_norm_v1.cc:L95

Value

out The result mx.symbol

mx.symbol.batch_dot

batch dot:Batchwise dot product.

Description

"batch_dot" is used to compute dot product of "x" and "y" when "x" and "y" are data in batch, namely N-D ($N \ge 3$) arrays in shape of '($B0, ..., B_i, ..., ...$).

Usage

```
mx.symbol.batch_dot(...)
```

Arguments

1hs NDArray-or-Symbol The first input rhs NDArray-or-Symbol The second input

transpose.a boolean, optional, default=0 If true then transpose the first input before dot. boolean, optional, default=0 If true then transpose the second input before dot. forward.stype None, 'csr', 'default', 'row_sparse', optional, default='None' The desired stor-

age type of the forward output given by user, if the combination of input storage types and this hint does not matchany implemented ones, the dot operator will perform fallback operationand still produce an output of the desired storage type.

name string, optional Name of the resulting symbol.

mx.symbol.batch_take 291

Details

```
For example, given "x" with shape '(B_0, ..., B_i, N, M)' and "y" with shape '(B_0, ..., B_i, M, K)', the result array will have shape '(B_0, ..., B_i, N, K)', which is computed by:: batch_dot(x,y)[b_0, ..., b_i, :, :] = dot(x[b_0, ..., b_i, :, :], y[b_0, ..., b_i, :, :]) Defined in src/operator/tensor/dot.cc:L126
```

Value

out The result mx.symbol

```
mx.symbol.batch_take batch take: Takes elements from a data batch.
```

Description

```
.. note:: 'batch_take' is deprecated. Use 'pick' instead.
```

Usage

```
mx.symbol.batch_take(...)
```

Arguments

a NDArray-or-Symbol The input array indices NDArray-or-Symbol The index array string, optional Name of the resulting symbol.

Details

Given an input array of shape "(d0, d1)" and indices of shape "(i0,)", the result will be an output array of shape "(i0,)" with::

```
output[i] = input[i, indices[i]]
```

Examples::

```
x = [[1., 2.], [3., 4.], [5., 6.]]
```

// takes elements with specified indices batch_take(x, [0,1,0]) = [1. 4. 5.]

Defined in src/operator/tensor/indexing_op.cc:L774

Value

```
out The result mx.symbol
```

```
mx.symbol.BilinearSampler
```

BilinearSampler: Applies bilinear sampling to input feature map.

Description

Bilinear Sampling is the key of [NIPS2015] \"Spatial Transformer Networks\". The usage of the operator is very similar to remap function in OpenCV, except that the operator has the backward pass.

Usage

```
mx.symbol.BilinearSampler(...)
```

Arguments

data NDArray-or-Symbol Input data to the BilinearsamplerOp.

grid NDArray-or-Symbol Input grid to the BilinearsamplerOp.grid has two channels:

x_src, y_src

cudnn.off boolean or None, optional, default=None whether to turn cudnn off

name string, optional Name of the resulting symbol.

Details

Given :math: 'data' and :math: 'grid', then the output is computed by

```
.. math:: x\_src = grid[batch, 0, y\_dst, x\_dst] \setminus y\_src = grid[batch, 1, y\_dst, x\_dst] \setminus output[batch, channel, y\_dst, x\_dst] = G(data[batch, channel, y\_src, x\_src)
```

:math:' x_dst' , :math:' y_dst' enumerate all spatial locations in :math:'output', and :math:'G()' denotes the bilinear interpolation kernel. The out-boundary points will be padded with zeros. The shape of the output will be (data.shape[0], data.shape[1], grid.shape[2], grid.shape[3]).

The operator assumes that :math:'data' has 'NCHW' layout and :math:'grid' has been normalized to [-1, 1].

BilinearSampler often cooperates with GridGenerator which generates sampling grids for BilinearSampler. GridGenerator supports two kinds of transformation: "affine" and "warp". If users want to design a CustomOp to manipulate :math: 'grid', please firstly refer to the code of GridGenerator.

Example 1::

```
## Zoom out data two times data = array([[[[1, 4, 3, 6], [1, 8, 8, 9], [0, 4, 1, 5], [1, 0, 1, 3]]]])
affine_matrix = array([[2, 0, 0], [0, 2, 0]])
affine_matrix = reshape(affine_matrix, shape=(1, 6))
grid = GridGenerator(data=affine_matrix, transform_type='affine', target_shape=(4, 4))
out = BilinearSampler(data, grid)
out [[[[0, 0, 0, 0], [0, 3.5, 6.5, 0], [0, 1.25, 2.5, 0], [0, 0, 0, 0]]]
```

```
Example 2::
## shift data horizontally by -1 pixel
data = array([[[[1, 4, 3, 6], [1, 8, 8, 9], [0, 4, 1, 5], [1, 0, 1, 3]]]])
warp_maxtrix = array([[[[1, 1, 1, 1], [1, 1, 1, 1], [1, 1, 1, 1], [1, 1, 1, 1]], [[0, 0, 0, 0], [0, 0, 0, 0], [0, 0, 0, 0]]])
grid = GridGenerator(data=warp_matrix, transform_type='warp') out = BilinearSampler(data, grid)
out [[[[4, 3, 6, 0], [8, 8, 9, 0], [4, 1, 5, 0], [0, 1, 3, 0]]]
```

Defined in src/operator/bilinear sampler.cc:L256

Value

out The result mx.symbol

mx.symbol.BlockGrad

BlockGrad:Stops gradient computation.

Description

Stops the accumulated gradient of the inputs from flowing through this operator in the backward direction. In other words, this operator prevents the contribution of its inputs to be taken into account for computing gradients.

Usage

```
mx.symbol.BlockGrad(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
v1 = [1, 2] v2 = [0, 1] a = Variable('a') b = Variable('b') b_stop_grad = stop_gradient(3 * b) loss = MakeLoss(b_stop_grad + a) executor = loss.simple_bind(ctx=cpu(), a=(1,2), b=(1,2)) executor.forward(is_train=True, a=v1, b=v2) executor.outputs [ 1. 5.] executor.backward() executor.grad_arrays [ 0. 0.] [ 1. 1.]

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L327
```

Value

mx.symbol.broadcast_add

broadcast_add:Returns element-wise sum of the input arrays with broadcasting.

Description

'broadcast_plus' is an alias to the function 'broadcast_add'.

Usage

```
mx.symbol.broadcast_add(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

```
Example::
```

```
x = [[ 1., 1., 1.], [ 1., 1., 1.]]

y = [[ 0.], [ 1.]]

broadcast_add(x, y) = [[ 1., 1., 1.], [ 2., 2., 2.]]

broadcast_plus(x, y) = [[ 1., 1., 1.], [ 2., 2., 2.]]

Supported sparse operations:
```

broadcast_add(csr, dense(1D)) = dense broadcast_add(dense(1D), csr) = dense

Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L58

Value

```
mx.symbol.broadcast_axes
```

broadcast_axes:Broadcasts the input array over particular axes.

Description

Broadcasting is allowed on axes with size 1, such as from '(2,1,3,1)' to '(2,8,3,9)'. Elements will be duplicated on the broadcasted axes.

Usage

```
mx.symbol.broadcast_axes(...)
```

Arguments

data	NDArray-or-Symbol The input
axis	Shape(tuple), optional, default=[] The axes to perform the broadcasting.
size	Shape(tuple), optional, default=[] Target sizes of the broadcasting axes.
name	string, optional Name of the resulting symbol.

Details

'broadcast_axes' is an alias to the function 'broadcast_axis'.

Example::

```
// given x of shape (1,2,1) x = [[[ 1.], [ 2.]]]
```

// broadcast x on on axis 2 broadcast_axis(x, axis=2, size=3) = [[[1., 1., 1.], [2., 2., 2.]]] // broadcast x on on axes 0 and 2 broadcast_axis(x, axis=(0,2), size=(2,3)) = [[[1., 1., 1.], [2., 2., 2.]], [[1., 1., 1.], [2., 2., 2.]]]

Defined in src/operator/tensor/broadcast_reduce_op_value.cc:L58

Value

```
mx.symbol.broadcast_axis
```

broadcast_axis:Broadcasts the input array over particular axes.

Description

Broadcasting is allowed on axes with size 1, such as from '(2,1,3,1)' to '(2,8,3,9)'. Elements will be duplicated on the broadcasted axes.

Usage

```
mx.symbol.broadcast_axis(...)
```

Arguments

data	NDArray-or-Symbol The input
axis	Shape(tuple), optional, default=[] The axes to perform the broadcasting.
size	Shape(tuple), optional, default=[] Target sizes of the broadcasting axes.
name	string, optional Name of the resulting symbol.

Details

'broadcast_axes' is an alias to the function 'broadcast_axis'.

Example::

```
// given x of shape (1,2,1) x = [[[ 1.], [ 2.]]]
```

// broadcast x on on axis 2 broadcast_axis(x, axis=2, size=3) = [[[1., 1., 1.], [2., 2., 2.]]] // broadcast x on on axes 0 and 2 broadcast_axis(x, axis=(0,2), size=(2,3)) = [[[1., 1., 1.], [2., 2., 2.]], [[1., 1., 1.], [2., 2., 2.]]]

Defined in src/operator/tensor/broadcast_reduce_op_value.cc:L58

Value

mx.symbol.broadcast_div

broadcast_div:Returns element-wise division of the input arrays with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_div(...)
```

Arguments

1hsNDArray-or-Symbol First input to the functionrhsNDArray-or-Symbol Second input to the functionnamestring, optional Name of the resulting symbol.

Details

Value

out The result mx.symbol

```
mx.symbol.broadcast_equal
```

broadcast_equal:Returns the result of element-wise **equal to** (==) comparison operation with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_equal(...)
```

Arguments

lhs	NDArray-or-Symbol First input to the function
rhs	NDArray-or-Symbol Second input to the function
name	string, optional Name of the resulting symbol.

Details

```
 \begin{aligned} x &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ y &= [[\ 0.],\ [\ 1.]] \\ broadcast\_equal(x,y) &= [[\ 0.,\ 0.,\ 0.],\ [\ 1.,\ 1.,\ 1.]] \\ Defined in src/operator/tensor/elemwise\_binary\_broadcast\_op\_logic.cc:L46 \end{aligned}
```

Value

out The result mx.symbol

```
mx.symbol.broadcast_greater
```

 $broadcast_greater:Returns$ the result of element-wise **greater than**(>) comparison operation with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_greater(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function rhs NDArray-or-Symbol Second input to the function name string, optional Name of the resulting symbol.

Details

```
 \begin{aligned} x &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ y &= [[\ 0.],\ [\ 1.]] \\ broadcast\_greater(x,\ y) &= [[\ 1.,\ 1.,\ 1.],\ [\ 0.,\ 0.,\ 0.]] \\ Defined in src/operator/tensor/elemwise\_binary\_broadcast\_op\_logic.cc:L82 \end{aligned}
```

Value

```
mx.symbol.broadcast_greater_equal
```

broadcast_greater_equal:Returns the result of element-wise **greater than or equal to**(>=) comparison operation with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_greater_equal(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

```
 \begin{aligned} x &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ y &= [[\ 0.],\ [\ 1.]] \\ broadcast\_greater\_equal(x,\ y) &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ Defined in src/operator/tensor/elemwise\_binary\_broadcast\_op\_logic.cc:L100 \end{aligned}
```

Value

out The result mx.symbol

```
mx.symbol.broadcast_hypot
```

broadcast_hypot: Returns the hypotenuse of a right angled triangle, given its "legs" with broadcasting.

Description

It is equivalent to doing :math: $\operatorname{sqrt}(x_1^2 + x_2^2)$.

Usage

```
mx.symbol.broadcast_hypot(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
rhs NDArray-or-Symbol Second input to the function
name string, optional Name of the resulting symbol.

Details

```
Example::
```

```
x = [[ 3., 3., 3.]]

y = [[ 4.], [ 4.]]

broadcast_hypot(x, y) = [[ 5., 5., 5.], [ 5., 5., 5.]]

z = [[ 0.], [ 4.]]

broadcast_hypot(x, z) = [[ 3., 3., 3.], [ 5., 5., 5.]]
```

Defined in src/operator/tensor/elemwise_binary_broadcast_op_extended.cc:L158

Value

out The result mx.symbol

```
mx.symbol.broadcast_lesser
```

broadcast_lesser:Returns the result of element-wise **lesser than** (<) comparison operation with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_lesser(...)
```

Arguments

1hsNDArray-or-Symbol First input to the functionrhsNDArray-or-Symbol Second input to the functionnamestring, optional Name of the resulting symbol.

Details

```
x = [[1., 1., 1.], [1., 1., 1.]]

y = [[0.], [1.]]

broadcast_lesser(x, y) = [[0., 0., 0.], [0., 0., 0.]]
```

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L118

Value

out The result mx.symbol

```
mx.symbol.broadcast_lesser_equal
```

broadcast_lesser_equal:Returns the result of element-wise **lesser than or equal to**(<=) comparison operation with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_lesser_equal(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

```
x = [[ 1., 1., 1.], [ 1., 1., 1.]]

y = [[ 0.], [ 1.]]

broadcast_lesser_equal(x, y) = [[ 0., 0., 0.], [ 1., 1., 1.]]

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L136
```

Value

```
mx.symbol.broadcast_like
```

broadcast_like:Broadcasts lhs to have the same shape as rhs.

Description

Broadcasting is a mechanism that allows NDArrays to perform arithmetic operations with arrays of different shapes efficiently without creating multiple copies of arrays. Also see, 'Broadcasting https://docs.scipy.org/doc/numpy/user/basics.broadcasting.html '_ for more explanation.

Usage

```
mx.symbol.broadcast_like(...)
```

Arguments

lhs	NDArray-or-Symbol First input.
rhs	NDArray-or-Symbol Second input.
lhs.axes	Shape or None, optional, default=None Axes to perform broadcast on in the first input array
rhs.axes	Shape or None, optional, default=None Axes to copy from the second input array
name	string, optional Name of the resulting symbol.

Details

Broadcasting is allowed on axes with size 1, such as from '(2,1,3,1)' to '(2,8,3,9)'. Elements will be duplicated on the broadcasted axes.

For example::

```
broadcast_like([[1,2,3]], [[5,6,7],[7,8,9]]) = [[ 1., 2., 3.], [ 1., 2., 3.]])
broadcast_like([9], [1,2,3,4,5], lhs_axes=(0,), rhs_axes=(-1,)) = [9,9,9,9,9]
Defined in src/operator/tensor/broadcast_reduce_op_value.cc:L135
```

Value

```
mx.symbol.broadcast_logical_and
```

broadcast_logical_and:Returns the result of element-wise **logical and** with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_logical_and(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

```
x = [[1., 1., 1.], [1., 1., 1.]]

y = [[0.], [1.]]

broadcast_logical_and(x, y) = [[0., 0., 0.], [1., 1., 1.]]

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L154
```

Value

out The result mx.symbol

```
mx.symbol.broadcast_logical_or
```

broadcast_logical_or:Returns the result of element-wise **logical or** with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_logical_or(...)
```

Arguments

1hs NDArray-or-Symbol First input to the functionrhs NDArray-or-Symbol Second input to the functionname string, optional Name of the resulting symbol.

Details

```
 \begin{aligned} x &= [[\ 1.,\ 1.,\ 0.],\ [\ 1.,\ 1.,\ 0.]] \\ y &= [[\ 1.],\ [\ 0.]] \\ broadcast\_logical\_or(x,\ y) &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 0.]] \\ Defined in src/operator/tensor/elemwise\_binary\_broadcast\_op\_logic.cc:L172 \end{aligned}
```

Value

out The result mx.symbol

```
mx.symbol.broadcast_logical_xor
```

broadcast_logical_xor:Returns the result of element-wise **logical xor** with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_logical_xor(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

```
x = [[1., 1., 0.], [1., 1., 0.]]

y = [[1.], [0.]]

broadcast_logical_xor(x, y) = [[0., 0., 1.], [1., 1., 0.]]

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L190
```

Value

```
mx.symbol.broadcast_maximum
```

broadcast_maximum:Returns element-wise maximum of the input arrays with broadcasting.

Description

This function compares two input arrays and returns a new array having the element-wise maxima.

Usage

```
mx.symbol.broadcast_maximum(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

```
Example::
```

```
x = [[ 1., 1., 1.], [ 1., 1., 1.]]
y = [[ 0.], [ 1.]]
broadcast_maximum(x, y) = [[ 1., 1., 1.], [ 1., 1., 1.]]
```

Defined in src/operator/tensor/elemwise_binary_broadcast_op_extended.cc:L81

Value

out The result mx.symbol

```
mx.symbol.broadcast_minimum
```

broadcast_minimum:Returns element-wise minimum of the input arrays with broadcasting.

Description

This function compares two input arrays and returns a new array having the element-wise minima.

Usage

```
mx.symbol.broadcast_minimum(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

Example::

```
x = [[1, 1, 1, 1], [1, 1, 1, 1]]

y = [[0, 1, 1]]

broadcast_maximum(x, y) = [[0, 0, 0, 0], [1, 1, 1, 1]]
```

Defined in src/operator/tensor/elemwise_binary_broadcast_op_extended.cc:L117

Value

out The result mx.symbol

```
mx.symbol.broadcast_minus
```

broadcast_minus:Returns element-wise difference of the input arrays with broadcasting.

Description

'broadcast_minus' is an alias to the function 'broadcast_sub'.

Usage

```
mx.symbol.broadcast_minus(...)
```

Arguments

1hsNDArray-or-Symbol First input to the functionrhsNDArray-or-Symbol Second input to the functionnamestring, optional Name of the resulting symbol.

Details

Example::

```
x = [[1., 1., 1.], [1., 1., 1.]]

y = [[0.], [1.]]

broadcast_sub(x, y) = [[1., 1., 1.], [0., 0., 0.]]

broadcast_minus(x, y) = [[1., 1., 1.], [0., 0., 0.]]
```

Supported sparse operations:

broadcast_sub/minus(csr, dense(1D)) = dense broadcast_sub/minus(dense(1D), csr) = dense

Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L106

Value

out The result mx.symbol

```
mx.symbol.broadcast_mod
```

broadcast_mod:Returns element-wise modulo of the input arrays with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_mod(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

```
x = [[8., 8., 8.], [8., 8., 8.]]

y = [[2.], [3.]]

broadcast_mod(x, y) = [[0., 0., 0.], [2., 2., 2.]]
```

Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L222

Value

mx.symbol.broadcast_mul

broadcast_mul:Returns element-wise product of the input arrays with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_mul(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

Value

out The result mx.symbol

```
mx.symbol.broadcast_not_equal
```

 $broadcast_not_equal:Returns$ the result of element-wise **not equal to^{**} (!=) comparison operation with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_not_equal(...)
```

Arguments

lhs	NDArray-or-Symbol First input to the function
rhs	NDArray-or-Symbol Second input to the function
name	string, optional Name of the resulting symbol.

Details

```
x = [[1., 1., 1.], [1., 1., 1.]]

y = [[0.], [1.]]

broadcast_not_equal(x, y) = [[1., 1., 1.], [0., 0., 0.]]

Defined in src/operator/tensor/elemwise_binary_broadcast_op_logic.cc:L64
```

Value

out The result mx.symbol

```
mx.symbol.broadcast_plus
```

broadcast_plus:Returns element-wise sum of the input arrays with broadcasting.

Description

'broadcast_plus' is an alias to the function 'broadcast_add'.

Usage

```
mx.symbol.broadcast_plus(...)
```

Arguments

1hsNDArray-or-Symbol First input to the functionrhsNDArray-or-Symbol Second input to the functionnamestring, optional Name of the resulting symbol.

Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L58

Details

```
Example::
```

```
x = [[1, 1, 1, 1], [1, 1, 1, 1]]

y = [[0, 1, 1]]

broadcast_add(x, y) = [[1, 1, 1, 1], [2, 2, 2, 2]]

broadcast_plus(x, y) = [[1, 1, 1, 1], [2, 2, 2, 2]]

Supported sparse operations:

broadcast_add(csr, dense(1D)) = dense broadcast_add(dense(1D), csr) = dense
```

Value

out The result mx.symbol

```
mx.symbol.broadcast_power
```

broadcast_power:Returns result of first array elements raised to powers from second array, element-wise with broadcasting.

Description

Example::

Usage

```
mx.symbol.broadcast_power(...)
```

Arguments

1hs NDArray-or-Symbol First input to the function
 rhs NDArray-or-Symbol Second input to the function
 name string, optional Name of the resulting symbol.

Details

```
x = [[ 1., 1., 1.], [ 1., 1., 1.]]
y = [[ 0.], [ 1.]]
broadcast_power(x, y) = [[ 2., 2., 2.], [ 4., 4., 4.]]
```

 $Defined\ in\ src/operator/tensor/elemwise_binary_broadcast_op_extended.cc:L45$

Value

```
mx.symbol.broadcast_sub
```

broadcast_sub:Returns element-wise difference of the input arrays with broadcasting.

Description

'broadcast_minus' is an alias to the function 'broadcast_sub'.

Usage

```
mx.symbol.broadcast_sub(...)
```

Arguments

lhs	NDArray-or-Symbol First input to the function
rhs	NDArray-or-Symbol Second input to the function
name	string, optional Name of the resulting symbol.

Details

```
Example::
```

```
 \begin{aligned} x &= [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] \\ y &= [[\ 0.],\ [\ 1.]] \\ broadcast\_sub(x,y) &= [[\ 1.,\ 1.,\ 1.],\ [\ 0.,\ 0.,\ 0.]] \\ broadcast\_minus(x,y) &= [[\ 1.,\ 1.,\ 1.],\ [\ 0.,\ 0.,\ 0.]] \end{aligned}
```

Supported sparse operations:

broadcast_sub/minus(csr, dense(1D)) = dense broadcast_sub/minus(dense(1D), csr) = dense

Defined in src/operator/tensor/elemwise_binary_broadcast_op_basic.cc:L106

Value

```
mx.symbol.broadcast_to
```

broadcast_to:Broadcasts the input array to a new shape.

Description

Broadcasting is a mechanism that allows NDArrays to perform arithmetic operations with arrays of different shapes efficiently without creating multiple copies of arrays. Also see, 'Broadcasting https://docs.scipy.org/doc/numpy/user/basics.broadcasting.html '_ for more explanation.

Usage

```
mx.symbol.broadcast_to(...)
```

Arguments

data	NDArray-	or-Symbol	The input

shape Shape(tuple), optional, default=[] The shape of the desired array. We can set the

dim to zero if it's same as the original. E.g 'A = broadcast_to(B, shape=(10, 0,

0))' has the same meaning as 'A = broadcast_axis(B, axis=0, size=10)'.

name string, optional Name of the resulting symbol.

Details

Broadcasting is allowed on axes with size 1, such as from '(2,1,3,1)' to '(2,8,3,9)'. Elements will be duplicated on the broadcasted axes.

For example::

```
broadcast_to([[1,2,3]], shape=(2,3)) = [[1., 2., 3.], [1., 2., 3.]])
```

The dimension which you do not want to change can also be kept as '0' which means copy the original value. So with 'shape=(2,0)', we will obtain the same result as in the above example.

Defined in src/operator/tensor/broadcast_reduce_op_value.cc:L82

Value

mx.symbol.Cast 313

mx.symbol.Cast

Cast: Casts all elements of the input to a new type.

Description

```
.. note:: "Cast" is deprecated. Use "cast" instead.
```

Usage

```
mx.symbol.Cast(...)
```

Arguments

data NDArray-or-Symbol The input.

dtype 'bool', 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', required

Output data type.

name string, optional Name of the resulting symbol.

Details

Example::

```
cast([0.9, 1.3], dtype='int32') = [0, 1] cast([1e20, 11.1], dtype='float16') = [inf, 11.09375] cast([300, 11.1, 10.9, -1, -3], dtype='uint8') = [44, 11, 10, 255, 253]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L665

Value

out The result mx.symbol

mx.symbol.cast

cast: Casts all elements of the input to a new type.

Description

```
.. note:: "Cast" is deprecated. Use "cast" instead.
```

Usage

```
mx.symbol.cast(...)
```

Arguments

data NDArray-or-Symbol The input.

dtype 'bool', 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', required

Output data type.

name string, optional Name of the resulting symbol.

Details

```
Example::
```

```
cast([0.9, 1.3], dtype='int32') = [0, 1] cast([1e20, 11.1], dtype='float16') = [inf, 11.09375] cast([300, 11.1, 10.9, -1, -3], dtype='uint8') = [44, 11, 10, 255, 253]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L665

Value

out The result mx.symbol

```
mx.symbol.cast_storage
```

cast_storage: Casts tensor storage type to the new type.

Description

When an NDArray with default storage type is cast to csr or row_sparse storage, the result is compact, which means:

Usage

```
mx.symbol.cast_storage(...)
```

Arguments

data NDArray-or-Symbol The input.

stype 'csr', 'default', 'row_sparse', required Output storage type.

name string, optional Name of the resulting symbol.

Details

- for csr, zero values will not be retained - for row_sparse, row slices of all zeros will not be retained

The storage type of "cast_storage" output depends on stype parameter:

```
- cast_storage(csr, 'default') = default - cast_storage(row_sparse, 'default') = default - cast_storage(default, 'csr') = csr - cast_storage(default, 'row_sparse') = row_sparse - cast_storage(csr, 'csr') = csr - cast_storage(row_sparse, 'row_sparse') = row_sparse
```

Example::

```
dense = [[0., 1., 0.], [2., 0., 3.], [0., 0., 0.], [0., 0., 0.]]
```

```
# cast to row_sparse storage type rsp = cast_storage(dense, 'row_sparse') rsp.indices = [0, 1] rsp.values = [[ 0., 1., 0.], [ 2., 0., 3.]]
```

```
# cast to csr storage type csr = cast_storage(dense, 'csr') csr.indices = [1, 0, 2] csr.values = [1, 2, 3.] csr.indptr = [0, 1, 3, 3, 3]
```

Defined in src/operator/tensor/cast_storage.cc:L71

mx.symbol.cbrt 315

Value

out The result mx.symbol

mx.symbol.cbrt

cbrt:Returns element-wise cube-root value of the input.

Description

```
.. math:: cbrt(x) = \sqrt{3}x
```

Usage

```
mx.symbol.cbrt(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
cbrt([1, 8, -125]) = [1, 2, -5]
```

The storage type of "cbrt" output depends upon the input storage type:

- $cbrt(default) = default - cbrt(row_sparse) = row_sparse - cbrt(csr) = csr$

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L216

Value

out The result mx.symbol

mx.symbol.ceil

ceil:Returns element-wise ceiling of the input.

Description

The ceil of the scalar x is the smallest integer i, such that $i \ge x$.

Usage

```
mx.symbol.ceil(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
ceil([-2.1, -1.9, 1.5, 1.9, 2.1]) = [-2., -1., 2., 2., 3.]
```

The storage type of "ceil" output depends upon the input storage type:

- ceil(default) = default - ceil(row_sparse) = row_sparse - ceil(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L818

Value

out The result mx.symbol

```
mx.symbol.choose_element_0index
```

choose_element_0index:Picks elements from an input array according to the input indices along the given axis.

Description

Given an input array of shape "(d0, d1)" and indices of shape "(i0,)", the result will be an output array of shape "(i0,)" with::

Usage

```
mx.symbol.choose_element_0index(...)
```

Arguments

data	NDArray-or-Symbol The input array
index	NDArray-or-Symbol The index array

axis int or None, optional, default='-1' int or None. The axis to picking the elements.

Negative values means indexing from right to left. If is 'None', the elements in

the index w.r.t the flattened input will be picked.

keepdims boolean, optional, default=0 If true, the axis where we pick the elements is left

in the result as dimension with size one.

mode 'clip', 'wrap', optional, default='clip' Specify how out-of-bound indices behave.

Default is "clip". "clip" means clip to the range. So, if all indices mentioned are too large, they are replaced by the index that addresses the last element along an

axis. "wrap" means to wrap around.

name string, optional Name of the resulting symbol.

mx.symbol.clip 317

Details

```
output[i] = input[i, indices[i]]
```

By default, if any index mentioned is too large, it is replaced by the index that addresses the last element along an axis (the 'clip' mode).

This function supports n-dimensional input and (n-1)-dimensional indices arrays.

Examples::

$$x = [[1., 2.], [3., 4.], [5., 6.]]$$

// picks elements with specified indices along axis 0 pick(x, y=[0,1], 0) = [1., 4.]

// picks elements with specified indices along axis 1 pick(x, y=[0,1,0], 1) = [1., 4., 5.]

$$y = [[1.], [0.], [2.]]$$

// picks elements with specified indices along axis 1 using 'wrap' mode // to place indicies that would normally be out of bounds pick(x, y=[2,-1,-2], 1, mode='wrap') = [1., 4., 5.]

$$y = [[1.], [0.], [2.]]$$

// picks elements with specified indices along axis 1 and dims are maintained pick(x,y, 1, keep-dims=True) = [[2.], [3.], [6.]]

Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L155

Value

out The result mx.symbol

mx.symbol.clip

clip:Clips (limits) the values in an array. Given an interval, values outside the interval are clipped to the interval edges. Clipping "x" between 'a_min' and 'a_max' would be:: .. math:: clip(x, a_min, a_max) = \max(\min(x, a_max), a_min)) Example:: x = [0, 1, 2, 3, 4, 5, 6, 7, 8, 9] clip(x,1,8) = [1., 1., 2., 3., 4., 5., 6., 7., 8., 8.] The storage type of "clip" output depends on storage types of inputs and the a_min, a_max \ parameter values: - clip(default) = default - clip(row_sparse, a_min <= 0, a_max >= 0) = row_sparse - clip(csr, a_min <= 0, a_max >= 0) = csr - clip(row_sparse, a_min < 0, a_max < 0) = default - clip(csr, a_min < 0, a_max < 0) = csr - clip(csr, a_min > 0, a_max > 0) = csr - clip(csr, a_m

Description

Defined in src/operator/tensor/matrix_op.cc:L671

Usage

```
mx.symbol.clip(...)
```

318 mx.symbol.Concat

Arguments

data	NDArray-or-Symbol Input array.
a.min	float, required Minimum value
a.max	float, required Maximum value
name	string, optional Name of the resulting symbol.

Value

out The result mx.symbol

 ${\tt mx.symbol.Concat}$

Perform an feature concat on channel dim (dim 1) over all the inputs.

Description

Perform an feature concat on channel dim (dim 1) over all the inputs.

Usage

```
mx.symbol.Concat(data, num.args, dim = NULL, name = NULL)
```

Arguments

data list, required List of tensors to concatenate

num.args int, required Number of inputs to be concated.

dim int, optional, default='1' the dimension to be concated.

name string, optional Name of the resulting symbol.

Value

mx.symbol.concat 319

mΥ	SVMho	l.concat

Perform an feature concat on channel dim (dim 1) over all the inputs.

Description

Perform an feature concat on channel dim (dim 1) over all the inputs.

Usage

```
mx.symbol.concat(data, num.args, dim = NULL, name = NULL)
```

Arguments

data list, required List of tensors to concatenate num.args int, required Number of inputs to be concated.

dim int, optional, default='1' the dimension to be concated.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

```
mx.symbol.Convolution Convolution: Compute *N*-D convolution on *(N+2)*-D input.
```

Description

In the 2-D convolution, given input data with shape *(batch_size, channel, height, width)*, the output is computed by

Usage

```
mx.symbol.Convolution(...)
```

Arguments

data	NDArray-or-Symbol Input data to the ConvolutionOp.
weight	NDArray-or-Symbol Weight matrix.
bias	NDArray-or-Symbol Bias parameter.
kernel	Shape(tuple), required Convolution kernel size: (w,), (h, w) or (d, h, w)
stride	Shape(tuple), optional, default=[] Convolution stride: (w,), (h, w) or (d, h, w). Defaults to 1 for each dimension.
dilate	Shape(tuple), optional, default=[] Convolution dilate: (w,), (h, w) or (d, h, w). Defaults to 1 for each dimension.

pad Shape(tuple), optional, default=[] Zero pad for convolution: (w,), (h, w) or (d,

h, w). Defaults to no padding.

num.filter int (non-negative), required Convolution filter(channel) number num.group int (non-negative), optional, default=1 Number of group partitions.

workspace long (non-negative), optional, default=1024 Maximum temporary workspace al-

lowed (MB) in convolution. This parameter has two usages. When CUDNN is not used, it determines the effective batch size of the convolution kernel. When CUDNN is used, it controls the maximum temporary storage used for tuning the

best CUDNN kernel when 'limited_workspace' strategy is used.

no.bias boolean, optional, default=0 Whether to disable bias parameter.

cudnn.tune None, 'fastest', 'limited_workspace', 'off',optional, default='None' Whether to

pick convolution algo by running performance test.

cudnn.off boolean, optional, default=0 Turn off cudnn for this layer.

layout None, 'NCDHW', 'NCHW', 'NDHWC', 'NHWC', optional, default='None'

Set layout for input, output and weight. Empty for default layout: NCW for 1d, NCHW for 2d and NCDHW for 3d.NHWC and NDHWC are only supported on

GPU.

name string, optional Name of the resulting symbol.

Details

.. math::

 $out[n,i,:,:] = bias[i] + \sum_{j=0}^{n} data[n,j,:,:] \operatorname{star weight}[i,j,:,:]$

where :math: '\star' is the 2-D cross-correlation operator.

For general 2-D convolution, the shapes are

- **data**: *(batch_size, channel, height, width)* - **weight**: *(num_filter, channel, kernel[0], kernel[1])* - **bias**: *(num_filter,)* - **out**: *(batch_size, num_filter, out_height, out_width)*.

Define::

f(x,k,p,s,d) = floor((x+2*p-d*(k-1)-1)/s)+1

then we have::

out_height=f(height, kernel[0], pad[0], stride[0], dilate[0]) out_width=f(width, kernel[1], pad[1], stride[1], dilate[1])

If "no_bias" is set to be true, then the "bias" term is ignored.

The default data "layout" is *NCHW*, namely *(batch_size, channel, height, width)*. We can choose other layouts such as *NWC*.

If "num_group" is larger than 1, denoted by *g*, then split the input "data" evenly into *g* parts along the channel axis, and also evenly split "weight" along the first dimension. Next compute the convolution on the *i*-th part of the data with the *i*-th weight part. The output is obtained by concatenating all the *g* results.

1-D convolution does not have *height* dimension but only *width* in space.

```
- **data**: *(batch_size, channel, width)* - **weight**: *(num_filter, channel, kernel[0])* - **bias**: *(num_filter,)* - **out**: *(batch_size, num_filter, out_width)*.
```

- 3-D convolution adds an additional *depth* dimension besides *height* and *width*. The shapes are
- **data**: *(batch_size, channel, depth, height, width)* **weight**: *(num_filter, channel, kernel[0], kernel[1], kernel[2])* **bias**: *(num_filter,)* **out**: *(batch_size, num_filter, out_depth, out_height, out_width)*.

Both "weight" and "bias" are learnable parameters.

There are other options to tune the performance.

- **cudnn_tune**: enable this option leads to higher startup time but may give faster speed. Options are
- **off**: no tuning **limited_workspace**:run test and pick the fastest algorithm that doesn't exceed workspace limit. **fastest**: pick the fastest algorithm and ignore workspace limit. **None** (default): the behavior is determined by environment variable "MXNET_CUDNN_AUTOTUNE_DEFAULT". 0 for off, 1 for limited workspace (default), 2 for fastest.
- **workspace**: A large number leads to more (GPU) memory usage but may improve the performance.

Defined in src/operator/nn/convolution.cc:L473

Value

out The result mx.symbol

```
mx.symbol.Convolution_v1
```

Convolution_v1:This operator is DEPRECATED. Apply convolution to input then add a bias.

Description

Convolution_v1:This operator is DEPRECATED. Apply convolution to input then add a bias.

Usage

```
mx.symbol.Convolution_v1(...)
```

Arguments

data	NDArray-or-Symbol Input data to the ConvolutionV1Op.
weight	NDArray-or-Symbol Weight matrix.
bias	NDArray-or-Symbol Bias parameter.
kernel	Shape(tuple), required convolution kernel size: (h, w) or (d, h, w)
stride	Shape(tuple), optional, default=[] convolution stride: (h, w) or (d, h, w)
dilate	Shape(tuple), optional, default=[] convolution dilate: (h, w) or (d, h, w)
pad	Shape(tuple), optional, default=[] pad for convolution: (h, w) or (d, h, w)

num. filter int (non-negative), required convolution filter(channel) number

num.group int (non-negative), optional, default=1 Number of group partitions. Equivalent

to slicing input into num_group partitions, apply convolution on each, then con-

catenate the results

workspace long (non-negative), optional, default=1024 Maximum temporary workspace al-

lowed for convolution (MB). This parameter determines the effective batch size of the convolution kernel, which may be smaller than the given batch size. Also, the workspace will be automatically enlarged to make sure that we can run the

kernel with batch_size=1

no.bias boolean, optional, default=0 Whether to disable bias parameter.

cudnn.tune None, 'fastest', 'limited_workspace', 'off',optional, default='None' Whether to

pick convolution algo by running performance test. Leads to higher startup time but may give faster speed. Options are: 'off': no tuning 'limited_workspace': run test and pick the fastest algorithm that doesn't exceed workspace limit. 'fastest': pick the fastest algorithm and ignore workspace limit. If set to None

(default), behavior is determined by environment variable MXNET CUDNN AUTOTUNE DEFAULT:

0 for off, 1 for limited workspace (default), 2 for fastest.

cudnn.off boolean, optional, default=0 Turn off cudnn for this layer.

layout None, 'NCDHW', 'NCHW', 'NDHWC', 'NHWC', optional, default='None' Set

layout for input, output and weight. Empty for default layout: NCHW for 2d

and NCDHW for 3d.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.Correlation Correlation: Applies correlation to inputs.

Description

The correlation layer performs multiplicative patch comparisons between two feature maps.

Usage

```
mx.symbol.Correlation(...)
```

Arguments

data1 NDArray-or-Symbol Input data1 to the correlation.

data2 NDArray-or-Symbol Input data2 to the correlation.

kernel.size int (non-negative), optional, default=1 kernel size for Correlation must be an

odd number

max.displacement

int (non-negative), optional, default=1 Max displacement of Correlation

stride1 int (non-negative), optional, default=1 stride1 quantize data1 globally

stride2 int (non-negative), optional, default=1 stride2 quantize data2 within the neigh-

borhood centered around data1

pad.size int (non-negative), optional, default=0 pad for Correlation

is.multiply boolean, optional, default=1 operation type is either multiplication or subduction

name string, optional Name of the resulting symbol.

Details

Given two multi-channel feature maps :math:'f_1, f_2', with :math:'w', :math:'h', and :math:'c' being their width, height, and number of channels, the correlation layer lets the network compare each patch from :math:'f_1' with each patch from :math:'f_2'.

For now we consider only a single comparison of two patches. The 'correlation' of two patches centered at :math: 'x_1' in the first map and :math: 'x_2' in the second map is then defined as:

.. math::

$$c(x_1, x_2) = \sum_{e} (-k,k) < f_1(x_1 + e), f_2(x_2 + e) > c$$

for a square patch of size :math: 'K:=2k+1'.

Note that the equation above is identical to one step of a convolution in neural networks, but instead of convolving data with a filter, it convolves data with other data. For this reason, it has no training weights.

Computing :math: $c(x_1, x_2)$ involves :math: k^2 multiplications. Comparing all patch combinations involves :math: k^2 such computations.

Given a maximum displacement :math:'d', for each location :math:' x_1 ' it computes correlations :math:' $c(x_1, x_2)$ ' only in a neighborhood of size :math:'D:=2d+1', by limiting the range of :math:' x_2 '. We use strides :math:' x_1 , x_2 ', to quantize :math:' x_1 ' globally and to quantize :math:' x_2 ' within the neighborhood centered around :math:' x_1 '.

The final output is defined by the following expression:

```
.. math:: out[n, q, i, j] = c(x_i, j, x_q)
```

where :math:'i' and :math:'j' enumerate spatial locations in :math:'f_1', and :math:'q' denotes the :math:'q^th' neighborhood of :math:'x_i,j'.

Defined in src/operator/correlation.cc:L198

Value

324 mx.symbol.cosh

mx.symbol.cos

cos: Computes the element-wise cosine of the input array.

Description

The input should be in radians (:math:'2\pi' rad equals 360 degrees).

Usage

```
mx.symbol.cos(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
.. math:: cos([0, \pi/4, \pi/2]) = [1, 0.707, 0]
```

The storage type of "cos" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L90

Value

out The result mx.symbol

mx.symbol.cosh

cosh:Returns the hyperbolic cosine of the input array, computed element-wise.

Description

```
.. math:: cosh(x) = 0.5 \times (exp(x) + exp(-x))
```

Usage

```
mx.symbol.cosh(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

mx.symbol.Crop 325

Details

The storage type of "cosh" output is always dense Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L351

Value

out The result mx.symbol

mx.symbol.Crop Crop:

Description

.. note:: 'Crop' is deprecated. Use 'slice' instead.

Usage

```
mx.symbol.Crop(...)
```

Arguments

data	Symbol or Symbol[] Tensor or List of Tensors, the second input will be used as crop_like shape reference
num.args	int, required Number of inputs for crop, if equals one, then we will use the h_wfor crop height and width, else if equals two, then we will use the heightand width of the second input symbol, we name crop_like here
offset	Shape(tuple), optional, default=[0,0] crop offset coordinate: (y, x)
h.w	Shape(tuple), optional, default=[0,0] crop height and width: (h, w)
center.crop	boolean, optional, default=0 If set to true, then it will use be the center_crop,or it will crop using the shape of crop_like
name	string, optional Name of the resulting symbol.

Details

Crop the 2nd and 3rd dim of input data, with the corresponding size of h_w or with width and height of the second input symbol, i.e., with one input, we need h_w to specify the crop height and width, otherwise the second input symbol's size will be used

Defined in src/operator/crop.cc:L50

Value

326 mx.symbol.crop

mx.symbol.crop

crop:Slices a region of the array. .. note:: "crop" is deprecated. Use "slice" instead. This function returns a sliced array between the indices given by 'begin' and 'end' with the corresponding 'step'. For an input array of "shape= $(d_0, d_1, ..., d_{n-1})$ ", slice operation with "begin= $(b_0, b_1...b_m-1)$ ", "end= $(e_0, e_1, ..., e_m-1)$ ", and " $step=(s_0, s_1, ..., s_m-1)$ ", where $m \le n$, results in an array with the shape "($|e\ 0-b\ 0|/|s\ 0|$, ..., $|e\ m-1-b\ m-1|/|s\ m-1|$, $d\ m$, ..., $d\ n-1$ 1)". The resulting array's *k*-th dimension contains elements from the *k*-th dimension of the input array starting from index "b k" (inclusive) with step "s_k" until reaching "e_k" (exclusive). If the *k*-th elements are 'None' in the sequence of 'begin', 'end', and 'step', the following rule will be used to set default values. If 's_k' is 'None', set $s_k=1$. If $s_k>0$, set $b_k=0$, $e_k=d_k$; else, set $b_k=d_k-1$, 'e_k=-1'. The storage type of "slice" output depends on storage types of inputs - slice(csr) = csr - otherwise, "slice" generates output with default storage .. note:: When input data storage type is csr, it only supports step=(), or step=(None,), or step=(1,) to generate a csr output. For other step parameter values, it falls back to slicing a dense tensor. Example:: x = [[1., 2., 3., 4.], [5., 6., 7., 8.], [9., 10., 11.]12.]] slice(x, begin=(0,1), end=(2,4)) = [[2., 3., 4.], [6., 7., 8.]]slice(x, begin=(None, 0), end=(None, 3), step=(-1, 2)) = [[9., 11.],[5., 7.], [1., 3.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L477

Usage

```
mx.symbol.crop(...)
```

Arguments

data	NDArray-or-Symbol Source input
begin	Shape(tuple), required starting indices for the slice operation, supports negative indices.
end	Shape(tuple), required ending indices for the slice operation, supports negative indices.
step	Shape(tuple), optional, default=[] step for the slice operation, supports negative values.
name	string, optional Name of the resulting symbol.

Value

mx.symbol.CTCLoss 327

mx.symbol.CTCLoss

CTCLoss: Connectionist Temporal Classification Loss.

Description

.. note:: The existing alias "contrib_CTCLoss" is deprecated.

Usage

```
mx.symbol.CTCLoss(...)
```

Arguments

data NDArray-or-Symbol Input ndarray

label NDArray-or-Symbol Ground-truth labels for the loss.

data.lengths NDArray-or-Symbol Lengths of data for each of the samples. Only required

when use_data_lengths is true.

label.lengths NDArray-or-Symbol Lengths of labels for each of the samples. Only required

when use_label_lengths is true.

use.data.lengths

 $boolean, optional, default = 0 \ Whether the \ data \ lengths \ are \ decided \ by \ `data_lengths`.$

If false, the lengths are equal to the max sequence length.

use.label.lengths

boolean, optional, default=0 Whether the label lengths are decided by 'label_lengths', or derived from 'padding_mask'. If false, the lengths are derived from the first occurrence of the value of 'padding_mask'. The value of 'padding_mask' is "0" when first CTC label is reserved for blank, and "-1" when last label is reserved

for blank. See 'blank label'.

blank.label 'first', 'last', optional, default='first' Set the label that is reserved for blank la-

bel.If "first", 0-th label is reserved, and label values for tokens in the vocabulary are between "1" and "alphabet_size-1", and the padding mask is "-1". If "last", last label value "alphabet_size-1" is reserved for blank label instead, and label values for tokens in the vocabulary are between "0" and "alphabet_size-2", and

the padding mask is "0".

name string, optional Name of the resulting symbol.

Details

The shapes of the inputs and outputs:

```
- **data**: '(sequence_length, batch_size, alphabet_size)' - **label**: '(batch_size, label_sequence_length)'
- **out**: '(batch_size)'
```

The 'data' tensor consists of sequences of activation vectors (without applying softmax), with ith channel in the last dimension corresponding to i-th label for i between 0 and alphabet_size-1 (i.e always 0-indexed). Alphabet size should include one additional value reserved for blank label.

328 mx.symbol.ctc_loss

When 'blank_label' is ""first"", the "0"-th channel is be reserved for activation of blank label, or otherwise if it is "last", "(alphabet_size-1)"-th channel should be reserved for blank label.

"label" is an index matrix of integers. When 'blank_label' is ""first"", the value 0 is then reserved for blank label, and should not be passed in this matrix. Otherwise, when 'blank_label' is ""last"", the value '(alphabet_size-1)' is reserved for blank label.

If a sequence of labels is shorter than *label_sequence_length*, use the special padding value at the end of the sequence to conform it to the correct length. The padding value is '0' when 'blank_label' is ""first"", and '-1' otherwise.

For example, suppose the vocabulary is '[a, b, c]', and in one batch we have three sequences 'ba', 'cbb', and 'abac'. When 'blank_label' is ""first"", we can index the labels as 'a': 1, 'b': 2, 'c': 3', and we reserve the 0-th channel for blank label in data tensor. The resulting 'label' tensor should be padded to be::

$$[[2, 1, 0, 0], [3, 2, 2, 0], [1, 2, 1, 3]]$$

When 'blank_label' is ""last"", we can index the labels as "a': 0, 'b': 1, 'c': 2', and we reserve the channel index 3 for blank label in data tensor. The resulting 'label' tensor should be padded to be::

$$[[1, 0, -1, -1], [2, 1, 1, -1], [0, 1, 0, 2]]$$

"out" is a list of CTC loss values, one per example in the batch.

See *Connectionist Temporal Classification: Labelling Unsegmented Sequence Data with Recurrent Neural Networks*, A. Graves *et al*. for more information on the definition and the algorithm.

Defined in src/operator/nn/ctc_loss.cc:L100

Value

out The result mx.symbol

mx.symbol.ctc_loss

ctc loss:Connectionist Temporal Classification Loss.

Description

.. note:: The existing alias "contrib_CTCLoss" is deprecated.

Usage

```
mx.symbol.ctc_loss(...)
```

Arguments

data NDArray-or-Symbol Input ndarray

label NDArray-or-Symbol Ground-truth labels for the loss.

data.lengths NDArray-or-Symbol Lengths of data for each of the samples. Only required

when use_data_lengths is true.

label.lengths NDArray-or-Symbol Lengths of labels for each of the samples. Only required

when use_label_lengths is true.

mx.symbol.ctc_loss 329

use.data.lengths

boolean, optional, default=0 Whether the data lengths are decided by 'data_lengths'. If false, the lengths are equal to the max sequence length.

use.label.lengths

boolean, optional, default=0 Whether the label lengths are decided by 'label_lengths', or derived from 'padding_mask'. If false, the lengths are derived from the first occurrence of the value of 'padding_mask'. The value of 'padding_mask' is "0" when first CTC label is reserved for blank, and "-1" when last label is reserved for blank. See 'blank label'.

blank.label

'first', 'last',optional, default='first' Set the label that is reserved for blank label.If "first", 0-th label is reserved, and label values for tokens in the vocabulary are between "1" and "alphabet_size-1", and the padding mask is "-1". If "last", last label value "alphabet_size-1" is reserved for blank label instead, and label values for tokens in the vocabulary are between "0" and "alphabet_size-2", and the padding mask is "0".

name

string, optional Name of the resulting symbol.

Details

The shapes of the inputs and outputs:

- **data**: '(sequence_length, batch_size, alphabet_size)' - **label**: '(batch_size, label_sequence_length)' - **out**: '(batch_size)'

The 'data' tensor consists of sequences of activation vectors (without applying softmax), with ith channel in the last dimension corresponding to i-th label for i between 0 and alphabet_size-1 (i.e always 0-indexed). Alphabet size should include one additional value reserved for blank label. When 'blank_label' is ""first"", the "0"-th channel is be reserved for activation of blank label, or otherwise if it is "last", "(alphabet_size-1)"-th channel should be reserved for blank label.

"label" is an index matrix of integers. When 'blank_label' is ""first"", the value 0 is then reserved for blank label, and should not be passed in this matrix. Otherwise, when 'blank_label' is ""last"", the value '(alphabet_size-1)' is reserved for blank label.

If a sequence of labels is shorter than *label_sequence_length*, use the special padding value at the end of the sequence to conform it to the correct length. The padding value is '0' when 'blank_label' is ""first"", and '-1' otherwise.

For example, suppose the vocabulary is '[a, b, c]', and in one batch we have three sequences 'ba', 'cbb', and 'abac'. When 'blank_label' is ""first"", we can index the labels as 'a': 1, 'b': 2, 'c': 3', and we reserve the 0-th channel for blank label in data tensor. The resulting 'label' tensor should be padded to be::

[[2, 1, 0, 0], [3, 2, 2, 0], [1, 2, 1, 3]]

When 'blank_label' is ""last"", we can index the labels as 'a': 0, 'b': 1, 'c': 2', and we reserve the channel index 3 for blank label in data tensor. The resulting 'label' tensor should be padded to be::

[[1, 0, -1, -1], [2, 1, 1, -1], [0, 1, 0, 2]]

"out" is a list of CTC loss values, one per example in the batch.

See *Connectionist Temporal Classification: Labelling Unsegmented Sequence Data with Recurrent Neural Networks*, A. Graves *et al*. for more information on the definition and the algorithm.

Defined in src/operator/nn/ctc_loss.cc:L100

330 mx.symbol.Custom

Value

out The result mx.symbol

mx.symbol.cumsum

cumsum:Return the cumulative sum of the elements along a given axis.

Description

Defined in src/operator/numpy/np_cumsum.cc:L70

Usage

```
mx.symbol.cumsum(...)
```

Arguments

a	NDArray-o	r-Symbol I	nput ndarray
---	-----------	------------	--------------

axis int or None, optional, default='None' Axis along which the cumulative sum is

computed. The default (None) is to compute the cumsum over the flattened

array.

dtype None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', optional, default='None'

Type of the returned array and of the accumulator in which the elements are summed. If dtype is not specified, it defaults to the dtype of a, unless a has an integer dtype with a precision less than that of the default platform integer. In

that case, the default platform integer is used.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.Custom Custom: Apply a custom operator implemented in a frontend language

(like Python).

Description

Custom operators should override required methods like 'forward' and 'backward'. The custom operator must be registered before it can be used. Please check the tutorial here: https://mxnet.incubator.apache.org/api/faq/new_

Usage

```
mx.symbol.Custom(...)
```

Arguments

data NDArray-or-Symbol[] Input data for the custom operator.

op. type string Name of the custom operator. This is the name that is passed to 'mx.operator.register'

to register the operator.

name string, optional Name of the resulting symbol.

Details

Defined in src/operator/custom/custom.cc:L546

Value

out The result mx.symbol

mx.symbol.Deconvolution

Deconvolution: Computes 1D or 2D transposed convolution (aka fractionally strided convolution) of the input tensor. This operation can be seen as the gradient of Convolution operation with respect to its input. Convolution usually reduces the size of the input. Transposed convolution works the other way, going from a smaller input to a larger output while preserving the connectivity pattern.

Description

Deconvolution:Computes 1D or 2D transposed convolution (aka fractionally strided convolution) of the input tensor. This operation can be seen as the gradient of Convolution operation with respect to its input. Convolution usually reduces the size of the input. Transposed convolution works the other way, going from a smaller input to a larger output while preserving the connectivity pattern.

Usage

```
mx.symbol.Deconvolution(...)
```

Arguments

data	NDArray-or-Symbol Input tensor to the deconvolution operation.
weight	NDArray-or-Symbol Weights representing the kernel.
bias	NDArray-or-Symbol Bias added to the result after the deconvolution operation.
kernel	Shape(tuple), required Deconvolution kernel size: (w,), (h, w) or (d, h, w). This is same as the kernel size used for the corresponding convolution
stride	Shape(tuple), optional, default=[] The stride used for the corresponding convolution: (w,), (h, w) or (d, h, w). Defaults to 1 for each dimension.
dilate	Shape(tuple), optional, default=[] Dilation factor for each dimension of the input: (w,), (h, w) or (d, h, w). Defaults to 1 for each dimension.

332 mx.symbol.degrees

pad	Shape(tuple), optional, default=[] The amount of implicit zero padding added during convolution for each dimension of the input: (w,), (h, w) or (d, h, w). "(kernel-1)/2" is usually a good choice. If 'target_shape' is set, 'pad' will be ignored and a padding that will generate the target shape will be used. Defaults to no padding.
adj	Shape(tuple), optional, default=[] Adjustment for output shape: (w,), (h, w) or (d, h, w). If 'target_shape' is set, 'adj' will be ignored and computed accordingly.
target.shape	Shape(tuple), optional, default=[] Shape of the output tensor: $(w,)$, (h, w) or (d, h, w) .
num.filter	int (non-negative), required Number of output filters.
num.group	int (non-negative), optional, default=1 Number of groups partition.
workspace	long (non-negative), optional, default=512 Maximum temporary workspace allowed (MB) in deconvolution. This parameter has two usages. When CUDNN is not used, it determines the effective batch size of the deconvolution kernel. When CUDNN is used, it controls the maximum temporary storage used for tuning the best CUDNN kernel when 'limited_workspace' strategy is used.
no.bias	boolean, optional, default=1 Whether to disable bias parameter.
cudnn.tune	None, 'fastest', 'limited_workspace', 'off',optional, default='None' Whether to pick convolution algorithm by running performance test.
cudnn.off	boolean, optional, default=0 Turn off cudnn for this layer.
layout	None, 'NCDHW', 'NCHW', 'NCW', 'NDHWC', 'NHWC', optional, default='None' Set layout for input, output and weight. Empty for default layout, NCW for 1d, NCHW for 2d and NCDHW for 3d.NHWC and NDHWC are only supported on GPU.

Value

name

out The result mx.symbol

 ${\tt mx.symbol.degrees}: Converts\ each\ element\ of\ the\ input\ array\ from\ radians\ to\ degrees.$

string, optional Name of the resulting symbol.

Description

```
.. math:: degrees([0, \pi/2, \pi/2, 2\pi/2, 2\pi/2]) = [0, 90, 180, 270, 360]
```

Usage

```
mx.symbol.degrees(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "degrees" output depends upon the input storage type:
- degrees(default) = default - degrees(row_sparse) = row_sparse - degrees(csr) = csr
Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L274

Value

out The result mx.symbol

mx.symbol.depth_to_space

depth_to_space:Rearranges(permutes) data from depth into blocks of spatial data. Similar to ONNX DepthToSpace operator: https://github.com/onnx/onnx/blob/master/docs/Operators.md#DepthToSpace. The output is a new tensor where the values from depth dimension are moved in spatial blocks to height and width dimension. The reverse of this operation is "space_to_depth". .. math:: \begingather* x \prime = $reshape(x, [N, block_size, block_size, C / (block_size ^ 2), H *$ $block \leq v + block \leq v + bloc$ [0, 3, 4, 1, 5, 2]\\\\\\y = reshape(x\\\prime\\\prime, [N, C/(block_size^\) 2), $H * block _size$, $W * block _size$]) \endgather* where :math: 'x' is an input tensor with default layout as :math: '[N, C, H, W]': [batch, channels, height, width] and :math: 'y' is the output tensor of layout :math: '[N, C / ($block \le ^ 2$), $H * block \le W * block \le '$ Example:: x = [[[0, 1, 2], [3, 4, 5]], [[6, 7, 8], [9, 10, 11]], [[12, 13, 1], [13, 1], [14, 15]]14], [15, 16, 17]], [[18, 19, 20], [21, 22, 23]]]] depth_to_space(x, 2) = [[[0, 6, 1, 7, 2, 8], [12, 18, 13, 19, 14, 20], [3, 9, 4, 10, 5, 11], [15, 15]]21, 16, 22, 17, 23]]]]

Description

Defined in src/operator/tensor/matrix_op.cc:L965

Usage

```
mx.symbol.depth_to_space(...)
```

Arguments

data NDArray-or-Symbol Input ndarray

block.size int, required Blocks of [block_size. block_size] are moved

name string, optional Name of the resulting symbol.

334 mx.symbol.diag

Value

out The result mx.symbol

mx.symbol.diag

diag:Extracts a diagonal or constructs a diagonal array.

Description

"diag"'s behavior depends on the input array dimensions:

Usage

```
mx.symbol.diag(...)
```

Arguments

data	NDArray-or-Symbol Input ndarray
k	int, optional, default='0' Diagonal in question. The default is 0. Use k>0 for diagonals above the main diagonal, and k<0 for diagonals below the main diagonal. If input has shape (S0 S1) k must be between -S0 and S1
axis1	int, optional, default='0' The first axis of the sub-arrays of interest. Ignored when the input is a 1-D array.
axis2	int, optional, default='1' The second axis of the sub-arrays of interest. Ignored when the input is a 1-D array.
name	string, optional Name of the resulting symbol.

Details

- 1-D arrays: constructs a 2-D array with the input as its diagonal, all other elements are zero. - N-D arrays: extracts the diagonals of the sub-arrays with axes specified by "axis1" and "axis2". The output shape would be decided by removing the axes numbered "axis1" and "axis2" from the input shape and appending to the result a new axis with the size of the diagonals in question.

For example, when the input shape is '(2, 3, 4, 5)', "axis1" and "axis2" are 0 and 2 respectively and "k" is 0, the resulting shape would be '(3, 5, 2)'.

Examples::

```
x = [[1, 2, 3], [4, 5, 6]]
diag(x) = [1, 5]
diag(x, k=1) = [2, 6]
diag(x, k=-1) = [4]
x = [1, 2, 3]
diag(x) = [[1, 0, 0], [0, 2, 0], [0, 0, 3]]
diag(x, k=1) = [[0, 1, 0], [0, 0, 2], [0, 0, 0]]
```

mx.symbol.dot 335

```
\begin{aligned} & \text{diag}(x, k=-1) = [[0, 0, 0], [1, 0, 0], [0, 2, 0]] \\ & x = [[[1, 2], [3, 4]], \\ & [[5, 6], [7, 8]]] \\ & \text{diag}(x) = [[1, 7], [2, 8]] \\ & \text{diag}(x, k=1) = [[3], [4]] \\ & \text{diag}(x, \text{axis1}=-2, \text{axis2}=-1) = [[1, 4], [5, 8]] \\ & \text{Defined in src/operator/tensor/diag\_op.cc:L87} \end{aligned}
```

Value

out The result mx.symbol

mx.symbol.dot

dot:Dot product of two arrays.

Description

"dot"'s behavior depends on the input array dimensions:

Usage

```
mx.symbol.dot(...)
```

Arguments

1hs NDArray-or-Symbol The first inputrhs NDArray-or-Symbol The second input

transpose.a boolean, optional, default=0 If true then transpose the first input before dot. transpose.b boolean, optional, default=0 If true then transpose the second input before dot.

forward.stype None, 'csr', 'default', 'row_sparse',optional, default='None' The desired stor-

age type of the forward output given by user, if the combination of input storage types and this hint does not matchany implemented ones, the dot operator will perform fallback operation and still produce an output of the desired storage type.

name string, optional Name of the resulting symbol.

Details

- 1-D arrays: inner product of vectors - 2-D arrays: matrix multiplication - N-D arrays: a sum product over the last axis of the first input and the first axis of the second input

For example, given 3-D "x" with shape '(n,m,k)' and "y" with shape '(k,r,s)', the result array will have shape '(n,m,r,s)'. It is computed by::

```
dot(x,y)[i,j,a,b] = sum(x[i,j,:]*y[:,a,b])
```

Example::

336 mx.symbol.Dropout

```
x = reshape([0,1,2,3,4,5,6,7], shape=(2,2,2)) y = reshape([7,6,5,4,3,2,1,0], shape=(2,2,2)) dot(x,y)[0,0,1,1]
= 0 \text{ sum}(x[0,0,:]*y[:,1,1]) = 0
```

The storage type of "dot" output depends on storage types of inputs, transpose option and forward stype option for output storage type. Implemented sparse operations include:

- dot(default, default, transpose_a=True/False, transpose_b=True/False) = default - dot(csr, default, transpose_a=True) = default - dot(csr, default, transpose_a=True) = row_sparse - dot(csr, default) = default - dot(csr, row_sparse) = default - dot(default, csr) = csr (CPU only) - dot(default, csr, forward_stype='default') = default - dot(default, csr, transpose_b=True, forward_stype='default') = default

If the combination of input storage types and forward_stype does not match any of the above patterns, "dot" will fallback and generate output with default storage.

.. Note::

If the storage type of the lhs is "csr", the storage type of gradient w.r.t rhs will be "row sparse". Only a subset of optimizers support sparse gradients, including SGD, AdaGrad and Adam. Note that by default lazy updates is turned on, which may perform differently from standard updates. For more details, please check the Optimization API at: https://mxnet.incubator.apache.org/api/python/optimization/optimization.html Defined in src/operator/tensor/dot.cc:L77

Value

out The result mx.symbol

Dropout:Applies dropout operation to input array.

mx.symbol.Dropout

Description

- During training, each element of the input is set to zero with probability p. The whole array is rescaled by :math: '1/(1-p)' to keep the expected sum of the input unchanged.

Usage

```
mx.symbol.Dropout(...)
```

Arguments

data	NDArray-or-Symbol Input array to which dropout will be applied.
p	float, optional, default=0.5 Fraction of the input that gets dropped out during training time.
mode	'always', 'training',optional, default='training' Whether to only turn on dropout during training or to also turn on for inference.
axes	Shape(tuple), optional, default=[] Axes for variational dropout kernel.
cudnn.off	boolean or None, optional, default=0 Whether to turn off cudnn in dropout operator. This option is ignored if axes is specified.
name	string, optional Name of the resulting symbol.

Details

- During testing, this operator does not change the input if mode is 'training'. If mode is 'always', the same computation as during training will be applied.

Example::

random.seed(998) input_array = array([[3., 0.5, -0.5, 2., 7.], [2., -0.4, 7., 3., 0.2]]) a = symbol.Variable('a') dropout = symbol.Dropout(a, p = 0.2) executor = dropout.simple_bind(a = input_array.shape)

If training executor.forward(is_train = True, a = input_array) executor.outputs [[3.75 0.625 -0. 2.5 8.75] [2.5 -0.5 8.75 3.75 0.]]

If testing executor.forward(is_train = False, a = input_array) executor.outputs [[3. 0.5 -0.5 2. 7.] [2. -0.4 7. 3. 0.2]]

Defined in src/operator/nn/dropout.cc:L96

Value

out The result mx.symbol

mx.symbol.ElementWiseSum

ElementWiseSum:Adds all input arguments element-wise.

Description

```
.. math:: add\_n(a_1, a_2, ..., a_n) = a_1 + a_2 + ... + a_n
```

Usage

```
mx.symbol.ElementWiseSum(...)
```

Arguments

args NDArray-or-Symbol[] Positional input arguments name string, optional Name of the resulting symbol.

Details

"add_n" is potentially more efficient than calling "add" by 'n' times.

The storage type of "add_n" output depends on storage types of inputs

- add_n(row_sparse, row_sparse, ..) = row_sparse - add_n(default, csr, default) = default - add_n(any input combinations longer than 4 (>4) with at least one default type) = default - otherwise, "add_n" falls all inputs back to default storage and generates default storage

Defined in src/operator/tensor/elemwise_sum.cc:L155

Value

```
mx.symbol.elemwise_add
```

elemwise_add:Adds arguments element-wise.

Description

The storage type of "elemwise_add" output depends on storage types of inputs

Usage

```
mx.symbol.elemwise_add(...)
```

Arguments

1hs NDArray-or-Symbol first inputrhs NDArray-or-Symbol second input

name string, optional Name of the resulting symbol.

Details

- elemwise_add(row_sparse, row_sparse) = row_sparse - elemwise_add(csr, csr) = csr - elemwise_add(default, csr) = default - elemwise_add(csr, default) = default - elemwise_add(default, rsp) = default - elemwise_add(rsp, default) = default - otherwise, "elemwise_add" generates output with default storage

Value

out The result mx.symbol

```
mx.symbol.elemwise_div
```

 $elemwise_div: Divides\ arguments\ element-wise.$

Description

The storage type of "elemwise_div" output is always dense

Usage

```
mx.symbol.elemwise_div(...)
```

Arguments

1hs NDArray-or-Symbol first inputrhs NDArray-or-Symbol second input

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

```
mx.symbol.elemwise_mul
```

elemwise_mul:Multiplies arguments element-wise.

Description

The storage type of "elemwise_mul" output depends on storage types of inputs

Usage

```
mx.symbol.elemwise_mul(...)
```

Arguments

1hs NDArray-or-Symbol first inputrhs NDArray-or-Symbol second input

name string, optional Name of the resulting symbol.

Details

- elemwise_mul(default, default) = default - elemwise_mul(row_sparse, row_sparse) = row_sparse - elemwise_mul(default, row_sparse) = row_sparse - elemwise_mul(row_sparse, default) = row_sparse - elemwise_mul(csr, csr) = csr - otherwise, "elemwise_mul" generates output with default storage

Value

out The result mx.symbol

```
mx.symbol.elemwise_sub
```

elemwise_sub:Subtracts arguments element-wise.

Description

The storage type of "elemwise_sub" output depends on storage types of inputs

Usage

```
mx.symbol.elemwise_sub(...)
```

Arguments

lhs	NDArray-or-Symbol first input
rhs	NDArray-or-Symbol second input

name string, optional Name of the resulting symbol.

Details

- elemwise_sub(row_sparse, row_sparse) = row_sparse - elemwise_sub(csr, csr) = csr - elemwise_sub(default, csr) = default - elemwise_sub(csr, default) = default - elemwise_sub(default, rsp) = default - elemwise_sub(rsp, default) = default - otherwise, "elemwise_sub" generates output with default storage

Value

out The result mx.symbol

Description

This operator maps words to real-valued vectors in a high-dimensional space, called word embeddings. These embeddings can capture semantic and syntactic properties of the words. For example, it has been noted that in the learned embedding spaces, similar words tend to be close to each other and dissimilar words far apart.

Usage

```
mx.symbol.Embedding(...)
```

Arguments

data NDArray-or-Symbol The input array to the embedding operator.

weight NDArray-or-Symbol The embedding weight matrix.
input.dim int, required Vocabulary size of the input indices.
output.dim int, required Dimension of the embedding vectors.

dtype 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, default='float32'

Data type of weight.

sparse.grad boolean, optional, default=0 Compute row sparse gradient in the backward cal-

culation. If set to True, the grad's storage type is row_sparse.

name string, optional Name of the resulting symbol.

mx.symbol.erf 341

Details

For an input array of shape (d1, ..., dK), the shape of an output array is (d1, ..., dK, output_dim). All the input values should be integers in the range [0, input_dim).

If the input_dim is ip0 and output_dim is op0, then shape of the embedding weight matrix must be (ip0, op0).

When "sparse_grad" is False, if any index mentioned is too large, it is replaced by the index that addresses the last vector in an embedding matrix. When "sparse_grad" is True, an error will be raised if invalid indices are found.

Examples::

 $input_dim = 4 output_dim = 5$

// Each row in weight matrix y represents a word. So, y = (w0,w1,w2,w3) y = [[0., 1., 2., 3., 4.], [5., 6., 7., 8., 9.], [10., 11., 12., 13., 14.], [15., 16., 17., 18., 19.]]

// Input array x represents n-grams(2-gram). So, x = [(w1, w3), (w0, w2)] x = [[1., 3.], [0., 2.]]

// Mapped input x to its vector representation y. Embedding(x, y, 4, 5) = [[[5., 6., 7., 8., 9.], [15., 16., 17., 18., 19.]],

```
[[ 0., 1., 2., 3., 4.], [ 10., 11., 12., 13., 14.]]]
```

The storage type of weight can be either row_sparse or default.

.. Note::

If "sparse_grad" is set to True, the storage type of gradient w.r.t weights will be "row_sparse". Only a subset of optimizers support sparse gradients, including SGD, AdaGrad and Adam. Note that by default lazy updates is turned on, which may perform differently from standard updates. For more details, please check the Optimization API at: https://mxnet.incubator.apache.org/api/python/optimization/optimization.html

Defined in src/operator/tensor/indexing_op.cc:L539

Value

out The result mx.symbol

mx.symbol.erf

erf:Returns element-wise gauss error function of the input.

Description

Example::

Usage

```
mx.symbol.erf(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

342 mx.symbol.erfinv

Details

```
erf([0, -1., 10.]) = [0., -0.8427, 1.]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L886

Value

out The result mx.symbol

mx.symbol.erfinv

erfinv:Returns element-wise inverse gauss error function of the input.

Description

Example::

Usage

```
mx.symbol.erfinv(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
erfinv([0, 0.5., -1.]) = [0., 0.4769, -inf]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L907

Value

mx.symbol.exp 343

mx.symbol.exp

exp:Returns element-wise exponential value of the input.

Description

```
.. math:: exp(x) = e^x \cdot 2.718^x
```

Usage

```
mx.symbol.exp(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
\exp([0, 1, 2]) = [1., 2.71828175, 7.38905621]
```

The storage type of "exp" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L63

Value

out The result mx.symbol

```
mx.symbol.expand_dims expand\_dims:Inserts a new axis of size 1 into the array shape For example, given "x" with shape "(2,3,4)", then "expand\_dims(x, axis=1)" will return a new array with shape "(2,1,3,4)".
```

Description

Defined in src/operator/tensor/matrix_op.cc:L390

Usage

```
mx.symbol.expand_dims(...)
```

344 mx.symbol.expm1

Arguments

data NDArray-or-Symbol Source input

axis int, required Position where new axis is to be inserted. Suppose that the in-

put 'NDArray''s dimension is 'ndim', the range of the inserted axis is '[-ndim,

ndim]'

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.expm1

expm1:Returns "exp(x) - 1" computed element-wise on the input.

Description

This function provides greater precision than "exp(x) - 1" for small values of "x".

Usage

```
mx.symbol.expm1(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "expm1" output depends upon the input storage type:

- expm1(default) = default - expm1(row_sparse) = row_sparse - expm1(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L224

Value

```
mx.symbol.fill_element_0index
```

fill_element_0index: Fill one element of each line(row for python, column for R/Julia) in lhs according to index indicated by rhs and values indicated by mhs. This function assume rhs uses 0-based index.

Description

fill_element_0index:Fill one element of each line(row for python, column for R/Julia) in lhs according to index indicated by rhs and values indicated by mhs. This function assume rhs uses 0-based index.

Usage

```
mx.symbol.fill_element_0index(...)
```

Arguments

1hsNDArray Left operand to the function.mhsNDArray Middle operand to the function.rhsNDArray Right operand to the function.namestring, optional Name of the resulting symbol.

Value

out The result mx.symbol

 ${\sf mx.symbol.fix}$

fix:Returns element-wise rounded value to the nearest \setminus integer towards zero of the input.

Description

Example::

Usage

```
mx.symbol.fix(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

346 mx.symbol.Flatten

Details

```
fix([-2.1, -1.9, 1.9, 2.1]) = [-2., -1., 1., 2.]
```

The storage type of "fix" output depends upon the input storage type:

- $fix(default) = default - fix(row_sparse) = row_sparse - fix(csr) = csr$

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L875

Value

out The result mx.symbol

mx.symbol.Flatten

Flatten:Flattens the input array into a 2-D array by collapsing the higher dimensions. .. note:: 'Flatten' is deprecated. Use 'flatten' instead. For an input array with shape "(d1, d2, ..., dk)", 'flatten' operation reshapes the input array into an output array of shape "(d1, d2*...*dk)". Note that the behavior of this function is different from numpy.ndarray.flatten, which behaves similar to mxnet.ndarray.reshape((-1,)). Example:: x = [[1,2,3], [4,5,6], [7,8,9]], [1,2,3], [4,5,6], [7,8,9]], flatten(x) = [1,2,3], [1,2,3], [1,2,3], [1,3],

Description

Defined in src/operator/tensor/matrix_op.cc:L249

Usage

```
mx.symbol.Flatten(...)
```

Arguments

data NDArray-or-Symbol Input array.

name string, optional Name of the resulting symbol.

Value

mx.symbol.flatten 347

mx.symbol.flatten

flatten:Flattens the input array into a 2-D array by collapsing the higher dimensions. .. note:: 'Flatten' is deprecated. Use 'flatten' instead. For an input array with shape "(d1, d2, ..., dk)", 'flatten' operation reshapes the input array into an output array of shape "(d1, d2*...*dk)". Note that the behavior of this function is different from numpy.ndarray.flatten, which behaves similar to mxnet.ndarray.reshape((-1,)). Example:: x = [[1,2,3], [4,5,6], [7,8,9]], [1,2,3], [4,5,6], [7,8,9]], flatten(x) = [1,2,3], [1,2,3], [1,2,3], [1,2,3], [1,2,3], [1

Description

Defined in src/operator/tensor/matrix_op.cc:L249

Usage

```
mx.symbol.flatten(...)
```

Arguments

data NDArray-or-Symbol Input array.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

 ${\tt mx.symbol.flip}$

flip:Reverses the order of elements along given axis while preserving array shape. Note: reverse and flip are equivalent. We use reverse in the following examples: x = [[0, 1, 2, 3, 4], [5, 6, 7, 8, 9]] reverse(x, axis=0) = [[5, 6, 7, 8, 9], [0, 1, 2, 3, 4]] reverse(x, axis=1) = [[4, 3, 2, 1, 0], [9, 8, 7, 6, 5]]

Description

Defined in src/operator/tensor/matrix_op.cc:L826

Usage

```
mx.symbol.flip(...)
```

348 mx.symbol.floor

Arguments

data NDArray-or-Symbol Input data array

axis Shape(tuple), required The axis which to reverse elements.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.floor

floor:Returns element-wise floor of the input.

Description

The floor of the scalar x is the largest integer i, such that $i \le x$.

Usage

```
mx.symbol.floor(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
floor([-2.1, -1.9, 1.5, 1.9, 2.1]) = [-3., -2., 1., 1., 2.]
```

The storage type of "floor" output depends upon the input storage type:

- floor(default) = default - floor(row_sparse) = row_sparse - floor(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L837

Value

mx.symbol.ftml_update ftml_update:The FTML optimizer described in *FTML - Follow the Moving Leader in Deep Learning*, available at http://proceedings.mlr.press/v70/zheng17a/zheng17a.pdf.

Description

.. math::

Usage

```
mx.symbol.ftml_update(...)
```

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
d	NDArray-or-Symbol Internal state "d_t"
V	NDArray-or-Symbol Internal state "v_t"
z	NDArray-or-Symbol Internal state "z_t"
lr	float, required Learning rate.
beta1	float, optional, default=0.600000024 Generally close to 0.5.
beta2	float, optional, default=0.999000013 Generally close to 1.
epsilon	double, optional, default=9.9999999392252903e-09 Epsilon to prevent div 0.
t	int, required Number of update.
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.grad	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
name	string, optional Name of the resulting symbol.

Details

```
 g_t = \addit J(W_t-1) \ v_t = \beta_2 \ v_t-1 + (1 - \beta_2) \ g_t^2 \ d_t = \frac \ 1 - \beta_1^t \ \eta_t \ \frac \ v_t \ 1 - \beta_2^t + \ensuremath{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\mbox{\s\mbox{\\mbox{\\mbox{\s\mbox{\s\mbox{\s\mbox{\s\mbox{\s\m\s\m\s\m\s\s\m\mbox{\\mbox{\s\mbox{\m\s\s\s\\mbox{\s\s\mbox{\m\s\s\s\s\s\s\s\s\s\s\s\m\s\s\s
```

Value

mx.symbol.ftrl_update ftrl_update:Update function for Ftrl optimizer. Referenced from *Ad Click Prediction: a View from the Trenches*, available at http://dl.acm.org/citation.cfm?id=2488200.

Description

It updates the weights using::

Usage

```
mx.symbol.ftrl_update(...)
```

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
z	NDArray-or-Symbol z
n	NDArray-or-Symbol Square of grad
lr	float, required Learning rate
lamda1	float, optional, default=0.00999999978 The L1 regularization coefficient.
beta	float, optional, default=1 Per-Coordinate Learning Rate beta.
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
name	string, optional Name of the resulting symbol.

Details

```
rescaled\_grad = clip(grad * rescale\_grad, clip\_gradient) \ z += rescaled\_grad - (sqrt(n + rescaled\_grad **2) - sqrt(n)) * weight / learning\_rate n += rescaled\_grad **2 w = (sign(z) * lamda1 - z) / ((beta + sqrt(n)) / learning\_rate + wd) * (abs(z) > lamda1)
```

If w, z and n are all of "row_sparse" storage type, only the row slices whose indices appear in grad.indices are updated (for w, z and n)::

for row in grad.indices: rescaled_grad[row] = clip(grad[row] * rescale_grad, clip_gradient) z[row] += rescaled_grad[row] - (sqrt(n[row] + rescaled_grad[row]**2) - sqrt(n[row])) * weight[row] / learning_rate n[row] += rescaled_grad[row]**2 w[row] = (sign(z[row]) * lamda1 - z[row]) / ((beta + sqrt(n[row])) / learning_rate + wd) * (abs(z[row]) > lamda1)

Defined in src/operator/optimizer_op.cc:L874

Value

out The result mx.symbol

```
mx.symbol.FullyConnected
```

FullyConnected:Applies a linear transformation: :math: $Y = XW^T + b^*$

Description

If "flatten" is set to be true, then the shapes are:

Usage

```
mx.symbol.FullyConnected(...)
```

Arguments

data NDArray-or-Symbol Input data.

weight NDArray-or-Symbol Weight matrix.

bias NDArray-or-Symbol Bias parameter.

num. hidden int, required Number of hidden nodes of the output.

no.bias boolean, optional, default=0 Whether to disable bias parameter.

flatten boolean, optional, default=1 Whether to collapse all but the first axis of the input

data tensor.

name string, optional Name of the resulting symbol.

Details

```
- **data**: '(batch_size, x1, x2, ..., xn)' - **weight**: '(num_hidden, x1 * x2 * ... * xn)' - **bias**: '(num_hidden,)' - **out**: '(batch_size, num_hidden)'
```

If "flatten" is set to be false, then the shapes are:

```
- **data**: '(x1, x2, ..., xn, input_dim)' - **weight**: '(num_hidden, input_dim)' - **bias**: '(num_hidden,)' - **out**: '(x1, x2, ..., xn, num_hidden)'
```

The learnable parameters include both "weight" and "bias".

If "no_bias" is set to be true, then the "bias" term is ignored.

.. Note:

The sparse support for FullyConnected is limited to forward evaluation with 'row_sparse' weight and bias, where the length of 'weight.indices' and 'bias.indices' must be equal to 'num_hidden'. This could be useful for model inference with 'row_sparse' weights trained with importance sampling or noise contrastive estimation.

To compute linear transformation with 'csr' sparse data, sparse.dot is recommended instead of sparse.FullyConnected.

Defined in src/operator/nn/fully_connected.cc:L291

352 mx.symbol.gammaln

Value

out The result mx.symbol

mx.symbol.gamma

gamma:Returns the gamma function (extension of the factorial function \ to the reals), computed element-wise on the input array.

Description

The storage type of "gamma" output is always dense

Usage

```
mx.symbol.gamma(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.gammaln

gammaln: Returns element-wise log of the absolute value of the gamma function \ of the input.

Description

The storage type of "gammaln" output is always dense

Usage

```
mx.symbol.gammaln(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Value

mx.symbol.gather_nd 353

 $mx.symbol.gather_nd$

gather_nd:Gather elements or slices from 'data' and store to a tensor whose shape is defined by 'indices'.

Description

Given 'data' with shape ' $(X_0, X_1, ..., X_{N-1})$ ' and indices with shape ' $(M, Y_0, ..., Y_{K-1})$ ', the output will have shape ' $(Y_0, ..., Y_{K-1}, X_M, ..., X_{N-1})$ ', where ' $M \le N$ '. If 'M = N', output shape will simply be ' $(Y_0, ..., Y_{K-1})$ '.

Usage

```
mx.symbol.gather_nd(...)
```

Arguments

data NDArray-or-Symbol data indices NDArray-or-Symbol indices

name string, optional Name of the resulting symbol.

Details

The elements in output is defined as follows::

```
output[y_0, ..., y_K-1, x_M, ..., x_N-1] = data[indices[0, y_0, ..., y_K-1], ..., indices[M-1, y_0, ..., y_K-1], x_M, ..., x_N-1]
```

Examples::

```
data = [[0, 1], [2, 3]] indices = [[1, 1, 0], [0, 1, 0]] gather_nd(data, indices) = [2, 3, 0]
data = [[[1, 2], [3, 4]], [[5, 6], [7, 8]]] indices = [[0, 1], [1, 0]] gather_nd(data, indices) = [[3, 4], [5, 6]]
```

Value

out The result mx.symbol

mx.symbol.GridGenerator

GridGenerator: Generates 2D sampling grid for bilinear sampling.

Description

GridGenerator:Generates 2D sampling grid for bilinear sampling.

354 mx.symbol.Group

Usage

```
mx.symbol.GridGenerator(...)
```

Arguments

data NDArray-or-Symbol Input data to the function.

transform.type 'affine', 'warp', required The type of transformation. For 'affine', input data

should be an affine matrix of size (batch, 6). For 'warp', input data should be an

optical flow of size (batch, 2, h, w).

target.shape Shape(tuple), optional, default=[0,0] Specifies the output shape (H, W). This is

required if transformation type is 'affine'. If transformation type is 'warp', this

parameter is ignored.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.Group

Create a symbol that groups symbols together.

Description

Create a symbol that groups symbols together.

Usage

```
mx.symbol.Group(...)
```

Arguments

kwarg

Variable length of symbols or list of symbol.

Value

The result symbol

mx.symbol.GroupNorm

GroupNorm:Group normalization.

Description

The input channels are separated into "num_groups" groups, each containing "num_channels / num_groups" channels. The mean and standard-deviation are calculated separately over the each group.

Usage

```
mx.symbol.GroupNorm(...)
```

Arguments

data NDArray-or-Symbol Input data gamma NDArray-or-Symbol gamma array beta NDArray-or-Symbol beta array

num.groups int, optional, default='1' Total number of groups.

eps float, optional, default=9.9999975e-06 An 'epsilon' parameter to prevent divi-

sion by 0.

output.mean.var

boolean, optional, default=0 Output the mean and std calculated along the given

axis.

name string, optional Name of the resulting symbol.

Details

```
.. math::
```

 $\label{eq:data} $$ data = data.reshape((N, num_groups, C // num_groups, ...)) out = \frac{a - mean(data, axis)}{qata - mean(data, axis)} $$ example (N, num_groups, C // num_groups, ...)) out = \frac{a - mean(data, axis)}{qata - mean(data, axis)} $$ example (N, num_groups, C // num_groups, ...)) out = \frac{a - mean(data, axis)}{qata - mean(data, axis)} $$ example (N, num_groups, C // num_groups, ...)) out = \frac{a - mean(data, axis)}{qata - mean(data, axis)} $$ example (N, num_groups, C // num_groups, ...)) out = \frac{a - mean(data, axis)}{qata - mean(data, axis)} $$ example (N, num_groups, C // num_groups, ...)) out = \frac{a - mean(data, axis)}{qata - mean(data, axis)} $$ example (N, num_groups, C // num_groups, ...)) out = \frac{a - mean(data, axis)}{qata - mean(data, axis)} $$ example (N, num_groups, C // num_groups) out = \frac{a - mean(data, axis)}{qata - mean(data, axis)} $$ example (N, num_groups, C // num_groups,$

Both "gamma" and "beta" are learnable parameters.

Defined in src/operator/nn/group_norm.cc:L77

Value

356 mx.symbol.identity

```
mx.symbol.hard_sigmoid
```

hard_sigmoid:Computes hard sigmoid of x element-wise.

Description

```
.. math:: y = max(0, min(1, alpha * x + beta))
```

Usage

```
mx.symbol.hard_sigmoid(...)
```

Arguments

data NDArray-or-Symbol The input array.

alpha float, optional, default=0.200000003 Slope of hard sigmoid

float, optional, default=0.5 Bias of hard sigmoid.

name string, optional Name of the resulting symbol.

Details

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L161

Value

out The result mx.symbol

```
mx.symbol.identity ide
```

identity:Returns a copy of the input.

Description

From:src/operator/tensor/elemwise_unary_op_basic.cc:246

Usage

```
mx.symbol.identity(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Value

mx.symbol.IdentityAttachKLSparseReg

IdentityAttachKLSparseReg:Apply a sparse regularization to the output a sigmoid activation function.

Description

IdentityAttachKLSparseReg:Apply a sparse regularization to the output a sigmoid activation function.

Usage

```
mx.symbol.IdentityAttachKLSparseReg(...)
```

Arguments

data NDArray-or-Symbol Input data.

sparseness.target

float, optional, default=0.100000001 The sparseness target

penalty float, optional, default=0.00100000005 The tradeoff parameter for the sparse-

ness penalty

momentum float, optional, default=0.899999976 The momentum for running average

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.infer.shape Inference the shape of arguments, outputs, and auxiliary states.

Description

Inference the shape of arguments, outputs, and auxiliary states.

Usage

```
mx.symbol.infer.shape(symbol, ...)
```

Arguments

symbol The mx.symbol object

```
mx.symbol.InstanceNorm
```

InstanceNorm:Applies instance normalization to the n-dimensional input array.

Description

This operator takes an n-dimensional input array where (n>2) and normalizes the input using the following formula:

Usage

```
mx.symbol.InstanceNorm(...)
```

Arguments

data	NDArray-or-Symbol An n-dimensional input array $(n > 2)$ of the form [batch, channel, spatial_dim1, spatial_dim2,].
gamma	NDArray-or-Symbol A vector of length 'channel', which multiplies the normalized input.
beta	NDArray-or-Symbol A vector of length 'channel', which is added to the product of the normalized input and the weight.
eps	float, optional, default=0.00100000005 An 'epsilon' parameter to prevent division by 0.
name	string, optional Name of the resulting symbol.

Details

```
.. math::
```

```
out = \fracx - mean[data] \sqrtVar[data] + \epsilon * gamma + beta
```

This layer is similar to batch normalization layer ('BatchNorm') with two differences: first, the normalization is carried out per example (instance), not over a batch. Second, the same normalization is applied both at test and train time. This operation is also known as 'contrast normalization'.

If the input data is of shape [batch, channel, spacial_dim1, spacial_dim2, ...], 'gamma' and 'beta' parameters must be vectors of shape [channel].

This implementation is based on this paper [1]_

.. [1] Instance Normalization: The Missing Ingredient for Fast Stylization, D. Ulyanov, A. Vedaldi, V. Lempitsky, 2016 (arXiv:1607.08022v2).

Examples::

```
// Input of shape (2,1,2) x = [[[ 1.1, 2.2]], [[ 3.3, 4.4]]]
// gamma parameter of length 1 gamma = [1.5]
// beta parameter of length 1 beta = [0.5]
```

mx.symbol.khatri_rao 359

// Instance normalization is calculated with the above formula InstanceNorm(x,gamma,beta) = [[[-0.997527, 1.99752665]], [[-0.99752653, 1.99752724]]]

Defined in src/operator/instance_norm.cc:L95

Value

out The result mx.symbol

mx.symbol.khatri_rao khatri_rao:Computes the Khatri-Rao product of the input matrices.

Description

Given a collection of :math:'n' input matrices,

Usage

```
mx.symbol.khatri_rao(...)
```

Arguments

args NDArray-or-Symbol[] Positional input matrices name string, optional Name of the resulting symbol.

Details

```
.. math:: A_1 \in M_1 \in M, ..., A_n \in M_n \in N, the (column-wise) Khatri-Rao product is defined as the matrix,
```

.. math:: $X = A \mid \text{otimes } \cdot A \mid \text{n } \mid \text{mathbbR}^{(M)} \mid \text{cdots } M \mid \text{n} \mid \text{times } N$,

where the :math:'k' th column is equal to the column-wise outer product :math:' A_1_k \otimes \cdots \otimes A_n_k ' where :math:' A_i_k ' is the kth column of the ith matrix.

Example::

```
»> A = mx.nd.array([[1, -1], »> [2, -3]]) »> B = mx.nd.array([[1, 4], »> [2, 5], »> [3, 6]]) »> C = mx.nd.khatri_rao(A, B) »> print(C.asnumpy()) [[ 1. -4.] [ 2. -5.] [ 3. -6.] [ 2. -12.] [ 4. -15.] [ 6. -18.]]
```

Defined in src/operator/contrib/krprod.cc:L108

Value

```
mx.symbol.L2Normalization
```

L2Normalization:Normalize the input array using the L2 norm.

Description

For 1-D NDArray, it computes::

Usage

```
mx.symbol.L2Normalization(...)
```

Arguments

data NDArray-or-Symbol Input array to normalize.

eps float, optional, default=1.00000001e-10 A small constant for numerical stability.

"channel", 'instance', 'spatial', optional, default='instance' Specify the dimen-

sion along which to compute L2 norm.

name string, optional Name of the resulting symbol.

Details

```
out = data / sqrt(sum(data ** 2) + eps)
```

For N-D NDArray, if the input array has shape (N, N, ..., N),

with "mode" = "instance", it normalizes each instance in the multidimensional array by its L2 norm.::

```
for i in 0...N out[i,:,:,...,:] = data[i,:,:,...,:] / sqrt(sum(data[i,:,:,...,:] ** 2) + eps)
```

with "mode" = "channel", it normalizes each channel in the array by its L2 norm.::

```
for i in 0...N out[:,i,:,...,:] = data[:,i,:,...,:] / sqrt(sum(data[:,i,:,...,:] ** 2) + eps)
```

with "mode" = "spatial", it normalizes the cross channel norm for each position in the array by its L2 norm.::

for dim in 2...N for i in 0...N out [....,i,...] = take(out, indices=i, axis=dim) / sqrt(sum(take(out, indices=i, axis=dim) ** 2) + eps) dim-

Example::

```
x = [[[1,2], [3,4]], [[2,2], [5,6]]]
```

L2Normalization(x, mode='instance') =[[[0.18257418 0.36514837] [0.54772252 0.73029673]] [[0.24077171 0.24077171] [0.60192931 0.72231513]]]

L2Normalization(x, mode='channel') =[[[0.31622776 0.44721359] [0.94868326 0.89442718]] [[0.37139067 0.31622776] [0.92847669 0.94868326]]]

L2Normalization(x, mode='spatial') =[[[0.44721359 0.89442718] [0.60000002 0.80000001]] [[0.70710677 0.70710677] [0.6401844 0.76822126]]]

Defined in src/operator/l2_normalization.cc:L196

mx.symbol.LayerNorm

361

Value

out The result mx.symbol

mx.symbol.LayerNorm LayerNorm:Layer normalization.

Description

Normalizes the channels of the input tensor by mean and variance, and applies a scale "gamma" as well as offset "beta".

Usage

```
mx.symbol.LayerNorm(...)
```

Arguments

data	NDArray-or-Symbol Input data to layer normalization
gamma	NDArray-or-Symbol gamma array
beta	NDArray-or-Symbol beta array
axis	int, optional, default='-1' The axis to perform layer normalization. Usually, this should be be axis of the channel dimension. Negative values means indexing from right to left.
eps	float, optional, default=9.99999975e-06 An 'epsilon' parameter to prevent division by 0.
output.mean.var	
	boolean, optional, default=0 Output the mean and std calculated along the given axis.
name	string, optional Name of the resulting symbol.

Details

Assume the input has more than one dimension and we normalize along axis 1. We first compute the mean and variance along this axis and then compute the normalized output, which has the same shape as input, as following:

```
.. math::
```

out = \fracdata - mean(data, axis)\sqrtvar(data, axis) + \epsilon * gamma + beta

Both "gamma" and "beta" are learnable parameters.

Unlike BatchNorm and InstanceNorm, the *mean* and *var* are computed along the channel dimension.

Assume the input has size k^* on axis 1, then both "gamma" and "beta" have shape k,k. If "output_mean_var" is set to be true, then outputs both "data_mean" and "data_std". Note that no gradient will be passed through these two outputs.

The parameter "axis" specifies which axis of the input shape denotes the 'channel' (separately normalized groups). The default is -1, which sets the channel axis to be the last item in the input shape.

Defined in src/operator/nn/layer_norm.cc:L156

Value

out The result mx.symbol

mx.symbol.LeakyReLU LeakyReLU:Applies Leaky rectified linear unit activation elementwise to the input.

Description

Leaky ReLUs attempt to fix the "dying ReLU" problem by allowing a small 'slope' when the input is negative and has a slope of one when input is positive.

Usage

```
mx.symbol.LeakyReLU(...)
```

Arguments

data	NDArray-or-Symbol Input data to activation function.
gamma	NDArray-or-Symbol Input data to activation function.
act.type	'elu', 'gelu', 'leaky', 'prelu', 'rrelu', 'selu', optional, default='leaky' Activation function to be applied.
slope	float, optional, default=0.25 Init slope for the activation. (For leaky and elu only)
lower.bound	float, optional, default=0.125 Lower bound of random slope. (For rrelu only)
upper.bound	float, optional, default=0.333999991 Upper bound of random slope. (For rrelu only)
name	string, optional Name of the resulting symbol.

Details

The following modified ReLU Activation functions are supported:

```
- *elu*: Exponential Linear Unit. 'y = x > 0 ? x : slope * (exp(x)-1)' - *selu*: Scaled Exponential Linear Unit. 'y = lambda * (x > 0 ? x : alpha * (exp(x) - 1))' where *lambda = 1.0507009873554804934193349852946* and *alpha = 1.6732632423543772848170429916717*. - *leaky*: Leaky ReLU. 'y = x > 0 ? x : slope * x' - *prelu*: Parametric ReLU. This is same as *leaky* except that 'slope' is learnt during training. - *rrelu*: Randomized ReLU. same as *leaky* but the 'slope' is uniformly and randomly chosen from *[lower_bound, upper_bound)* for training, while fixed to be *(lower_bound+upper_bound)/2* for inference.
```

Defined in src/operator/leaky_relu.cc:L161

mx.symbol.linalg_det

363

Value

out The result mx.symbol

```
mx.symbol.linalg_det:Compute the determinant of a matrix. Input is a tensor *A* of dimension *n >= 2*.
```

Description

```
If *n=2*, *A* is a square matrix. We compute:
```

Usage

```
mx.symbol.linalg_det(...)
```

Arguments

A NDArray-or-Symbol Tensor of square matrix

name string, optional Name of the resulting symbol.

Details

```
*out* = *det(A)*
```

If *n>2*, *det* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only. .. note:: There is no gradient backwarded when A is non-invertible (which is equivalent to det(A) = 0) because zero is rarely hit upon in float point computation and the Jacobi's formula on determinant gradient is not computationally efficient when A is non-invertible.

Examples::

```
Single matrix determinant A = [[1., 4.], [2., 3.]] det(A) = [-5.]
```

Batch matrix determinant A = [[[1., 4.], [2., 3.]], [[2., 3.], [1., 4.]]] det(A) = [-5., 5.]

Defined in src/operator/tensor/la_op.cc:L970

Value

```
mx.symbol.linalg_extractdiag
```

linalg_extractdiag:Extracts the diagonal entries of a square matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, then *A* represents a single square matrix which diagonal elements get extracted as a 1-dimensional tensor.

Usage

```
mx.symbol.linalg_extractdiag(...)
```

Arguments

A NDArray-or-Symbol Tensor of square matrices

offset int, optional, default='0' Offset of the diagonal versus the main diagonal. 0

corresponds to the main diagonal, a negative/positive value to diagonals be-

low/above the main diagonal.

name string, optional Name of the resulting symbol.

Details

If *n>2*, then *A* represents a batch of square matrices on the trailing two dimensions. The extracted diagonals are returned as an *n-1*-dimensional tensor.

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix diagonal extraction A = [[1.0, 2.0], [3.0, 4.0]]

extractdiag(A) = [1.0, 4.0]

extractdiag(A, 1) = [2.0]

Batch matrix diagonal extraction A = [[[1.0, 2.0], [3.0, 4.0]], [[5.0, 6.0], [7.0, 8.0]]]

extractdiag(A) = [[1.0, 4.0], [5.0, 8.0]]

Defined in src/operator/tensor/la_op.cc:L495

Value

```
mx.symbol.linalg_extracttrian
```

linalg_extracttrian:Extracts a triangular sub-matrix from a square matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, then *A* represents a single square matrix from which a triangular sub-matrix is extracted as a 1-dimensional tensor.

Usage

```
mx.symbol.linalg_extracttrian(...)
```

Arguments

A NDArray-or-Symbol Tensor of square matrices

offset int, optional, default='0' Offset of the diagonal versus the main diagonal. 0

corresponds to the main diagonal, a negative/positive value to diagonals be-

low/above the main diagonal.

lower boolean, optional, default=1 Refer to the lower triangular matrix if lower=true,

refer to the upper otherwise. Only relevant when offset=0

name string, optional Name of the resulting symbol.

Details

If *n>2*, then *A* represents a batch of square matrices on the trailing two dimensions. The extracted triangular sub-matrices are returned as an *n-1*-dimensional tensor.

The *offset* and *lower* parameters determine the triangle to be extracted:

- When *offset = 0* either the lower or upper triangle with respect to the main diagonal is extracted depending on the value of parameter *lower*. When *offset = k > 0* the upper triangle with respect to the k-th diagonal above the main diagonal is extracted. When *offset = k < 0* the lower triangle with respect to the k-th diagonal below the main diagonal is extracted.
- .. note:: The operator supports float32 and float64 data types only.

Examples::

```
Single triagonal extraction A = [[1.0, 2.0], [3.0, 4.0]]
```

extracttrian(A) = [1.0, 3.0, 4.0] extracttrian(A, lower=False) = [1.0, 2.0, 4.0] extracttrian(A, 1) = [2.0] extracttrian(A, -1) = [3.0]

Batch triagonal extraction A = [[[1.0, 2.0], [3.0, 4.0]], [[5.0, 6.0], [7.0, 8.0]]]

extracttrian(A) = [[1.0, 3.0, 4.0], [5.0, 7.0, 8.0]]

Defined in src/operator/tensor/la_op.cc:L605

Value

mx.symbol.linalg_gelqf

linalg_gelqf:LQ factorization for general matrix. Input is a tensor *A* of dimension $*n \ge 2*$.

Description

If *n=2*, we compute the LQ factorization (LAPACK *gelqf*, followed by *orglq*). *A* must have shape *(x, y)* with *x <= y*, and must have full rank *=x*. The LQ factorization consists of *L* with shape *(x, x)* and *Q* with shape *(x, y)*, so that:

Usage

```
mx.symbol.linalg_gelqf(...)
```

Arguments

A NDArray-or-Symbol Tensor of input matrices to be factorized

name string, optional Name of the resulting symbol.

Details

```
*A* = *L* \ **O*
```

Here, *L* is lower triangular (upper triangle equal to zero) with nonzero diagonal, and *Q* is row-orthonormal, meaning that

```
*Q* \* *Q*\ :sup:'T'
```

is equal to the identity matrix of shape *(x, x)*.

If *n>2*, *gelqf* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single LQ factorization A = [[1., 2., 3.], [4., 5., 6.]] Q, L = gelqf(A) Q = [[-0.26726124, -0.53452248, -0.80178373], [0.87287156, 0.21821789, -0.43643578]] L = [[-3.74165739, 0.], [-8.55235974, 1.96396101]]

Batch LQ factorization A = [[[1, 2., 3.], [4., 5., 6.]], [[7., 8., 9.], [10., 11., 12.]]] Q, L = gelqf(A) Q = [[[-0.26726124, -0.53452248, -0.80178373], [0.87287156, 0.21821789, -0.43643578]], [[-0.50257071, -0.57436653, -0.64616234], [0.7620735, 0.05862104, -0.64483142]]] L = [[[-3.74165739, 0.], [-8.55235974, 1.96396101]], [[-13.92838828, 0.], [-19.09768702, 0.52758934]]]

Defined in src/operator/tensor/la_op.cc:L798

Value

mx.symbol.linalg_gemm linalg_gemm:Performs general matrix multiplication and accumulation. Input are tensors *A*, *B*, *C*, each of dimension *n >= 2* and having the same shape on the leading *n-2* dimensions.

Description

If *n=2*, the BLAS3 function *gemm* is performed:

Usage

```
mx.symbol.linalg_gemm(...)
```

Arguments

Α	NDArray-or-Symbol Tensor of input matrices
В	NDArray-or-Symbol Tensor of input matrices
С	NDArray-or-Symbol Tensor of input matrices
transpose.a	boolean, optional, default=0 Multiply with transposed of first input (A).
transpose.b	boolean, optional, default=0 Multiply with transposed of second input (B).
alpha	double, optional, default=1 Scalar factor multiplied with A*B.
beta	double, optional, default=1 Scalar factor multiplied with C.
axis	int, optional, default='-2' Axis corresponding to the matrix rows.
name	string, optional Name of the resulting symbol.

Details

```
*out* = *alpha* \ **op* \ (*A*) \ **op* \ (*B*) + *beta* \ **C*
```

Here, *alpha* and *beta* are scalar parameters, and *op()* is either the identity or matrix transposition (depending on *transpose_a*, *transpose_b*).

If *n>2*, *gemm* is performed separately for a batch of matrices. The column indices of the matrices are given by the last dimensions of the tensors, the row indices by the axis specified with the *axis* parameter. By default, the trailing two dimensions will be used for matrix encoding.

For a non-default axis parameter, the operation performed is equivalent to a series of swapaxes/gemm/swapaxes calls. For example let *A*, *B*, *C* be 5 dimensional tensors. Then gemm(*A*, *B*, *C*, axis=1) is equivalent to the following without the overhead of the additional swapaxis operations::

```
A1 = swapaxes(A, dim1=1, dim2=3) B1 = swapaxes(B, dim1=1, dim2=3) C = swapaxes(C, dim1=1, dim2=3) C = gemm(A1, B1, C) C = swapaxis(C, dim1=1, dim2=3)
```

When the input data is of type float32 and the environment variables MXNET_CUDA_ALLOW_TENSOR_CORE and MXNET_CUDA_TENSOR_OP_MATH_ALLOW_CONVERSION are set to 1, this operator will try to use pseudo-float16 precision (float32 math with float16 I/O) precision in order to use Tensor Cores on suitable NVIDIA GPUs. This can sometimes give significant speedups.

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix multiply-add $A = [[1.0, 1.0], [1.0, 1.0]] B = [[1.0, 1.0], [1.0, 1.0], [1.0, 1.0]] C = [[1.0, 1.0, 1.0], [1.0, 1.0], [1.0, 1.0]] gemm(A, B, C, transpose_b=True, alpha=2.0, beta=10.0) = [[14.0, 14.0, 14.0], [14.0, 14.0, 14.0]]$

Batch matrix multiply-add $A = [[[1.0, 1.0]], [[0.1, 0.1]]] B = [[[1.0, 1.0]], [[0.1, 0.1]]] C = [[[10.0]], [[0.01]]] gemm(A, B, C, transpose_b=True, alpha=2.0, beta=10.0) = [[[104.0]], [[0.14]]]$

Defined in src/operator/tensor/la_op.cc:L89

Value

out The result mx.symbol

```
mx.symbol.linalg_gemm2
```

linalg_gemm2:Performs general matrix multiplication. Input are tensors *A*, *B*, each of dimension *n >= 2* and having the same shape on the leading *n-2* dimensions.

Description

If *n=2*, the BLAS3 function *gemm* is performed:

Usage

```
mx.symbol.linalg_gemm2(...)
```

Arguments

A NDArray-or-Symbol Tensor of input matrices

B NDArray-or-Symbol Tensor of input matrices

transpose.a boolean, optional, default=0 Multiply with transposed of first input (A).
transpose.b boolean, optional, default=0 Multiply with transposed of second input (B).

alpha double, optional, default=1 Scalar factor multiplied with A*B.

axis int, optional, default='-2' Axis corresponding to the matrix row indices.

name string, optional Name of the resulting symbol.

Details

```
*out* = *alpha* \ **op* \ (*A*) \ **op* \ (*B*)
```

Here *alpha* is a scalar parameter and *op()* is either the identity or the matrix transposition (depending on *transpose_a*, *transpose_b*).

If *n>2*, *gemm* is performed separately for a batch of matrices. The column indices of the matrices are given by the last dimensions of the tensors, the row indices by the axis specified with the *axis* parameter. By default, the trailing two dimensions will be used for matrix encoding.

For a non-default axis parameter, the operation performed is equivalent to a series of swapaxes/gemm/swapaxes calls. For example let *A*, *B* be 5 dimensional tensors. Then gemm(*A*, *B*, axis=1) is equivalent to the following without the overhead of the additional swapaxis operations::

```
A1 = swapaxes(A, dim1=1, dim2=3) B1 = swapaxes(B, dim1=1, dim2=3) C = gemm2(A1, B1) C = swapaxis(C, dim1=1, dim2=3)
```

When the input data is of type float32 and the environment variables MXNET_CUDA_ALLOW_TENSOR_CORE and MXNET_CUDA_TENSOR_OP_MATH_ALLOW_CONVERSION are set to 1, this operator will try to use pseudo-float16 precision (float32 math with float16 I/O) precision in order to use Tensor Cores on suitable NVIDIA GPUs. This can sometimes give significant speedups.

.. note:: The operator supports float32 and float64 data types only.

Examples::

```
Single matrix multiply A = [[1.0, 1.0], [1.0, 1.0]] B = [[1.0, 1.0], [1.0, 1.0], [1.0, 1.0]] gemm2(A, B, transpose_b=True, alpha=2.0) = [[4.0, 4.0, 4.0], [4.0, 4.0, 4.0]]
```

Batch matrix multiply $A = [[[1.0, 1.0]], [[0.1, 0.1]]] B = [[[1.0, 1.0]], [[0.1, 0.1]]] gemm2(A, B, transpose_b=True, alpha=<math>2.0$) = [[[4.0]], [[0.04]]]

Defined in src/operator/tensor/la_op.cc:L163

Value

out The result mx.symbol

```
mx.symbol.linalg_inverse
```

linalg_inverse:Compute the inverse of a matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

```
If *n=2*, *A* is a square matrix. We compute:
```

Usage

```
mx.symbol.linalg_inverse(...)
```

Arguments

A NDArray-or-Symbol Tensor of square matrix

name string, optional Name of the resulting symbol.

```
*out* = *A* \ :sup: `-1`
```

If *n>2*, *inverse* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

```
Single matrix inverse A = [[1., 4.], [2., 3.]] inverse(A) = [[-0.6, 0.8], [0.4, -0.2]]
```

Batch matrix inverse A = [[[1., 4.], [2., 3.]], [[1., 3.], [2., 4.]]] inverse(A) = [[[-0.6, 0.8], [0.4, -0.2]], [[-2., 1.5], [1., -0.5]]]

Defined in src/operator/tensor/la_op.cc:L917

Value

out The result mx.symbol

```
mx.symbol.linalg_makediag
```

linalg_makediag:Constructs a square matrix with the input as diagonal. Input is a tensor *A* of dimension *n >= 1*.

Description

If *n=1*, then *A* represents the diagonal entries of a single square matrix. This matrix will be returned as a 2-dimensional tensor. If *n>1*, then *A* represents a batch of diagonals of square matrices. The batch of diagonal matrices will be returned as an *n+1*-dimensional tensor.

Usage

```
mx.symbol.linalg_makediag(...)
```

Arguments

A NDArray-or-Symbol Tensor of diagonal entri	ıes
--	-----

offset int, optional, default='0' Offset of the diagonal versus the main diagonal. 0

corresponds to the main diagonal, a negative/positive value to diagonals be-

low/above the main diagonal.

name string, optional Name of the resulting symbol.

```
.. note:: The operator supports float32 and float64 data types only. Examples:: Single diagonal matrix construction A = [1.0, 2.0] makediag(A) = [[1.0, 0.0], [0.0, 2.0]] makediag(A, 1) = [[0.0, 1.0, 0.0], [0.0, 0.0, 2.0], [0.0, 0.0, 0.0]] Batch diagonal matrix construction A = [[1.0, 2.0], [3.0, 4.0]] makediag(A) = [[[1.0, 0.0], [0.0, 2.0]], [[3.0, 0.0], [0.0, 4.0]]] Defined in src/operator/tensor/la_op.cc:L547
```

Value

out The result mx.symbol

```
mx.symbol.linalg_maketrian
```

linalg_maketrian:Constructs a square matrix with the input representing a specific triangular sub-matrix. This is basically the inverse of *linalg.extracttrian*. Input is a tensor *A* of dimension *n >= 1*.

Description

If *n=1*, then *A* represents the entries of a triangular matrix which is lower triangular if *off-set<0* or *offset=0*, *lower=true*. The resulting matrix is derived by first constructing the square matrix with the entries outside the triangle set to zero and then adding *offset*-times an additional diagonal with zero entries to the square matrix.

Usage

```
mx.symbol.linalg_maketrian(...)
```

Arguments

A	NDArray-or-Symbol Tensor of triangular matrices stored as vectors
offset	int, optional, default='0' Offset of the diagonal versus the main diagonal. 0 corresponds to the main diagonal, a negative/positive value to diagonals below/above the main diagonal.
lower	boolean, optional, default=1 Refer to the lower triangular matrix if lower=true, refer to the upper otherwise. Only relevant when offset=0
name	string, optional Name of the resulting symbol.

If *n>1*, then *A* represents a batch of triangular sub-matrices. The batch of corresponding square matrices is returned as an *n+1*-dimensional tensor.

.. note:: The operator supports float32 and float64 data types only.

Examples::

```
Single matrix construction A = [1.0, 2.0, 3.0]
```

```
maketrian(A) = [[1.0, 0.0], [2.0, 3.0]]
```

maketrian(A, lower=false) = [[1.0, 2.0], [0.0, 3.0]]

maketrian(A, offset=1) = [[0.0, 1.0, 2.0], [0.0, 0.0, 3.0], [0.0, 0.0, 0.0]] maketrian(A, offset=-1) = [[0.0, 0.0, 0.0], [1.0, 0.0, 0.0], [2.0, 3.0, 0.0]]

Batch matrix construction A = [[1.0, 2.0, 3.0], [4.0, 5.0, 6.0]]

```
maketrian(A) = [[[1.0, 0.0], [2.0, 3.0]], [[4.0, 0.0], [5.0, 6.0]]]
```

maketrian(A, offset=1) = [[[0.0, 1.0, 2.0], [0.0, 0.0, 3.0], [0.0, 0.0, 0.0]], [[0.0, 4.0, 5.0], [0.0, 0.0, 6.0], [0.0, 0.0, 0.0]]]

Defined in src/operator/tensor/la_op.cc:L673

Value

out The result mx.symbol

```
mx.symbol.linalg_potrf
```

linalg_potrf: Performs Cholesky factorization of a symmetric positivedefinite matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, the Cholesky factor *B* of the symmetric, positive definite matrix *A* is computed. *B* is triangular (entries of upper or lower triangle are all zero), has positive diagonal entries, and:

Usage

```
mx.symbol.linalg_potrf(...)
```

Arguments

A NDArray-or-Symbol Tensor of input matrices to be decomposed

name string, optional Name of the resulting symbol.

```
A^* = B^* \ Sp: T' \ if \ lower = true A^* = B^* \ sup: T' \ k B^* \ if \ lower = false B^* \ k B^* \ if \ k B^* \ k B^* \ if \ k B^* \ k B^
```

If *n>2*, *potrf* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix factorization A = [[4.0, 1.0], [1.0, 4.25]] potrf(A) = [[2.0, 0], [0.5, 2.0]]

Batch matrix factorization A = [[[4.0, 1.0], [1.0, 4.25]], [[16.0, 4.0], [4.0, 17.0]]] potrf(A) = [[[2.0, 0], [0.5, 2.0]], [[4.0, 0], [1.0, 4.0]]]

Defined in src/operator/tensor/la_op.cc:L214

Value

out The result mx.symbol

```
mx.symbol.linalg_potri
```

linalg_potri:Performs matrix inversion from a Cholesky factorization. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, *A* is a triangular matrix (entries of upper or lower triangle are all zero) with positive diagonal. We compute:

Usage

```
mx.symbol.linalg_potri(...)
```

Arguments

A NDArray-or-Symbol Tensor of lower triangular matrices

name string, optional Name of the resulting symbol.

Details

```
*out* = *A*\ :sup:'-T' \* *A*\ :sup:'-1' if *lower* = *true* *out* = *A*\ :sup:'-1' \* *A*\ :sup:'-T' if *lower* = *false*
```

In other words, if *A* is the Cholesky factor of a symmetric positive definite matrix *B* (obtained by *potrf*), then

```
*out* = *B*\ :sup:'-1'
```

If *n>2*, *potri* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

.. note:: Use this operator only if you are certain you need the inverse of *B*, and cannot use the Cholesky factor *A* (*potrf*), together with backsubstitution (*trsm*). The latter is numerically much safer, and also cheaper.

Examples::

Single matrix inverse A = [[2.0, 0], [0.5, 2.0]] potri(A) = [[0.26563, -0.0625], [-0.0625, 0.25]] Batch matrix inverse A = [[[2.0, 0], [0.5, 2.0]], [[4.0, 0], [1.0, 4.0]]] potri(A) = [[[0.26563, -0.0625], [-0.0625, 0.25]], [[0.06641, -0.01562], [-0.01562, 0.0625]]]

Defined in src/operator/tensor/la_op.cc:L275

Value

out The result mx.symbol

```
mx.symbol.linalg_slogdet
```

linalg_slogdet:Compute the sign and log of the determinant of a matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, *A* is a square matrix. We compute:

Usage

```
mx.symbol.linalg_slogdet(...)
```

Arguments

A NDArray-or-Symbol Tensor of square matrix name string, optional Name of the resulting symbol.

Details

```
*sign* = *sign(det(A))* *logabsdet* = *log(abs(det(A)))*
```

If *n>2*, *slogdet* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only. .. note:: The gradient is not properly defined on sign, so the gradient of it is not backwarded. .. note:: No gradient is backwarded when A is non-invertible. Please see the docs of operator det for detail.

Examples::

Single matrix signed log determinant A = [[2., 3.], [1., 4.]] sign, logabsdet = slogdet(A) sign = [1.] logabsdet = [1.609438]

Batch matrix signed log determinant A = [[[2., 3.], [1., 4.]], [[1., 2.], [2., 4.]], [[1., 2.], [4., 3.]]] sign, logabsdet = slogdet(A) sign = [1., 0., -1.] logabsdet = [1.609438, -inf, 1.609438]

Defined in src/operator/tensor/la_op.cc:L1027

Value

out The result mx.symbol

```
mx.symbol.linalg_sumlogdiag
```

linalg_sumlogdiag:Computes the sum of the logarithms of the diagonal elements of a square matrix. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, *A* must be square with positive diagonal entries. We sum the natural logarithms of the diagonal elements, the result has shape (1,).

Usage

```
mx.symbol.linalg_sumlogdiag(...)
```

Arguments

A NDArray-or-Symbol Tensor of square matrices

name string, optional Name of the resulting symbol.

Details

If *n>2*, *sumlogdiag* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix reduction A = [[1.0, 1.0], [1.0, 7.0]] sumlogdiag(A) = [1.9459]

Batch matrix reduction A = [[[1.0, 1.0], [1.0, 7.0]], [[3.0, 0], [0, 17.0]]] sumlogdiag(A) = [1.9459, 3.9318]

Defined in src/operator/tensor/la_op.cc:L445

Value

mx.symbol.linalg_syrk linalg_syrk:Multiplication of matrix with its transpose. Input is a tensor *A* of dimension *n >= 2*.

Description

If *n=2*, the operator performs the BLAS3 function *syrk*:

Usage

```
mx.symbol.linalg_syrk(...)
```

Arguments

A NDArray-or-Symbol Tensor of input matrices

transpose boolean, optional, default=0 Use transpose of input matrix.

alpha double, optional, default=1 Scalar factor to be applied to the result.

name string, optional Name of the resulting symbol.

Details

```
*out* = *alpha* \* *A* \* *A*\ :sup: 'T' if *transpose=False*, or 
*out* = *alpha* \* *A*\ :sup: 'T' \ \* *A* if *transpose=True*.
```

If *n>2*, *syrk* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

```
Single matrix multiply A = [[1., 2., 3.], [4., 5., 6.]] syrk(A, alpha=1., transpose=False) = [[14., 32.], [32., 77.]] syrk(A, alpha=1., transpose=True) = [[17., 22., 27.], [22., 29., 36.], [27., 36., 45.]]
```

Batch matrix multiply A = [[[1., 1.]], [[0.1, 0.1]]] syrk(A, alpha=2., transpose=False) = [[[4.]], [[0.04]]]

Defined in src/operator/tensor/la_op.cc:L730

Value

mx.symbol.linalg_trmm $linalg_trmm:Performs$ multiplication with a lower triangular matrix. Input are tensors *A*, *B*, each of dimension *n >= 2* $ext{and having}$ $ext{the same shape on the leading *n-2* dimensions}.$

Description

If *n=2*, *A* must be triangular. The operator performs the BLAS3 function *trmm*:

Usage

```
mx.symbol.linalg_trmm(...)
```

Arguments

A	NDArray-or-Symbol Tensor of lower triangular matrices
В	NDArray-or-Symbol Tensor of matrices

transpose boolean, optional, default=0 Use transposed of the triangular matrix

rightside boolean, optional, default=0 Multiply triangular matrix from the right to non-

triangular one.

lower boolean, optional, default=1 True if the triangular matrix is lower triangular,

false if it is upper triangular.

alpha double, optional, default=1 Scalar factor to be applied to the result.

name string, optional Name of the resulting symbol.

Details

```
*out* = *alpha* \* *op*\ (*A*) \* *B*
if *rightside=False*, or
*out* = *alpha* \* *B* \* *op*\ (*A*)
```

if *rightside=True*. Here, *alpha* is a scalar parameter, and *op()* is either the identity or the matrix transposition (depending on *transpose*).

If *n>2*, *trmm* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single triangular matrix multiply A = [[1.0, 0], [1.0, 1.0]] B = [[1.0, 1.0, 1.0], [1.0, 1.0]] trmm(A, B, alpha=2.0) = [[2.0, 2.0, 2.0], [4.0, 4.0, 4.0]]

Batch triangular matrix multiply A = [[[1.0, 0], [1.0, 1.0]], [[1.0, 0], [1.0, 1.0]]] B = [[[1.0, 1.0, 1.0], [1.0, 1.0]], [[0.5, 0.5, 0.5], [0.5, 0.5, 0.5]]] trmm(A, B, alpha=2.0) = [[[2.0, 2.0, 2.0], [4.0, 4.0, 4.0]], [[1.0, 1.0, 1.0], [2.0, 2.0, 2.0]]]

Defined in src/operator/tensor/la_op.cc:L333

Value

out The result mx.symbol

mx.symbol.linalg_trsm linalg_trsm:Solves matrix equation involving a lower triangular matrix. Input are tensors *A*, *B*, each of dimension *n >= 2* and having the same shape on the leading *n-2* dimensions.

Description

If *n=2*, *A* must be triangular. The operator performs the BLAS3 function *trsm*, solving for *out* in:

Usage

```
mx.symbol.linalg_trsm(...)
```

Arguments

A NDArray-or-Symbol Tensor of lower triangular matrices

B NDArray-or-Symbol Tensor of matrices

transpose boolean, optional, default=0 Use transposed of the triangular matrix

rightside boolean, optional, default=0 Multiply triangular matrix from the right to non-

triangular one.

lower boolean, optional, default=1 True if the triangular matrix is lower triangular,

false if it is upper triangular.

alpha double, optional, default=1 Scalar factor to be applied to the result.

name string, optional Name of the resulting symbol.

Details

```
*op*\(*A*)\* *out* = *alpha* \* *B*
if *rightside=False*, or
```

$$*out* \ **op* \ (*A*) = *alpha* \ **B*$$

if *rightside=True*. Here, *alpha* is a scalar parameter, and *op()* is either the identity or the matrix transposition (depending on *transpose*).

If *n>2*, *trsm* is performed separately on the trailing two dimensions for all inputs (batch mode).

.. note:: The operator supports float32 and float64 data types only.

Examples::

Single matrix solve A = [[1.0, 0], [1.0, 1.0]] B = [[2.0, 2.0, 2.0], [4.0, 4.0, 4.0]] trsm(A, B, alpha=0.5) = [[1.0, 1.0, 1.0], [1.0, 1.0, 1.0]]

Batch matrix solve A = [[[1.0, 0], [1.0, 1.0]], [[1.0, 0], [1.0, 1.0]]] B = [[[2.0, 2.0, 2.0], [4.0, 4.0, 4.0]], [[4.0, 4.0, 4.0], [8.0, 8.0, 8.0]]] trsm(A, B, alpha=0.5) = [[[1.0, 1.0, 1.0], [1.0, 1.0, 1.0]], [[2.0, 2.0, 2.0], [2.0, 2.0, 2.0]]]

Defined in src/operator/tensor/la_op.cc:L396

Value

out The result mx.symbol

mx.symbol.LinearRegressionOutput

LinearRegressionOutput:Computes and optimizes for squared loss during backward propagation. Just outputs "data" during forward propagation.

Description

If :math: '\haty_i' is the predicted value of the i-th sample, and :math: 'y_i' is the corresponding target value, then the squared loss estimated over :math: 'n' samples is defined as

Usage

```
mx.symbol.LinearRegressionOutput(...)
```

Arguments

data NDArray-or-Symbol Input data to the function.

1abel NDArray-or-Symbol Input label to the function.

grad.scale float, optional, default=1 Scale the gradient by a float factor

name string, optional Name of the resulting symbol.

Details

 $: math: `\text{textSquaredLoss}(\text{textbfY}, \text{hat}\text{textbfY}) = \frac{1n \sum_{i=0}^{n-1} \text{textbfy}_i - \text{hat}\text{textbfy}_i - \text{hat}\text{textbfy}_i$

.. note:: Use the LinearRegressionOutput as the final output layer of a net.

The storage type of "label" can be "default" or "csr"

 $- Linear Regression Output (default, \ default) = default - Linear Regression Output (default, \ csr) = default$

By default, gradients of this loss function are scaled by factor '1/m', where m is the number of regression outputs of a training example. The parameter 'grad_scale' can be used to change this scale to 'grad_scale/m'.

Defined in src/operator/regression_output.cc:L92

Value

380 mx.symbol.load.json

 ${\it mx.symbol.load}$

Load an mx.symbol object

Description

Load an mx.symbol object

Usage

```
mx.symbol.load(file.name)
```

Arguments

filename

the filename (including the path)

Examples

```
data = mx.symbol.Variable('data')
mx.symbol.save(data, 'temp.symbol')
data2 = mx.symbol.load('temp.symbol')
```

mx.symbol.load.json

Load an mx.symbol object from a json string

Description

Load an mx.symbol object from a json string

Arguments

str

the json str represent a mx.symbol

mx.symbol.log 381

mx.symbol.log

log:Returns element-wise Natural logarithmic value of the input.

Description

The natural logarithm is logarithm in base *e*, so that "log(exp(x)) = x"

Usage

```
mx.symbol.log(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "log" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L76

Value

out The result mx.symbol

mx.symbol.log10

log10:Returns element-wise Base-10 logarithmic value of the input.

Description

```
10**log10(x) = x
```

Usage

```
mx.symbol.log10(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "log10" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L93

382 mx.symbol.log2

Value

out The result mx.symbol

mx.symbol.log1p

log1p:Returns element-wise "log(1 + x)" value of the input.

Description

This function is more accurate than "log(1 + x)" for small "x" so that :math: '1+x\approx 1'

Usage

```
mx.symbol.log1p(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "log1p" output depends upon the input storage type:

 $-\log 1p(\text{default}) = \text{default} - \log 1p(\text{row_sparse}) = \text{row_sparse} - \log 1p(\text{csr}) = \text{csr}$

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L206

Value

out The result mx.symbol

mx.symbol.log2

log2:Returns element-wise Base-2 logarithmic value of the input.

Description

$$2**\log 2(x) = x$$

Usage

```
mx.symbol.log2(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

mx.symbol.logical_not

Details

The storage type of "log2" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_logexp.cc:L105

Value

out The result mx.symbol

mx.symbol.logical_not logical_not:Returns the result of logical NOT (!) function

Description

```
Example: logical_not([-2., 0., 1.]) = [0., 1., 0.]
```

Usage

```
mx.symbol.logical_not(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

```
\verb|mx.symbol.LogisticRegressionOutput|\\
```

LogisticRegressionOutput:Applies a logistic function to the input.

Description

The logistic function, also known as the sigmoid function, is computed as :math: '\frac11+exp(-\textbfx)'.

Usage

```
mx.symbol.LogisticRegressionOutput(...)
```

Arguments

data NDArray-or-Symbol Input data to the function.

1abel NDArray-or-Symbol Input label to the function.

grad. scale float, optional, default=1 Scale the gradient by a float factor

name string, optional Name of the resulting symbol.

Details

Commonly, the sigmoid is used to squash the real-valued output of a linear model :math: 'wTx+b' into the [0,1] range so that it can be interpreted as a probability. It is suitable for binary classification or probability prediction tasks.

.. note:: Use the LogisticRegressionOutput as the final output layer of a net.

The storage type of "label" can be "default" or "csr"

LogisticRegressionOutput(default, default) = default - LogisticRegressionOutput(default, csr) = default

The loss function used is the Binary Cross Entropy Loss:

```
:math: -(y\log(p) + (1 - y)\log(1 - p))
```

Where 'y' is the ground truth probability of positive outcome for a given example, and 'p' the probability predicted by the model. By default, gradients of this loss function are scaled by factor '1/m', where m is the number of regression outputs of a training example. The parameter 'grad_scale' can be used to change this scale to 'grad_scale/m'.

Defined in src/operator/regression_output.cc:L152

Value

out The result mx.symbol

Description

Examples::

Usage

```
mx.symbol.log_softmax(...)
```

mx.symbol.LRN 385

Arguments

data	NDArray-or-Symbol The input array.
axis	int, optional, default='-1' The axis along which to compute softmax.
temperature	double or None, optional, default=None Temperature parameter in softmax
dtype	None, 'float16', 'float32', 'float64',optional, default='None' DType of the output in case this can't be inferred. Defaults to the same as input's dtype if not defined (dtype=None).
use.length	boolean or None, optional, default=0 Whether to use the length input as a mask over the data input.
name	string, optional Name of the resulting symbol.

Details

```
>> x = mx.nd.array([1, 2, .1]) >> mx.nd.log_softmax(x).asnumpy() array([-1.41702998, -0.41702995, -2.31702995], dtype=float32)
>> x = mx.nd.array([[1, 2, .1],[.1, 2, 1]]) >> mx.nd.log_softmax(x, axis=0).asnumpy() array([[-0.34115392, -0.69314718, -1.24115396], [-1.24115396, -0.69314718, -0.34115392]], dtype=float32)
```

Value

out The result mx.symbol

mx.symbol.LRN	LRN:Applies local response normalization to the input.
---------------	--

Description

The local response normalization layer performs "lateral inhibition" by normalizing over local input regions.

Usage

```
mx.symbol.LRN(...)
```

Arguments

data	NDArray-or-Symbol Input data to LRN
alpha	float, optional, default=9.99999975e-05 The variance scaling parameter :math: '\alpha' in the LRN expression.
beta	float, optional, default=0.75 The power parameter :math:'\beta' in the LRN expression.
knorm	float, optional, default=2 The parameter :math:'k' in the LRN expression.
nsize	int (non-negative), required normalization window width in elements.
name	string, optional Name of the resulting symbol.

If :math: 'a_x,y^i' is the activity of a neuron computed by applying kernel :math: 'i' at position :math: '(x, y)' and then applying the ReLU nonlinearity, the response-normalized activity :math: 'b_x,y^i' is given by the expression:

.. math:: b_x,y^i = $\frac{x,y^i}Bigg(k + \frac{sum_j=max(0, i-\frac{2)^min(N-1, i+\frac{2)}{n}}{2}}{(a_x,y^j)^2}Bigg)^beta$

where the sum runs over :math: 'n' "adjacent" kernel maps at the same spatial position, and :math: 'N' is the total number of kernels in the layer.

Defined in src/operator/nn/lrn.cc:L164

Value

out The result mx.symbol

mx.symbol.MAERegressionOutput

MAERegressionOutput:Computes mean absolute error of the input.

Description

MAE is a risk metric corresponding to the expected value of the absolute error.

Usage

```
mx.symbol.MAERegressionOutput(...)
```

Arguments

data NDArray-or-Symbol Input data to the function.

1abel NDArray-or-Symbol Input label to the function.

grad.scale float, optional, default=1 Scale the gradient by a float factor

name string, optional Name of the resulting symbol.

Details

If :math: '\haty_i' is the predicted value of the i-th sample, and :math: 'y_i' is the corresponding target value, then the mean absolute error (MAE) estimated over :math: 'n' samples is defined as :math: '\textMAE(\textbfY, \hat\textbfY) = \frac1n \sum_i=0^n-1 \lVert \textbfy_i - \hat\textbfy_i \rVert 1'

.. note:: Use the MAERegressionOutput as the final output layer of a net.

The storage type of "label" can be "default" or "csr"

- MAERegressionOutput(default, default) = default - MAERegressionOutput(default, csr) = default By default, gradients of this loss function are scaled by factor '1/m', where m is the number of regression outputs of a training example. The parameter 'grad_scale' can be used to change this scale to 'grad scale/m'.

Defined in src/operator/regression_output.cc:L120

mx.symbol.MakeLoss 387

Value

out The result mx.symbol

mx.symbol.MakeLoss

MakeLoss:Make your own loss function in network construction.

Description

This operator accepts a customized loss function symbol as a terminal loss and the symbol should be an operator with no backward dependency. The output of this function is the gradient of loss with respect to the input data.

Usage

```
mx.symbol.MakeLoss(...)
```

Arguments

data NDArray-or-Symbol Input array.

grad.scale float, optional, default=1 Gradient scale as a supplement to unary and binary

operators

valid.thresh float, optional, default=0 clip each element in the array to 0 when it is less than

"valid_thresh". This is used when "normalization" is set to "valid".

normalization 'batch', 'null', 'valid', optional, default='null' If this is set to null, the output

gradient will not be normalized. If this is set to batch, the output gradient will be divided by the batch size. If this is set to valid, the output gradient will be

divided by the number of valid input elements.

name string, optional Name of the resulting symbol.

Details

For example, if you are a making a cross entropy loss function. Assume "out" is the predicted output and "label" is the true label, then the cross entropy can be defined as::

```
cross\_entropy = label * log(out) + (1 - label) * log(1 - out) loss = MakeLoss(cross\_entropy)
```

We will need to use "MakeLoss" when we are creating our own loss function or we want to combine multiple loss functions. Also we may want to stop some variables' gradients from backpropagation. See more detail in "BlockGrad" or "stop_gradient".

In addition, we can give a scale to the loss by setting "grad_scale", so that the gradient of the loss will be rescaled in the backpropagation.

.. note:: This operator should be used as a Symbol instead of NDArray.

Defined in src/operator/make_loss.cc:L71

Value

388 mx.symbol.max

mx.symbol.make_loss

make_loss:Make your own loss function in network construction.

Description

This operator accepts a customized loss function symbol as a terminal loss and the symbol should be an operator with no backward dependency. The output of this function is the gradient of loss with respect to the input data.

Usage

```
mx.symbol.make_loss(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

For example, if you are a making a cross entropy loss function. Assume "out" is the predicted output and "label" is the true label, then the cross entropy can be defined as::

```
cross\_entropy = label * log(out) + (1 - label) * log(1 - out) loss = make\_loss(cross\_entropy)
```

We will need to use "make_loss" when we are creating our own loss function or we want to combine multiple loss functions. Also we may want to stop some variables' gradients from backpropagation. See more detail in "BlockGrad" or "stop_gradient".

The storage type of "make_loss" output depends upon the input storage type:

- make_loss(default) = default - make_loss(row_sparse) = row_sparse

Defined in src/operator/tensor/elemwise unary op basic.cc:L360

Value

out The result mx.symbol

mx.symbol.max

max: Computes the max of array elements over given axes.

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L32

Usage

```
mx.symbol.max(...)
```

mx.symbol.max_axis 389

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.max_axis

max_axis:Computes the max of array elements over given axes.

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L32

Usage

```
mx.symbol.max_axis(...)
```

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead

Negative values means indexing from right to left.

390 mx.symbol.mean

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.mean

mean: Computes the mean of array elements over given axes.

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L83

Usage

```
mx.symbol.mean(...)
```

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

name string, optional Name of the resulting symbol.

Value

mx.symbol.moments 391

mx.symbol.moments

moments: Calculate the mean and variance of 'data'.

Description

The mean and variance are calculated by aggregating the contents of data across axes. If x is 1-D and axes = [0] this is just the mean and variance of a vector.

Usage

```
mx.symbol.moments(...)
```

Arguments

data NDArray-or-Symbol Input ndarray

axes Shape or None, optional, default=None Array of ints. Axes along which to

compute mean and variance.

keepdims boolean, optional, default=0 produce moments with the same dimensionality as

the input.

name string, optional Name of the resulting symbol.

Details

Example:

```
x = [[1, 2, 3], [4, 5, 6]] mean, var = moments(data=x, axes=[0]) mean = [2.5, 3.5, 4.5] var = [2.25, 2.25, 2.25] mean, var = moments(data=x, axes=[1]) mean = [2.0, 5.0] var = [0.66666667] mean, var = moments(data=x, axis=[0, 1]) mean = [3.5] var = [2.9166667]
```

Defined in src/operator/nn/moments.cc:L54

Value

out The result mx.symbol

```
mx.symbol.mp_nag_mom_update
```

mp_nag_mom_update:Update function for multi-precision Nesterov Accelerated Gradient(NAG) optimizer.

Description

Defined in src/operator/optimizer_op.cc:L743

Usage

```
mx.symbol.mp_nag_mom_update(...)
```

Arguments

weight NDArray-or-Symbol Weight
grad NDArray-or-Symbol Gradient
mom NDArray-or-Symbol Momentum
weight32 NDArray-or-Symbol Weight32
lr float, required Learning rate

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

```
mx.symbol.mp_sgd_mom_update
```

mp_sgd_mom_update:Updater function for multi-precision sgd optimizer

Description

mp_sgd_mom_update:Updater function for multi-precision sgd optimizer

Usage

```
mx.symbol.mp_sgd_mom_update(...)
```

Arguments

weight NDArray-or-Symbol Weight grad NDArray-or-Symbol Gradient MDArray-or-Symbol Momentum weight32 NDArray-or-Symbol Weight32 1r float, required Learning rate

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip_gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

lazy.update boolean, optional, default=1 If true, lazy updates are applied if gradient's stype

is row_sparse and both weight and momentum have the same stype

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.mp_sgd_update

mp_sgd_update:Updater function for multi-precision sgd optimizer

Description

mp sgd update: Updater function for multi-precision sgd optimizer

Usage

```
mx.symbol.mp_sgd_update(...)
```

Arguments

weight NDArray-or-Symbol Weight grad NDArray-or-Symbol gradient weight32 NDArray-or-Symbol Weight32 lr float, required Learning rate

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

lazy.update boolean, optional, default=1 If true, lazy updates are applied if gradient's stype

is row_sparse.

name string, optional Name of the resulting symbol.

394 mx.symbol.multi_lars

Value

out The result mx.symbol

```
mx.symbol.multi_all_finite
```

multi_all_finite: Check if all the float numbers in all the arrays are finite (used for AMP)

Description

Defined in src/operator/contrib/all_finite.cc:L133

Usage

```
mx.symbol.multi_all_finite(...)
```

Arguments

data NDArray-or-Symbol[] Arrays

num.arrays int, optional, default='1' Number of arrays.

init.output boolean, optional, default=1 Initialize output to 1.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.multi_lars multi_lars:Compute the LARS coefficients of multiple weights and grads from their sums of square"

Description

Defined in src/operator/contrib/multi_lars.cc:L37

Usage

```
mx.symbol.multi_lars(...)
```

Arguments

1rs NDArray-or-Symbol Learning rates to scale by LARS coefficient

weights.sum.sq NDArray-or-Symbol sum of square of weights arrays grads.sum.sq NDArray-or-Symbol sum of square of gradients arrays

wds NDArray-or-Symbol weight decays

eta float, required LARS eta eps float, required LARS eps

rescale.grad float, optional, default=1 Gradient rescaling factor string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.multi_mp_sgd_mom_update

multi_mp_sgd_mom_update:Momentum update function for multiprecision Stochastic Gradient Descent (SGD) optimizer.

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Usage

```
mx.symbol.multi_mp_sgd_mom_update(...)
```

Arguments

data NDArray-or-Symbol[] Weights

1rs tuple of <float>, required Learning rates.

wds tuple of <float>, required Weight decay augments the objective function with

a regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

name string, optional Name of the resulting symbol.

```
.. math:: v_1 = \alpha V_0 \times V_t = \gamma V_t - \alpha V_t
```

Value

out The result mx.symbol

```
mx.symbol.multi\_mp\_sgd\_update
```

multi_mp_sgd_update:Update function for multi-precision Stochastic Gradient Descent (SDG) optimizer.

Description

It updates the weights using::

Usage

```
mx.symbol.multi_mp_sgd_update(...)
```

Arguments

data	NDArray-or-Symbol[] Weights
lrs	tuple of <float>, required Learning rates.</float>
wds	tuple of <float>, required Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.</float>
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
num.weights	int, optional, default='1' Number of updated weights.
name	string, optional Name of the resulting symbol.

Details

```
weight = weight - learning_rate * (gradient + wd * weight)
Defined in src/operator/optimizer_op.cc:L415
```

Value

out The result mx.symbol

```
{\tt mx.symbol.multi\_sgd\_mom\_update}
```

multi_sgd_mom_update:Momentum update function for Stochastic Gradient Descent (SGD) optimizer.

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Usage

```
mx.symbol.multi_sgd_mom_update(...)
```

Arguments

data	NDArray-or-Symbol[] Weights, gradients and momentum
lrs	tuple of <float>, required Learning rates.</float>
wds	tuple of <float>, required Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.</float>
momentum	float, optional, default=0 The decay rate of momentum estimates at each epoch.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
num.weights	int, optional, default='1' Number of updated weights.
name	string, optional Name of the resulting symbol.

Details

```
.. math:: v_1 = \alpha V_0 \times V_t = \gamma V_1 - \alpha V_1
```

Value

```
{\tt mx.symbol.multi\_sgd\_update}
```

multi_sgd_update:Update function for Stochastic Gradient Descent (SDG) optimizer.

Description

It updates the weights using::

Usage

```
mx.symbol.multi_sgd_update(...)
```

Arguments

data	NDArray-or-Symbol[] Weights
lrs	tuple of <float>, required Learning rates.</float>
wds	tuple of <float>, required Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.</float>
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
num.weights	int, optional, default='1' Number of updated weights.
name	string, optional Name of the resulting symbol.

Details

```
weight = weight - learning_rate * (gradient + wd * weight)
Defined in src/operator/optimizer_op.cc:L327
```

Value

```
mx.symbol.multi_sum_sq
```

multi_sum_sq:Compute the sums of squares of multiple arrays

Description

Defined in src/operator/contrib/multi_sum_sq.cc:L36

Usage

```
mx.symbol.multi_sum_sq(...)
```

Arguments

data NDArray-or-Symbol[] Arrays

num.arrays int, required number of input arrays.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

```
mx.symbol.nag_mom_update
```

nag_mom_update:Update function for Nesterov Accelerated Gradient(NAG) optimizer. It updates the weights using the following formula,

Description

```
.. math:: v_t = \gamma v_{t-1} + \epsilon * \Lambda J(W_{t-1} - \gamma v_t) W_t = W_{t-1} - v_t
```

Usage

```
mx.symbol.nag_mom_update(...)
```

Arguments

weight NDArray-or-Symbol Weight
grad NDArray-or-Symbol Gradient
mom NDArray-or-Symbol Momentum
lr float, required Learning rate

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

400 mx.symbol.nanprod

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

name string, optional Name of the resulting symbol.

Details

Where :math: '\eta' is the learning rate of the optimizer :math: '\gamma' is the decay rate of the momentum estimate :math: '\v_t' is the update vector at time step 't' :math: '\W_t' is the weight vector at time step 't'

Defined in src/operator/optimizer_op.cc:L724

Value

out The result mx.symbol

mx.symbol.nanprod nanprod:Computes the product of array elements over given axes

treating Not a Numbers ("NaN") as one.

Description

nanprod:Computes the product of array elements over given axes treating Not a Numbers ("NaN") as one.

Usage

```
mx.symbol.nanprod(...)
```

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

mx.symbol.nansum 401

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

name string, optional Name of the resulting symbol.

Details

Defined in src/operator/tensor/broadcast_reduce_prod_value.cc:L46

Value

out The result mx.symbol

mx.symbol.nansum nansum: Computes the sum of array elements over given axes treating Not a Numbers ("NaN") as zero.

Description

nansum:Computes the sum of array elements over given axes treating Not a Numbers ("NaN") as zero.

Usage

```
mx.symbol.nansum(...)
```

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

name string, optional Name of the resulting symbol.

402 mx.symbol.norm

Details

Defined in src/operator/tensor/broadcast_reduce_sum_value.cc:L100

Value

out The result mx.symbol

mx.symbol.negative

negative: Numerical negative of the argument, element-wise.

Description

The storage type of "negative" output depends upon the input storage type:

Usage

```
mx.symbol.negative(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
- negative(default) = default - negative(row_sparse) = row_sparse - negative(csr) = csr
```

Value

out The result mx.symbol

mx.symbol.norm

norm: Computes the norm on an NDArray.

Description

This operator computes the norm on an NDArray with the specified axis, depending on the value of the ord parameter. By default, it computes the L2 norm on the entire array. Currently only ord=2 supports sparse ndarrays.

Usage

```
mx.symbol.norm(...)
```

mx.symbol.normal 403

Arguments

data	NDArray-or-Symbol The input
ord	int, optional, default='2' Order of the norm. Currently ord=1 and ord=2 is supported.
axis	Shape or None, optional, default=None The axis or axes along which to perform the reduction. The default, 'axis=()', will compute over all elements into a scalar array with shape '(1,)'. If 'axis' is int, a reduction is performed on a particular axis. If 'axis' is a 2-tuple, it specifies the axes that hold 2-D matrices, and the matrix norms of these matrices are computed.
out.dtype	None, 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', optional, default='None' The data type of the output.
keepdims	boolean, optional, default=0 If this is set to 'True', the reduced axis is left in the result as dimension with size one.
name	string, optional Name of the resulting symbol.

Details

```
Examples::
```

```
x = [[[1, 2], [3, 4]], [[2, 2], [5, 6]]]

norm(x, ord=2, axis=1) = [[3.1622777 4.472136] [5.3851647 6.3245554]]

norm(x, ord=1, axis=1) = [[4., 6.], [7., 8.]]

rsp = x.cast_storage('row_sparse')

norm(rsp) = [5.47722578]

csr = x.cast_storage('csr')

norm(csr) = [5.47722578]

Defined in src/operator/tensor/broadcast_reduce_norm_value.cc:L89
```

Value

out The result mx.symbol

mx.symbol.normal

normal:Draw random samples from a normal (Gaussian) distribution.

Description

.. note:: The existing alias "normal" is deprecated.

Usage

```
mx.symbol.normal(...)
```

Arguments

loc	float, optional, default=0 Mean of the distribution.
scale	float, optional, default=1 Standard deviation of the distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

Samples are distributed according to a normal distribution parametrized by *loc* (mean) and *scale* (standard deviation).

Example::

```
normal(loc=0, scale=1, shape=(2,2)) = [[ 1.89171135, -1.16881478], [-1.23474145, 1.55807114]] Defined in src/operator/random/sample_op.cc:L113
```

Value

out The result mx.symbol

Description

Examples::

Usage

```
mx.symbol.ones_like(...)
```

Arguments

data	NDArray-or-Symbol	The input
------	-------------------	-----------

name string, optional Name of the resulting symbol.

Details

```
x = [[0., 0., 0.], [0., 0., 0.]]
ones_like(x) = [[1., 1., 1.], [1., 1., 1.]]
```

mx.symbol.one_hot 405

Value

out The result mx.symbol

mx.symbol.one_hot

one_hot:Returns a one-hot array.

Description

The locations represented by 'indices' take value 'on_value', while all other locations take value 'off_value'.

Usage

```
mx.symbol.one_hot(...)
```

Arguments

indices NDArray-or-Symbol array of locations where to set on_value

depth int, required Depth of the one hot dimension.

on.value double, optional, default=1 The value assigned to the locations represented by indices.

off.value double, optional, default=0 The value assigned to the locations not represented by indices.

dtype 'float16', 'float32', 'float64', 'int32', 'int64', 'int8', 'uint8', optional, default='float32'
DType of the output

Details

name

```
'one_hot' operation with 'indices' of shape "(i0, i1)" and 'depth' of "d" would result in an output array of shape "(i0, i1, d)" with:: output[i,j,:] = off_value output[i,j,indices[i,j]] = on_value  

Examples:: one_hot([1,0,2,0], 3) = [[ 0. 1. 0.] [ 1. 0. 0.] [ 0. 0. 1.] [ 1. 0. 0.]]  
one_hot([1,0,2,0], 3, on_value=8, off_value=1, dtype='int32') = [[1 8 1] [8 1 1] [1 1 8] [8 1 1]]  
one_hot([[1,0],[1,0],[2,0]], 3) = [[[ 0. 1. 0.] [ 1. 0. 0.]]  
[[ 0. 1. 0.] [ 1. 0. 0.]]  
[[ 0. 0. 1.] [ 1. 0. 0.]]]  
Defined in src/operator/tensor/indexing_op.cc:L821
```

string, optional Name of the resulting symbol.

Value

406 mx.symbol.Pad

mx.symbol.Pad

Pad: Pads an input array with a constant or edge values of the array.

Description

.. note:: 'Pad' is deprecated. Use 'pad' instead.

Usage

```
mx.symbol.Pad(...)
```

Arguments

data NDArray-or-Symbol An n-dimensional input array.

mode 'constant', 'edge', 'reflect', required Padding type to use. "constant" pads with

'constant_value' "edge" pads using the edge values of the input array "reflect"

pads by reflecting values with respect to the edges.

pad.width Shape(tuple), required Widths of the padding regions applied to the edges of

each axis. It is a tuple of integer padding widths for each axis of the format "(before_1, after_1, ..., before_N, after_N)". It should be of length "2*N" where "N" is the number of dimensions of the array. This is equivalent to pad_width in

numpy.pad, but flattened.

constant.value double, optional, default=0 The value used for padding when 'mode' is "con-

stant".

name string, optional Name of the resulting symbol.

Details

.. note:: Current implementation only supports 4D and 5D input arrays with padding applied only on axes 1, 2 and 3. Expects axes 4 and 5 in 'pad_width' to be zero.

This operation pads an input array with either a 'constant_value' or edge values along each axis of the input array. The amount of padding is specified by 'pad_width'.

'pad_width' is a tuple of integer padding widths for each axis of the format "(before_1, after_1, ..., before_N, after_N)". The 'pad_width' should be of length "2*N" where "N" is the number of dimensions of the array.

For dimension "N" of the input array, "before_N" and "after_N" indicates how many values to add before and after the elements of the array along dimension "N". The widths of the higher two dimensions "before_1", "after_1", "before_2", "after_2" must be 0.

Example::

```
x = [[[[ 1. 2. 3.] [ 4. 5. 6.]]
[[ 7. 8. 9.] [ 10. 11. 12.]]]
[[[ 11. 12. 13.] [ 14. 15. 16.]]
[[ 17. 18. 19.] [ 20. 21. 22.]]]]
```

mx.symbol.pad 407

```
pad(x,mode="edge", pad_width=(0,0,0,0,1,1,1,1)) =

[[[[ 1. 1. 2. 3. 3.] [ 1. 1. 2. 3. 3.] [ 4. 4. 5. 6. 6.] [ 4. 4. 5. 6. 6.]]

[[ 7. 7. 8. 9. 9.] [ 7. 7. 8. 9. 9.] [ 10. 10. 11. 12. 12.] [ 10. 10. 11. 12. 12.]]]

[[[ 11. 11. 12. 13. 13.] [ 11. 11. 12. 13. 13.] [ 14. 14. 15. 16. 16.] [ 14. 14. 15. 16. 16.]]

[[ 17. 17. 18. 19. 19.] [ 17. 17. 18. 19. 19.] [ 20. 20. 21. 22. 22.] [ 20. 20. 21. 22. 22.]]]]

pad(x, mode="constant", constant_value=0, pad_width=(0,0,0,0,1,1,1,1)) =

[[[ 0. 0. 0. 0. 0.] [ 0. 1. 2. 3. 0.] [ 0. 4. 5. 6. 0.] [ 0. 0. 0. 0. 0.]]

[[ 0. 0. 0. 0. 0.] [ 0. 7. 8. 9. 0.] [ 0. 10. 11. 12. 0.] [ 0. 0. 0. 0. 0.]]

[[ 0. 0. 0. 0. 0.] [ 0. 17. 18. 19. 0.] [ 0. 20. 21. 22. 0.] [ 0. 0. 0. 0. 0.]]]]

Defined in src/operator/pad.cc:L766
```

Value

out The result mx.symbol

mx.symbol.pad

pad:Pads an input array with a constant or edge values of the array.

Description

.. note:: 'Pad' is deprecated. Use 'pad' instead.

Usage

```
mx.symbol.pad(...)
```

Arguments

data	NDArray-or-Symbol An n-dimensional inp	ut array.
------	--	-----------

mode 'constant', 'edge', 'reflect', required Padding type to use. "constant" pads with

'constant_value' "edge" pads using the edge values of the input array "reflect"

pads by reflecting values with respect to the edges.

pad.width Shape(tuple), required Widths of the padding regions applied to the edges of

each axis. It is a tuple of integer padding widths for each axis of the format "(before_1, after_1, ..., before_N, after_N)". It should be of length "2*N" where "N" is the number of dimensions of the array. This is equivalent to pad_width in

numpy.pad, but flattened.

constant.value double, optional, default=0 The value used for padding when 'mode' is "con-

stant".

name string, optional Name of the resulting symbol.

408 mx.symbol.pick

Details

.. note:: Current implementation only supports 4D and 5D input arrays with padding applied only on axes 1, 2 and 3. Expects axes 4 and 5 in 'pad_width' to be zero.

This operation pads an input array with either a 'constant_value' or edge values along each axis of the input array. The amount of padding is specified by 'pad_width'.

'pad_width' is a tuple of integer padding widths for each axis of the format "(before_1, after_1, ..., before_N, after_N)". The 'pad_width' should be of length "2*N" where "N" is the number of dimensions of the array.

For dimension "N" of the input array, "before_N" and "after_N" indicates how many values to add before and after the elements of the array along dimension "N". The widths of the higher two dimensions "before_1", "after_1", "before_2", "after_2" must be 0.

Example::

```
x = [[[[ 1. 2. 3.] [ 4. 5. 6.]]
[[ 7. 8. 9.] [ 10. 11. 12.]]]
[[[ 11. 12. 13.] [ 14. 15. 16.]]
[[ 17. 18. 19.] [ 20. 21. 22.]]]]
pad(x,mode="edge", pad_width=(0,0,0,1,1,1,1)) =
[[[[ 1. 1. 2. 3. 3.] [ 1. 1. 2. 3. 3.] [ 4. 4. 5. 6. 6.] [ 4. 4. 5. 6. 6.]]
[[ 7. 7. 8. 9. 9.] [ 7. 7. 8. 9. 9.] [ 10. 10. 11. 12. 12.] [ 10. 10. 11. 12. 12.]]]
[[[ 11. 11. 12. 13. 13.] [ 11. 11. 12. 13. 13.] [ 14. 14. 15. 16. 16.] [ 14. 14. 15. 16. 16.]]
[[ 17. 17. 18. 19. 19.] [ 17. 17. 18. 19. 19.] [ 20. 20. 21. 22. 22.] [ 20. 20. 21. 22. 22.]]]]
pad(x, mode="constant", constant_value=0, pad_width=(0,0,0,0,1,1,1,1)) =
[[[ 0. 0. 0. 0. 0.] [ 0. 1. 2. 3. 0.] [ 0. 4. 5. 6. 0.] [ 0. 0. 0. 0. 0.]]
[[ 0. 0. 0. 0. 0.] [ 0. 11. 12. 13. 0.] [ 0. 14. 15. 16. 0.] [ 0. 0. 0. 0. 0.]]
[[ 0. 0. 0. 0. 0.] [ 0. 17. 18. 19. 0.] [ 0. 20. 21. 22. 0.] [ 0. 0. 0. 0. 0.]]]]
Defined in src/operator/pad.cc:L766
```

Value

out The result mx.symbol

mx.symbol.pick pick: Picks elements from an input array according to the input indices along the given axis.

Description

Given an input array of shape "(d0, d1)" and indices of shape "(i0,)", the result will be an output array of shape "(i0,)" with::

mx.symbol.pick 409

Usage

```
mx.symbol.pick(...)
```

Arguments

data NDArray-or-Symbol The input array index NDArray-or-Symbol The index array

axis int or None, optional, default='-1' int or None. The axis to picking the elements.

Negative values means indexing from right to left. If is 'None', the elements in

the index w.r.t the flattened input will be picked.

keepdims boolean, optional, default=0 If true, the axis where we pick the elements is left

in the result as dimension with size one.

mode 'clip', 'wrap', optional, default='clip' Specify how out-of-bound indices behave.

Default is "clip". "clip" means clip to the range. So, if all indices mentioned are too large, they are replaced by the index that addresses the last element along an

axis. "wrap" means to wrap around.

name string, optional Name of the resulting symbol.

Details

output[i] = input[i, indices[i]]

By default, if any index mentioned is too large, it is replaced by the index that addresses the last element along an axis (the 'clip' mode).

This function supports n-dimensional input and (n-1)-dimensional indices arrays.

Examples::

```
x = [[1., 2.], [3., 4.], [5., 6.]]
```

// picks elements with specified indices along axis 0 pick(x, y=[0,1], 0) = [1., 4.]

// picks elements with specified indices along axis 1 pick(x, y=[0,1,0], 1) = [1., 4., 5.]

$$y = [[1.], [0.], [2.]]$$

// picks elements with specified indices along axis 1 using 'wrap' mode // to place indicies that would normally be out of bounds pick(x, y=[2,-1,-2], 1, mode='wrap') = [1., 4., 5.]

$$y = [[1.], [0.], [2.]]$$

// picks elements with specified indices along axis 1 and dims are maintained pick(x,y, 1, keep-dims=True) = [[2.], [3.], [6.]]

Defined in src/operator/tensor/broadcast_reduce_op_index.cc:L155

Value

410 mx.symbol.Pooling

mx.symbol.Pooling

Pooling:Performs pooling on the input.

Description

The shapes for 1-D pooling are

Usage

```
mx.symbol.Pooling(...)
```

Arguments

data NDArray-or-Symbol Input data to the pooling operator.

kernel Shape(tuple), optional, default=[] Pooling kernel size: (y, x) or (d, y, x)

pool.type 'avg', 'lp', 'max', 'sum',optional, default='max' Pooling type to be applied.

global.pool boolean, optional, default=0 Ignore kernel size, do global pooling based on cur-

rent input feature map.

cudnn.off boolean, optional, default=0 Turn off cudnn pooling and use MXNet pooling

operator.

pooling.convention

'full', 'same', 'valid', optional, default='valid' Pooling convention to be applied.

stride Shape(tuple), optional, default=[] Stride: for pooling (y, x) or (d, y, x). Defaults

to 1 for each dimension.

pad Shape(tuple), optional, default=[] Pad for pooling: (y, x) or (d, y, x). Defaults to

no padding.

p.value int or None, optional, default='None' Value of p for Lp pooling, can be 1 or 2,

required for Lp Pooling.

count.include.pad

boolean or None, optional, default=None Only used for AvgPool, specify whether to count padding elements for averagecalculation. For example, with a 5*5 kernel on a 3*3 corner of a image, the sum of the 9 valid elements will be divided by 25 if this is set to true, or it will be divided by 9 if this is set to false. Defaults

to true.

layout None, 'NCDHW', 'NCHW', 'NCW', 'NDHWC', 'NHWC', 'NWC', optional,

default='None' Set layout for input and output. Empty for default layout: NCW

for 1d, NCHW for 2d and NCDHW for 3d.

name string, optional Name of the resulting symbol.

Details

- **data** and **out**: *(batch_size, channel, width)* (NCW layout) or *(batch_size, width, channel)* (NWC layout),

The shapes for 2-D pooling are

- **data** and **out**: *(batch_size, channel, height, width)* (NCHW layout) or *(batch_size, height, width, channel)* (NHWC layout),

out_height = f(height, kernel[0], pad[0], stride[0]) out_width = f(width, kernel[1], pad[1], stride[1])

The definition of *f* depends on "pooling_convention", which has two options:

- **valid** (default)::

f(x, k, p, s) = floor((x+2*p-k)/s)+1

- **full**, which is compatible with Caffe::

$$f(x, k, p, s) = ceil((x+2*p-k)/s)+1$$

When "global_pool" is set to be true, then global pooling is performed. It will reset "kernel=(height, width)" and set the appropriate padding to 0.

Three pooling options are supported by "pool_type":

- **avg**: average pooling - **max**: max pooling - **sum**: sum pooling - **lp**: Lp pooling

For 3-D pooling, an additional *depth* dimension is added before *height*. Namely the input data and output will have shape *(batch_size, channel, depth, height, width)* (NCDHW layout) or *(batch_size, depth, height, width, channel)* (NDHWC layout).

Notes on Lp pooling:

Lp pooling was first introduced by this paper: https://arxiv.org/pdf/1204.3968.pdf. L-1 pooling is simply sum pooling, while L-inf pooling is simply max pooling. We can see that Lp pooling stands between those two, in practice the most common value for p is 2.

For each window "X", the mathematical expression for Lp pooling is:

```
:math: f(X) = \sqrt{p}\sum_x^X x^p
```

Defined in src/operator/nn/pooling.cc:L417

Value

out The result mx.symbol

mx.symbol.Pooling_v1 Pooling_v1:This operator is DEPRECATED. Perform pooling on the input.

Description

The shapes for 2-D pooling is

Usage

```
mx.symbol.Pooling_v1(...)
```

Arguments

data NDArray-or-Symbol Input data to the pooling operator.

kernel Shape(tuple), optional, default=[] pooling kernel size: (y, x) or (d, y, x)

pool.type 'avg', 'max', 'sum',optional, default='max' Pooling type to be applied.

global.pool boolean, optional, default=0 Ignore kernel size, do global pooling based on cur-

rent input feature map.

pooling.convention

'full', 'valid', optional, default='valid' Pooling convention to be applied.

stride Shape(tuple), optional, default=[] stride: for pooling (y, x) or (d, y, x)

pad Shape(tuple), optional, default=[] pad for pooling: (y, x) or (d, y, x)

name string, optional Name of the resulting symbol.

Details

- **data**: *(batch_size, channel, height, width)* - **out**: *(batch_size, num_filter, out_height, out_width)*, with::

out_height = f(height, kernel[0], pad[0], stride[0]) out_width = f(width, kernel[1], pad[1], stride[1])

The definition of *f* depends on "pooling convention", which has two options:

- **valid** (default)::

f(x, k, p, s) = floor((x+2*p-k)/s)+1

- **full**, which is compatible with Caffe::

f(x, k, p, s) = ceil((x+2*p-k)/s)+1

But "global_pool" is set to be true, then do a global pooling, namely reset "kernel=(height, width)".

Three pooling options are supported by "pool_type":

- **avg**: average pooling - **max**: max pooling - **sum**: sum pooling

1-D pooling is special case of 2-D pooling with *weight=1* and *kernel[1]=1*.

For 3-D pooling, an additional *depth* dimension is added before *height*. Namely the input data will have shape *(batch_size, channel, depth, height, width)*.

Defined in src/operator/pooling_v1.cc:L104

Value

```
mx.symbol.preloaded_multi_mp_sgd_mom_update
```

preloaded_multi_mp_sgd_mom_update:Momentum update function for multi-precision Stochastic Gradient Descent (SGD) optimizer.

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Usage

```
mx.symbol.preloaded_multi_mp_sgd_mom_update(...)
```

Arguments

data	NDArray-or-Symbol[] Weights, gradients, momentums, learning rates and weight
	dagaya

decays

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

name string, optional Name of the resulting symbol.

Details

```
.. math::
```

```
v_1 = \alpha V_1 - \alpha V_2 - \alpha V_1 - \alpha V_1 - \alpha V_2 - \alpha V_1 - \alpha V_2 - \alpha V_2
```

It updates the weights using::

v = momentum * v - learning_rate * gradient weight += v

Where the parameter "momentum" is the decay rate of momentum estimates at each epoch.

Defined in src/operator/contrib/preloaded_multi_sgd.cc:L200

Value

```
mx.symbol.preloaded_multi_mp_sgd_update
```

preloaded_multi_mp_sgd_update:Update function for multi-precision Stochastic Gradient Descent (SDG) optimizer.

Description

It updates the weights using::

Usage

```
mx.symbol.preloaded_multi_mp_sgd_update(...)
```

Arguments

data NDArray-or-Symbol[] Weights, gradients, learning rates and weight decays rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

name string, optional Name of the resulting symbol.

Details

```
weight = weight - learning_rate * (gradient + wd * weight)
Defined in src/operator/contrib/preloaded_multi_sgd.cc:L140
```

Value

out The result mx.symbol

```
mx.symbol.preloaded_multi_sgd_mom_update
```

preloaded_multi_sgd_mom_update:Momentum update function for Stochastic Gradient Descent (SGD) optimizer.

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Usage

```
mx.symbol.preloaded_multi_sgd_mom_update(...)
```

Arguments

data NDArray-or-Symbol[] Weights, gradients, momentum, learning rates and weight

decays

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

name string, optional Name of the resulting symbol.

Details

.. math::

 $v_1 = \alpha + \lambda J(W_0) \\ v_t = \gamma v_{-1} - \alpha + \lambda J(W_{-1}) \\ W_t = W_{-1} + v_t \\ W_t = W_t - 1 + v_t \\ W_t = W_t$

It updates the weights using::

v = momentum * v - learning_rate * gradient weight += v

Where the parameter "momentum" is the decay rate of momentum estimates at each epoch.

Defined in src/operator/contrib/preloaded_multi_sgd.cc:L91

Value

out The result mx.symbol

mx.symbol.preloaded_multi_sgd_update

preloaded_multi_sgd_update:Update function for Stochastic Gradient

Descent (SDG) optimizer.

Description

It updates the weights using::

Usage

```
mx.symbol.preloaded_multi_sgd_update(...)
```

Arguments

data NDArray-or-Symbol[] Weights, gradients, learning rates and weight decays rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip gradient float, optional, default=-1 Clip gradient to the range of [-clip gradient, clip gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

num.weights int, optional, default='1' Number of updated weights.

name string, optional Name of the resulting symbol.

416 mx.symbol.prod

Details

```
weight = weight - learning_rate * (gradient + wd * weight)
Defined in src/operator/contrib/preloaded_multi_sgd.cc:L42
```

Value

out The result mx.symbol

mx.symbol.prod

prod:Computes the product of array elements over given axes.

Description

Defined in src/operator/tensor/./broadcast_reduce_op.h:L31

Usage

```
mx.symbol.prod(...)
```

Arguments

NDArray-or-Symbol The input
Shape or None, optional, default=None The axis or axes along which to perform the reduction.
The default, 'axis=()', will compute over all elements into a scalar array with shape '(1,)'.
If 'axis' is int, a reduction is performed on a particular axis.
If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in the tuple.
If 'exclude' is true, reduction will be performed on the axes that are NOT in axis instead.
Negative values means indexing from right to left.
boolean, optional, default=0 If this is set to 'True', the reduced axes are left in the result as dimension with size one.
boolean, optional, default=0 Whether to perform reduction on axis that are NOT in axis instead.

string, optional Name of the resulting symbol.

Value

name

mx.symbol.radians 417

mx.symbol.radians

radians: Converts each element of the input array from degrees to radians.

Description

Usage

```
mx.symbol.radians(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "radians" output depends upon the input storage type:

- radians(default) = default - radians(row_sparse) = row_sparse - radians(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L293

Value

out The result mx.symbol

```
mx.symbol.random_exponential
```

random_exponential:Draw random samples from an exponential distribution.

Description

Samples are distributed according to an exponential distribution parametrized by *lambda* (rate).

Usage

```
mx.symbol.random_exponential(...)
```

Arguments

lam	float, optional, default=1 Lambda parameter (rate) of the exponential distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

Example::

```
exponential(lam=4, shape=(2,2)) = \hbox{\tt [[\ 0.0097189\ ,\ 0.08999364],\ [\ 0.04146638,\ 0.31715935]]} Defined in src/operator/random/sample_op.cc:L137
```

Value

out The result mx.symbol

```
mx.symbol.random_gamma
```

 $random_gamma: Draw\ random\ samples\ from\ a\ gamma\ distribution.$

Description

Samples are distributed according to a gamma distribution parametrized by *alpha* (shape) and *beta* (scale).

Usage

```
mx.symbol.random_gamma(...)
```

Arguments

alpha	float, optional, default=1 Alpha parameter (shape) of the gamma distribution.
beta	float, optional, default=1 Beta parameter (scale) of the gamma distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

Example::

gamma(alpha=9, beta=0.5, shape=(2,2)) = [[7.10486984, 3.37695289], [3.91697288, 3.65933681]] Defined in src/operator/random/sample_op.cc:L125

Value

out The result mx.symbol

```
mx.symbol.random_generalized_negative_binomial
```

random_generalized_negative_binomial:Draw random samples from a generalized negative binomial distribution.

Description

Samples are distributed according to a generalized negative binomial distribution parametrized by *mu* (mean) and *alpha* (dispersion). *alpha* is defined as *1/k* where *k* is the failure limit of the number of unsuccessful experiments (generalized to real numbers). Samples will always be returned as a floating point data type.

Usage

```
mx.symbol.random_generalized_negative_binomial(...)
```

Arguments

mu	float, optional, default=1 Mean of the negative binomial distribution.
alpha	float, optional, default=1 Alpha (dispersion) parameter of the negative binomial distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

```
Example::
```

```
generalized_negative_binomial(mu=2.0, alpha=0.3, shape=(2,2)) = [[ 2., 1.], [ 6., 4.]] Defined in src/operator/random/sample_op.cc:L179
```

Value

```
mx.symbol.random_negative_binomial
```

random_negative_binomial:Draw random samples from a negative binomial distribution.

Description

Samples are distributed according to a negative binomial distribution parametrized by *k* (limit of unsuccessful experiments) and *p* (failure probability in each experiment). Samples will always be returned as a floating point data type.

Usage

```
mx.symbol.random_negative_binomial(...)
```

Arguments

k	int, optional, default='1' Limit of unsuccessful experiments.
p	float, optional, default=1 Failure probability in each experiment.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

```
Example::
```

```
negative\_binomial(k=3, p=0.4, shape=(2,2)) = [[\ 4.,\ 7.],\ [\ 2.,\ 5.]]
```

Defined in src/operator/random/sample_op.cc:L164

Value

```
mx.symbol.random_normal
```

random_normal:Draw random samples from a normal (Gaussian) distribution.

Description

.. note:: The existing alias "normal" is deprecated.

Usage

```
mx.symbol.random_normal(...)
```

Arguments

loc	float, optional, default=0 Mean of the distribution.
scale	float, optional, default=1 Standard deviation of the distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64',optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

Samples are distributed according to a normal distribution parametrized by *loc* (mean) and *scale* (standard deviation).

Example::

```
normal(loc=0, scale=1, shape=(2,2)) = [[1.89171135, -1.16881478], [-1.23474145, 1.55807114]]
Defined in src/operator/random/sample_op.cc:L113
```

Value

```
mx.symbol.random_pdf_dirichlet
```

random_pdf_dirichlet:Computes the value of the PDF of *sample* of Dirichlet distributions with parameter *alpha*.

Description

The shape of *alpha* must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *alpha*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the value of *alpha* at index *i*.

Usage

```
mx.symbol.random_pdf_dirichlet(...)
```

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
alpha	NDArray-or-Symbol Concentration parameters of the distributions.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.
name	string, optional Name of the resulting symbol.

Details

Examples::

```
 \begin{array}{l} {\rm random\_pdf\_dirichlet(sample=[[1,2],[2,3],[3,4]], \, alpha=[2.5,\,2.5])=[38.413498,\,199.60245,\,564.56085]} \\ {\rm sample=[[[1,2,3],\,[10,\,20,\,30],\,[100,\,200,\,300]],\,[[0.1,\,0.2,\,0.3],\,[0.01,\,0.02,\,0.03],\,[0.001,\,0.002,\,0.003]]]} \\ {\rm random\_pdf\_dirichlet(sample=sample,\,\,alpha=[0.1,\,0.4,\,0.9])=[[2.3257459e-02,\,5.8420084e-04,\,1.4674458e-05],\,[9.2589635e-01,\,3.6860607e+01,\,1.4674468e+03]]} \\ {\rm Defined\ in\ src/operator/random/pdf\_op.cc:L316} \\ \end{array}
```

Value

```
mx.symbol.random_pdf_exponential
```

random_pdf_exponential:Computes the value of the PDF of *sample* of exponential distributions with parameters *lam* (rate).

Description

The shape of *lam* must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *lam*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the value of *lam* at index *i*.

Usage

```
mx.symbol.random_pdf_exponential(...)
```

Arguments

sample NDArray-or-Symbol Samples from the distributions.

lam NDArray-or-Symbol Lambda (rate) parameters of the distributions.

is.log boolean, optional, default=0 If set, compute the density of the log-probability

instead of the probability.

name string, optional Name of the resulting symbol.

Details

Examples::

```
random_pdf_exponential(sample=[[1, 2, 3]], lam=[1]) = [[0.36787945, 0.13533528, 0.04978707]] sample = [[1,2,3], [1,2,3], [1,2,3]]
```

 $random_pdf_exponential(sample=sample, lam=[1,0.5,0.25]) = [[0.36787945, 0.13533528, 0.04978707], \\ [0.30326533, 0.18393973, 0.11156508], [0.1947002, 0.15163267, 0.11809164]]$

Defined in src/operator/random/pdf_op.cc:L305

Value

mx.symbol.random_pdf_gamma

random_pdf_gamma:Computes the value of the PDF of *sample* of gamma distributions with parameters *alpha* (shape) and *beta* (rate).

Description

alpha and *beta* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *alpha* and *beta*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *alpha* and *beta* at index *i*.

Usage

```
mx.symbol.random_pdf_gamma(...)
```

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
alpha	NDArray-or-Symbol Alpha (shape) parameters of the distributions.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.
beta	NDArray-or-Symbol Beta (scale) parameters of the distributions.
name	string, optional Name of the resulting symbol.

Details

Examples::

```
random_pdf_gamma(sample=[[1,2,3,4,5]], alpha=[5], beta=[1]) = [[0.01532831, 0.09022352, 0.16803136, 0.19536681, 0.17546739]] sample = [[1, 2, 3, 4, 5], [2, 3, 4, 5, 6], [3, 4, 5, 6, 7]] random_pdf_gamma(sample=sample, alpha=[5,6,7], beta=[1,1,1]) = [[0.01532831, 0.09022352, 0.16803136, 0.19536681, 0.17546739], [0.03608941, 0.10081882, 0.15629345, 0.17546739, 0.16062315], [0.05040941, 0.10419563, 0.14622283, 0.16062315, 0.14900276]] Defined in src/operator/random/pdf_op.cc:L303
```

Value

```
mx.symbol.random_pdf_generalized_negative_binomial
```

random_pdf_generalized_negative_binomial:Computes the value of the PDF of *sample* of generalized negative binomial distributions with parameters *mu* (mean) and *alpha* (dispersion). This can be understood as a reparameterization of the negative binomial, where *k* = *1 / alpha*and *p* = *1 / (mu * alpha + 1)*.

Description

mu and *alpha* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *mu* and *alpha*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *mu* and *alpha* at index *i*.

Usage

```
mx.symbol.random_pdf_generalized_negative_binomial(...)
```

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
mu	NDArray-or-Symbol Means of the distributions.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.
alpha	NDArray-or-Symbol Alpha (dispersion) parameters of the distributions.
name	string, optional Name of the resulting symbol.

Details

Examples::

```
random\_pdf\_generalized\_negative\_binomial(sample=[[1, 2, 3, 4]], alpha=[1], mu=[1]) = [[0.25, 0.125, 0.0625, 0.03125]]
```

```
sample = \hbox{\tt [[1,2,3,4],[1,2,3,4]]} \ random\_pdf\_generalized\_negative\_binomial(sample=sample, alpha=\hbox{\tt [1,0.6666]}, mu=\hbox{\tt [1,1.5]}) = \hbox{\tt [[0.25,0.125,0.0625,0.03125]}, \hbox{\tt [0.26517063,0.16573331,0.09667706,0.05437994]}
```

Defined in src/operator/random/pdf_op.cc:L314

Value

```
mx.symbol.random_pdf_negative_binomial
```

random_pdf_negative_binomial:Computes the value of the PDF of samples of negative binomial distributions with parameters *k* (failure limit) and *p* (failure probability).

Description

k and *p* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *k* and *p*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *k* and *p* at index *i*.

Usage

```
mx.symbol.random_pdf_negative_binomial(...)
```

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
k	NDArray-or-Symbol Limits of unsuccessful experiments.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.
p	NDArray-or-Symbol Failure probabilities in each experiment.
name	string, optional Name of the resulting symbol.

Details

Examples::

```
 \begin{array}{l} random\_pdf\_negative\_binomial(sample=[[1,2,3,4]], k=[1], p=a[0.5]) = [[0.25, 0.125, 0.0625, 0.03125]] \\ \# Note that k may be real-valued sample = [[1,2,3,4], [1,2,3,4]] \\ random\_pdf\_negative\_binomial(sample=sample, k=[1, 1.5], p=[0.5, 0.5]) = [[0.25, 0.125, 0.0625, 0.03125], [0.26516506, 0.16572815, 0.09667476, 0.05437956]] \\ \end{array}
```

Defined in src/operator/random/pdf_op.cc:L310

Value

```
mx.symbol.random_pdf_normal
```

random_pdf_normal:Computes the value of the PDF of *sample* of normal distributions with parameters *mu* (mean) and *sigma* (standard deviation).

Description

mu and *sigma* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *mu* and *sigma*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *mu* and *sigma* at index *i*.

Usage

```
mx.symbol.random_pdf_normal(...)
```

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
Jampie	
mu	NDArray-or-Symbol Means of the distributions.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.
sigma	NDArray-or-Symbol Standard deviations of the distributions.
name	string, optional Name of the resulting symbol.

Details

Examples::

```
sample = \hbox{\tt [[-2,-1,0,1,2]]} \ random\_pdf\_normal(sample=sample, mu=[0], sigma=[1]) = \hbox{\tt [[0.05399097,0.24197073,0.3989423,0.24197073,0.05399097]]}
```

random_pdf_normal(sample=sample*2, mu=[0,0], sigma=[1,2]) = [[0.05399097, 0.24197073, 0.3989423, 0.24197073, 0.05399097], [0.12098537, 0.17603266, 0.19947115, 0.17603266, 0.12098537]]

Defined in src/operator/random/pdf_op.cc:L300

Value

```
mx.symbol.random_pdf_poisson
```

random_pdf_poisson:Computes the value of the PDF of *sample* of Poisson distributions with parameters *lam* (rate).

Description

The shape of *lam* must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *lam*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the value of *lam* at index *i*.

Usage

```
mx.symbol.random_pdf_poisson(...)
```

Arguments

sample NDArray-or-Symbol Samples from the distributions.

lam NDArray-or-Symbol Lambda (rate) parameters of the distributions.

is.log boolean, optional, default=0 If set, compute the density of the log-probability

instead of the probability.

name string, optional Name of the resulting symbol.

Details

Examples::

```
\begin{split} & \text{random\_pdf\_poisson}(\text{sample=}[[0,1,2,3]], \text{lam=}[1]) = [[0.36787945, 0.36787945, 0.18393973, 0.06131324]] \\ & \text{sample} = [[0,1,2,3], [0,1,2,3], [0,1,2,3]] \end{split}
```

 $random_pdf_poisson(sample=sample, lam=[1,2,3]) = [[0.36787945, 0.36787945, 0.18393973, 0.06131324], \\ [0.13533528, 0.27067056, 0.27067056, 0.18044704], [0.04978707, 0.14936121, 0.22404182, 0.22404182]]$

Defined in src/operator/random/pdf_op.cc:L307

Value

```
mx.symbol.random_pdf_uniform
```

random_pdf_uniform: Computes the value of the PDF of *sample* of uniform distributions on the intervals given by *[low,high)*.

Description

low and *high* must have the same shape, which must match the leftmost subshape of *sample*. That is, *sample* can have the same shape as *low* and *high*, in which case the output contains one density per distribution, or *sample* can be a tensor of tensors with that shape, in which case the output is a tensor of densities such that the densities at index *i* in the output are given by the samples at index *i* in *sample* parameterized by the values of *low* and *high* at index *i*.

Usage

```
mx.symbol.random_pdf_uniform(...)
```

Arguments

sample	NDArray-or-Symbol Samples from the distributions.
low	NDArray-or-Symbol Lower bounds of the distributions.
is.log	boolean, optional, default=0 If set, compute the density of the log-probability instead of the probability.
high	NDArray-or-Symbol Upper bounds of the distributions.
name	string, optional Name of the resulting symbol.

Details

Examples::

```
random_pdf_uniform(sample=[[1,2,3,4]], low=[0], high=[10]) = [0.1, 0.1, 0.1, 0.1] sample = [[[1, 2, 3], [1, 2, 3]], [[1, 2, 3], [1, 2, 3]]] low = [[0, 0], [0, 0]] high = [[ 5, 10], [15, 20]] random_pdf_uniform(sample=sample, low=low, high=high) = [[[0.2, 0.2, 0.2], [0.1, 0.1, 0.1]], [[0.06667, 0.06667, 0.06667], [0.05, 0.05, 0.05]]]

Defined in src/operator/random/pdf_op.cc:L298
```

Value

```
mx.symbol.random_poisson
```

random_poisson:Draw random samples from a Poisson distribution.

Description

Samples are distributed according to a Poisson distribution parametrized by *lambda* (rate). Samples will always be returned as a floating point data type.

Usage

```
mx.symbol.random_poisson(...)
```

Arguments

lam	float, optional, default=1 Lambda parameter (rate) of the Poisson distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

```
Example::
```

```
poisson(lam=4, shape=(2,2)) = [[ 5., 2.], [ 4., 6.]]
Defined in src/operator/random/sample_op.cc:L150
```

Value

out The result mx.symbol

```
mx.symbol.random_randint
```

random_randint:Draw random samples from a discrete uniform distribution.

Description

Samples are uniformly distributed over the half-open interval *[low, high)* (includes *low*, but excludes *high*).

Usage

```
mx.symbol.random_randint(...)
```

Arguments

low long, required Lower bound of the distribution.high long, required Upper bound of the distribution.

shape Shape(tuple), optional, default=None Shape of the output.

ctx string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n).

Only used for imperative calls.

dtype 'None', 'int32', 'int64', optional, default='None' DType of the output in case

this can't be inferred. Defaults to int32 if not defined (dtype=None).

name string, optional Name of the resulting symbol.

Details

Example::

randint(low=0, high=5, shape=(2,2)) = [[0, 2], [3, 1]] Defined in src/operator/random/sample_op.cc:L194

Value

out The result mx.symbol

mx.symbol.random_uniform

random_uniform:Draw random samples from a uniform distribution.

Description

.. note:: The existing alias "uniform" is deprecated.

Usage

```
mx.symbol.random_uniform(...)
```

Arguments

low	float, optional, default=0 Lower bound of the distribution.
high	float, optional, default=1 Upper bound of the distribution.
shape	Shape(tuple), optional, default=None Shape of the output.

ctx string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n).

Only used for imperative calls.

dtype 'None', 'float16', 'float32', 'float64', optional, default='None' DType of the out-

put in case this can't be inferred. Defaults to float32 if not defined (dtype=None).

name string, optional Name of the resulting symbol.

Details

Samples are uniformly distributed over the half-open interval *[low, high)* (includes *low*, but excludes *high*).

Example::

uniform(low=0, high=1, shape=(2,2)) = [[0.60276335, 0.85794562], [0.54488319, 0.84725171]] Defined in src/operator/random/sample_op.cc:L96

Value

out The result mx.symbol

```
mx.symbol.ravel_multi_index
```

ravel_multi_index:Converts a batch of index arrays into an array of flat indices. The operator follows numpy conventions so a single multi index is given by a column of the input matrix. The leading dimension may be left unspecified by using -1 as placeholder.

Description

Examples::

```
A = [[3,6,6],[4,5,1]] \text{ ravel}(A, \text{shape}=(7,6)) = [22,41,37] \text{ ravel}(A, \text{shape}=(-1,6)) = [22,41,37]
```

Usage

```
mx.symbol.ravel_multi_index(...)
```

Arguments

data NDArray-or-Symbol Batch of multi-indices

shape Shape(tuple), optional, default=None Shape of the array into which the multi-

indices apply.

name string, optional Name of the resulting symbol.

Details

Defined in src/operator/tensor/ravel.cc:L42

Value

mx.symbol.rcbrt 433

mx.symbol.rcbrt

rcbrt:Returns element-wise inverse cube-root value of the input.

Description

```
.. math:: rcbrt(x) = 1 \land sqrt[3]x
```

Usage

```
mx.symbol.rcbrt(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
Example::
```

```
rcbrt([1,8,-125]) = [1.0, 0.5, -0.2]
```

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L269

Value

out The result mx.symbol

mx.symbol.reciprocal

reciprocal: Returns the reciprocal of the argument, element-wise.

Description

Calculates 1/x.

Usage

```
mx.symbol.reciprocal(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

434 mx.symbol.relu

Details

```
Example::
```

```
reciprocal([-2, 1, 3, 1.6, 0.2]) = [-0.5, 1.0, 0.33333334, 0.625, 5.0]
```

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L42

Value

out The result mx.symbol

mx.symbol.relu

relu:Computes rectified linear activation.

Description

```
.. math:: max(features, 0)
```

Usage

```
mx.symbol.relu(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "relu" output depends upon the input storage type:

```
- relu(default) = default - relu(row_sparse) = row_sparse - relu(csr) = csr
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L85

Value

out The result mx.symbol

mx.symbol.repeat 435

mx.symbol.repeat

repeat:Repeats elements of an array. By default, "repeat" flattens the input array into 1-D and then repeats the elements:: x = [[1, 2], [3, 4]] repeat(x, repeats=2) = [1., 1., 2., 2., 3., 3., 4., 4.] The parameter "axis" specifies the axis along which to perform repeat:: repeat(x, repeats=2, axis=1) = [[1., 1., 2., 2.], [3., 3., 4., 4.]] repeat(x, repeats=2, axis=0) = [[1., 2.], [1., 2.], [3., 4.], [3., 4.]] repeat(x, repeats=2, axis=-1) = [[1., 1., 2., 2.], [3., 3., 4., 4.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L738

Usage

```
mx.symbol.repeat(...)
```

Arguments

data NDArray-or-Symbol Input data array

repeats int, required The number of repetitions for each element.

axis int or None, optional, default='None' The axis along which to repeat values.

The negative numbers are interpreted counting from the backward. By default,

use the flattened input array, and return a flat output array.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

```
mx.symbol.reset_arrays
```

reset_arrays:Set to zero multiple arrays

Description

Defined in src/operator/contrib/reset_arrays.cc:L36

```
mx.symbol.reset_arrays(...)
```

436 mx.symbol.Reshape

Arguments

data NDArray-or-Symbol[] Arrays

num.arrays int, required number of input arrays.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.Reshape

Reshape: Reshapes the input array. .. note:: "Reshape" is deprecated, use "reshape" Given an array and a shape, this function returns a copy of the array in the new shape. The shape is a tuple of integers such as (2,3,4). The size of the new shape should be same as the size of the input array. Example:: reshape([1,2,3,4], shape=(2,2)) = [[1,2],[3,4]] Some dimensions of the shape can take special values from the set 0, -1, -2, -3, -4. The significance of each is explained below: - "0" copy this dimension from the input to the output shape. Example:: input shape = (2,3,4), shape = (4,0,2), output shape = (4,3,2) - input shape = (2,3,4), shape = (2,0,0), output shape = (2,3,4) - "-1" infers the dimension of the output shape by using the remainder of the input dimensions keeping the size of the new array same as that of the input array. At most one dimension of shape can be -1. Example:: - input shape = (2,3,4), shape = (6,1,-1), output shape = (6,1,4) - input shape= (2,3,4), shape = (3,-1,8), output shape = (3,1,8) - input shape =(2,3,4), shape=(-1,), output shape=(24,) - "-2" copy all/remainder of the input dimensions to the output shape. Example:: - input shape = (2,3,4), shape = (-2,), output shape = (2,3,4) - input shape = (2,3,4), shape = (2,-2), output shape = (2,3,4) - input shape = (2,3,4), shape = (-2,1,1), output shape = (2,3,4,1,1) - "-3" use the product of two consecutive dimensions of the input shape as the output dimension. Example:: - input shape = (2,3,4), shape = (-3,4), output shape = (6,4) - input shape = (2,3,4,5), shape = (-3,-3), output shape = (6,20)- input shape = (2,3,4), shape = (0,-3), output shape = (2,12) - input shape = (2,3,4), shape = (-3,-2), output shape = (6,4) - "-4" split one dimension of the input into two dimensions passed subsequent to -4 in shape (can contain -1). Example:: - input shape = (2,3,4), shape = (-4,1,2,-2), output shape = (1,2,3,4) - input shape = (2,3,4), shape = (2,-4,-1,3,-2), output shape = (2,1,3,4) If the argument 'reverse' is set to 1, then the special values are inferred from right to left. Example:: - without reverse=1, for input shape = (10,5,4), shape = (-1,0), output shape would be (40,5) - with reverse=1, output shape will be (50,4).

Description

Defined in src/operator/tensor/matrix_op.cc:L175

mx.symbol.reshape 437

Usage

```
mx.symbol.Reshape(...)
```

Arguments

data

keep.highest

shape	Shape(tuple), optional, default=[] The target shape
reverse	boolean, optional, default=0 If true then the special values are inferred from right to left
target.shape	Shape(tuple), optional, default=[] (Deprecated! Use "shape" instead.) Target new shape. One and only one dim can be 0, in which case it will be inferred from the rest of dims

NDArray-or-Symbol Input data to reshape.

boolean, optional, default=0 (Deprecated! Use "shape" instead.) Whether keep the highest dim unchanged.If set to true, then the first dim in target_shape is

ignored, and always fixed as input

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

438 mx.symbol.reshape

mx.symbol.reshape

reshape: Reshapes the input array. .. note:: "Reshape" is deprecated, use "reshape" Given an array and a shape, this function returns a copy of the array in the new shape. The shape is a tuple of integers such as (2,3,4). The size of the new shape should be same as the size of the input array. Example:: reshape([1,2,3,4], shape=(2,2)) = [[1,2],[3,4]] Some dimensions of the shape can take special values from the set 0, -1, -2, -3, -4. The significance of each is explained below: - "0" copy this dimension from the input to the output shape. Example:: input shape = (2,3,4), shape = (4,0,2), output shape = (4,3,2) - input shape = (2,3,4), shape = (2,0,0), output shape = (2,3,4) - "-1" infers the dimension of the output shape by using the remainder of the input dimensions keeping the size of the new array same as that of the input array. At most one dimension of shape can be -1. Example:: - input shape = (2,3,4), shape = (6,1,-1), output shape = (6,1,4) - input shape = (2,3,4), shape = (3,-1,8), output shape = (3,1,8) - input shape =(2,3,4), shape=(-1,), $output\ shape=(24,)$ - "-2" $copy\ all/remainder$ of the input dimensions to the output shape. Example:: - input shape = (2,3,4), shape = (-2,), output shape = (2,3,4) - input shape = (2,3,4), shape = (2,-2), output shape = (2,3,4) - input shape = (2,3,4), shape = (-2,1,1), output shape = (2,3,4,1,1) - "-3" use the product of two consecutive dimensions of the input shape as the output dimension. Example:: - input shape = (2,3,4), shape = (-3,4), output shape = (6,4) - input shape = (2,3,4,5), shape = (-3,-3), output shape = (6,20)- input shape = (2,3,4), shape = (0,-3), output shape = (2,12) - input shape = (2,3,4), shape = (-3,-2), output shape = (6,4) - "-4" split one dimension of the input into two dimensions passed subsequent to -4 in shape (can contain -1). Example:: - input shape = (2,3,4), shape = (-4,1,2,-2), output shape = (1,2,3,4) - input shape = (2,3,4), shape = (2,-4,-1,3,-2), output shape = (2,1,3,4) If the argument 'reverse' is set to 1, then the special values are inferred from right to left. Example:: - without reverse=1, for input shape = (10,5,4), shape = (-1,0), output shape would be (40,5) - with reverse=1, output shape will be (50,4).

Description

Defined in src/operator/tensor/matrix_op.cc:L175

Usage

```
mx.symbol.reshape(...)
```

Arguments

data NDArray-or-Symbol Input data to reshape.

shape Shape(tuple), optional, default=[] The target shape

reverse boolean, optional, default=0 If true then the special values are inferred from

right to left

target.shape Shape(tuple), optional, default=[] (Deprecated! Use "shape" instead.) Target

new shape. One and only one dim can be 0, in which case it will be inferred

from the rest of dims

keep.highest boolean, optional, default=0 (Deprecated! Use "shape" instead.) Whether keep

the highest dim unchanged. If set to true, then the first dim in target_shape is

ignored, and always fixed as input

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.reshape_like

reshape_like:Reshape some or all dimensions of 'lhs' to have the same shape as some or all dimensions of 'rhs'.

Description

Returns a **view** of the 'lhs' array with a new shape without altering any data.

Usage

```
mx.symbol.reshape_like(...)
```

Arguments

1hs NDArray-or-Symbol First input.rhs NDArray-or-Symbol Second input.

1hs.begin int or None, optional, default='None' Defaults to 0. The beginning index along

which the lhs dimensions are to be reshaped. Supports negative indices.

1hs.end int or None, optional, default='None' Defaults to None. The ending index along

which the lhs dimensions are to be used for reshaping. Supports negative in-

dices.

rhs.begin int or None, optional, default='None' Defaults to 0. The beginning index along

which the rhs dimensions are to be used for reshaping. Supports negative in-

dices.

rhs. end int or None, optional, default='None' Defaults to None. The ending index along

which the rhs dimensions are to be used for reshaping. Supports negative in-

dices.

name string, optional Name of the resulting symbol.

440 mx.symbol.reverse

Details

Example::

```
x = [1, 2, 3, 4, 5, 6] y = [[0, -4], [3, 2], [2, 2]] reshape_like(x, y) = [[1, 2], [3, 4], [5, 6]]
```

More precise control over how dimensions are inherited is achieved by specifying \ slices over the 'lhs' and 'rhs' array dimensions. Only the sliced 'lhs' dimensions \ are reshaped to the 'rhs' sliced dimensions, with the non-sliced 'lhs' dimensions staying the same.

Examples::

- lhs shape = (30,7), rhs shape = (15,2,4), lhs_begin=0, lhs_end=1, rhs_begin=0, rhs_end=2, output shape = (15,2,7) - lhs shape = (3,5), rhs shape = (1,15,4), lhs_begin=0, lhs_end=2, rhs_begin=1, rhs_end=2, output shape = (15)

Negative indices are supported, and 'None' can be used for either 'lhs_end' or 'rhs_end' to indicate the end of the range.

Example::

- lhs shape = (30, 12), rhs shape = (4, 2, 2, 3), lhs_begin=-1, lhs_end=None, rhs_begin=1, rhs_end=None, output shape = (30, 2, 2, 3)

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L513

Value

out The result mx.symbol

reverse(x, axis=1) = [[4., 3., 2., 1., 0.], [9., 8., 7., 6., 5.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L826

Usage

```
mx.symbol.reverse(...)
```

Arguments

data NDArray-or-Symbol Input data array

axis Shape(tuple), required The axis which to reverse elements.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.rint 441

mx.symbol.rint

rint:Returns element-wise rounded value to the nearest integer of the input.

Description

```
.. note:: - For input "n.5" "rint" returns "n" while "round" returns "n+1". - For input "-n.5" both "rint" and "round" returns "-n-1".
```

Usage

```
mx.symbol.rint(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
rint([-1.5, 1.5, -1.9, 1.9, 2.1]) = [-2., 1., -2., 2., 2.]
```

The storage type of "rint" output depends upon the input storage type:

- rint(default) = default - rint(row_sparse) = row_sparse - rint(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L799

Value

out The result mx.symbol

```
mx.symbol.rmspropalex_update
```

 $rmspropalex_update: Update\ function\ for\ RMSPropAlex\ optimizer.$

Description

'RMSPropAlex' is non-centered version of 'RMSProp'.

```
mx.symbol.rmspropalex_update(...)
```

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
n	NDArray-or-Symbol n
g	NDArray-or-Symbol g
delta	NDArray-or-Symbol delta
lr	float, required Learning rate
gamma1	float, optional, default=0.949999988 Decay rate.
gamma2	float, optional, default=0.899999976 Decay rate.
epsilon	float, optional, default=9.99999994e-09 A small constant for numerical stability.
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
clip.weights	float, optional, default=-1 Clip weights to the range of [-clip_weights, clip_weights] If clip_weights <= 0, weight clipping is turned off. weights = max(min(weights, clip_weights), -clip_weights).
name	string, optional Name of the resulting symbol.

Details

Define :math: 'E[g^2]_t' is the decaying average over past squared gradient and :math: 'E[g]_t' is the decaying average over past gradient.

```
.. math:: E[g^2]_t = \gamma_1 * E[g^2]_{t-1} + (1 - \gamma_1) * g_t^2 * E[g]_t = \gamma_1 * E[g]_{t-1} + (1 - \gamma_1) * g_t + (1 - \gamma_1)
```

The update step is

.. math:: $\theta_t = \theta_t + \Delta_t + \Delta_t$

The RMSPropAlex code follows the version in http://arxiv.org/pdf/1308.0850v5.pdf Eq(38) - Eq(45) by Alex Graves, 2013.

Graves suggests the momentum term :math: '\gamma_1' to be 0.95, :math: '\gamma_2' to be 0.9 and the learning rate :math: '\eta' to be 0.0001.

Defined in src/operator/optimizer_op.cc:L834

Value

out The result mx.symbol

```
mx.symbol.rmsprop_update
```

rmsprop_update:Update function for 'RMSProp' optimizer.

Description

'RMSprop' is a variant of stochastic gradient descent where the gradients are divided by a cache which grows with the sum of squares of recent gradients?

Usage

```
mx.symbol.rmsprop_update(...)
```

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
n	NDArray-or-Symbol n
lr	float, required Learning rate
gamma1	float, optional, default=0.949999988 The decay rate of momentum estimates.
epsilon	float, optional, default=9.99999994e-09 A small constant for numerical stability.
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
clip.weights	float, optional, default=-1 Clip weights to the range of [-clip_weights, clip_weights] If clip_weights <= 0, weight clipping is turned off. weights = max(min(weights, clip_weights), -clip_weights).
name	string, optional Name of the resulting symbol.

Details

'RMSProp' is similar to 'AdaGrad', a popular variant of 'SGD' which adaptively tunes the learning rate of each parameter. 'AdaGrad' lowers the learning rate for each parameter monotonically over the course of training. While this is analytically motivated for convex optimizations, it may not be ideal for non-convex problems. 'RMSProp' deals with this heuristically by allowing the learning rates to rebound as the denominator decays over time.

Define the Root Mean Square (RMS) error criterion of the gradient as :math: 'RMS[g]_t = \sqrtE[g^2]_t + \epsilon', where :math: 'g' represents gradient and :math: 'E[g^2]_t' is the decaying average over past squared gradient.

444 mx.symbol.RNN

```
The :math: E[g^2]_t is given by:
```

```
.. math:: E[g^2]_t = \gamma * E[g^2]_{t-1} + (1-\gamma * gamma) * g_t^2
```

The update step is

.. $math:: \theta_t = \theta_t - \frac{1}{2} g_t$

The RMSProp code follows the version in http://www.cs.toronto.edu/~tijmen/csc321/slides/lecture_slides_lec6.pdf Tieleman & Hinton, 2012.

Hinton suggests the momentum term :math: '\gamma' to be 0.9 and the learning rate :math: '\eta' to be 0.001.

Defined in src/operator/optimizer_op.cc:L795

Value

out The result mx.symbol

mx.symbol.RNN	RNN:Applies recurrent layers to input data. Currently, vanilla RNN, LSTM and GRU are implemented, with both multi-layer and bidirectional approach.
	tional support.

Description

When the input data is of type float32 and the environment variables MXNET_CUDA_ALLOW_TENSOR_CORE and MXNET_CUDA_TENSOR_OP_MATH_ALLOW_CONVERSION are set to 1, this operator will try to use pseudo-float16 precision (float32 math with float16 I/O) precision in order to use Tensor Cores on suitable NVIDIA GPUs. This can sometimes give significant speedups.

Usage

```
mx.symbol.RNN(...)
```

Arguments

data	NDArray-or-Symbol Input data to RNN
parameters	NDArray-or-Symbol Vector of all RNN trainable parameters concatenated
state	NDArray-or-Symbol initial hidden state of the RNN
state.cell	NDArray-or-Symbol initial cell state for LSTM networks (only for LSTM)
sequence.lengt	h
	NDArray-or-Symbol Vector of valid sequence lengths for each element in batch. (Only used if use_sequence_length kwarg is True)
state.size	int (non-negative), required size of the state for each layer
num.layers	int (non-negative), required number of stacked layers
bidirectional	boolean, optional, default=0 whether to use bidirectional recurrent layers
mode	'gru', 'lstm', 'rnn_relu', 'rnn_tanh', required the type of RNN to compute

mx.symbol.RNN 445

p float, optional, default=0 drop rate of the dropout on the outputs of each RNN layer, except the last layer.

state.outputs boolean, optional, default=0 Whether to have the states as symbol outputs. projection.size

int or None, optional, default='None' size of project size

lstm.state.clip.min

double or None, optional, default=None Minimum clip value of LSTM states. This option must be used together with lstm state clip max.

lstm.state.clip.max

double or None, optional, default=None Maximum clip value of LSTM states. This option must be used together with 1stm state clip min.

lstm.state.clip.nan

boolean, optional, default=0 Whether to stop NaN from propagating in state by clipping it to min/max. If clipping range is not specified, this option is ignored.

use.sequence.length

boolean, optional, default=0 If set to true, this layer takes in an extra input parameter 'sequence_length' to specify variable length sequence

name string, optional Name of the resulting symbol.

Details

Vanilla RNN

Applies a single-gate recurrent layer to input X. Two kinds of activation function are supported: ReLU and Tanh.

With ReLU activation function:

```
.. math:: h_t = relu(W_ih * x_t + b_ih + W_hh * h_(t-1) + b_hh)
```

With Tanh activtion function:

```
.. math:: h_t = \tanh(W_ih * x_t + b_ih + W_hh * h_(t-1) + b_hh)
```

Reference paper: Finding structure in time - Elman, 1988. https://crl.ucsd.edu/~elman/Papers/fsit.pdf **LSTM**

Long Short-Term Memory - Hochreiter, 1997. http://www.bioinf.jku.at/publications/older/2604.pdf

Gated Recurrent Unit - Cho et al. 2014. http://arxiv.org/abs/1406.1078

The definition of GRU here is slightly different from paper but compatible with CUDNN.

```
.. math:: \beginarrayll r_t = \mathrmsigmoid(W_ir x_t + b_ir + W_hr h_(t-1) + b_hr) \ z_t = \mathrmsigmoid(W_iz x_t + b_iz + W_hz h_(t-1) + b_hz) \ n_t = \tanh(W_in x_t + b_in + r_t * (W_hn h_(t-1) + b_hn)) \ h_t = (1 - z_t) * n_t + z_t * h_(t-1) \ \endarray
```

Defined in src/operator/rnn.cc:L351

Value

out The result mx.symbol

 ${\tt mx.symbol.ROIPooling:} Performs\ region\ of\ interest(ROI)\ pooling\ on\ the\ input\ array.$

Description

ROI pooling is a variant of a max pooling layer, in which the output size is fixed and region of interest is a parameter. Its purpose is to perform max pooling on the inputs of non-uniform sizes to obtain fixed-size feature maps. ROI pooling is a neural-net layer mostly used in training a 'Fast R-CNN' network for object detection.

Usage

```
mx.symbol.ROIPooling(...)
```

Arguments

data	NDArray-or-Symbol The input array to the pooling operator, a 4D Feature maps
rois	NDArray-or-Symbol Bounding box coordinates, a 2D array of [[batch_index, x1, y1, x2, y2]], where (x1, y1) and (x2, y2) are top left and bottom right corners of designated region of interest. 'batch_index' indicates the index of corresponding image in the input array
pooled.size	Shape(tuple), required ROI pooling output shape (h,w)
spatial.scale	float, required Ratio of input feature map height (or w) to raw image height (or w). Equals the reciprocal of total stride in convolutional layers
name	string, optional Name of the resulting symbol.

Details

This operator takes a 4D feature map as an input array and region proposals as 'rois', then it pools over sub-regions of input and produces a fixed-sized output array regardless of the ROI size.

To crop the feature map accordingly, you can resize the bounding box coordinates by changing the parameters 'rois' and 'spatial_scale'.

The cropped feature maps are pooled by standard max pooling operation to a fixed size output indicated by a 'pooled_size' parameter. batch_size will change to the number of region bounding boxes after 'ROIPooling'.

The size of each region of interest doesn't have to be perfectly divisible by the number of pooling sections ('pooled_size').

Example::

```
x = [[[[ 0., 1., 2., 3., 4., 5.], [ 6., 7., 8., 9., 10., 11.], [ 12., 13., 14., 15., 16., 17.], [ 18., 19., 20., 21., 22., 23.], [ 24., 25., 26., 27., 28., 29.], [ 30., 31., 32., 33., 34., 35.], [ 36., 37., 38., 39., 40., 41.], [ 42., 43., 44., 45., 46., 47.]]]]
```

mx.symbol.round 447

```
// region of interest i.e. bounding box coordinates. y = [[0,0,0,4,4]]
```

// returns array of shape (2,2) according to the given roi with max pooling. ROIPooling(x, y, (2,2), 1.0) = [[[[14., 16.], [26., 28.]]]]

// region of interest is changed due to the change in 'spacial_scale' parameter. ROIPooling(x, y, (2,2), (2,7) = [[[[7., 9.], [19., 21.]]]]

Defined in src/operator/roi_pooling.cc:L225

Value

out The result mx.symbol

mx.symbol.round

round:Returns element-wise rounded value to the nearest integer of the input.

Description

Example::

Usage

```
mx.symbol.round(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
round([-1.5, 1.5, -1.9, 1.9, 2.1]) = [-2., 2., -2., 2., 2.]
```

The storage type of "round" output depends upon the input storage type:

- round(default) = default - round(row_sparse) = row_sparse - round(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L778

Value

out The result mx.symbol

mx.symbol.rsqrt

rsqrt:Returns element-wise inverse square-root value of the input.

Description

```
.. math:: rsqrt(x) = 1 \land sqrtx
```

Usage

```
mx.symbol.rsqrt(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
rsqrt([4,9,16]) = [0.5, 0.33333334, 0.25]
```

The storage type of "rsqrt" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L193

Value

out The result mx.symbol

```
mx.symbol.sample_exponential
```

sample_exponential:Concurrent sampling from multiple exponential distributions with parameters lambda (rate).

Description

The parameters of the distributions are provided as an input array. Let *[s]* be the shape of the input array, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

```
mx.symbol.sample_exponential(...)
```

lam	NDArray-or-Symbol Lambda (rate) parameters of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

For any valid *n*-dimensional index *i* with respect to the input array, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input value at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input array.

Examples::

```
lam = [1.0, 8.5]
```

// Draw a single sample for each distribution sample_exponential(lam) = [0.51837951, 0.09994757]

// Draw a vector containing two samples for each distribution sample_exponential(lam, shape=(2)) = [[0.51837951, 0.19866663], [0.09994757, 0.50447971]]

Defined in src/operator/random/multisample_op.cc:L284

Value

out The result mx.symbol

```
mx.symbol.sample_gamma
```

sample_gamma:Concurrent sampling from multiple gamma distributions with parameters *alpha* (shape) and *beta* (scale).

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

```
mx.symbol.sample_gamma(...)
```

alpha	NDArray-or-Symbol Alpha (shape) parameters of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
beta	NDArray-or-Symbol Beta (scale) parameters of the distributions.
name	string, optional Name of the resulting symbol.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Examples::

```
alpha = [0.0, 2.5] beta = [1.0, 0.7] // Draw a single sample for each distribution sample_gamma(alpha, beta) = [0., 2.25797319] // Draw a vector containing two samples for each distribution sample_gamma(alpha, beta, shape=(2)) = [[0., 0.], [2.25797319, 1.70734084]] Defined in src/operator/random/multisample_op.cc:L282
```

Value

out The result mx.symbol

```
mx.symbol.sample_generalized_negative_binomial

sample_generalized_negative_binomial:Concurrent sampling from

multiple generalized negative binomial distributions with parameters

*mu* (mean) and *alpha* (dispersion).
```

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

```
mx.symbol.sample_generalized_negative_binomial(...)
```

mu	NDArray-or-Symbol Means of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
alpha	NDArray-or-Symbol Alpha (dispersion) parameters of the distributions.
name	string, optional Name of the resulting symbol.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Samples will always be returned as a floating point data type.

Examples::

```
mu = [2.0, 2.5] alpha = [1.0, 0.1]
```

// Draw a single sample for each distribution sample_generalized_negative_binomial(mu, alpha) = [0., 3.]

// Draw a vector containing two samples for each distribution sample_generalized_negative_binomial(mu, alpha, shape=(2)) = [[0., 3.], [3., 1.]]

Defined in src/operator/random/multisample_op.cc:L293

Value

out The result mx.symbol

```
mx.symbol.sample_multinomial
```

sample_multinomial:Concurrent sampling from multiple multinomial distributions.

Description

data is an *n* dimensional array whose last dimension has length *k*, where *k* is the number of possible outcomes of each multinomial distribution. This operator will draw *shape* samples from each distribution. If shape is empty one sample will be drawn from each distribution.

```
mx.symbol.sample_multinomial(...)
```

data	NDArray-or-Symbol Distribution probabilities. Must sum to one on the last axis.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
get.prob	boolean, optional, default=0 Whether to also return the log probability of sampled result. This is usually used for differentiating through stochastic variables, e.g. in reinforcement learning.
dtype	'float16', 'float32', 'float64', 'int32', 'uint8', optional, default='int32' DType of the output in case this can't be inferred.
name	string, optional Name of the resulting symbol.

Details

If *get_prob* is true, a second array containing log likelihood of the drawn samples will also be returned. This is usually used for reinforcement learning where you can provide reward as head gradient for this array to estimate gradient.

Note that the input distribution must be normalized, i.e. *data* must sum to 1 along its last axis.

Examples::

```
probs = [[0, 0.1, 0.2, 0.3, 0.4], [0.4, 0.3, 0.2, 0.1, 0]]

// Draw a single sample for each distribution sample_multinomial(probs) = [3, 0]

// Draw a vector containing two samples for each distribution sample_multinomial(probs, shape=(2)) = [[4, 2], [0, 0]]

// requests log likelihood sample_multinomial(probs, get_prob=True) = [2, 1], [0.2, 0.3]
```

Value

out The result mx.symbol

```
mx.symbol.sample_negative_binomial
```

sample_negative_binomial:Concurrent sampling from multiple negative binomial distributions with parameters *k* (failure limit) and *p* (failure probability).

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

Usage

```
mx.symbol.sample_negative_binomial(...)
```

Arguments

k	NDArray-or-Symbol Limits of unsuccessful experiments.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
р	NDArray-or-Symbol Failure probabilities in each experiment.
name	string, optional Name of the resulting symbol.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Samples will always be returned as a floating point data type.

Examples::

```
k = [\ 20,\ 49\ ]\ p = [\ 0.4\ ,\ 0.77\ ] // Draw a single sample for each distribution sample_negative_binomial(k, p) = [\ 15.,\ 16.] // Draw a vector containing two samples for each distribution sample_negative_binomial(k, p, shape=(2)) = [[\ 15.,\ 50.],\ [\ 16.,\ 12.]]
```

Defined in src/operator/random/multisample_op.cc:L289

Value

out The result mx.symbol

```
mx.symbol.sample_normal
```

sample_normal:Concurrent sampling from multiple normal distributions with parameters *mu* (mean) and *sigma* (standard deviation).

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

Usage

```
mx.symbol.sample_normal(...)
```

Arguments

mu	NDArray-or-Symbol Means of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
sigma	NDArray-or-Symbol Standard deviations of the distributions.
name	string, optional Name of the resulting symbol.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Examples::

```
mu = [ 0.0, 2.5 ] sigma = [ 1.0, 3.7 ]

// Draw a single sample for each distribution sample_normal(mu, sigma) = [-0.56410581, 0.95934606]

// Draw a vector containing two samples for each distribution sample_normal(mu, sigma, shape=(2))

= [[-0.56410581, 0.2928229 ], [ 0.95934606, 4.48287058]]

Defined in src/operator/random/multisample_op.cc:L279
```

Value

out The result mx.symbol

```
mx.symbol.sample_poisson
```

sample_poisson:Concurrent sampling from multiple Poisson distributions with parameters lambda (rate).

Description

The parameters of the distributions are provided as an input array. Let *[s]* be the shape of the input array, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

```
mx.symbol.sample_poisson(...)
```

lam	NDArray-or-Symbol Lambda (rate) parameters of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

For any valid *n*-dimensional index *i* with respect to the input array, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input value at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input array.

Samples will always be returned as a floating point data type.

Examples::

```
lam = [ 1.0, 8.5 ]
```

// Draw a single sample for each distribution sample_poisson(lam) = [0., 13.]

// Draw a vector containing two samples for each distribution sample_poisson(lam, shape=(2)) = [[0, 4.], [13., 8.]]

Defined in src/operator/random/multisample_op.cc:L286

Value

out The result mx.symbol

```
mx.symbol.sample_uniform
```

sample_uniform: Concurrent sampling from multiple uniform distributions on the intervals given by *[low,high)*.

Description

The parameters of the distributions are provided as input arrays. Let *[s]* be the shape of the input arrays, *n* be the dimension of *[s]*, *[t]* be the shape specified as the parameter of the operator, and *m* be the dimension of *[t]*. Then the output will be a *(n+m)*-dimensional array with shape *[s]x[t]*.

```
mx.symbol.sample_uniform(...)
```

456 mx.symbol.save

Arguments

low	NDArray-or-Symbol Lower bounds of the distributions.
shape	Shape(tuple), optional, default=[] Shape to be sampled from each random distribution.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
high	NDArray-or-Symbol Upper bounds of the distributions.

Tight Tibraray of Symbol Opper bounds of the distributi

name string, optional Name of the resulting symbol.

Details

For any valid *n*-dimensional index *i* with respect to the input arrays, *output[i]* will be an *m*-dimensional array that holds randomly drawn samples from the distribution which is parameterized by the input values at index *i*. If the shape parameter of the operator is not set, then one sample will be drawn per distribution and the output array has the same shape as the input arrays.

Examples::

```
low = [0.0, 2.5] high = [1.0, 3.7]
```

// Draw a single sample for each distribution sample_uniform(low, high) = [0.40451524, 3.18687344]

// Draw a vector containing two samples for each distribution sample_uniform(low, high, shape=(2)) = [[0.40451524, 0.18017688], [3.18687344, 3.68352246]]

Defined in src/operator/random/multisample_op.cc:L277

Value

out The result mx.symbol

mx.symbol.save

Save an mx.symbol object

Description

Save an mx.symbol object

Usage

```
mx.symbol.save(symbol, filename)
```

Arguments

symbol the mx.symbol object

filename (including the path)

mx.symbol.scatter_nd 457

Examples

```
data = mx.symbol.Variable('data')
mx.symbol.save(data, 'temp.symbol')
data2 = mx.symbol.load('temp.symbol')
```

mx.symbol.scatter_nd scatter_nd:Scatters data into a new tensor according to indices.

Description

Given 'data' with shape ' $(Y_0, ..., Y_K-1, X_M, ..., X_N-1)$ ' and indices with shape ' $(M, Y_0, ..., Y_K-1)$ ', the output will have shape ' $(X_0, X_1, ..., X_N-1)$ ', where ' $M \le N$ '. If 'M == N', data shape should simply be ' $(Y_0, ..., Y_K-1)$ '.

Usage

```
mx.symbol.scatter_nd(...)
```

Arguments

data NDArray-or-Symbol data indices NDArray-or-Symbol indices

shape Shape(tuple), required Shape of output.

name string, optional Name of the resulting symbol.

Details

The elements in output is defined as follows::

```
output[indices[0, y_0, ..., y_K-1], ..., indices[M-1, y_0, ..., y_K-1], x_M, ..., x_N-1] = data[y_0, ..., y_K-1, x_M, ..., x_N-1]
```

all other entries in output are 0.

.. warning::

If the indices have duplicates, the result will be non-deterministic and the gradient of 'scatter_nd' will not be correct!!

Examples::

```
data = [2, 3, 0] indices = [[1, 1, 0], [0, 1, 0]] shape = (2, 2) scatter_nd(data, indices, shape) = [[0, 0], [2, 3]]
```

```
data = [[[1, 2], [3, 4]], [[5, 6], [7, 8]]] indices = [[0, 1], [1, 1]] shape = (2, 2, 2, 2) scatter_nd(data, indices, shape) = [[[[0, 0], [0, 0]],
```

```
[[1, 2], [3, 4]]],
```

[[[0, 0], [0, 0]],

[[5, 6], [7, 8]]]]

Value

out The result mx.symbol

```
mx.symbol.SequenceLast
```

SequenceLast:Takes the last element of a sequence.

Description

This function takes an n-dimensional input array of the form [max_sequence_length, batch_size, other_feature_dims] and returns a (n-1)-dimensional array of the form [batch_size, other_feature_dims].

Usage

```
mx.symbol.SequenceLast(...)
```

Arguments

data NDArray-or-Symbol n-dimensional input array of the form [max_sequence_length,

batch_size, other_feature_dims] where n>2

sequence.length

NDArray-or-Symbol vector of sequence lengths of the form [batch_size]

use.sequence.length

boolean, optional, default=0 If set to true, this layer takes in an extra input pa-

rameter 'sequence_length' to specify variable length sequence

axis int, optional, default='0' The sequence axis. Only values of 0 and 1 are currently

supported.

name string, optional Name of the resulting symbol.

Details

Parameter 'sequence_length' is used to handle variable-length sequences. 'sequence_length' should be an input array of positive ints of dimension [batch_size]. To use this parameter, set 'use_sequence_length' to 'True', otherwise each example in the batch is assumed to have the max sequence length.

.. note:: Alternatively, you can also use 'take' operator.

Example::

```
x = [[[ 1., 2., 3.], [ 4., 5., 6.], [ 7., 8., 9.]],

[[ 10., 11., 12.], [ 13., 14., 15.], [ 16., 17., 18.]],

[[ 19., 20., 21.], [ 22., 23., 24.], [ 25., 26., 27.]]]

// returns last sequence when sequence_length parameter is not used SequenceLast(x) = [[ 19., 20., 21.], [ 22., 23., 24.], [ 25., 26., 27.]]

// sequence_length is used SequenceLast(x, sequence_length=[1,1,1], use_sequence_length=True)

= [[ 1., 2., 3.], [ 4., 5., 6.], [ 7., 8., 9.]]
```

```
// sequence_length is used SequenceLast(x, sequence_length=[1,2,3], use_sequence_length=True) = [[ 1., 2., 3.], [ 13., 14., 15.], [ 25., 26., 27.]]
```

Defined in src/operator/sequence_last.cc:L106

Value

out The result mx.symbol

mx.symbol.SequenceMask

SequenceMask:Sets all elements outside the sequence to a constant value.

Description

This function takes an n-dimensional input array of the form [max_sequence_length, batch_size, other_feature_dims] and returns an array of the same shape.

Usage

```
mx.symbol.SequenceMask(...)
```

Arguments

data NDArray-or-Symbol n-dimensional input array of the form [max_sequence_length,

batch_size, other_feature_dims] where n>2

sequence.length

NDArray-or-Symbol vector of sequence lengths of the form [batch_size]

use.sequence.length

boolean, optional, default=0 If set to true, this layer takes in an extra input pa-

rameter 'sequence_length' to specify variable length sequence

value float, optional, default=0 The value to be used as a mask.

axis int, optional, default='0' The sequence axis. Only values of 0 and 1 are currently

supported.

name string, optional Name of the resulting symbol.

Details

Parameter 'sequence_length' is used to handle variable-length sequences. 'sequence_length' should be an input array of positive ints of dimension [batch_size]. To use this parameter, set 'use_sequence_length' to 'True', otherwise each example in the batch is assumed to have the max sequence length and this operator works as the 'identity' operator.

Example::

```
x = [[[1., 2., 3.], [4., 5., 6.]], [7., 8., 9.], [10., 11., 12.]],
```

```
[[ 13., 14., 15.], [ 16., 17., 18.]]]

// Batch 1 B1 = [[ 1., 2., 3.], [ 7., 8., 9.], [ 13., 14., 15.]]

// Batch 2 B2 = [[ 4., 5., 6.], [ 10., 11., 12.], [ 16., 17., 18.]]
```

// works as identity operator when sequence_length parameter is not used SequenceMask(x) = [[[1., 2., 3.], [4., 5., 6.]],

```
[[ 7., 8., 9.], [ 10., 11., 12.]],
```

[[13., 14., 15.], [16., 17., 18.]]]

// sequence_length [1,1] means 1 of each batch will be kept // and other rows are masked with default mask value = 0 SequenceMask(x, sequence_length=[1,1], use_sequence_length=True) = [[[1., 2., 3.], [4., 5., 6.]],

[[0., 0., 0.], [0., 0., 0.]],

[[0., 0., 0.], [0., 0., 0.]]]

// sequence_length [2,3] means 2 of batch B1 and 3 of batch B2 will be kept // and other rows are masked with value = 1 SequenceMask(x, sequence_length=[2,3], use_sequence_length=True, value=1) = [[[1., 2., 3.], [4., 5., 6.]],

[[1., 1., 1.], [16., 17., 18.]]]

Defined in src/operator/sequence_mask.cc:L186

Value

out The result mx.symbol

mx.symbol.SequenceReverse

SequenceReverse:Reverses the elements of each sequence.

Description

This function takes an n-dimensional input array of the form [max_sequence_length, batch_size, other_feature_dims] and returns an array of the same shape.

Usage

```
mx.symbol.SequenceReverse(...)
```

Arguments

data

NDArray-or-Symbol n-dimensional input array of the form [max_sequence_length, batch_size, other dims] where n>2

sequence.length

NDArray-or-Symbol vector of sequence lengths of the form [batch_size]

use.sequence.length

boolean, optional, default=0 If set to true, this layer takes in an extra input parameter 'sequence_length' to specify variable length sequence

axis

int, optional, default='0' The sequence axis. Only 0 is currently supported.

name

string, optional Name of the resulting symbol.

Details

Parameter 'sequence_length' is used to handle variable-length sequences. 'sequence_length' should be an input array of positive ints of dimension [batch_size]. To use this parameter, set 'use_sequence_length' to 'True', otherwise each example in the batch is assumed to have the max sequence length.

Example::

```
x = [[[1., 2., 3.], [4., 5., 6.]],
```

[[7., 8., 9.], [10., 11., 12.]],

[[13., 14., 15.], [16., 17., 18.]]]

// Batch 1 B1 = [[1., 2., 3.], [7., 8., 9.], [13., 14., 15.]]

// Batch 2 B2 =
$$[[4., 5., 6.], [10., 11., 12.], [16., 17., 18.]]$$

// returns reverse sequence when sequence_length parameter is not used SequenceReverse(x) = [[[13., 14., 15.], [16., 17., 18.]],

[[7., 8., 9.], [10., 11., 12.]],

// sequence_length [2,2] means 2 rows of // both batch B1 and B2 will be reversed. SequenceReverse(x, sequence_length=[2,2], use_sequence_length=True) = [[[7., 8., 9.], [10., 11., 12.]],

[[1., 2., 3.], [4., 5., 6.]],

// sequence_length [2,3] means 2 of batch B2 and 3 of batch B3 // will be reversed. SequenceReverse(x, sequence_length=[2,3], use_sequence_length=[2,3], use_sequence_length=[2,3], [16., 17., 18.]],

[[1., 2., 3.], [10., 11., 12.]],

Defined in src/operator/sequence_reverse.cc:L122

Value

out The result mx.symbol

mx.symbol.sgd_mom_update

sgd_mom_update:Momentum update function for Stochastic Gradient Descent (SGD) optimizer.

Description

Momentum update has better convergence rates on neural networks. Mathematically it looks like below:

Usage

```
mx.symbol.sgd_mom_update(...)
```

Arguments

weight NDArray-or-Symbol Weight
grad NDArray-or-Symbol Gradient
mom NDArray-or-Symbol Momentum
lr float, required Learning rate

momentum float, optional, default=0 The decay rate of momentum estimates at each epoch.

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip.gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

lazy.update boolean, optional, default=1 If true, lazy updates are applied if gradient's stype

is row_sparse and both weight and momentum have the same stype

name string, optional Name of the resulting symbol.

Details

```
.. math::
```

```
v_1 = \alpha + \lambda J(W_0) \ v_t = \gamma v_{-1} - \alpha + \lambda J(W_{-1}) \ W_t = W_{-1} + v_t = W_
```

It updates the weights using::

```
v = momentum * v - learning_rate * gradient weight += v
```

Where the parameter "momentum" is the decay rate of momentum estimates at each epoch.

However, if grad's storage type is "row_sparse", "lazy_update" is True and weight's storage type is the same as momentum's storage type, only the row slices whose indices appear in grad.indices are updated (for both weight and momentum)::

463

```
for row in gradient.indices: v[row] = momentum[row] * v[row] - learning_rate * gradient[row] weight[row] += v[row]
```

Defined in src/operator/optimizer_op.cc:L563

Value

out The result mx.symbol

```
\verb|mx.symbol.sgd_update| sgd_update: Update function for Stochastic Gradient Descent (SGD) \\ optimizer.
```

Description

It updates the weights using::

Usage

```
mx.symbol.sgd_update(...)
```

Arguments

weight	NDArray-or-Symbol Weight
grad	NDArray-or-Symbol Gradient
lr	float, required Learning rate
wd	float, optional, default=0 Weight decay augments the objective function with a regularization term that penalizes large weights. The penalty scales with the square of the magnitude of each weight.
rescale.grad	float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.
clip.gradient	float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad, clip_gradient), -clip_gradient).
lazy.update	boolean, optional, default=1 If true, lazy updates are applied if gradient's stype is row_sparse.

Details

name

```
weight = weight - learning_rate * (gradient + wd * weight)
```

However, if gradient is of "row_sparse" storage type and "lazy_update" is True, only the row slices whose indices appear in grad.indices are updated::

string, optional Name of the resulting symbol.

for row in gradient.indices: weight[row] = weight[row] - learning_rate * (gradient[row] + wd * weight[row])

Defined in src/operator/optimizer_op.cc:L522

464 mx.symbol.shuffle

Value

out The result mx.symbol

mx.symbol.shape_array shape_array:Returns a 1D int64 array containing the shape of data.

Description

Example::

Usage

```
mx.symbol.shape_array(...)
```

Arguments

data NDArray-or-Symbol Input Array.

name string, optional Name of the resulting symbol.

Details

```
shape_array([[1,2,3,4], [5,6,7,8]]) = [2,4]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L574

Value

out The result mx.symbol

mx.symbol.shuffle

shuffle:Randomly shuffle the elements.

Description

This shuffles the array along the first axis. The order of the elements in each subarray does not change. For example, if a 2D array is given, the order of the rows randomly changes, but the order of the elements in each row does not change.

Usage

```
mx.symbol.shuffle(...)
```

Arguments

data NDArray-or-Symbol Data to be shuffled.

name string, optional Name of the resulting symbol.

mx.symbol.sigmoid 465

Value

out The result mx.symbol

 ${\sf mx.symbol.sigmoid}$

sigmoid:Computes sigmoid of x element-wise.

Description

```
.. math:: y = 1 / (1 + \exp(-x))
```

Usage

```
mx.symbol.sigmoid(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "sigmoid" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L119

Value

out The result mx.symbol

 $\verb|mx.symbol.sign|$

sign:Returns element-wise sign of the input.

Description

Example::

Usage

```
mx.symbol.sign(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
sign([-2, 0, 3]) = [-1, 0, 1]
```

The storage type of "sign" output depends upon the input storage type:

- sign(default) = default - sign(row_sparse) = row_sparse - sign(csr) = csr

Defined in src/operator/tensor/elemwise unary op basic.cc:L759

Value

out The result mx.symbol

```
mx.symbol.signsgd_update
```

signsgd_update:Update function for SignSGD optimizer.

Description

.. math::

Usage

```
mx.symbol.signsgd_update(...)
```

Arguments

weight NDArray-or-Symbol Weight grad NDArray-or-Symbol Gradient 1r float, required Learning rate

wd float, optional, default=0 Weight decay augments the objective function with a

regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

clip_gradient float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient]

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

name string, optional Name of the resulting symbol.

Details

```
g\_t = \n J(W\_t-1) \ W\_t = W\_t-1 - \eta\_t \ \textsign(g\_t)
```

It updates the weights using::

weight = weight - learning_rate * sign(gradient)

.. note:: - sparse ndarray not supported for this optimizer yet.

Defined in src/operator/optimizer_op.cc:L61

Value

out The result mx.symbol

```
mx.symbol.signum_update
```

signum_update:SIGN momentUM (Signum) optimizer.

Description

.. math::

Usage

```
mx.symbol.signum_update(...)
```

Arguments

NDArray-or-Symbol Weight weight grad NDArray-or-Symbol Gradient NDArray-or-Symbol Momentum mom lr float, required Learning rate momentum

float, optional, default=0 The decay rate of momentum estimates at each epoch. float, optional, default=0 Weight decay augments the objective function with a wd regularization term that penalizes large weights. The penalty scales with the

square of the magnitude of each weight.

rescale.grad float, optional, default=1 Rescale gradient to grad = rescale_grad*grad.

float, optional, default=-1 Clip gradient to the range of [-clip_gradient, clip_gradient] clip.gradient

If clip_gradient <= 0, gradient clipping is turned off. grad = max(min(grad,

clip_gradient), -clip_gradient).

wd.1h float, optional, default=0 The amount of weight decay that does not go into gra-

dient/momentum calculationsotherwise do weight decay algorithmically only.

string, optional Name of the resulting symbol. name

Details

```
g_t = \Lambda J(W_{t-1}) = \Delta m_{t-1} + (1 - \beta g_t) - (1 - \beta J(W_{t-1}) = M_{t-1} - \beta J(W_{t-1})
```

It updates the weights using:: state = momentum * state + (1-momentum) * gradient weight = weight - learning_rate * sign(state)

Where the parameter "momentum" is the decay rate of momentum estimates at each epoch.

.. note:: - sparse ndarray not supported for this optimizer yet.

Defined in src/operator/optimizer_op.cc:L90

Value

out The result mx.symbol

468 mx.symbol.sinh

mx.symbol.sin

sin: Computes the element-wise sine of the input array.

Description

The input should be in radians (:math:'2\pi' rad equals 360 degrees).

Usage

```
mx.symbol.sin(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

```
.. math:: \sin([0, \pi/4, \pi/2]) = [0, 0.707, 1]
```

The storage type of "sin" output depends upon the input storage type:

- sin(default) = default - sin(row_sparse) = row_sparse - sin(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L47

Value

out The result mx.symbol

 $\verb|mx.symbol.sinh|$

sinh:Returns the hyperbolic sine of the input array, computed elementwise.

Description

```
.. math:: sinh(x) = 0.5 \times (exp(x) - exp(-x))
```

Usage

```
mx.symbol.sinh(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

mx.symbol.size_array 469

Details

The storage type of "sinh" output depends upon the input storage type:

- sinh(default) = default - sinh(row_sparse) = row_sparse - sinh(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L313

Value

out The result mx.symbol

mx.symbol.size_array size_array:Returns a 1D int64 array containing the size of data.

Description

Example::

Usage

```
mx.symbol.size_array(...)
```

Arguments

data NDArray-or-Symbol Input Array.

name string, optional Name of the resulting symbol.

Details

```
size\_array([[1,2,3,4], [5,6,7,8]]) = [8]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L625

Value

470 mx.symbol.slice

mx.symbol.slice

slice:Slices a region of the array. .. note:: "crop" is deprecated. Use "slice" instead. This function returns a sliced array between the indices given by 'begin' and 'end' with the corresponding 'step'. For an input array of "shape= $(d_0, d_1, ..., d_{n-1})$ ", slice operation with "begin= $(b_0, b_1...b_m-1)$ ", "end= $(e_0, e_1, ..., e_m-1)$ ", and " $step=(s_0, s_1, ..., s_m-1)$ ", where $m \le n$, results in an array with the shape "($|e\ 0-b\ 0|/|s\ 0|$, ..., $|e\ m-1-b\ m-1|/|s\ m-1|$, $d\ m$, ..., $d\ n-1$ 1)". The resulting array's *k*-th dimension contains elements from the *k*-th dimension of the input array starting from index "b k" (inclusive) with step "s_k" until reaching "e_k" (exclusive). If the *k*-th elements are 'None' in the sequence of 'begin', 'end', and 'step', the following rule will be used to set default values. If 's_k' is 'None', set $s_k=1$. If $s_k>0$, set $b_k=0$, $e_k=d_k$; else, set $b_k=d_k-1$, 'e_k=-1'. The storage type of "slice" output depends on storage types of inputs - slice(csr) = csr - otherwise, "slice" generates output with default storage .. note:: When input data storage type is csr, it only supports step=(), or step=(None,), or step=(1,) to generate a csr output. For other step parameter values, it falls back to slicing a dense tensor. Example:: x = [[1., 2., 3., 4.], [5., 6., 7., 8.], [9., 10., 11.]12.]] slice(x, begin=(0,1), end=(2,4)) = [[2., 3., 4.], [6., 7., 8.]]slice(x, begin=(None, 0), end=(None, 3), step=(-1, 2)) = [[9., 11.],[5., 7.], [1., 3.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L477

Usage

```
mx.symbol.slice(...)
```

Arguments

data	NDArray-or-Symbol Source input
begin	Shape(tuple), required starting indices for the slice operation, supports negative indices.
end	Shape(tuple), required ending indices for the slice operation, supports negative indices.
step	Shape(tuple), optional, default=[] step for the slice operation, supports negative values.
name	string, optional Name of the resulting symbol.

Value

mx.symbol.SliceChannel

SliceChannel:Splits an array along a particular axis into multiple subarrays.

Description

.. note:: "SliceChannel" is deprecated. Use "split" instead.

Usage

```
mx.symbol.SliceChannel(...)
```

Arguments

data NDArray-or-Symbol The input

num.outputs int, required Number of splits. Note that this should evenly divide the length of

the 'axis'.

axis int, optional, default='1' Axis along which to split.

squeeze.axis boolean, optional, default=0 If true, Removes the axis with length 1 from the

shapes of the output arrays. **Note** that setting 'squeeze_axis' to "true" removes axis with length 1 only along the 'axis' which it is split. Also 'squeeze_axis'

can be set to "true" only if "input.shape[axis] == num_outputs".

name string, optional Name of the resulting symbol.

Details

Note that 'num_outputs' should evenly divide the length of the axis along which to split the array.

Example::

```
x = [[[ 1.] [ 2.]] [[ 3.] [ 4.]] [[ 5.] [ 6.]]] x.shape = (3, 2, 1)
y = split(x, axis=1, num_outputs=2) // a list of 2 arrays with shape (3, 1, 1) y = [[[ 1.]] [[ 3.]] [[ 5.]]]
[[[ 2.]] [[ 4.]] [[ 6.]]]
y[0].shape = (3, 1, 1)
z = split(x, axis=0, num_outputs=3) // a list of 3 arrays with shape (1, 2, 1) z = [[[ 1.] [ 2.]]]
[[[ 3.] [ 4.]]]
[[[ 5.] [ 6.]]]
z[0].shape = (1, 2, 1)
```

'squeeze_axis=1' removes the axis with length 1 from the shapes of the output arrays. **Note** that setting 'squeeze_axis' to "1" removes axis with length 1 only along the 'axis' which it is split. Also 'squeeze_axis' can be set to true only if "input.shape[axis] == num_outputs".

Example::

472 mx.symbol.slice_axis

```
 z = split(x, axis=0, num\_outputs=3, squeeze\_axis=1) \text{ // a list of 3 arrays with shape (2, 1) } z = [[\ 1.] [\ 2.]]   [[\ 3.] \ [\ 4.]]   [[\ 5.] \ [\ 6.]] \ z[0].shape = (2\ ,1\ )  Defined in src/operator/slice_channel.cc:L107
```

Value

out The result mx.symbol

```
mx.symbol.slice_axis slice_axis:Slices along a given axis. Returns an array slice along a given 'axis' starting from the 'begin' index to the 'end' index. Examples:: x = [[\ 1.,\ 2.,\ 3.,\ 4.],\ [\ 5.,\ 6.,\ 7.,\ 8.],\ [\ 9.,\ 10.,\ 11.,\ 12.]] slice_axis(x,\ axis=0,\ begin=1,\ end=3) = [[\ 5.,\ 6.,\ 7.,\ 8.],\ [\ 9.,\ 10.,\ 11.,\ 12.]] slice_axis(x,\ axis=1,\ begin=0,\ end=2) = [[\ 1.,\ 2.],\ [\ 5.,\ 6.],\ [\ 9.,\ 10.]] slice_axis(x,\ axis=1,\ begin=-3,\ end=-1) = [[\ 2.,\ 3.],\ [\ 6.,\ 7.],\ [\ 10.,\ 11.]]
```

Description

Defined in src/operator/tensor/matrix_op.cc:L565

Usage

```
mx.symbol.slice_axis(...)
```

Arguments

data	NDArray-or-Symbol Source input
axis	int, required Axis along which to be sliced, supports negative indexes.
begin	int, required The beginning index along the axis to be sliced, supports negative indexes.
end	int or None, required The ending index along the axis to be sliced, supports negative indexes.
name	string, optional Name of the resulting symbol.

Value

mx.symbol.slice_like 473

mx.symbol.slice_like

slice_like:Slices a region of the array like the shape of another array. This function is similar to "slice", however, the 'begin' are always '0's and 'end' of specific axes are inferred from the second input 'shape_like'. Given the second 'shape_like' input of "shape= (d_0, d_0, d_0) ". d 1, ..., d n-1)", a "slice like" operator with default empty 'axes', it performs the following operation: "out = slice(input, begin=(0, 0, 0, 0))" ..., 0), $end=(d_0, d_1, ..., d_{n-1}))$ ". When 'axes' is not empty, it is used to speficy which axes are being sliced. Given a 4-d input data, "slice_like" operator with "axes=(0, 2, -1)" will perform the following operation: " out = slice(input, begin=(0, 0, 0, 0), end= $(d_0, 0, 0)$), end= $(d_0, 0, 0)$ None, d_2 , d_3)". Note that it is allowed to have first and second input with different dimensions, however, you have to make sure the 'axes' are specified and not exceeding the dimension limits. For example, given 'input_1' with "shape=(2,3,4,5)" and 'input_2' with "shape=(1,2,3)", it is not allowed to use: "out = slice like(a, b)" because ndim of 'input_1' is 4, and ndim of 'input_2' is 3. The following is allowed in this situation: "out = $slice_like(a, b, axes=(0, 2))$ " Example:: x = [[1., 2., 3., 4.], [5., 6., 7., 8.], [9., 10., 11., 12.]] y =[[0., 0., 0.], [0., 0., 0.]] $slice_like(x, y) = [[1., 2., 3.], [5., 6., 7.]]$ $slice_like(x, y, axes=(0, 1)) = [[1., 2., 3.] [5., 6., 7.]] slice_like(x, y, axes=(0, 1)) = [[1., 2., 3.] [5., 4.]] slice_like(x, y, axes=(0, 1)) = [[1., 2., 3.]] slice_like$ axes=(0)) = [[1., 2., 3., 4.] [5., 6., 7., 8.]] $slice_like(x, y, axes=(-1))$ = [[1., 2., 3.] [5., 6., 7.] [9., 10., 11.]]

Description

Defined in src/operator/tensor/matrix_op.cc:L619

Usage

```
mx.symbol.slice_like(...)
```

Arguments

data NDArray-or-Symbol Source input shape.like NDArray-or-Symbol Shape like input

axes Shape(tuple), optional, default=[] List of axes on which input data will be sliced

according to the corresponding size of the second input. By default will slice on

all axes. Negative axes are supported.

name string, optional Name of the resulting symbol.

Value

474 mx.symbol.Softmax

mx.symbol.smooth_11

smooth_l1:Calculate Smooth L1 Loss(lhs, scalar) by summing

Description

.. math::

Usage

```
mx.symbol.smooth_l1(...)
```

Arguments

data NDArray-or-Symbol source input

scalar float scalar input

name string, optional Name of the resulting symbol.

Details

 $f(x) = \text{logincases (\sigma x)^2/2,\& \textif x < 1/sigma^2\ |x|-0.5/\sigma^2,\& \textotherwise \endoxes | \cdots | \cdo$

where :math: 'x' is an element of the tensor *lhs* and :math: '\sigma' is the scalar.

Example::

 $smooth_{11}([1, 2, 3, 4]) = [0.5, 1.5, 2.5, 3.5] smooth_{11}([1, 2, 3, 4], scalar=1) = [0.5, 1.5, 2.5, 3.5]$

Defined in src/operator/tensor/elemwise_binary_scalar_op_extended.cc:L108

Value

out The result mx.symbol

mx.symbol.Softmax

Softmax: Computes the gradient of cross entropy loss with respect to softmax output.

Description

- This operator computes the gradient in two steps. The cross entropy loss does not actually need to be computed.

Usage

```
mx.symbol.Softmax(...)
```

475 mx.symbol.Softmax

Arguments

data NDArray-or-Symbol Input array. label NDArray-or-Symbol Ground truth label. grad.scale float, optional, default=1 Scales the gradient by a float factor. ignore.label float, optional, default=-1 The instances whose 'labels' == 'ignore_label' will be ignored during backward, if 'use_ignore' is set to "true"). boolean, optional, default=0 If set to "true", the softmax function will be commulti.output puted along axis "1". This is applied when the shape of input array differs from the shape of label array. use.ignore boolean, optional, default=0 If set to "true", the 'ignore_label' value will not contribute to the backward gradient. boolean, optional, default=0 If set to "true", the softmax function will be compreserve.shape puted along the last axis ("-1"). 'batch', 'null', 'valid', optional, default='null' Normalizes the gradient. normalization boolean, optional, default=0 Multiplies gradient with output gradient elementout.grad wise.

smooth.alpha float, optional, default=0 Constant for computing a label smoothed version of cross-entropyfor the backwards pass. This constant gets subtracted from theonehot encoding of the gold label and distributed uniformly to all other labels.

name string, optional Name of the resulting symbol.

Details

- Applies softmax function on the input array. Computes and returns the gradient of cross entropy loss w.r.t. the softmax output.
- The softmax function, cross entropy loss and gradient is given by:
- Softmax Function:
- .. math:: $\text{textsoftmax}(x)_i = \frac{x_i}{x_j}$
- Cross Entropy Function:
- .. math:: \textCE(label, output) = \sum_i \textlabel_i \log(\textoutput_i)
- The gradient of cross entropy loss w.r.t softmax output:
- .. math:: \textgradient = \textoutput \textlabel
- During forward propagation, the softmax function is computed for each instance in the input array.

For general *N*-D input arrays with shape :math: '(d_1, d_2, ..., d_n)'. The size is :math: 's=d_1 \cdot d_2 \cdot \cdot \cdot d_n'. We can use the parameters 'preserve_shape' and 'multi_output' to specify the way to compute softmax:

- By default, 'preserve_shape' is "false". This operator will reshape the input array into a 2-D array with shape :math: '(d_1, \fracsd_1)' and then compute the softmax function for each row in the reshaped array, and afterwards reshape it back to the original shape :math: '(d 1, d 2, ..., d n)'. - If 'preserve_shape' is "true", the softmax function will be computed along the last axis ('axis' = "-1"). - If 'multi_output' is "true", the softmax function will be computed along the second axis ('axis' = "1").

476 mx.symbol.softmax

- During backward propagation, the gradient of cross-entropy loss w.r.t softmax output array is computed. The provided label can be a one-hot label array or a probability label array.

- If the parameter 'use_ignore' is "true", 'ignore_label' can specify input instances with a particular label to be ignored during backward propagation. **This has no effect when softmax 'output' has same shape as 'label'**.

Example::

- The parameter 'grad_scale' can be used to rescale the gradient, which is often used to give each loss function different weights.
- This operator also supports various ways to normalize the gradient by 'normalization', The 'normalization' is applied if softmax output has different shape than the labels. The 'normalization' mode can be set to the followings:
- "'null'": do nothing. "'batch'": divide the gradient by the batch size. "'valid'": divide the gradient by the number of instances which are not ignored.

Defined in src/operator/softmax_output.cc:L231

Value

out The result mx.symbol

mx.symbol.softmax

softmax: Applies the softmax function.

Description

The resulting array contains elements in the range (0,1) and the elements along the given axis sum up to 1.

Usage

```
mx.symbol.softmax(...)
```

Arguments

data NDArray-or-Symbol The input array.

length NDArray-or-Symbol The length array.

axis int, optional, default='-1' The axis along which to compute softmax.

temperature double or None, optional, default=None Temperature parameter in softmax

dtype None, 'float16', 'float32', 'float64', optional, default='None' DType of the out-

put in case this can't be inferred. Defaults to the same as input's dtype if not

defined (dtype=None).

use.length boolean or None, optional, default=0 Whether to use the length input as a mask

over the data input.

name string, optional Name of the resulting symbol.

Details

```
.. math:: softmax(\mathbfz/t)_j = \frace^z_j/t\sum_k=1^K e^z_k/t for :math: 'j = 1, ..., K' t is the temperature parameter in softmax function. By default, t equals 1.0 Example:: x = [[\ 1.\ 1.\ 1.]\ [\ 1.\ 1.\ 1.]] softmax(x,axis=0) = [[\ 0.5\ 0.5\ 0.5]\ [\ 0.5\ 0.5\ 0.5]] softmax(x,axis=1) = [[\ 0.33333334, 0.3333334, 0.3333334], [\ 0.33333334, 0.33333334]] Defined in src/operator/nn/softmax.cc:L103
```

Value

out The result mx.symbol

```
mx.symbol.SoftmaxActivation
```

SoftmaxActivation:Applies softmax activation to input. This is intended for internal layers.

Description

.. note::

Usage

```
mx.symbol.SoftmaxActivation(...)
```

Arguments

data NDArray-or-Symbol The input array.

mode 'channel', 'instance', optional, default='instance' Specifies how to compute the

softmax. If set to "instance", it computes softmax for each instance. If set to "channel", It computes cross channel softmax for each position of each instance.

name string, optional Name of the resulting symbol.

Details

This operator has been deprecated, please use 'softmax'.

If 'mode' = "instance", this operator will compute a softmax for each instance in the batch. This is the default mode.

If 'mode' = "channel", this operator will compute a k-class softmax at each position of each instance, where 'k' = "num_channel". This mode can only be used when the input array has at least 3 dimensions. This can be used for 'fully convolutional network', 'image segmentation', etc.

Example::

»> input_array = mx.nd.array([[3., 0.5, -0.5, 2., 7.], »> [2., -.4, 7., 3., 0.2]]) »> softmax_act =
mx.nd.SoftmaxActivation(input_array) »> print softmax_act.asnumpy() [[1.78322066e-02 1.46375655e03 5.38485940e-04 6.56010211e-03 9.73605454e-01] [6.56221947e-03 5.95310994e-04 9.73919690e01 1.78379621e-02 1.08472735e-03]]

Defined in src/operator/nn/softmax_activation.cc:L59

Value

out The result mx.symbol

```
mx.symbol.SoftmaxOutput
```

SoftmaxOutput: Computes the gradient of cross entropy loss with respect to softmax output.

Description

- This operator computes the gradient in two steps. The cross entropy loss does not actually need to be computed.

Usage

```
mx.symbol.SoftmaxOutput(...)
```

Arguments

data	NDArray-or-Symbol Input array.
label	NDArray-or-Symbol Ground truth label.
grad.scale	float, optional, default=1 Scales the gradient by a float factor.
ignore.label	float, optional, default=-1 The instances whose 'labels' == 'ignore_label' will be ignored during backward, if 'use_ignore' is set to "true").
multi.output	boolean, optional, default=0 If set to "true", the softmax function will be computed along axis "1". This is applied when the shape of input array differs from the shape of label array.
use.ignore	boolean, optional, default=0 If set to "true", the 'ignore_label' value will not contribute to the backward gradient.

preserve. shape boolean, optional, default=0 If set to "true", the softmax function will be com-

puted along the last axis ("-1").

normalization 'batch', 'null', 'valid', optional, default='null' Normalizes the gradient.

boolean, optional, default=0 Multiplies gradient with output gradient elementout.grad

smooth.alpha float, optional, default=0 Constant for computing a label smoothed version of

cross-entropyfor the backwards pass. This constant gets subtracted from theone-

hot encoding of the gold label and distributed uniformly to all other labels.

string, optional Name of the resulting symbol. name

Details

- Applies softmax function on the input array. - Computes and returns the gradient of cross entropy loss w.r.t. the softmax output.

- The softmax function, cross entropy loss and gradient is given by:
- Softmax Function:
- .. math:: $\text{textsoftmax}(x)_i = \frac{x_i}{x_j}$
- Cross Entropy Function:
- .. math:: \textCE(label, output) = \sum_i \textlabel_i \log(\textoutput_i)
- The gradient of cross entropy loss w.r.t softmax output:
- .. math:: \textgradient = \textoutput \textlabel
- During forward propagation, the softmax function is computed for each instance in the input array.

For general *N*-D input arrays with shape :math: '(d_1, d_2, ..., d_n)'. The size is :math: 's=d_1 \cdot d_2 \cdot \cdot \cdot d_n'. We can use the parameters 'preserve_shape' and 'multi_output' to specify the way to compute softmax:

- By default, 'preserve_shape' is "false". This operator will reshape the input array into a 2-D array with shape :math: '(d 1, \fracsd 1)' and then compute the softmax function for each row in the reshaped array, and afterwards reshape it back to the original shape :math: '(d_1, d_2, ..., d_n)'.
- If 'preserve_shape' is "true", the softmax function will be computed along the last axis ('axis' = "-1"). - If 'multi_output' is "true", the softmax function will be computed along the second axis ('axis' = "1").
- During backward propagation, the gradient of cross-entropy loss w.r.t softmax output array is computed. The provided label can be a one-hot label array or a probability label array.
- If the parameter 'use_ignore' is "true", 'ignore_label' can specify input instances with a particular label to be ignored during backward propagation. **This has no effect when softmax 'output' has same shape as 'label'**.

Example::

label = label,\multi_output=true, use_ignore=true,\ignore_label=ignore_label) ## forward softmax output [[0.0320586 0.08714432 0.23688284 0.64391428] [0.25 0.25 0.25 0.25] [0.25 0.25 0.25 0.25] [0.25 0.25 0.25 0.25]] ## backward gradient output [[0. 0. 0. 0.] [-0.75 0.25 0.25 0.25] [0.25 0.25 -0.75 0.25] [0.25 0.25 0.25 -0.75]] ## notice that the first row is all 0 because label[0] is 1, which is equal to ignore_label.

- The parameter 'grad_scale' can be used to rescale the gradient, which is often used to give each loss function different weights.
- This operator also supports various ways to normalize the gradient by 'normalization', The 'normalization' is applied if softmax output has different shape than the labels. The 'normalization' mode can be set to the followings:
- "'null'": do nothing. "'batch'": divide the gradient by the batch size. "'valid'": divide the gradient by the number of instances which are not ignored.

Defined in src/operator/softmax_output.cc:L231

Value

out The result mx.symbol

```
mx.symbol.softmax_cross_entropy
```

softmax_cross_entropy:Calculate cross entropy of softmax output and one-hot label.

Description

- This operator computes the cross entropy in two steps: - Applies softmax function on the input array. - Computes and returns the cross entropy loss between the softmax output and the labels.

Usage

```
mx.symbol.softmax_cross_entropy(...)
```

Arguments

data NDArray-or-Symbol Input data label NDArray-or-Symbol Input label

name string, optional Name of the resulting symbol.

Details

- The softmax function and cross entropy loss is given by:
- Softmax Function:
- .. math:: $\text{textsoftmax}(x)_i = \frac{x_i}{\sum_i \exp(x_i)}$
- Cross Entropy Function:
- .. math:: \textCE(label, output) = \sum_i \textlabel_i \log(\textoutput_i)

Example::

```
x = [[1, 2, 3], [11, 7, 5]]
```

label = [2, 0]

softmax(x) = [[0.09003057, 0.24472848, 0.66524094], [0.97962922, 0.01794253, 0.00242826]]

softmax cross entropy(data, label) = $-\log(0.66524084) - \log(0.97962922) = 0.4281871$

Defined in src/operator/loss_binary_op.cc:L59

mx.symbol.softmin 481

Value

out The result mx.symbol

mx.symbol.softmin softmin:Applies the softmin function.

Description

The resulting array contains elements in the range (0,1) and the elements along the given axis sum up to 1.

Usage

```
mx.symbol.softmin(...)
```

Arguments

axis int, optional, default='-1' The axis along which to compute softmax.

temperature double or None, optional, default=None Temperature parameter in softmax

None, 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to the same as input's dtype if not defined (dtype=None).

use.length boolean or None, optional, default=0 Whether to use the length input as a mask over the data input.

name string, optional Name of the resulting symbol.

Details

```
\label{eq:continuous_softmin} $$ ... math:: softmin(\mathbfz/t)_j = \frac{-z_j/t\sum_{k=1}^K e^-z_k/t}$$ for :math: $$ is the temperature parameter in softmax function. By default, $t$ equals $1.0$$ Example:: $$ x = [[ 1. 2. 3.] [ 3. 2. 1.]]$$ softmin(x,axis=0) = [[ 0.88079703, 0.5, 0.11920292], [ 0.11920292, 0.5, 0.88079703]]$$ softmin(x,axis=1) = [[ 0.66524094, 0.24472848, 0.09003057], [ 0.09003057, 0.24472848, 0.66524094]]$$ Defined in src/operator/nn/softmin.cc:L57
```

Value

482 mx.symbol.sort

mx.symbol.softsign

softsign: Computes softsign of x element-wise.

Description

```
.. math:: y = x / (1 + abs(x))
```

Usage

```
mx.symbol.softsign(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "softsign" output is always dense

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L191

Value

out The result mx.symbol

mx.symbol.sort

sort:Returns a sorted copy of an input array along the given axis.

Description

Examples::

Usage

```
mx.symbol.sort(...)
```

Arguments

data NDArray-or-Symbol The input array

axis int or None, optional, default='-1' Axis along which to choose sort the input

tensor. If not given, the flattened array is used. Default is -1.

is.ascend boolean, optional, default=1 Whether to sort in ascending or descending order.

name string, optional Name of the resulting symbol.

Details

```
x = [[1, 4], [3, 1]]

// sorts along the last axis sort(x) = [[1., 4.], [1., 3.]]

// flattens and then sorts sort(x, axis=None) = [1., 1., 3., 4.]

// sorts along the first axis sort(x, axis=0) = [[1., 1.], [3., 4.]]

// in a descend order sort(x, is_ascend=0) = [[4., 1.], [3., 1.]]

Defined in src/operator/tensor/ordering_op.cc:L131
```

Value

out The result mx.symbol

mx.symbol.space_to_depth

space_to_depth:Rearranges(permutes) blocks of spatial data into depth. Similar to ONNX SpaceToDepth operator: https://github.com/onnx/onnx/blob/master/docs/Operators.md#SpaceToDepth The output is a new tensor where the values from height and width dimension are moved to the depth dimension. The reverse of this operation is "depth_to_space". .. math:: \begingather* x \prime = reshape(x, [N, C, H / block | size, block | size, W / block | size, $block_size]) \setminus x \setminus prime \setminus prime = transpose(x \setminus prime, [0, 3, 5, 1,$ 2, 4]) $\ y = reshape(x \rangle prime \rangle prime, [N, C * (block size ^ 2), H /$ block_size, W / block_size]) \endgather* where :math: 'x' is an input tensor with default layout as :math: '[N, C, H, W]': [batch, channels, height, width] and :math: 'y' is the output tensor of layout :math: '[N, $C * (block size ^ 2), H/block size, W/block size] Example:: x =$ [[[0, 6, 1, 7, 2, 8], [12, 18, 13, 19, 14, 20], [3, 9, 4, 10, 5, 11], [15, 21, 16, 22, 17, 23]]] $space_to_depth(x, 2) = [[[[0, 1, 2], [3, 4, 5]],$ [[6, 7, 8], [9, 10, 11]], [[12, 13, 14], [15, 16, 17]], [[18, 19, 20], [21, 22, 23]]]]

Description

Defined in src/operator/tensor/matrix_op.cc:L1011

Usage

```
mx.symbol.space_to_depth(...)
```

Arguments

data NDArray-or-Symbol Input ndarray

block.size int, required Blocks of [block_size. block_size] are moved

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

 ${\tt mx.symbol.SpatialTransformer}$

SpatialTransformer:Applies a spatial transformer to input feature map.

Description

SpatialTransformer:Applies a spatial transformer to input feature map.

Usage

```
\verb|mx.symbol.SpatialTransformer(...)|
```

Arguments

data	NDArray-or-Symbol Input data to the SpatialTransformerOp.
loc	NDArray-or-Symbol localisation net, the output dim should be 6 when transform_type is affine. You shold initialize the weight and bias with identity tranform.
target.shape	Shape(tuple), optional, default=[0,0] output shape(h, w) of spatial transformer: (y,x)
transform.type	'affine', required transformation type
sampler.type	'bilinear', required sampling type
cudnn.off	boolean or None, optional, default=None whether to turn cudnn off

string, optional Name of the resulting symbol.

Value

name

mx.symbol.split 485

mx.symbol.split

split:Splits an array along a particular axis into multiple sub-arrays.

Description

```
.. note:: "SliceChannel" is deprecated. Use "split" instead.
```

Usage

```
mx.symbol.split(...)
```

Arguments

data NDArray-or-Symbol The input

num.outputs int, required Number of splits. Note that this should evenly divide the length of

the 'axis'.

axis int, optional, default='1' Axis along which to split.

squeeze.axis boolean, optional, default=0 If true, Removes the axis with length 1 from the

shapes of the output arrays. **Note** that setting 'squeeze_axis' to "true" removes axis with length 1 only along the 'axis' which it is split. Also 'squeeze_axis'

can be set to "true" only if "input.shape[axis] == num_outputs".

name string, optional Name of the resulting symbol.

Details

Note that 'num_outputs' should evenly divide the length of the axis along which to split the array.

Example::

```
 \begin{aligned} x &= & [[[\ 1.]\ [\ 2.]]\ [[\ 3.]\ [\ 4.]]\ [[\ 5.]\ [\ 6.]]] \ x.shape = (3,\,2,\,1) \\ y &= & \text{split}(x,\,axis=1,\,num\_outputs=2) \ \text{$//$} \ a \ \text{list of 2 arrays with shape } (3,\,1,\,1) \ y = & [[[\ 1.]]\ [[\ 3.]]\ [[\ 5.]]] \\ [[[\ 2.]]\ [[\ 4.]]\ [[\ 6.]]] \\ y &= & \text{split}(x,\,axis=0,\,num\_outputs=3) \ \text{$//$} \ a \ \text{list of 3 arrays with shape } (1,\,2,\,1) \ z = & [[[\ 1.]\ [\ 2.]]] \\ [[[\ 3.]\ [\ 4.]]] \\ [[[\ 5.]\ [\ 6.]]] \\ z &= & [\ 0.]\ [\ 5.]\ [\ 6.]]] \end{aligned}
```

'squeeze_axis=1' removes the axis with length 1 from the shapes of the output arrays. **Note** that setting 'squeeze_axis' to "1" removes axis with length 1 only along the 'axis' which it is split. Also 'squeeze_axis' can be set to true only if "input.shape[axis] == num_outputs".

Example:

```
z = split(x, axis=0, num\_outputs=3, squeeze\_axis=1) // a list of 3 arrays with shape (2, 1) <math>z = [[1.] [2.]]
```

486 mx.symbol.sqrt

```
[[ 3.] [ 4.]]
[[ 5.] [ 6.]] z[0].shape = (2 ,1 )
Defined in src/operator/slice_channel.cc:L107
```

Value

out The result mx.symbol

mx.symbol.sqrt

sqrt:Returns element-wise square-root value of the input.

Description

```
.. math:: \text{textrmsqrt}(x) = \text{sqrt}x
```

Usage

```
mx.symbol.sqrt(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
sqrt([4, 9, 16]) = [2, 3, 4]
```

The storage type of "sqrt" output depends upon the input storage type:

- $sqrt(default) = default - sqrt(row_sparse) = row_sparse - sqrt(csr) = csr$

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L142

Value

mx.symbol.square 487

mx.symbol.square

square: Returns element-wise squared value of the input.

Description

```
.. math:: square(x) = x^2
```

Usage

```
mx.symbol.square(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
square([2, 3, 4]) = [4, 9, 16]
```

The storage type of "square" output depends upon the input storage type:

- square(default) = default - square(row_sparse) = row_sparse - square(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_pow.cc:L118

Value

out The result mx.symbol

mx.symbol.squeeze

squeeze:Remove single-dimensional entries from the shape of an array. Same behavior of defining the output tensor shape as numpy.squeeze for the most of cases. See the following note for exception. Examples:: data = [[[0], [1], [2]]] squeeze(data) = [0, 1, 2] squeeze(data, axis=0) = [[0], [1], [2]] squeeze(data, axis=2) = [[0, 1, 2]] squeeze(data, axis=0) = [0, 1, 2] . Note:: The output of this operator will keep at least one dimension not removed. For example, squeeze([[[4]]]) = [4], while in numpy.squeeze, the output will become a scalar.

488 mx.symbol.stack

Description

squeeze:Remove single-dimensional entries from the shape of an array. Same behavior of defining the output tensor shape as numpy.squeeze for the most of cases. See the following note for exception. Examples:: data = [[[0], [1], [2]]] squeeze(data) = [0, 1, 2] squeeze(data, axis=0) = [[0], [1], [2]] squeeze(data, axis=0) = [[0, 1, 2]] squeeze(data, axis=0, 2) = [0, 1, 2] . Note:: The output of this operator will keep at least one dimension not removed. For example, squeeze([[[4]]]) = [4], while in numpy.squeeze, the output will become a scalar.

Usage

```
mx.symbol.squeeze(...)
```

Arguments

data NDArray-or-Symbol data to squeeze

axis Shape or None, optional, default=None Selects a subset of the single-dimensional

entries in the shape. If an axis is selected with shape entry greater than one, an

error is raised.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.stack

stack: Join a sequence of arrays along a new axis. The axis parameter specifies the index of the new axis in the dimensions of the result. For example, if axis=0 it will be the first dimension and if axis=-1 it will be the last dimension. Examples:: x = [1, 2] y = [3, 4] stack(x, y) = [1, 2], [3, 4] stack(x, y) axis=1) = [1, 3], [2, 4]

Description

stack: Join a sequence of arrays along a new axis. The axis parameter specifies the index of the new axis in the dimensions of the result. For example, if axis=0 it will be the first dimension and if axis=-1 it will be the last dimension. Examples:: x = [1, 2] y = [3, 4] stack(x, y) = [[1, 2], [3, 4]] stack(x, y, axis=1) = [[1, 3], [2, 4]]

Usage

```
mx.symbol.stack(...)
```

Arguments

data NDArray-or-Symbol[] List of arrays to stack

axis int, optional, default='0' The axis in the result array along which the input arrays

are stacked.

num.args int, required Number of inputs to be stacked.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

```
mx.symbol.stop_gradient
```

stop_gradient:Stops gradient computation.

Description

Stops the accumulated gradient of the inputs from flowing through this operator in the backward direction. In other words, this operator prevents the contribution of its inputs to be taken into account for computing gradients.

Usage

```
mx.symbol.stop_gradient(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

Example::

```
v1 = [1, 2] v2 = [0, 1] a = Variable('a') b = Variable('b') b_stop_grad = stop_gradient(3 * b) loss = MakeLoss(b_stop_grad + a) executor = loss.simple_bind(ctx=cpu(), a=(1,2), b=(1,2)) executor.forward(is_train=True, a=v1, b=v2) executor.outputs [ 1. 5.] executor.backward() executor.grad_arrays [ 0. 0.] [ 1. 1.]
```

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L327

Value

490 mx.symbol.sum

mx.symbol.sum

sum: Computes the sum of array elements over given axes.

Description

.. Note::

Usage

```
mx.symbol.sum(...)
```

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

name string, optional Name of the resulting symbol.

Details

'sum' and 'sum_axis' are equivalent. For ndarray of csr storage type summation along axis 0 and axis 1 is supported. Setting keepdims or exclude to True will cause a fallback to dense operator.

Example::

```
data = [[[1, 2], [2, 3], [1, 3]], [[1, 4], [4, 3], [5, 2]], [[7, 1], [7, 2], [7, 3]]] sum(data, axis=1) [[ 4. 8.] [ 10. 9.] [ 21. 6.]] sum(data, axis=[1,2]) [ 12. 19. 27.] data = [[1, 2, 0], [3, 0, 1], [4, 1, 0]] csr = cast_storage(data, 'csr') sum(csr, axis=0) [ 8. 3. 1.] sum(csr, axis=1) [ 3. 4. 5.]
```

Defined in src/operator/tensor/broadcast_reduce_sum_value.cc:L67

mx.symbol.sum_axis 491

Value

out The result mx.symbol

mx.symbol.sum_axis

sum_axis: Computes the sum of array elements over given axes.

Description

.. Note::

Usage

```
mx.symbol.sum_axis(...)
```

Arguments

data NDArray-or-Symbol The input

axis Shape or None, optional, default=None The axis or axes along which to perform

the reduction.

The default, 'axis=()', will compute over all elements into a scalar array with

shape '(1,)'.

If 'axis' is int, a reduction is performed on a particular axis.

If 'axis' is a tuple of ints, a reduction is performed on all the axes specified in

the tuple.

If 'exclude' is true, reduction will be performed on the axes that are NOT in axis

instead.

Negative values means indexing from right to left.

keepdims boolean, optional, default=0 If this is set to 'True', the reduced axes are left in

the result as dimension with size one.

exclude boolean, optional, default=0 Whether to perform reduction on axis that are NOT

in axis instead.

name string, optional Name of the resulting symbol.

Details

'sum' and 'sum_axis' are equivalent. For ndarray of csr storage type summation along axis 0 and axis 1 is supported. Setting keepdims or exclude to True will cause a fallback to dense operator.

Example::

```
data = [[[1, 2], [2, 3], [1, 3]], [[1, 4], [4, 3], [5, 2]], [[7, 1], [7, 2], [7, 3]]] sum(data, axis=1) [[ 4. 8.] [ 10. 9.] [ 21. 6.]] sum(data, axis=[1,2]) [ 12. 19. 27.] data = [[1, 2, 0], [3, 0, 1], [4, 1, 0]] csr = cast_storage(data, 'csr')
```

```
sum(csr, axis=0) [ 8. 3. 1.]
sum(csr, axis=1) [ 3. 4. 5.]
```

Defined in src/operator/tensor/broadcast_reduce_sum_value.cc:L67

Value

out The result mx.symbol

 ${\tt mx.symbol.SVMOutput:} {\it Computes support vector machine based transformation of the input.}$

Description

This tutorial demonstrates using SVM as output layer for classification instead of softmax: https://github.com/dmlc/mxnet/tre

Usage

```
mx.symbol.SVMOutput(...)
```

Arguments

data NDArray-or-Symbol Input data for SVM transformation.

label NDArray-or-Symbol Class label for the input data.

margin float, optional, default=1 The loss function penalizes outputs that lie outside this

margin. Default margin is 1.

regularization.coefficient

float, optional, default=1 Regularization parameter for the SVM. This balances

the tradeoff between coefficient size and error.

use.linear boolean, optional, default=0 Whether to use L1-SVM objective. L2-SVM ob-

jective is used by default.

name string, optional Name of the resulting symbol.

Value

mx.symbol.swapaxes 493

mx.symbol.swapaxes

swapaxes:Interchanges two axes of an array.

Description

Examples::

Usage

```
mx.symbol.swapaxes(...)
```

Arguments

data NDArray-or-Symbol Input array.

dim1 int, optional, default='0' the first axis to be swapped.dim2 int, optional, default='0' the second axis to be swapped.

name string, optional Name of the resulting symbol.

Details

```
x = [[1, 2, 3]] swapaxes(x, 0, 1) = [[1], [2], [3]]

x = [[[0, 1], [2, 3]], [[4, 5], [6, 7]]] // (2,2,2) array

swapaxes(x, 0, 2) = [[[0, 4], [2, 6]], [[1, 5], [3, 7]]]

Defined in src/operator/swapaxis.cc:L70
```

Value

out The result mx.symbol

mx.symbol.SwapAxis

SwapAxis:Interchanges two axes of an array.

Description

Examples::

Usage

```
mx.symbol.SwapAxis(...)
```

494 mx.symbol.take

Arguments

data	NDArray-or-Symbol Input array.
dim1	int, optional, default='0' the first axis to be swapped.
dim2	int, optional, default='0' the second axis to be swapped.
name	string, optional Name of the resulting symbol.

Details

```
x = [[1, 2, 3]]) swapaxes(x, 0, 1) = [[1], [2], [3]]

x = [[[0, 1], [2, 3]], [[4, 5], [6, 7]]] // (2,2,2) array

swapaxes(x, 0, 2) = [[[0, 4], [2, 6]], [[1, 5], [3, 7]]]

Defined in src/operator/swapaxis.cc:L70
```

Value

out The result mx.symbol

mx.symbol.take

take: Takes elements from an input array along the given axis.

Description

This function slices the input array along a particular axis with the provided indices.

Usage

```
mx.symbol.take(...)
```

Arguments

a	NDArray-or-Symbol The input array.
indices	NDArray-or-Symbol The indices of the values to be extracted.
axis	int, optional, default='0' The axis of input array to be taken. For input tensor of rank r, it could be in the range of [-r, r-1]
mode	'clip', 'raise', 'wrap',optional, default='clip' Specify how out-of-bound indices bahave. Default is "clip". "clip" means clip to the range. So, if all indices mentioned are too large, they are replaced by the index that addresses the last element along an axis. "wrap" means to wrap around. "raise" means to raise an error when index out of range.
name	string, optional Name of the resulting symbol.

mx.symbol.tan 495

Details

Given data tensor of rank $r \ge 1$, and indices tensor of rank q, gather entries of the axis dimension of data (by default outer-most one as axis=0) indexed by indices, and concatenates them in an output tensor of rank q + (r - 1).

```
Examples::
```

```
x = [4. 5. 6.]
```

// Trivial case, take the second element along the first axis.

$$take(x, [1]) = [5.]$$

// The other trivial case, axis=-1, take the third element along the first axis

$$take(x, [3], axis=-1, mode='clip') = [6.]$$

$$x = [[1., 2.], [3., 4.], [5., 6.]]$$

// In this case we will get rows 0 and 1, then 1 and 2. Along axis 0

$$take(x, [[0,1],[1,2]]) = [[[1., 2.], [3., 4.]],$$

// In this case we will get rows 0 and 1, then 1 and 2 (calculated by wrapping around). // Along axis 1

```
take(x, [[0, 3], [-1, -2]], axis=1, mode='wrap') = [[[ 1. 2.] [ 2. 1.]]
```

[[3. 4.] [4. 3.]]

[[5. 6.] [6. 5.]]]

The storage type of "take" output depends upon the input storage type:

- take(default, default) = default - take(csr, default, axis=0) = csr

Defined in src/operator/tensor/indexing_op.cc:L716

Value

out The result mx.symbol

mx.symbol.tan

tan: Computes the element-wise tangent of the input array.

Description

The input should be in radians (:math: '2\pi' rad equals 360 degrees).

Usage

```
mx.symbol.tan(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

496 mx.symbol.tanh

Details

```
.. math:: tan([0, \pi/4, \pi/2]) = [0, 1, -inf]
```

The storage type of "tan" output depends upon the input storage type:

- tan(default) = default - tan(row_sparse) = row_sparse - tan(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L140

Value

out The result mx.symbol

mx.symbol.tanh

tanh:Returns the hyperbolic tangent of the input array, computed element-wise.

Description

```
.. math:: tanh(x) = sinh(x) / cosh(x)
```

Usage

```
mx.symbol.tanh(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

Details

The storage type of "tanh" output depends upon the input storage type:

- tanh(default) = default - tanh(row_sparse) = row_sparse - tanh(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_trig.cc:L393

Value

mx.symbol.tile 497

mx.symbol.tile

tile:Repeats the whole array multiple times. If "reps" has length *d*, and input array has dimension of *n*. There are three cases: *n=d*. Repeat *i*-th dimension of the input by "reps[i]" times:: x = [[1, 2], [3, 4]] tile(x, reps=(2,3)) = [[1, 2, 1, 2, 1, 2, 1, 2, 1, 2, 1, 3, 4,

Description

Defined in src/operator/tensor/matrix_op.cc:L790

Usage

```
mx.symbol.tile(...)
```

Arguments

data NDArray-or-Symbol Input data array

reps Shape(tuple), required The number of times for repeating the tensor a. Each dim

size of reps must be a positive integer. If reps has length d, the result will have dimension of max(d, a.ndim); If a.ndim < d, a is promoted to be d-dimensional by prepending new axes. If a.ndim > d, reps is promoted to a.ndim by pre-

pending 1's to it.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

 ${\it mx.symbol.topk}$

topk:Returns the indices of the top *k* elements in an input array along the given axis (by default). If ret_type is set to 'value' returns the value of top *k* elements (instead of indices). In case of ret_type = 'both', both value and index would be returned. The returned elements will be sorted.

498 mx.symbol.topk

Description

Examples::

Usage

```
mx.symbol.topk(...)
```

Arguments

data	NDArray-or-Symbol The input array
axis	int or None, optional, default='-1' Axis along which to choose the top k indices. If not given, the flattened array is used. Default is -1.
k	int, optional, default='1' Number of top elements to select, should be always smaller than or equal to the element number in the given axis. A global sort is performed if set $k < 1$.
ret.typ	'both', 'indices', 'mask', 'value',optional, default='indices' The return type. "value" means to return the top k values, "indices" means to return the indices of the top k values, "mask" means to return a mask array containing 0 and 1. 1 means the top k values. "both" means to return a list of both values and indices of top k elements.
is.ascend	boolean, optional, default=0 Whether to choose k largest or k smallest elements. Top K largest elements will be chosen if set to false.
dtype	'float16', 'float32', 'float64', 'int32', 'int64', 'uint8', optional, default='float32' DType of the output indices when ret_typ is "indices" or "both". An error will be raised if the selected data type cannot precisely represent the indices.
name	string, optional Name of the resulting symbol.

Details

```
 x = [[\ 0.3,\ 0.2,\ 0.4],\ [\ 0.1,\ 0.3,\ 0.2]]  // returns an index of the largest element on last axis topk(x) = [[\ 2.],\ [\ 1.]] 
 // returns the value of top-2 largest elements on last axis topk(x, ret_typ='value', k=2) = [[\ 0.4,\ 0.3], [\ 0.3,\ 0.2]] 
 // returns the value of top-2 smallest elements on last axis topk(x, ret_typ='value', k=2, is_ascend=1) = [[\ 0.2,\ 0.3], [\ 0.1,\ 0.2]] 
 // returns the value of top-2 largest elements on axis 0 topk(x, axis=0, ret_typ='value', k=2) = [[\ 0.3,\ 0.3,\ 0.4], [\ 0.1,\ 0.2,\ 0.2]] 
 // flattens and then returns list of both values and indices topk(x, ret_typ='both', k=2) = [[[\ 0.4,\ 0.3], [\ 0.3,\ 0.2]], [[\ 2.,\ 0.], [\ 1.,\ 2.]]] 
 Defined in src/operator/tensor/ordering_op.cc:L68
```

Value

mx.symbol.transpose 499

 $\begin{array}{ll} \text{mx.symbol.transpose} & \textit{transpose:Permutes the dimensions of an array. Examples:: } x = [[\ 1, \ 2], \ [\ 3, \ 4]] \ \textit{transpose}(x) = [[\ 1., \ 3.], \ [\ 2., \ 4.]] \ x = [[[\ 1., \ 2.], \ [\ 3., \ 4.]], \\ [[\ 5., \ 6.], \ [\ 7., \ 8.]]] \ \textit{transpose}(x) = [[[\ 1., \ 5.], \ [\ 3., \ 7.]], \ [[\ 2., \ 6.]], \ [\ 4., \ 8.]]] \\ \textit{transpose}(x, \ \textit{axes} = (1,0,2)) = [[[\ 1., \ 2.], \ [\ 5., \ 6.]], \ [[\ 3., \ 4.], \ [\ 7., \ 8.]]] \\ \text{mx.symbol.transpose}(x) = [[\ 1., \ 2.], \ [\ 5., \ 6.]], \ [\ 3., \ 4.], \ [\ 7., \ 8.]]] \\ \text{mx.symbol.transpose}(x) = [[\ 1., \ 2.], \ [\ 5., \ 6.]], \ [\ 3., \ 4.], \ [\ 7., \ 8.]] \\ \text{mx.symbol.transpose}(x) = [[\ 1., \ 2.], \ [\ 5., \ 6.]], \ [\ 3., \ 4.], \ [\ 7., \ 8.]] \\ \text{mx.symbol.transpose}(x) = [[\ 1., \ 2.], \ [\ 5., \ 6.]], \ [\ 3., \ 4.], \ [\ 7., \ 8.]] \\ \text{mx.symbol.transpose}(x) = [[\ 1., \ 2.], \ [\ 5., \ 6.]], \ [\ 3., \ 4.], \ [\ 7., \ 8.]] \\ \text{mx.symbol.transpose}(x) = [[\ 1., \ 2.], \ [\ 3., \ 4.], \ [\ 3., \$

Description

Defined in src/operator/tensor/matrix_op.cc:L325

Usage

```
mx.symbol.transpose(...)
```

Arguments

data NDArray-or-Symbol Source input

axes Shape(tuple), optional, default=[] Target axis order. By default the axes will be

inverted.

name string, optional Name of the resulting symbol.

Value

out The result mx.symbol

mx.symbol.trunc trunc:Return the element-wise truncated value of the input.

Description

The truncated value of the scalar x is the nearest integer i which is closer to zero than x is. In short, the fractional part of the signed number x is discarded.

Usage

```
mx.symbol.trunc(...)
```

Arguments

data NDArray-or-Symbol The input array.

name string, optional Name of the resulting symbol.

500 mx.symbol.uniform

Details

```
Example::
```

```
trunc([-2.1, -1.9, 1.5, 1.9, 2.1]) = [-2., -1., 1., 1., 2.]
```

The storage type of "trunc" output depends upon the input storage type:

- trunc(default) = default - trunc(row_sparse) = row_sparse - trunc(csr) = csr

Defined in src/operator/tensor/elemwise_unary_op_basic.cc:L857

Value

out The result mx.symbol

mx.symbol.uniform

uniform:Draw random samples from a uniform distribution.

Description

.. note:: The existing alias "uniform" is deprecated.

Usage

```
mx.symbol.uniform(...)
```

Arguments

low	float, optional, default=0 Lower bound of the distribution.
high	float, optional, default=1 Upper bound of the distribution.
shape	Shape(tuple), optional, default=None Shape of the output.
ctx	string, optional, default="Context of output, in format [cpulgpulcpu_pinned](n). Only used for imperative calls.
dtype	'None', 'float16', 'float32', 'float64', optional, default='None' DType of the output in case this can't be inferred. Defaults to float32 if not defined (dtype=None).
name	string, optional Name of the resulting symbol.

Details

Samples are uniformly distributed over the half-open interval *[low, high)* (includes *low*, but excludes *high*).

```
Example::
```

```
uniform(low=0, high=1, shape=(2,2)) = [[ 0.60276335, 0.85794562], [ 0.54488319, 0.84725171]] Defined in src/operator/random/sample_op.cc:L96
```

Value

mx.symbol.unravel_index

unravel_index:Converts an array of flat indices into a batch of index arrays. The operator follows numpy conventions so a single multi index is given by a column of the output matrix. The leading dimension may be left unspecified by using -1 as placeholder.

Description

Examples::

Usage

```
mx.symbol.unravel_index(...)
```

Arguments

data NDArray-or-Symbol Array of flat indices

shape Shape(tuple), optional, default=None Shape of the array into which the multi-

indices apply.

name string, optional Name of the resulting symbol.

Details

```
A = [22,41,37] \text{ unravel}(A, \text{shape}=(7,6)) = [[3,6,6],[4,5,1]] \text{ unravel}(A, \text{shape}=(-1,6)) = [[3,6,6],[4,5,1]]
Defined in src/operator/tensor/ravel.cc:L67
```

Value

out The result mx.symbol

mx.symbol.UpSampling UpSampling:Upsamples the given input data.

Description

Two algorithms ("sample_type") are available for upsampling:

Usage

```
mx.symbol.UpSampling(...)
```

Arguments

data NDArray-or-Symbol[] Array of tensors to upsample. For bilinear upsampling,

there should be 2 inputs - 1 data and 1 weight.

scale int, required Up sampling scale

num.filter int, optional, default='0' Input filter. Only used by bilinear sample_type.Since

bilinear upsampling uses deconvolution, num_filters is set to the number of

channels.

sample.type 'bilinear', 'nearest', required upsampling method

multi.input.mode

'concat', 'sum', optional, default='concat' How to handle multiple input. concat means concatenate upsampled images along the channel dimension. sum means

add all images together, only available for nearest neighbor upsampling.

num.args int, required Number of inputs to be upsampled. For nearest neighbor upsam-

pling, this can be 1-N; the size of output will be(scale*h_0,scale*w_0) and all other inputs will be upsampled to thesame size. For bilinear upsampling this

must be 2; 1 input and 1 weight.

workspace long (non-negative), optional, default=512 Tmp workspace for deconvolution

(MB)

name string, optional Name of the resulting symbol.

Details

- Nearest Neighbor - Bilinear

Nearest Neighbor Upsampling

Input data is expected to be NCHW.

Example::

UpSampling(x, scale=2, sample_type='nearest') = [[[[1. 1. 1. 1. 1. 1. 1.] [1. 1. 1. 1. 1.] [1. 1. 1. 1. 1.] [1. 1. 1. 1. 1.] [1. 1. 1. 1. 1.] [1. 1. 1. 1. 1.]]]]

Bilinear Upsampling

Uses 'deconvolution' algorithm under the hood. You need provide both input data and the kernel.

Input data is expected to be NCHW.

'num_filter' is expected to be same as the number of channels.

Example::

```
\mathbf{x} = [[[[1. \ 1. \ 1.] \ [1. \ 1. \ 1.] \ [1. \ 1. \ 1.]]]]
```

 $\mathbf{w} = [[[[1.\ 1.\ 1.\ 1.\ 1.]\ [1.\ 1.\ 1.\ 1.]\ [1.\ 1.\ 1.\ 1.]\ [1.\ 1.\ 1.\ 1.]]]]$

UpSampling(x, w, scale=2, sample_type='bilinear', num_filter=1) = [[[[1. 2. 2. 2. 2. 2. 1.] [2. 4. 4. 4. 4. 2.] [2. 4. 4. 4. 4. 2.] [2. 4. 4. 4. 4. 2.] [1. 2. 2. 2. 2. 1.]]]]

Defined in src/operator/nn/upsampling.cc:L173

Value

mx.symbol.Variable 503

mx.symbol.Variable

Create a symbolic variable with specified name.

Description

Create a symbolic variable with specified name.

Arguments

name

string The name of the result symbol.

Value

The result symbol

mx.symbol.where

where:Return the elements, either from x or y, depending on the condition.

Description

Given three ndarrays, condition, x, and y, return an ndarray with the elements from x or y, depending on the elements from condition are true or false. x and y must have the same shape. If condition has the same shape as x, each element in the output array is from x if the corresponding element in the condition is true, and from y if false.

Usage

```
mx.symbol.where(...)
```

Arguments

condition NDArray-or-Symbol condition array

x NDArray-or-Symboly NDArray-or-Symbol

name string, optional Name of the resulting symbol.

Details

If condition does not have the same shape as x, it must be a 1D array whose size is the same as x's first dimension size. Each row of the output array is from x's row if the corresponding element from condition is true, and from y's row if false.

Note that all non-zero values are interpreted as "True" in condition.

Examples::

```
x = [[1, 2], [3, 4]] y = [[5, 6], [7, 8]] cond = [[0, 1], [-1, 0]]
where(cond, x, y) = [[5, 2], [3, 8]]
csr_cond = cast_storage(cond, 'csr')
where(csr_cond, x, y) = [[5, 2], [3, 8]]
Defined in src/operator/tensor/control_flow_op.cc:L57
```

Value

out The result mx.symbol

```
mx.symbol.zeros_like zeros_like:Return an array of zeros with the same shape, type and storage type as the input array.
```

Description

The storage type of "zeros_like" output depends on the storage type of the input

Usage

```
mx.symbol.zeros_like(...)
```

Arguments

data NDArray-or-Symbol The input

name string, optional Name of the resulting symbol.

Details

```
- zeros_like(row_sparse) = row_sparse - zeros_like(csr) = csr - zeros_like(default) = default Examples:: x = [[\ 1.,\ 1.,\ 1.],\ [\ 1.,\ 1.,\ 1.]] zeros_like(x) = [[\ 0.,\ 0.,\ 0.],\ [\ 0.,\ 0.,\ 0.]]
```

Value

mx.unserialize 505

mx.unserialize

Unserialize MXNet model from Robject.

Description

Unserialize MXNet model from Robject.

Usage

```
mx.unserialize(model)
```

Arguments

model

The mxnet model loaded from RData files.

mxnet

MXNet: Flexible and Efficient GPU computing and Deep Learning.

Description

MXNet is a flexible and efficient GPU computing and deep learning framework.

Details

It enables you to write seamless tensor/matrix computation with multiple GPUs in R.

It also enables you construct and customize the state-of-art deep learning models in R, and apply them to tasks such as image classification and data science challenges.

mxnet.export

Internal function to generate mxnet_generated.R Users do not need to call this function.

Description

Internal function to generate mxnet_generated.R Users do not need to call this function.

Usage

```
mxnet.export(path)
```

Arguments

path

The path to the root of the package.

506 outputs

Ops.MXNDArray

Binary operator overloading of mx.ndarray

Description

Binary operator overloading of mx.ndarray

Usage

```
## S3 method for class 'MXNDArray'
Ops(e1, e2)
```

Arguments

e1 The first operand

e1 The second operand

outputs

Get the outputs of a symbol.

Description

Get the outputs of a symbol.

Usage

```
outputs(x)
```

Arguments

Х

The input symbol

```
predict.MXFeedForwardModel
```

Predict the outputs given a model and dataset.

Description

Predict the outputs given a model and dataset.

Usage

```
## $3 method for class 'MXFeedForwardModel'
predict(model, X, ctx = NULL,
    array.batch.size = 128, array.layout = "auto",
    allow.extra.params = FALSE)
```

Arguments

model The MXNet Model.

X The dataset to predict.

ctx mx.cpu() or mx.gpu(). The device used to generate the prediction.

array.batch.size

The batch size used in batching. Only used when X is R's array.

array.layout

can be "auto", "colmajor", "rowmajor", (detault=auto) The layout of array. "rowmajor" is only supported for two dimensional array. For matrix, "rowmajor" means $\dim(X) = c(\text{nexample}, \text{nfeatures})$, "colmajor" means $\dim(X) = c(\text{nfeatures}, \text{nexample})$ "auto" will auto detect the layout by match the feature size, and will report error when X is a square matrix to ask user to explicitly specify layout.

allow.extra.params

Whether allow extra parameters that are not needed by symbol. If this is TRUE, no error will be thrown when arg_params or aux_params contain extra parameters that is not needed by the executor.

print.MXNDArray

print operator overload of mx.ndarray

Description

print operator overload of mx.ndarray

Usage

```
## S3 method for class 'MXNDArray'
print(nd)
```

508 rnn.graph.unroll

Arguments

nd The mx.ndarray

rnn.graph

Generate a RNN symbolic model - requires CUDA

Description

Generate a RNN symbolic model - requires CUDA

Usage

```
rnn.graph(num_rnn_layer, input_size = NULL, num_embed = NULL,
   num_hidden, num_decode, dropout = 0, ignore_label = -1,
   bidirectional = F, loss_output = NULL, config, cell_type,
   masking = F, output_last_state = F, rnn.state = NULL,
   rnn.state.cell = NULL, prefix = "")
```

Arguments

num_rnn_layer int, number of stacked layers

input_size int, number of levels in the data - only used for embedding

num_embed int, default = NULL - no embedding. Dimension of the embedding vectors

num_hidden int, size of the state in each RNN layer

num_decode int, number of output variables in the decoding layer

dropout

config Either seq-to-one or one-to-one cell_type Type of RNN cell: either gru or lstm

rnn.graph.unroll

Unroll representation of RNN running on non CUDA device

Description

Unroll representation of RNN running on non CUDA device

Usage

```
rnn.graph.unroll(num_rnn_layer, seq_len, input_size = NULL,
  num_embed = NULL, num_hidden, num_decode, dropout = 0,
  ignore_label = -1, loss_output = NULL, init.state = NULL, config,
  cell_type = "lstm", masking = F, output_last_state = F,
  prefix = "", data_name = "data", label_name = "label")
```

rnn.graph.unroll 509

Arguments

num_rnn_layer int, number of stacked layers

seq_len int, number of time steps to unroll

input_size int, number of levels in the data - only used for embedding

num_embed int, default = NULL - no embedding. Dimension of the embedding vectors

num_hidden int, size of the state in each RNN layer

num_decode int, number of output variables in the decoding layer

dropout

config Either seq-to-one or one-to-one

cell_type Type of RNN cell: either gru or lstm

Index

```
*Topic datasets
                                                mx.exec.update.arg.arrays, 25
    mx.metric.accuracy, 56
                                                mx.exec.update.aux.arrays, 25
    mx.metric.logistic_acc, 56
                                                mx.exec.update.grad.arrays, 26
    mx.metric.logloss, 57
                                                mx.gpu, 26
    mx.metric.mae, 57
                                                mx.infer.rnn, 26
    mx.metric.mse, 57
                                                mx.infer.rnn.one, 27
    mx.metric.Perplexity, 58
                                                mx.infer.rnn.one.unroll, 27
    mx.metric.rmse, 58
                                                mx.init.create, 28
    mx.metric.rmsle, 58
                                                mx.init.internal.default, 28
    mx.metric.top_k_accuracy, 59
                                                mx.init.normal, 29
                                                mx.init.uniform, 29
arguments, 15
                                                mx.init.Xavier, 29
as.array.MXNDArray, 15
                                                mx.io.arrayiter, 30
as.matrix.MXNDArray, 16
                                                mx.io.bucket.iter, 30
                                                mx.io.CSVIter, 31
children, 16
                                                mx.io.extract, 32
ctx, 16
                                                mx.io.ImageDetRecordIter, 33
                                                mx.io.ImageRecordInt8Iter, 36
dim. MXNDArray, 17
                                                mx.io.ImageRecordIter, 39
graph.viz, 17
                                                mx.io.ImageRecordIter_v1, 42
                                                mx.io.ImageRecordUInt8Iter, 46
im2rec. 18
                                                mx.io.ImageRecordUInt8Iter_v1, 49
internals, 19
                                                mx.io.LibSVMIter, 52
is.mx.context, 19
                                                mx.io.MNISTIter, 53
is.mx.dataiter, 19
                                                mx.kv.create, 54
is.mx.ndarray, 20
                                                mx.lr_scheduler.FactorScheduler, 55
is.mx.symbol, 20
                                                mx.lr_scheduler.MultiFactorScheduler,
is.serialized, 21
                                                mx.metric.accuracy, 56
length.MXNDArray, 21
                                                mx.metric.custom, 56
                                                mx.metric.logistic_acc, 56
mx.apply, 21
                                                mx.metric.logloss, 57
mx.callback.early.stop, 22
                                                mx.metric.mae, 57
mx.callback.log.speedometer, 22
                                                mx.metric.mse, 57
mx.callback.log.train.metric, 23
                                                mx.metric.Perplexity, 58
mx.callback.save.checkpoint, 23
                                                mx.metric.rmse, 58
mx.cpu, 24
mx.ctx.default, 24
                                                mx.metric.rmsle, 58
mx.exec.backward, 24
                                                mx.metric.top_k_accuracy, 59
mx.exec.forward, 25
                                                mx.mlp, 59
```

mx.model.buckets, 60	mx.nd.broadcast.not.equal, 92
mx.model.FeedForward.create, 61	mx.nd.broadcast.plus, 92
mx.model.init.params, 62	mx.nd.broadcast.power, 93
mx.model.load, 63	mx.nd.broadcast.sub, 94
mx.model.save, 63	mx.nd.broadcast.to, 94
mx.nd.abs, 64	mx.nd.Cast, 95
mx.nd.Activation, 64	mx.nd.cast, 96
mx.nd.adam.update, 65	mx.nd.cast.storage, 96
mx.nd.add.n, 66	mx.nd.cbrt, 97
mx.nd.all.finite, 66	mx.nd.ceil, 98
mx.nd.amp.cast, 67	mx.nd.choose.element.0index, 98
mx.nd.amp.multicast, 67	mx.nd.clip, 99
mx.nd.arccos, 68	mx.nd.Concat, 100
mx.nd.arccosh, 68	mx.nd.concat, 101
mx.nd.arcsin, 69	mx.nd.Convolution, 101
mx.nd.arcsinh, 69	mx.nd.Convolution.v1, 103
mx.nd.arctan, 70	mx.nd.copyto, 104
mx.nd.arctanh, 70	mx.nd.Correlation, 105
mx.nd.argmax, 71	mx.nd.cos, 106
mx.nd.argmax.channel,71	mx.nd.cosh, 106
mx.nd.argmin, 72	mx.nd.Crop, 107
mx.nd.argsort, 73	mx.nd.crop, 108
mx.nd.array, 73	mx.nd.ctc.loss, 109
mx.nd.batch.dot, 74	mx.nd.CTCLoss, 110
mx.nd.batch.take, 75	mx.nd.cumsum, 112
mx.nd.BatchNorm, 75	mx.nd.Custom, 112
mx.nd.BatchNorm.v1,77	mx.nd.Deconvolution, 113
mx.nd.BilinearSampler, 78	mx.nd.degrees, 114
mx.nd.BlockGrad, 79	mx.nd.depth.to.space, 115
mx.nd.broadcast.add, 80	mx.nd.diag, 115
mx.nd.broadcast.axes, 81	mx.nd.dot, 116
mx.nd.broadcast.axis, 81	mx.nd.Dropout, 118
mx.nd.broadcast.div, 82	mx.nd.ElementWiseSum, 119
mx.nd.broadcast.equal, 83	mx.nd.elemwise.add, 119
mx.nd.broadcast.greater, 83	mx.nd.elemwise.div, 120
mx.nd.broadcast.greater.equal, 84	mx.nd.elemwise.mul, 120
mx.nd.broadcast.hypot, 84	mx.nd.elemwise.sub, 121
mx.nd.broadcast.lesser, 85	mx.nd.Embedding, 121
mx.nd.broadcast.lesser.equal, 86	mx.nd.erf, 122
mx.nd.broadcast.like, 86	mx.nd.erfinv, 123
mx.nd.broadcast.logical.and, 87	mx.nd.exp, 123
mx.nd.broadcast.logical.or, 88	mx.nd.expand.dims, 124
mx.nd.broadcast.logical.xor, 88	mx.nd.expand.dlm3, 124
mx.nd.broadcast.logical.xor, 88 mx.nd.broadcast.maximum, 89	mx.nd.expmi, 124 mx.nd.fill.element.0index, 125
mx.nd.broadcast.minimum, 89	mx.nd.fix, 125
mx.nd.broadcast.minus, 90	mx.nd.Flatten, 126
mx.nd.broadcast.mod, 91	mx.nd.flatten, 126
mx.nd.broadcast.mul, 91	mx.nd.flip, 127

mx.nd.floor, 127	mx.nd.mean, 163
mx.nd.ftml.update, 128	mx.nd.min, 164
mx.nd.ftrl.update, 129	mx.nd.min.axis, 165
mx.nd.FullyConnected, 130	mx.nd.moments, 165
mx.nd.gamma, 131	mx.nd.mp.nag.mom.update, 166
mx.nd.gammaln, 131	mx.nd.mp.sgd.mom.update, 167
mx.nd.gather.nd, 132	mx.nd.mp.sgd.update, 167
mx.nd.GridGenerator, 132	mx.nd.multi.all.finite, 168
mx.nd.GroupNorm, 133	mx.nd.multi.lars, 169
mx.nd.hard.sigmoid, 134	mx.nd.multi.mp.sgd.mom.update, 169
mx.nd.identity, 134	mx.nd.multi.mp.sgd.update, 170
mx.nd.IdentityAttachKLSparseReg, 135	mx.nd.multi.sgd.mom.update, 171
mx.nd.InstanceNorm, 135	mx.nd.multi.sgd.update, 172
mx.nd.khatri.rao, 136	mx.nd.multi.sum.sq, 172
mx.nd.L2Normalization, 137	mx.nd.nag.mom.update, 173
mx.nd.LayerNorm, 138	mx.nd.nanprod, 174
mx.nd.LeakyReLU, 139	mx.nd.nansum, 174
mx.nd.linalg.det, 140	mx.nd.negative, 175
mx.nd.linalg.extractdiag, 140	mx.nd.norm, 176
mx.nd.linalg.extracttrian, 141	mx.nd.normal, 177
mx.nd.linalg.gelqf, 142	mx.nd.one.hot, 177
mx.nd.linalg.gemm, 143	mx.nd.ones, 178
mx.nd.linalg.gemm2, 144	mx.nd.ones.like, 179
mx.nd.linalg.inverse, 145	mx.nd.Pad, 179
mx.nd.linalg.makediag, 146	mx.nd.pad, 181
mx.nd.linalg.maketrian, 147	mx.nd.pick, 182
mx.nd.linalg.potrf, 148	mx.nd.Pooling, 183
mx.nd.linalg.potri, 148	mx.nd.Pooling.v1, 185
mx.nd.linalg.slogdet, 149	mx.nd.preloaded.multi.mp.sgd.mom.update,
mx.nd.linalg.sumlogdiag, 150	186
mx.nd.linalg.syrk, 151	<pre>mx.nd.preloaded.multi.mp.sgd.update,</pre>
mx.nd.linalg.trmm, 152	187
mx.nd.linalg.trsm, 153	<pre>mx.nd.preloaded.multi.sgd.mom.update,</pre>
mx.nd.LinearRegressionOutput, 154	187
mx.nd.load, 154	mx.nd.preloaded.multi.sgd.update, 188
mx.nd.log, 155	mx.nd.prod, 189
mx.nd.log.softmax, 155	mx.nd.radians, 189
mx.nd.log10, 156	mx.nd.random.exponential, 190
mx.nd.log1p, 157	mx.nd.random.gamma, 191
mx.nd.log2, 157	<pre>mx.nd.random.generalized.negative.binomial,</pre>
mx.nd.logical.not, 158	191
mx.nd.LogisticRegressionOutput, 158	mx.nd.random.negative.binomial, 192
mx.nd.LRN, 159	mx.nd.random.normal, 193
mx.nd.MAERegressionOutput, 160	mx.nd.random.pdf.dirichlet, 194
mx.nd.make.loss, 160	mx.nd.random.pdf.exponential, 194
mx.nd.MakeLoss, 161	mx.nd.random.pdf.gamma, 195
mx.nd.max, 162	mx.nd.random.pdf.generalized.negative.binomial
mx.nd.max.axis, 163	196

<pre>mx.nd.random.pdf.negative.binomial,</pre>	mx.nd.sinh, 236
197	mx.nd.size.array, 236
mx.nd.random.pdf.normal, 198	mx.nd.slice.axis, 237
mx.nd.random.pdf.poisson, 199	mx.nd.slice.like, 238
mx.nd.random.pdf.uniform, 199	mx.nd.SliceChannel, 239
mx.nd.random.poisson, 200	mx.nd.smooth.11, 240
mx.nd.random.randint, 201	mx.nd.Softmax, 240
mx.nd.random.uniform, 201	mx.nd.softmax, 242
mx.nd.ravel.multi.index, 202	mx.nd.softmax.cross.entropy, 243
mx.nd.rcbrt, 203	mx.nd.SoftmaxActivation, 244
mx.nd.reciprocal, 203	mx.nd.SoftmaxOutput, 245
mx.nd.relu, 204	mx.nd.softmin, 246
mx.nd.repeat, 204	mx.nd.softsign, 247
mx.nd.reset.arrays, 205	mx.nd.sort, 248
mx.nd.Reshape, 205	mx.nd.space.to.depth, 248
mx.nd.reshape, 207	mx.nd.SpatialTransformer, 249
mx.nd.reshape.like, 208	mx.nd.split, 250
mx.nd.reverse, 209	mx.nd.sqrt, 251
mx.nd.rint, 210	mx.nd.square, 251
mx.nd.rmsprop.update, 210	mx.nd.squeeze, 252
mx.nd.rmspropalex.update, 211	mx.nd.stack, 252
mx.nd.RNN, 213	mx.nd.stop.gradient, 253
mx.nd.ROIPooling, 214	mx.nd.sum, 254
mx.nd.round, 216	mx.nd.sum.axis, 255
mx.nd.rsqrt, 216	mx.nd.SVMOutput, 256
mx.nd.sample.exponential, 217	mx.nd.swapaxes, 256
mx.nd.sample.gamma, 218	mx.nd.SwapAxis, 257
<pre>mx.nd.sample.generalized.negative.binomial,</pre>	mx.nd.take, 257
219	mx.nd.tan, 258
mx.nd.sample.multinomial, 220	mx.nd.tanh, 259
mx.nd.sample.negative.binomial, 221	mx.nd.tile, 260
mx.nd.sample.normal, 222	mx.nd.topk, 260
mx.nd.sample.poisson, 223	mx.nd.transpose, 261
mx.nd.sample.uniform, 224	mx.nd.trunc, 262
mx.nd.save, 225	mx.nd.uniform, 263
mx.nd.scatter.nd, 225	mx.nd.unravel.index, 263
mx.nd.SequenceLast, 226	mx.nd.UpSampling, 264
mx.nd.SequenceMask, 227	mx.nd.where, 265
mx.nd.SequenceReverse, 228	mx.nd.zeros, 266
mx.nd.sgd.mom.update, 230	mx.nd.zeros.like, 266
mx.nd.sgd.update, 231	mx.opt.adadelta, 267
mx.nd.shape.array,232	mx.opt.adagrad, 267
mx.nd.shuffle, 232	mx.opt.adam, 268
mx.nd.sigmoid, 233	mx.opt.create, 269
mx.nd.sign, 233	mx.opt.get.updater, 269
mx.nd.signsgd.update, 234	mx.opt.nag, 270
mx.nd.signum.update, 234	mx.opt.rmsprop, 270
mx.nd.sin, 235	mx.opt.sgd, 271

mx.profiler.config, 272	mx.symbol.broadcast_mul,308
mx.profiler.state, 272	mx.symbol.broadcast_not_equal, 308
mx.rnorm, 273	mx.symbol.broadcast_plus, 309
mx.runif, 273	<pre>mx.symbol.broadcast_power, 310</pre>
mx.serialize, 274	<pre>mx.symbol.broadcast_sub, 311</pre>
mx.set.seed, 274	mx.symbol.broadcast_to,312
mx.simple.bind, 275	mx.symbol.Cast, 313
mx.symbol.abs, 275	mx.symbol.cast, 313
mx.symbol.Activation, 276	mx.symbol.cast_storage, 314
mx.symbol.adam_update, 276	mx.symbol.cbrt, 315
mx.symbol.add_n, 278	mx.symbol.ceil,315
mx.symbol.all_finite, 278	mx.symbol.choose_element_0index, 316
mx.symbol.amp_cast, 279	mx.symbol.clip, 317
mx.symbol.amp_multicast, 279	mx.symbol.Concat, 318
mx.symbol.arccos, 280	mx.symbol.concat, 319
mx.symbol.arccosh, 281	mx.symbol.Convolution, 319
mx.symbol.arcsin, 281	mx.symbol.Convolution_v1, 321
mx.symbol.arcsinh, 282	mx.symbol.Correlation, 322
mx.symbol.arctan, 283	mx.symbol.cos, 324
mx.symbol.arctanh, 283	mx.symbol.cosh, 324
mx.symbol.argmax, 284	mx.symbol.Crop, 325
mx.symbol.argmax_channel, 285	mx.symbol.crop, 326
mx.symbol.argmin, 285	mx.symbol.ctc_loss, 328
mx.symbol.argsort, 286	mx.symbol.CTCLoss, 327
mx.symbol.batch_dot, 290	mx.symbol.cumsum, 330
mx.symbol.batch_take, 291	mx.symbol.Custom, 330
mx.symbol.BatchNorm, 287	mx.symbol.Deconvolution, 331
mx.symbol.BatchNorm_v1, 289	mx.symbol.degrees, 332
mx.symbol.BilinearSampler, 292	mx.symbol.degrees, 332
mx.symbol.BlockGrad, 293	mx.symbol.diag, 334
mx.symbol.broadcast_add, 294	
	mx.symbol.dot, 335
mx.symbol.broadcast_axes, 295	mx.symbol.Dropout, 336
mx.symbol.broadcast_axis, 296	mx.symbol.ElementWiseSum, 337
mx.symbol.broadcast_div, 297	mx.symbol.elemwise_add, 338
mx.symbol.broadcast_equal, 297	mx.symbol.elemwise_div, 338
mx.symbol.broadcast_greater, 298	mx.symbol.elemwise_mul, 339
mx.symbol.broadcast_greater_equal, 299	mx.symbol.elemwise_sub, 339
mx.symbol.broadcast_hypot, 299	mx.symbol.Embedding, 340
mx.symbol.broadcast_lesser, 300	mx.symbol.erf, 341
mx.symbol.broadcast_lesser_equal, 301	mx.symbol.erfinv, 342
mx.symbol.broadcast_like, 302	mx.symbol.exp, 343
mx.symbol.broadcast_logical_and, 303	mx.symbol.expand_dims, 343
mx.symbol.broadcast_logical_or, 303	mx.symbol.expm1, 344
mx.symbol.broadcast_logical_xor, 304	mx.symbol.fill_element_0index, 345
mx.symbol.broadcast_maximum, 305	mx.symbol.fix, 345
mx.symbol.broadcast_minimum, 305	mx.symbol.Flatten, 346
mx.symbol.broadcast_minus, 306	mx.symbol.flatten,347
mx.symbol.broadcast_mod, 307	mx.symbol.flip,347

mx.symbol.floor, 348	mx.symbol.MAERegressionOutput, 386
mx.symbol.ftml_update, 349	mx.symbol.make_loss, 388
mx.symbol.ftrl_update,350	mx.symbol.MakeLoss, 387
mx.symbol.FullyConnected, 351	mx.symbol.max,388
mx.symbol.gamma, 352	mx.symbol.max_axis, 389
mx.symbol.gammaln, 352	mx.symbol.mean, 390
mx.symbol.gather_nd,353	mx.symbol.moments, 391
mx.symbol.GridGenerator, 353	mx.symbol.mp_nag_mom_update, 391
mx.symbol.Group, 354	mx.symbol.mp_sgd_mom_update, 392
mx.symbol.GroupNorm, 355	mx.symbol.mp_sgd_update, 393
mx.symbol.hard_sigmoid, 356	mx.symbol.multi_all_finite, 394
mx.symbol.identity, 356	mx.symbol.multi_lars,394
mx.symbol.IdentityAttachKLSparseReg,	mx.symbol.multi_mp_sgd_mom_update, 395
357	mx.symbol.multi_mp_sgd_update, 396
mx.symbol.infer.shape, 357	mx.symbol.multi_sgd_mom_update, 397
mx.symbol.InstanceNorm, 358	mx.symbol.multi_sgd_update, 398
mx.symbol.khatri_rao,359	mx.symbol.multi_sum_sq, 399
mx.symbol.L2Normalization, 360	mx.symbol.nag_mom_update, 399
mx.symbol.LayerNorm, 361	mx.symbol.nanprod, 400
mx.symbol.LeakyReLU, 362	mx.symbol.nansum, 401
mx.symbol.linalg_det,363	mx.symbol.negative, 402
mx.symbol.linalg_extractdiag, 364	mx.symbol.norm, 402
mx.symbol.linalg_extracttrian, 365	mx.symbol.normal, 403
mx.symbol.linalg_gelqf,366	mx.symbol.one_hot, 405
mx.symbol.linalg_gemm, 367	mx.symbol.ones_like, 404
mx.symbol.linalg_gemm2, 368	mx.symbol.Pad, 406
mx.symbol.linalg_inverse, 369	mx.symbol.pad, 407
mx.symbol.linalg_makediag,370	mx.symbol.pick, 408
mx.symbol.linalg_maketrian, 371	mx.symbol.Pooling, 410
mx.symbol.linalg_potrf, 372	mx.symbol.Pooling_v1,411
mx.symbol.linalg_potri, 373	<pre>mx.symbol.preloaded_multi_mp_sgd_mom_update,</pre>
mx.symbol.linalg_slogdet, 374	413
mx.symbol.linalg_sumlogdiag, 375	<pre>mx.symbol.preloaded_multi_mp_sgd_update,</pre>
mx.symbol.linalg_syrk,376	414
mx.symbol.linalg_trmm,377	<pre>mx.symbol.preloaded_multi_sgd_mom_update,</pre>
mx.symbol.linalg_trsm, 378	414
mx.symbol.LinearRegressionOutput, 379	<pre>mx.symbol.preloaded_multi_sgd_update,</pre>
mx.symbol.load, 380	415
mx.symbol.load.json,380	mx.symbol.prod,416
mx.symbol.log,381	mx.symbol.radians, 417
mx.symbol.log10,381	mx.symbol.random_exponential, 417
mx.symbol.log1p, 382	mx.symbol.random_gamma, 418
mx.symbol.log2,382	mx.symbol.random_generalized_negative_binomial
mx.symbol.log_softmax, 384	419
mx.symbol.logical_not, 383	mx.symbol.random_negative_binomial,
mx.symbol.LogisticRegressionOutput,	420
383	mx.symbol.random_normal, 421
mx.symbol.LRN, 385	mx.symbol.random_pdf_dirichlet, 422

```
mx.symbol.random_pdf_exponential, 423
                                               mx.symbol.sigmoid, 465
mx.symbol.random_pdf_gamma, 424
                                               mx.symbol.sign, 465
mx.symbol.random_pdf_generalized_negative_binmomisnlmbol.signsgd_update, 466
                                               mx.symbol.signum_update, 467
mx.symbol.random_pdf_negative_binomial,
                                               mx.symbol.sin, 468
        426
                                               mx.symbol.sinh, 468
mx.symbol.random_pdf_normal, 427
                                               mx.symbol.size_array, 469
mx.symbol.random_pdf_poisson, 428
                                               mx.symbol.slice, 470
mx.symbol.random_pdf_uniform, 429
                                               mx.symbol.slice_axis, 472
mx.symbol.random_poisson, 430
                                               mx.symbol.slice_like, 473
mx.symbol.random_randint, 430
                                               mx.symbol.SliceChannel, 471
mx.symbol.random_uniform, 431
                                               mx.symbol.smooth_11,474
mx.symbol.ravel_multi_index, 432
                                               mx.symbol.Softmax, 474
mx.symbol.rcbrt, 433
                                               mx.symbol.softmax, 476
mx.symbol.reciprocal, 433
                                               mx.symbol.softmax_cross_entropy, 480
mx.symbol.relu, 434
                                               mx.symbol.SoftmaxActivation.477
mx.symbol.repeat, 435
                                               mx.symbol.SoftmaxOutput, 478
mx.symbol.reset_arrays, 435
                                               mx.symbol.softmin, 481
mx.symbol.Reshape, 436
                                               mx.symbol.softsign, 482
mx.symbol.reshape, 437
                                               mx.symbol.sort, 482
mx.symbol.reshape_like, 439
                                               mx.symbol.space_to_depth, 483
                                               {\tt mx.symbol.SpatialTransformer,484}
mx.symbol.reverse, 440
mx.symbol.rint, 441
                                               mx.symbol.split, 485
mx.symbol.rmsprop_update, 443
                                               mx.symbol.sqrt, 486
mx.symbol.rmspropalex_update, 441
                                               mx.symbol.square, 487
mx.symbol.RNN, 444
                                               mx.symbol.squeeze, 487
mx.symbol.ROIPooling, 446
                                               mx.symbol.stack, 488
mx.symbol.round, 447
                                               mx.symbol.stop_gradient, 489
mx.symbol.rsqrt, 448
                                               mx.symbol.sum, 490
mx.symbol.sample_exponential, 448
                                               mx.symbol.sum_axis, 491
                                               mx.symbol.SVMOutput, 492
mx.symbol.sample_gamma, 449
mx.symbol.sample_generalized_negative_binomianlx.symbol.swapaxes, 493
        450
                                               mx.symbol.SwapAxis, 493
mx.symbol.sample_multinomial, 451
                                               mx.symbol.take, 494
mx.symbol.sample_negative_binomial,
                                               mx.symbol.tan, 495
        452
                                               mx.symbol.tanh, 496
mx.symbol.sample_normal, 453
                                               mx.symbol.tile, 497
mx.symbol.sample_poisson, 454
                                               mx.symbol.topk, 497
mx.symbol.sample_uniform, 455
                                               mx.symbol.transpose, 499
mx.symbol.save, 456
                                               mx.symbol.trunc, 499
mx.symbol.scatter_nd, 457
                                               mx.symbol.uniform, 500
mx.symbol.SequenceLast, 458
                                               mx.symbol.unravel_index, 501
                                               mx.symbol.UpSampling, 501
mx.symbol.SequenceMask, 459
mx.symbol.SequenceReverse, 460
                                               mx.symbol.Variable, 503
mx.symbol.sgd_mom_update, 462
                                               mx.symbol.where, 503
mx.symbol.sgd_update, 463
                                               mx.symbol.zeros_like, 504
mx.symbol.shape_array,464
                                               mx.unserialize, 505
                                               mxnet, 505
mx.symbol.shuffle, 464
```

```
mxnet-package (mxnet), 505
mxnet.export, 505

Ops.MXNDArray, 506
outputs, 506
predict.MXFeedForwardModel, 507
print.MXNDArray, 507

rnn.graph, 508
rnn.graph.unroll, 508
```