Apache Cassandra 3.11.17 Installation on Windows OS

Table of Contents

1.	Ove	erview:	4
2.	Pre	requisites:	5
3.	Inst	tall Cassandra:	6
	3.1.	Download Cassandra Binaries:	6
	3.2.	Set up Environment variables:	8
	3.3.	Verify Cassandra Installation:	12
4.	Con	nfigure Cassandra:	14
5.	Sta	rt Cassandra:	16
	5.1.	Start Cassandra Service:	16
	5.2.	Verify Node Status:	17
6.	Con	nfigure Multi-Node Cluster:	19
	6.1.	Extract Cassandra Binaries:	19
	6.2.	Modify Configuration Files:	19
	6.3.	Remove Environment Variable:	22
	6.4.	Start Cassandra Service:	23
	6.5.	Verify Node Status:	25
7.	CQI	LSH:	26
	7.1.	Describe Cluster:	28
	7.2.	View Version:	28
	7.3.	Show Host:	28
	7.4.	Create Keyspace:	29
	7.5.	Create Table:	30
	7.6.	Insert Data:	31
	7.7.	Read Data:	31
	7.8.	Batch Queries:	32
	7.9.	Data Replication:	33
8.	No	deTool Utility:	34
	8.1.	Nodetool help:	35
	8 2	Nodetool describecluster:	35

8.3.	Nodetool status:	36
8.4.	Nodetool ring:	36
8.5.	Nodetool gossipinfo:	37
8.6.	Nodetool getlogginglevels:	37
8.7.	Nodetool netstats:	38
8.8.	Nodetool tablestats:	38
8.9.	Nodetool cleanup:	38
8.10.	Nodetool compact:	38
8.11.	Nodetool decommission:	39
8.12.	Nodetool drain:	39
8.13.	Nodetool garbagecollect:	39
8.14.	Nodetool join:	40
8.15.	Nodetool removenode:	40
8.16.	Nodetool assasinate:	40
8.17.	Nodetool repair:	41

This document outlines the steps needed to install **Apache Cassandra 3.11.17** with single-node and multi-node cluster configuration on Windows Operating system.

1. Overview:

Apache Cassandra is an open-source, highly scalable and distributed NoSQL (Not only SQL) database management system that is designed to handle large amounts of structured and unstructured data distributed across multiple commodity servers.

Apache Cassandra is initially developed at **Facebook** with a combination of distribution storage and replication model from Amazon Dynamo and column-family data model from Google Bigtable. It has a distributed architecture where large volumes of structed and unstructured data can be stored on multiple commodity hardware machines which provides high availability with no single point of failure, making it a popular choice for enterprises needing robust data solutions.

Apache Cassandra follows decentralized, peer to peer model. Unlike traditional databases that use master-slave architecture, Cassandra operates on peer-to-peer model which is nothing but all nodes in Cassandra cluster are identical, with no master nodes and each node communicates with other nodes directly, ensuring no bottlenecks and single point of failure.

The key components of Cassandra include **Node**, **Data Center**, **Cluster**, **Commit log**, **Mem-table**, **SSTable**. It is important to understand these terminologies in Cassandra.

- **Node**: It is the basic component in Cassandra. A node is nothing but a machine where data is actually stored
- **Data Center**: It is a collection of many nodes.
- **Cluster**: It is a collection of multiple data centers
- **Commit Log**: It is the first entry point while data to Cassandra. Data is first written to commit log which is a durable write-ahead log on disk. This helps in data recovery and sync in case of any crash in nodes.
- **Mem-table**: After writing data to commit log, data is stored in memtable which is an inmemory data structure.
- **SSTable**: Once the mem-table reaches a certain size, then data is flushed to disk and is stored in a SSTable (Sorted String table), an immutable data file.
- **Consistency levels**: Cassandra allows users to choose consistency level for their read and write operations, balancing between consistency and availability.
- Partitioning: Cassandra uses partitioning concept to distribute data across cluster. It hashes
 partition key of a row with a consistent hashing mechanism and determines which node will
 store that row.
- **Replication Strategy**: Based on the replication factor configured, Cassandra replicates partitions across multiple nodes to ensure data availability and fault tolerance. Cassandra

follows two replication strategies – **SimpleStrategy** (allows to specify single replication factor to copy data across cluster) **NetworkTopologyStrategy** (allows to specify replication factor for each data center in the cluster)

Note:

The latest release of Apache Cassandra from 4.0+ does not support the direct installation on Windows operating system. If you would like to use Apache Cassandra 4.0+ version, then go with Docker image or install it on Linux operating system.

2. Prerequisites:

The following prerequisites need to be installed before running Cassandra.

- File Archiver: Any file archiver such as 7zip or WinRAR is needed to unzip the downloaded Spark binaries. 7zip can be downloaded from the 7zip Downloads website and WinRAR can be downloaded from the RAR lab Downloads website.
- JRE 8: Cassandra 3.11 requires Java 8 runtime environment supporting up to JDK
 1.8_251 release. You can download the JDK 8u251 release from Oracle Java Archive Downloads website. For the complete JDK installation steps, look at here.

Verify the installed Java version using the below command:

```
java -version
```

```
Command Prompt

Microsoft Windows [Version 10.0.19045.5247]

(c) Microsoft Corporation. All rights reserved.

C:\Users\hp>java -version
java version "1.8.0_251"

Java(TM) SE Runtime Environment (build 1.8.0_251-b08)


Java HotSpot(TM) 64-Bit Server VM (build 25.251-b08, mixed mode)

C:\Users\hp>
```

3. **Python 2.7**: Cassandra 3.11 requires Python 2.7 to be installed to be able to use **cqlsh** tool. You can install Python 2.7.8 release from the official <u>Python Downloads</u> website and set the python install location in PATH environment variable.

Verify the installed Python version using the below command:

```
python --version
```



It displays that **Python 2.7.8** version is installed.

3. Install Cassandra:

Let us see the step by step procedure to install Apache Cassandra in Windows.

3.1. Download Cassandra Binaries:

You can get the stable release from the official <u>Apache Cassandra Downloads</u> website. At the time of this document preparation, the most recent stable release is **4.1.7** which cannot be used on Windows system directly. So, let us go the <u>Cassandra Archive location</u> and download **3.11.17** release.

On the <u>Cassandra Archive 3.11.17</u> page, click on <u>apache-cassandra-3.11.17-bin.tar.gz</u> link which downloads the file into your **Downloads** folder in your machine.




Index of /dist/cassandra/3.11.17


	Name	Last modified	Size	Description
.	Parent Directory		-	
	apache-cassandra-3.11.17-bin.tar.gz	2024-04-12 17:44	31M	
	apache-cassandra-3.11.17-bin.tar.gz.asc	2024-04-12 17:44	833	
	apache-cassandra-3.11.17-bin.tar.gz.sha256	2024-04-12 17:44	65	
	apache-cassandra-3.11.17-bin.tar.gz.sha512	2024-04-12 17:44	129	
	apache-cassandra-3.11.17-src.tar.gz	2024-04-12 17:44	16M	
	apache-cassandra-3.11.17-src.tar.gz.asc	2024-04-12 17:44	833	
	<pre>apache-cassandra-3.11.17-src.tar.gz.sha256</pre>	2024-04-12 17:44	65	
	apache-cassandra-3.11.17-src.tar.gz.sha512	2024-04-12 17:44	129	

After the binary file is downloaded, unpack it using any file archiver (**7zip** or **WinRAR**) utility as below:


• Choose the installation directory in your machine and copy apache-cassandra-3.11.17-bin.tar.gz file to that directory. Here, we are choosing Cassandra installation directory as D:\ProgramFiles\Cassandra.




Right click on apache-cassandra-3.11.17-bin.tar.gz and choose 7-Zip ->
 Extract Here option which extracts a new packed file apache-cassandra-3.11.17-bin.tar.



• Next, unpack apache-cassandra-3.11.17-bin.tar file using 7zip utility.



 The tar file extraction may take few minutes to finish. After finishing, you see a folder named apache-cassandra-3.11.17-bin which consists of Cassandra binaries and libraries.



3.2. Set up Environment variables:


After installing pre-requisites and Cassandra binaries, we should configure the below environment variables defining Java and Cassandra default paths.

- **JAVA_HOME**: This is the JDK installation directory path in the machine (in my machine, it is D:\ProgramFiles\Java\jdk1.8.0 251). Ignore it if this is already done.
- **CASSANDRA_HOME**: This is the Cassandra installation directory path in the machine (in our case, it is D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17)


These variables need to be added to either **User environment variables** or **System environment variables** depending on Cassandra configuration needed **for a single user** or **for multiple users**.

In this tutorial, we will add <u>User environment variables</u> since we are configuring Cassandra for a single user. If you would like to configure Cassandra for multiple users, then define <u>System</u> environment variables.


In the Windows search bar, start typing "environment variables" and select the first match which opens up **System Properties** dialog.




On the **System Properties** window, press **Environment Variables** button.




In the **Environment Variables** dialog, click on **New** under **User variables** section.



Add JAVA_HOME variable and press OK.




Click on New again and add CASSANDRA_HOME variable and press OK.




Now, we will update PATH variable to add Java, and Cassandra binary paths.

Select PATH variable under **User Variables** and press **Edit** button.




Press New and add the following values and press OK.

%JAVA_HOME%\bin
%CASSANDRA HOME%\bin



Press OK again to apply environment variable changes and close window.



3.3. Verify Cassandra Installation:

Open **Windows PowerShell** and run the following command to verify if Cassandra is installed properly: (you cannot do this from **Command Prompt** and must use **Windows PowerShell**)

cassandra -v

Note:

While executing the above script, you may encounter an error cassandra: File D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin\cassandra.ps1 cannot be loaded because running scripts is disabled on this system, as shown below. This error occurs when you do not have permissions to execute the PowerShell script.

To resolve the above error, run the below command to set the execution policy to 'Remotesigned' for the current user.

powershell Set-ExecutionPolicy RemoteSigned -Scope CurrentUser

```
Windows PowerShell
PS C:\Users\hp> powershell Set-ExecutionPolicy RemoteSigned -Scope CurrentUser
PS C:\Users\hp>
```

Now, you should be able to verify the Cassandra version installed by running this command

cassandra -v

```
Windows PowerShell

Windows PowerShell

Copyright (C) Microsoft Corporation. All rights reserved.

Try the new cross-platform PowerShell https://aka.ms/pscore6

PS C:\Users\hp> cassandra -v

***

WARNING! Automatic page file configuration detected.

It is recommended that you disable swap when running Cassandra for performance and stability reasons.

**

WARNING! Detected a power profile other than High Performance.

Performance of this node will suffer.

Modify conf\cassandra.env.ps1 to suppress this warning.

**

Cassandra Version: 3.11.17

PS C:\Users\np>
```

Here, it shows **3.11.17** version which indicates that Cassandra has been installed successfully.

Note:

It is necessary to have PowerShell execution policy set to either 'RemoteSigned' or 'Unrestricted' to be able to run Cassandra commands from **Windows PowerShell** prompt in Windows system. Going forward, we will execute Cassandra commands from **Command Prompt** itself and so let us revert the execution policy that we have set earlier by executing the below command in Windows PowerShell.

powershell Set-ExecutionPolicy Undefined -Scope CurrentUser

```
Windows PowerShell

PS C:\Users\hp> powershell Set-ExecutionPolicy Undefined -Scope CurrentUser

PS C:\Users\hp>
```

4. Configure Cassandra:

When Cassandra is used on a single node, there is no need to make any changes to the default configuration but if you would like to setup a Cassandra cluster with multiple nodes, it is important to know the configuration details.

The key configuration files used in Cassandra are available under <code>%CASSANDRA_HOME%\conf</code> folder.

- 1. **cassandra.yml** It is the primary config file for each node instance to configure the cluster name, IP address, directory paths, etc.
- cassandra-env.sh Environment file to set java environment settings such as MAX_HEAP_SIZE.
- 3. **Cassandra-rackdc.properties** Config file used to set the rack and data center to which the node belongs to.
- 4. **Cassandra-topology.properties** Config file used to specify the IP address for racks and data centers in the cluster.

Though we are using Cassandra with single node, let us see how some configuration changes can be made for cluster setup.

Open cassandra.yml from %CASSANDRA_HOME%\conf directory and set the following properties:


- cluster_name: Name of the cluster. By default, it is set to Test Cluster. You can change it to the desired name, for instance, CassandraDBCluster. Make sure that all nodes in the cluster use the same cluster name.
- num_tokens: Number of tokens. By default, this is set to 256. Any value greater than 1 is treated as virtual node so that token distribution will happen automatically.
- listen_address: IP address or hostname of the current node to be used by other nodes to connect to this node. By default, it is set to localhost but you can change it to the internal IP address of the node.
- rpc_address: Internal IP address for thrift client connections. By default, it is set to localhost but you can change it to the internal IP address of the node.
- seed_provider: List of internal IP addresses of hosts that are deemed contact points. In the config file of every node, we should specify the IP address of seed nodes. By default, it is set to "127.0.0.1" and should be updated with internal IP addresses of all hosts in the cluster.
- endpoint_snitch: It gives some information about network topology so that Cassandra can efficiently route requests. By default, it is set to SimpleSnatch class which is appropriate for cluster setup with single datacenter. For multi-data center

deployments, it is recommended to use GossipingPropertyFileSnitch with which rack and datacenter for the local node are specified in Cassandra-rackdc.properties and propagated to other nodes via gossip. Cassandra supports other types of snitches such as PropertyFileSnitch, Ec2Snitch, Ec2MultiRegionSnitch, RackInferringSnitch, etc.

 auto_bootstrap: This configuration is not available in the file and can be added and set to false. This configuration is optional if nodes are added to existing cluster but required when creating a new cluster with no data.

Locate the above settings in cassandra.yml file and modify as below:

When the endpoint_snitch is set to GossipingPropertyFileSnitch in cassandra.yaml file, it always loads cassandra-topology.properties file if present and so, it is recommended to remove or rename this file in %CASSANDRA HOME%\conf directory on all nodes.



Now, we can assign a datacenter and a rack name of the current node in %CASSANDRA_HOME%\conf\cassandra-rackdc.properties file. By default, dc is set to dc1 and rack is set to rack1. Change these settings if you want to put the node on a different rack in a different datacenter.

In cassandra-rackdc.properties file, modify as below:

dc=Asia rack=South

```
D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\conf\cassandra-rackdc.properties - Notepad+
File Edit Search View Encoding Language Settings Tools Macro Run Plugins Window ?
 3 🖶 🖰 📭 😘 🙈 🚜 🖍 🏗 🗩 c i 🛎 🛬 🔍 📭
님 cassandra-rackdc.properties 🛚 🖺
         # Unless required by applicable law or agreed to in writing,
         # distributed under the License is distributed on an "AS IS"
        # WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either expre
 14
        # See the License for the specific language governing permis
  15
         # limitations under the License.
 16
         # These properties are used with GossipingPropertyFileSnitch
 18
         # indicate the rack and dc for this node
  19
         dc=Asia
        rack=South
 21
         # Add a suffix to a datacenter name. Used by the Ec2Snitch a
         # to append a string to the EC2 region name.
        #dc suffix=
```


5. Start Cassandra:

It is time to start the Cassandra service and test the connection.

5.1. Start Cassandra Service:

Open Command Prompt and start Cassandra service using the below command:

cassandra



```
61805722479, 3940901447638997505, 4090988768067983344, 4094476459790089890, 4101194620958841001, 4135121121262872145, 41
47222441685375432, 4291127629069345553, 4299091422361713208, 43451334708866044433, 4502108715109004055, 45062032236530682
4, 4657364847329478655, 480064096989452572, 4861393139745299557, 4936637902862111774, 4951764796520171424, 5041488644686
39931, 5141251703003215490, 5234548352294079437, 5249745494224681877, 5276776363265125381, 5341067158627933453, 5356022
315289864244, 5505414569388553281, 5947320301395286306, 5964448109290499855, 59767433064599030227, 6149834389298781345, 616935394953573688, 6252487626068581148, 6311673945759522311, 6378328524850616581, 6421541172671519055, 65575319276630621
72, 6609561935489953240, 6751900433691548334, 6774242367089314308, 680663296013548161, 6939008319541526405, 696650518472
5587872, 6987846021164193551, 7072963785972566886, 7103469070463959878, 713828549554575361, 7553413995239462666, 7644842
5936838348, 764836095418275591, 7700109442774356720, 77120947777193868, 7718859536555751817, 77510883486894188084, 78
90498386799930014, 7968980211998771930, 7998686796765875243, 8153141935840144760, 8279401591116454503, 83315389368235470
71, 835765426332002881, 8426584744379278506, 8600095122214242184, 863735089149857987, 8096196755699747165, 8727187669105
365463, 8813511851536048354, 88518766525576432097, 889154596127442779, 8945536090725393954, 9125731636500548706, 91283906
66290355109, 945146485359895093, 972350692951721767]
INFO [main] 2024-11-04 15:51:22,4765 StorageService.java:2595 - [Node /127.0.0.1 state jump to NORMAL]
INFO [main] 2024-11-04 15:51:22,4765 StorageService.java:2595 - [Node /127.0.0.1 state jump to NORMAL]
INFO [main] 2024-11-04 15:51:22,4765 StorageService.java:2595 - [Node /127.0.0.1 state jump to NORMAL]
INFO [main] 2024-11-04 15:51:22,4765 StorageService.java:1590 - Normal state jump to NORMAL]
INFO [main] 2024-11-04 15:51:22,872 Server.java:158 - Using Netty Version: [netty-buffer=netty-buffer-4.0.44.Final.452812a, netty-component-y
```

On the console, you will see a message "Node /127.0.0.1 state jump to NORMAL" which indicates that the Cassandra instance has started and is up and running. Do not close this command prompt window.

We can also use the jps command to verify Cassandra service:

jps

It should display CassandraDaemon which denotes that Cassandra service is running.

C:\Users\hp>jps 10132 Jps 20356 CassandraDaemon C:\Users\hp>

5.2. Verify Node Status:

Now, let us check the status of current node using nodetool utility with the following command:

nodetool status

```
Command Prompt
Microsoft Windows [Version 10.0.19045.5247]
(c) Microsoft Corporation. All rights reserved.
C:\Users\hp>nodetool status
Datacenter: Asia
Status=Up/Down
// State=Normal/Leaving/Joining/Moving
   Address
                                     Owns (effective) Host ID
                                                                                           Rack
            Load
                        Tokens
UN 127.0.0.1 71 KiB
                         256
                                     100.0%
                                                       d0007c4c-2473-40e7-b81c-99b28d4c7e77
                                                                                           South
C:\Users\hp>
```

Here, you can see the process status, listening address, tokens, host ID, data center and rack name of the current node.

Check the token distribution of the node using the following command

nodetool ring


Command Prompt									
C:\Users\hp>nodetool ring									
Datacenter: Asia									
======= Address	: Rack	Status	State	Load	Owns	Token			
ridai C55	Ruck	Scacas	Jeace	Loud	OWITS	9198172161589035499			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-9220766189894006494			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-9196783473201380593			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-9174924999278814718			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-9082946624651449735			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8945939214799445344			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8861366292819070799			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8854521770147567993			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8761557866473840096			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8612738747689475005			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8497631400471766578			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8233610501614516548			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8219959649294129584			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8111325480103805980			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8093252645883671730			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8078908293991773158			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-8043736546566491682			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-7878559214147165878			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-7866918914852178298			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-7847196978973970820			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-7840220626997078810			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-7694745601724351458			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-7686091334425154620			
127.0.0.1	South	Up	Normal	71 KiB	100.00%	-7644384978999218452			

6. Configure Multi-Node Cluster:


For the purpose of this documentation, we will create a second Cassandra node in the same system with a different address but in the real-time project, we should configure one node per system in a Cassandra cluster.

6.1. Extract Cassandra Binaries:

To set up a new Cassandra node, create a new folder where a new instance of Cassandra can be installed. In my case, I created node2 folder under D: \ProgramFiles\Cassandra location.



Copy the Cassandra binary file apache-cassandra-3.11.17-bin.tar.gz to the new folder and extract contents of it.



6.2. Modify Configuration Files:

We should update the following files in the new Cassandra install location to configure the second node.

```
cassandra.yaml
cassandra-rackdc.properties
cassandra-env.sh
```

Go to D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\conf and edit cassandra.yaml file with the following settings:

```
D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\conf\cassandra.yaml - Notepad++

File Edit Search View Encoding Language Settings Tools Macro Run Plugins Window ?

Cassandra.yaml 

# Cassandra storage config YAML

# NOTE:

# See http://wiki.apache.org/cassandra/StorageConfiguration for

# full explanations of configuration directives


# /NOTE

# The name of the cluster. This is mainly used to prevent machines in

# one logical cluster from joining another.

Cluster_name: 'CassandraDBCluster'
```

When the endpoint_snitch is set to GossipingPropertyFileSnitch in cassandra.yaml file, it always loads cassandra-topology.properties file if present and so, it is recommended to remove or rename this file.



Now, open cassandra-rackdc.properties file and change the data center and rack name as below. Note that we are putting this new node altogether in a different data center compared to the existing node which is on Asia DC.

```
D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\conf\cassandra-rackdc.properties - Notepad+
File Edit Search View Encoding Language Settings Tools Macro Run Plugins Window ?
 🕽 📇 🗎 🖺 🥦 😘 🚔 🚜 🕦 🐚 ⊃ c | ## 🛬 | 🔍 🤘 📭 🖼 📑 11 🔢 🗷 🗯 🕼 🖷 🔑 🗉
🔚 cassandra-rackdc.properties 🛛
 14
         # See the License for the specific language governing permissions
         # limitations under the License.
 15
 16
 17
         # These properties are used with GossipingPropertyFileSnitch and
 18
         # indicate the rack and dc for this node
 19
        dc=North America
 20
        rack=US
 21
         # Add a suffix to a datacenter name. Used by the Ec2Snitch and Ec
 22
 23
         # to append a string to the EC2 region name.
 24
         #dc suffix=
```

Additionally, it is required to change JMX port number in cassandra-env.ps1 and cassandra.bat files.

Open cassandra-env.ps1 in D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\conf location and update JMX PORT value from 7199 to 7299.

```
D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\conf\cassandra-env.ps1 - Notepad++
<u>File Edit Search View Encoding Language Settings Tools Macro Run Plugins Window ?</u>
 3 🔄 🗎 🖺 🖺 🕞 🤚 🚜 🐧 🖍 🖺 😭 🖒 🖒 🕽 🗩 🖒 🗀 🖒 🗀 😢
🔚 cassandra-env.ps1 🛚 🔻
402
403
             # print an heap histogram on OutOfMemoryError
404
             # $env:JVM OPTS="$env:JVM OPTS -Dcassandra.printHeapHistogramOn
405
             if ($env:JVM VERSION.CompareTo("1.8.0") -eq -1 -or [convert]::T
406
407
             {
408
                 echo "Cassandra 3.0 and later require Java 8u40 or later."
409
410
411
412
             # Specifies the default port over which Cassandra will be avail
413
             # JMX connections.
             $JMX PORT="7299
415
416
             # store in env to check if it's avail in verification
417
             $env:JMX_PORT=$JMX_PORT
418
419
             # Configure the following for JEMallocAllocator and if jemalloc
```

Open cassandra.bat in D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin location and update Dcassandra.jmx.local.port value from 7199 to 7299.

```
D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin\cassandra.bat - Notepad++
<u>File Edit Search View Encoding Language Settings Tools Macro Run Plugins Window ?</u>
 ] 🚽 🗎 🛍 🕞 😘 📤 🚜 🐚 🛍 🗩 C 🛍 🗽 🤏 🔍 🧸 📭 🖺 🌃 🔑 1
 🚽 cassandra.bat 🗵
         if NOT DEFINED CASSANDRA MAIN set CASSANDRA MAIN=org.apache.cassan
        if NOT DEFINED JAVA HOME goto :err
         REM JVM Opts we'll use in legacy run or installation
         -javaagent:"%CASSANDRA_HOME%\lib\jamm-0.3.0.jar"^
-Xms2G^
         set JAVA_OPTS=-ea^
         -XX: +HeapDumpOnOutOfMemoryError^
         -XX:+UseParNewGC^
  62
63
64
65
66
         -XX:+UseConcMarkSweepGC^
         -XX:+CMSParallelRemarkEnabled^
-XX:SurvivorRatio=8^
         -XX:MaxTenuringThreshold=1^
-XX:CMSInitiatingOccupancyFraction=75^
         -XX:+UseCMSInitiatingOccupancyOnly
       -XX:\fuseCMSInitiatinguccupancyoniy
-Dlogback.configurationFile=logback.xml^
-Djava.library.path="\cassandra_fmme\tau\)lib\sigar-bin"^
-Dcassandra.jmx.local.port=7299


REM **** JMX REMOTE ACCESS SETTINGS SEE: https://wiki.apache.org/c
        REM -Dcom.sun.management.jmxremote.port=7199
```

6.3. Remove Environment Variable:

Whenever we try to start Cassandra, it always refers to the configuration defined in CASSANDRA_HOME environment variable and when this variable is not set, it tries to look for config files available in the current directory.

Since we are configuring the second node on the same machine, we should remove CASSANDRA HOME environment variable that we set earlier.

Open **Environment Variables** window and select CASSANDRA_HOME under **User variables** section and click on **Delete** button. Then press OK to apply environment variable changes and close window.



6.4. Start Cassandra Service:

Open **Command Prompt** and start Cassandra service by navigating to the location where the second instance was installed:

D:

cd D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin
cassandra


```
Command Prompt - cassandra
Microsoft Windows [Version 10.0.19045.5011]
 c) Microsoft Corporation. All rights reserved.
 :\Users\hp>d:
D:\>cd D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin
D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin>cassandra
 ARNING! Powershell script execution unavailable.
  Please use 'powershell Set-ExecutionPolicy Unrestricted'
  on this user-account to run cassandra with fully featured
   functionality on this platform.
Starting with legacy startup options
Starting Cassandra Server
INFO [main] 2024-11-05 00:33:29,154 YamlConfigurationLoader.java:93 - Configuration location: file:/D:/ProgramFiles/Cas
sandra/node2/apache-cassandra-3.11.17/conf/cassandra.yaml
INFO [main] 2024-11-05 00:33:30,459 Config.java:555 - Node configuration:[allocate_tokens_for_keyspace=null; allow_exto
 insecure_udfs=false; allow_insecure_udfs=false; authenticator=AllowAllAuthenticator; authorizer=AllowAllAuthorizer; a_
to_bootstrap=true; auto_snapshot=true; back_pressure_enabled=false; back_pressure_strategy=org.apache.cassandra.net.Rate
BasedBackPressure{high_ratio=0.9, factor=5, flow=FAST}; batch_size_fail_threshold_in_kb=50; batch_size_warn_threshold_in_kb=5; batch_size_warn_threshold_in_kb=5; batchlog_replay_throttle_in_kb=1024; broadcast_address=null; broadcast_rpc_address=null; buffer_pool_use_heap_if_
exhausted=true; cache_load_timeout_seconds=30; cas_contention_timeout_in_ms=1000; cdc_enabled=false; cdc_free_space_chec
c_interval_ms=250; cdc_raw_directory=null; cdc_total_space_in_mb=0; check_for_duplicate_rows_during_compaction=true; check_for_duplicate_rows_during_compaction=true; check_for_duplicate_rows_during_reads=true; client_encryption_options=<REDACTED>; cluster_name=CassandraDBCluster; column_i
ndex_cache_size_in_kb=2; column_index_size_in_kb=64; commit_failure_policy=stop; commitlog_compression=null; commitlog_
irectory=null; commitlog_max_compression_buffers_in_pool=3; commitlog_periodic_queue_size=-1; commitlog_segment_size_in_
mb=32; commitlog_sync=periodic; commitlog_sync_batch_window_in_ms=NaN; commitlog_sync_period_in_ms=10000; commitlog_tota
 _space_in_mb=null; compaction_large_partition_warning_threshold_mb=100; compaction_throughput_mb_per_sec=16; concurrent
_compactors=null; concurrent_counter_writes=32; concurrent_materialized_view_writes=32; concurrent_reads=32; concurrent
6, 8933004167469705215, 8985454071046882497, 8999275567735935968, 9027529757300811824, 9068372863315183013, 907471298811
2272, 9088932742065174718, 9149876486995601281, 9169816072771879699, 9170520109063776117, 9183189117584481895, 950883422
487647366, 984948746961175334]
INFO [main] 2024-11-05 00:33:44,343 StorageService.java:1670 - JOINING: Finish joining ring
      [GossipStage:1] 2024-11-05 00:33:44,911 Gossiper.java:1197 - Node /127.0.0.1 has restarted, now UP
INFO [HANDSHAKE-/127.0.0.1] 2024-11-05 00:33:44,919 OutboundTcpConnection.java:561 - Handshaking version with /127.0.0.
INFO [GossipStage:1] 2024-11-05 00:33:44,965 StorageService.java:2595 - Node /127.0.0.1 state jump to NORMAL
INFO [GossipStage:1] 2024-11-05 00:33:45,076 TokenMetadata.java:507 - Updating topology for /127.0.0.1
INFO [GossipStage:1] 2024-11-05 00:33:45,106 TokenMetadata.java:507 - Updating topology for /127.0.0.1
INFO [GossipStage:1] 2024-11-05 00:33:45,123 Gossiper.java:116<u>1 - InetAddress /127.0.0.1 is now UP</u>
      [main] 2024-11-05 00:33:45,158 StorageService.java:2595 - Node /127.0.0.2 state jump to NORMAL
INFO [main] 2024-11-05 00:33:45,176 Gossiper.java:1869 - Waiting for gossip to settle..
WARN [GossipTasks:1] 2024-11-05 00:33:45,255 FailureDetector.java:278 - Not marking nodes down due to local pause of 10
100288500 > 50000000000
INFO [main] 2024-11-05 00:33:53,187 Gossiper.java:1900 - No gossip backlog; proceeding
INFO [main] 2024-11-05 00:33:53,670 NativeTransportService.java:73 - Netty using Java NIO event loop
INFO [main] 2024-11-05 00:33:53,869 Server.java:158 - Using Netty Version: [netty-buffer=netty-buffer-4.0.44.Final.4528
12a, netty-codec=netty-codec-4.0.44.Final.452812a, netty-codec-haproxy=netty-codec-haproxy-4.0.44.Final.452812a, netty-c
odec-http=netty-codec-http-4.0.44.Final.452812a, netty-codec-socks=netty-codec-socks-4.0.44.Final.452812a, netty-common
netty-common-4.0.44.Final.452812a, netty-handler=netty-handler-4.0.44.Final.452812a, netty-tcnative=netty-tcnative-1.1.3
3.Fork26.142ecbb, netty-transport=netty-transport-4.0.44.Final.452812a, netty-transport-native-epoll=netty-transport-nat
ive-epoll-4.0.44.Final.452812a, netty-transport-rxtx=netty-transport-rxtx-4.0.44.Final.452812a, netty-transport-sctp=net
ty-transport-sctp-4.0.44.Final.452812a, netty-transport-udt=netty-transport-udt-4.0.44.Final.452812a]
INFO [main] 2024-11-05 00:33:53,872 Server.java:159 - Starting listening for CQL clients on /127.0.0.2:9042 (unencrypte
d)...
INFO [main] 2024-11-05 00:33:54,484 CassandraDaemon.java:561 - Not starting RPC server as requested. Use JMX (StorageSe
rvice->startRPCServer()) or nodetool (enablethrift) to start it
INFO [main] 2024-11-05 00:33:54,485 CassandraDaemon.java:647 - Startup complete
```

On the console, you will see a message "Node /127.0.0.2 state jump to NORMAL" which indicates that the Cassandra instance has started and is up and running. Do not close this command prompt window.

We can also use the jps command to verify Cassandra service:

ips

It should display two **CassandraDaemon** daemons which denotes that 2 instances of **Cassandra** are running.



6.5. Verify Node Status:

Now, let us check the status of nodes using nodetool utility by running the following commands:

D: cd D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin nodetool status

```
Command Prompt
Microsoft Windows [Version 10.0.19045.5011]
(c) Microsoft Corporation. All rights reserved.
C:\Users\hp>d:
D:\>cd D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin
D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin>nodetool status
Datacenter: Asia
Status=Up/Down
// State=Normal/Leaving/Joining/Moving
   Address Load Tokens
                                    Owns (effective) Host ID
                                                                                          Rack
UN 127.0.0.1 312.38 KiB 256
                                     100.0%
                                                      a1fb7a29-fdf0-4418-add9-517a4b35b64c
                                                                                          South
Datacenter: North America
Status=Up/Down
// State=Normal/Leaving/Joining/Moving
   Address Load Tokens Owns (effective) Host ID
                                                                                          Rack
UN 127.0.0.2 205.96 KiB 256
                                    100.0%
                                                      0a7a1b59-067b-479d-aa2b-658341e27db5 US
D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin>
```

Here, you can see that node1 under Asia DC and node 2 under North America DC and both nodes status shows UN which means the node is **U**p and reporting **N**ormal state.

Run the following nodetool command to get the gossip information of each node:

nodetool gossipinfo

```
D:\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin>nodetool gossipinfo
/127.0.0.1
 generation:1730746830
 heartbeat:877
 STATUS:18:NORMAL,-1088057816839888778
 LOAD:828:319881.0
 SCHEMA:14:e84b6a60-24cf-30ca-9b58-452d92911703
 DC:10:Asia
 RACK:12:South
 RELEASE_VERSION:5:3.11.17
 INTERNAL_IP:8:127.0.0.1
 RPC ADDRESS:4:127.0.0.1
 NET VERSION:2:11
 HOST_ID:3:a1fb7a29-fdf0-4418-add9-517a4b35b64c
 RPC_READY:21:true
 SSTABLE_VERSIONS:6:big-me
 TOKENS:17:<hidden>
127.0.0.2
 generation:1730747023
 heartbeat:677
 STATUS:18:NORMAL,-1042386692657617965
 LOAD:643:210902.0
 SCHEMA:14:e84b6a60-24cf-30ca-9b58-452d92911703
 DC:10:North America
 RACK:12:US
 RELEASE_VERSION:5:3.11.17
 INTERNAL IP:8:127.0.0.2
 RPC ADDRESS:4:127.0.0.2
 NET VERSION:2:11
 HOST ID:3:0a7a1b59-067b-479d-aa2b-658341e27db5
 RPC_READY:32:true
 SSTABLE_VERSIONS:6:big-me
 TOKENS:17:<hidden>
```

7. CQLSH:

Cassandra provides an interactive tool called Cassandra Query Language Shell (cqlsh) to communicate with Cassandra database and execute queries using Cassandra Query Language (CQL). The CQL is very similar to SQL but suited for JOINless structure.

While using cqlsh, we can specify the IP address and port to connect to a specific Cassandra node with specific username and password. We can use the default user cassandra and password cassandra to connect to database.

Open **Command Prompt** and run the following commands to launch CQLSH tool connecting to second node in our system

```
cd D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin cqlsh 127.0.0.2 9042
```

or

cd D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin
cqlsh 127.0.0.2 9042 -u cassandra -p cassandra

```
Command Prompt - cqlsh 127.0.0.2 9042 -u cassandra -p cassandra

Microsoft Windows [Version 10.0.19045.5011]
(c) Microsoft Corporation. All rights reserved.

C:\Users\hp>d:

D:\>cd D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin

D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>cqlsh 127.0.0.2 9042 -u cassandra -p cassandra

WARNING: console codepage must be set to cp65001 to support utf-8 encoding on Windows platforms.

If you experience encoding problems, change your console codepage with 'chcp 65001' before starting cqlsh.

Connected to CassandraDBCluster at 127.0.0.2:9042.

[cqlsh 5.0.1 | Cassandra 3.11.17 | CQL spec 3.4.4 | Native protocol v4]

Use HELP for help.

WARNING: pyreadline dependency missing. Install to enable tab completion.

cassandra@cqlsh>
```

Here, we can see that it is connected to CassandraDBCluster at node address 127.0.0.2:9042

On cqlsh> prompt, use HELP command that lists out all possible commands that can be triggered to interact with Cassandra.

```
cqlsh> HELP
Documented shell commands:
CAPTURE CLS
                   COPY DESCRIBE EXPAND LOGIN SERIAL SOURCE
                                                                        UNICODE
       CONSISTENCY DESC EXIT
                                      HEI P
                                              PAGTNG SHOW
                                                               TRACTNG
CQL help topics:
                                                    DROP TRIGGER
AGGREGATES
                         CREATE_KEYSPACE
ALTER KEYSPACE
                         CREATE_MATERIALIZED_VIEW DROP_TYPE
ALTER_MATERIALIZED_VIEW CREATE_ROLE
                                                                       TIMESTAMP
ALTER_TABLE
                         CREATE_TABLE
                                                    FUNCTIONS
                                                                       TRUNCATE
ALTER_TYPE
ALTER USER
                         CREATE_TRIGGER
                                                    GRANT
                         CREATE TYPE
                                                    TNSFRT
                                                                      UPDATE
                         CREATE_USER
APPLY
                                                    INSERT_JSON
                                                                       UUID
BATCH
                         DELETE
                                                    JSON
                         DROP AGGREGATE
                                                    KEYWORDS
BEGIN
BLOB
                         DROP_COLUMNFAMILY
                                                    LIST_PERMISSIONS
                        DROP_FUNCTION
DROP_INDEX
DROP_KEYSPACE
BOOLEAN
                                                    LIST_ROLES
COUNTER
                                                    LIST_USERS
CREATE_AGGREGATE
                                                    PERMISSIONS
CREATE_COLUMNFAMILY
                         DROP MATERIALIZED VIEW
                                                    REVOKE
CREATE_FUNCTION
                         DROP_ROLE
REATE_INDEX
                         DROP_TABLE
                                                    SELECT_JSON
```

To get more help on each command, use HELP followed by command name. For example, to know more details about SHOW command, run HELP SHOW as shown here

```
cqlsh> HELP SHOW

SHOW [cqlsh only]

Displays information about the current cqlsh session. Can be called in the following ways:

SHOW VERSION

Shows the version and build of the connected Cassandra instance, as well as the versions of the CQL spec and the Thrift protocol that the connected Cassandra instance understands.

SHOW HOST

Shows where cqlsh is currently connected.

SHOW SESSION <sessionid>
Pretty-prints the requested tracing session.
```

7.1. Describe Cluster:

Use the below CQLSH command to see the information about the connected Cassandra cluster, such as the cluster name, and the partitioner and snitch in use. When you are connected to a non-system keyspace, also shows endpoint-range ownership information for the Cassandra ring.

DESCRIBE CLUSTER

```
cassandra@cqlsh>
cassandra@cqlsh> describe cluster
Cluster: CassandraDBCluster
Partitioner: Murmur3Partitioner
cassandra@cqlsh>
```

7.2. View Version:

Use the below CQLSH command to see the version and build of the connected Cassandra instance:

SHOW VERSION

```
cassandra@cqlsh> show version
[cqlsh 5.0.1 | Cassandra 3.11.17 | CQL spec 3.4.4 | Native protocol v4]
cassandra@cqlsh>
```

Here, you can see that the CQLSH version 5.0.1 and Cassandra 3.11.17 that we installed.

7.3. Show Host:

To see where the current CQLSH session is connected, run the below command:

SHOW HOST

```
cassandra@cqlsh> show host
Connected to CassandraDBCluster at 127.0.0.2:9042.
cassandra@cqlsh>
```

Here, you can see that the current CQLSH instance is connected to CassaandraDBCluster.

7.4. Create Keyspace:

A keyspace in Cassandra is like database in RDBMS and contains column families, indexes, user defined types, data center awareness, strategy used in keyspace, replication factor, etc.

Let us create a new keyspace named testspace with replication factor 2 using the below command:

```
CREATE KEYSPACE testspace WITH replication =
{'class':'SimpleStrategy', 'replication_factor':2};

cassandra@cqlsh> CREATE KEYSPACE testspace WITH replication = {'class':'SimpleStrategy', 'replication_factor':2};
```

Cassandra keyspace can be created with two types of strategy declaration:

- **SimpleStrategy**: This strategy is used in the case of one data center. In this strategy, the first replica is placed on the selected node and the remaining nodes are placed in clockwise direction in the ring without considering rack or node location.
- NetworkTopologyStrategy: This strategy is used in the case of more than one data centers. In this strategy, you have to provide replication factor for each data center separately.

Replication Factor is another property to be specified for a keyspace. Replication factor is the number of replicas of data placed on different nodes.

Use describe command to verify if the new keyspace was created or not:

DESCRIBE KEYSPACES;

```
cassandra@cqlsh> DESCRIBE KEYSPACES;
system_schema system_auth system system_distributed testspace system_traces
cassandra@cqlsh>
```

The use command in Cassandra sets the current working keyspace. Run the following command to set testspace as our working keyspace:

USE testspace;

```
cassandra@cqlsh> USE testspace;
cassandra@cqlsh:testspace>
```

7.5. Create Table:

In Cassandra, CREATE TABLE command is used to create a table with column families to store data just like table in RDBMS. This command expects the table name, column name, data type and a primary key. The datatypes in Cassandra can be text, int, date, decimal, double, float, set, list, map, etc.

Use this command to create table named student:

```
CREATE TABLE student (
student_id INT PRIMARY KEY,
student_name TEXT,
student_city TEXT,
student_fees INT
);
```

Use describe command to verify if the table was created or not:

DESCRIBE TABLES;

```
cassandra@cqlsh:testspace> DESCRIBE TABLES;
student
cassandra@cqlsh:testspace>
```

7.6. Insert Data:

The INSERT command is used to insert data into table columns.

Run the following commands to insert some data into student table:

```
INSERT INTO student (student_id, student_name, student_city,
student_fees)
VALUES (1, 'Rakesh', 'Hyderabad', 5000);
INSERT INTO student (student_id, student_name, student_city,
student_fees)
VALUES (2, 'Ramana', 'Bangalore', 7000);
INSERT INTO student (student_id, student_name, student_city,
student_fees)
VALUES (3, 'Kranthi', 'Chennai', 4000);
```

7.7. Read Data:

Use SELECT command to read data from the table.

SELECT * FROM student;

```
cassandra@cqlsh:testspace> SELECT * FROM student;
student_id | student_city | student_fees | student_name
         1 l
                Hyderabad
                                     5000
                                                  Rakesh
          2 |
                Bangalore
                                     7000
                                                  Ramana
         3 I
                  Chennai
                                     4000
                                                 Kranthi
(3 rows)
cassandra@cqlsh:testspace>
```

SELECT * FROM student WHERE student id=2;

7.8. Batch Queries:

In Cassandra, the BATCH command is used to execute multiple DML statements such as insert, update, delete, etc. simultaneously. It is very useful when you have to update some column as well as delete some of the existing data.

Run the following batch operations to insert a new record, update the existing record and delete a column data.

```
BEGIN BATCH
INSERT INTO student (student_id, student_name, student_city,
student_fees) VALUES (4, 'Shivani', 'Mumbai', 10000);
UPDATE student SET student_fees = 8000 WHERE student_id = 2;
DELETE student_fees FROM student WHERE student_id=1;
APPLY BATCH;
```

Now the BATCH is applied, we can verify it by using SELECT command:

SELECT * FROM student;

```
cassandra@cqlsh:testspace> SELECT * FROM student;
student_id | student_city | student_fees | student_name
               Hyderabad
         1 |
                                  null |
                                               Rakesh
         2
               Bangalore
                                 8000
                                              Ramana
         4
                Mumbai
                                10000
                                              Shivani
                 Chennai |
                                  4000
                                             Kranthi
(4 rows)
cassandra@cqlsh:testspace>
```

Use exit; command to exit out of cqlsh.

7.9. Data Replication:

Now, let us connect to the first node instance to verify if the data is replicated.

```
cd D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin
cqlsh 127.0.0.1 9042 -u cassandra -p cassandra
```

```
D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>cqlsh 127.0.0.1 9042 -u cassandra -p cassandra
WARNING: console codepage must be set to cp65001 to support utf-8 encoding on Windows platforms.
If you experience encoding problems, change your console codepage with 'chcp 65001' before starting cqlsh.

Connected to CassandraDBCluster at 127.0.0.1:9042.
[cqlsh 5.0.1 | Cassandra 3.11.17 | CQL spec 3.4.4 | Native protocol v4]

Use HELP for help.

WARNING: pyreadline dependency missing. Install to enable tab completion.

cassandra@cqlsh>
```

Run the following commands to see the table data that we created in the second node.

```
DESCRIBE KEYSPACES;
USE testspace;
DESCRIBE TABLES;
SELECT * FROM student;
```

```
cassandra@cqlsh> DESCRIBE KEYSPACES;
system_schema system_auth system testspace system_distributed system_traces
cassandra@cqlsh> USE testspace;
cassandra@cqlsh:testspace> SHOW TABLES;
Improper SHOW command.
cassandra@cqlsh:testspace> DESCRIBE TABLES;
student
cassandra@cqlsh:testspace> SELECT * FROM student;
 student_id | student_city | student_fees | student_name
                Hyderabad
         1
                                   null
                                                Rakesh
         2
                Bangalore |
                                  8000
                                                Ramana
         4
                  Mumbai
                                  10000
                                               Shivani
         3 l
                  Chennai
                                  4000
                                               Kranthi
(4 rows)
cassandra@cqlsh:testspace>
```

8. NodeTool Utility:

Cassandra provides a nodetool utility which is a command line interface for monitoring Cassandra cluster and performing routine database operations. This utility is commonly used to output a quick summary of the ring and its current state of general health with status command.

The nodetool utility provides commands for decommissioning a node, running repair, and moving partitioning tokens and for viewing detailed metrics for tables, server metrics, and compaction statistics, etc.

When you have multi-node cluster, you can provide the node host name and JMX port to connect:

```
nodetool -h HOSTNAME -p JMX PORT COMMAND
```

If a username and password for RMI authentication are set explicitly in the <code>cassandra-env.sh</code> file, then you must specify credentials along with hostname/IP address and port to connect to a specific Cassandra node:

```
nodetool -h HOSTNAME -p JMX_PORT -u JMX_USERNAME -pw JMX_PASSWORD COMMAND
```

Open **Command Prompt** and run the following commands to get node status connecting to primary node in our system:

```
cd D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin
nodetool -h 127.0.0.1 -p 7199 -u cassandra -pw cassandra status
```

Use the below command to connect to secondary node in our system:

nodetool -h 127.0.0.1 -p 7299 -u cassandra -pw cassandra status

```
rogramFiles\Cassandra\apache-cassandra-3.11.17\bin>nodetool -h 127.0.0.1 -p 7199 -u cassandra -pw cassandra status
Datacenter: Asia
tatus=Up/Down
 State=Normal/Leaving/Joining/Moving
                        Tokens Owns (effective) Host ID
  Address Load Token
127.0.0.1 294.39 KiB 256
                                                                                               Rack
                                       100.0%
                                                         a1fb7a29-fdf0-4418-add9-517a4b35b64c
Datacenter: North America
Status=Up/Down
/ State=Normal/Leaving/Joining/Moving
                        Tokens
                                      Owns (effective) Host ID
   127.0.0.2 194.15 KiB 256
                                                          0a7a1b59-067b-479d-aa2b-658341e27db5
                                       100.0%
 :\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>
```

Some of the generally used commands are described below for your understanding.

8.1. Nodetool help:

This is a basic command which lists all the available nodetool commands. This command is useful to learn about the available commands.

nodetool help

```
Command Prompt
 :\ProgramFiles\Cassandra\node2\apache-cassandra-3.11.17\bin>nodetool help
usage: nodetool [(-h <host> | --host <host>)] [(-p <port> | --port <port>)]
        [(-u <username> | --username <username>)]
[(-pw <password> | --password <password>)]
        [(-pwf <passwordFilePath> | --password-file <passwordFilePath>)] <command>
        [<args>]
The most commonly used nodetool commands are:
                                  Forcefully remove a dead node without re-replicating any data. Use as a last resort if
   assassinate
you cannot removenode
   bootstrap
                                  Monitor/manage node's bootstrap process
    cleanup
                                   Triggers the immediate cleanup of keys no longer belonging to a node. By default, clean
 all keyspaces
   clearsnapshot
                                  Remove the snapshot with the given name from the given keyspaces. If no snapshotName is
specified we will remove all snapshots
                                  Force a (major) compaction on one or more tables or user-defined compaction on given SS
   compact
Tables
   compactionhistory
                                  Print history of compaction
   compactionstats
                                  Print statistics on compactions
   decommission
                                  Decommission the *node I am connecting to*
                                  Print the name, snitch, partitioner and schema version of a cluster Shows the token ranges info of a given keyspace \,
   describecluster
   describering
   disableautocompaction
                                  Disable autocompaction for the given keyspace and table
                                  Disable incremental backup
   disablebackup
                                   Disable native transport (binary protocol)
   disablebinary
                                   Disable gossip (effectively marking the node down)
   disablegossip
                                  Disable storing hinted handoffs
Disable hints for a data center
   disablehandoff
   disablehintsfordc
```

8.2. Nodetool describecluster:

This command provides the basic cluster information such as cluster name, endpoint-snitch being used, partitioner and schema versions.

Follow the below syntax to use this command:

nodetool [options] describecluster

8.3. Nodetool status:

This command is useful to monitor the cluster's health and performance. It can help detect any ongoing anomalies as well as the status of each of the nodes.

Follow the below syntax to use this command:

```
nodetool <options> status ( -r | --resolve-ip ) -- <keyspace>
```

```
:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>nodetool status
Datacenter: Asia
Status=Up/Down
/ State=Normal/Leaving/Joining/Moving
-- Address Load Tokens
JN 127.0.0.1 241.51 KiB 256
                                       Owns (effective) Host ID
                                                                                                   Rack
                                                            a0eadcc0-2bb4-4b09-8ae3-4b0e8f81fece South
                                         100.0%
atacenter: North America
Status=Up/Down
/ State=Normal/Leaving/Joining/Moving
  Address Load Token
127.0.0.2 242.59 KiB 256
                                        Owns (effective) Host ID
                                                           cd34282f-e91c-493b-a74c-4ea11dfa24ff US
:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>
```

8.4. Nodetool ring:

It displays token ring information with the status of each of the ndoes. The token ring is responsible for managing the partitioning of data within the Cassandra cluster. This command is critical if a cluster is facing data consistency issues. By default, nodetool ring displays all nodes that are involved in the ring and tokens that are assigned to each one of them. Optionally, you can specify the keyspace name and table name arguments to filter the output and display information.

Follow the below syntax to use this command:

nodetool ring [keyspace] [table]

D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>nodetool ring									
Datacenter: Asia									
======================================									
Address	Rack	Status	State	Load	Owns	Token			
						9208723366316796972			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-9181914919680777424			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-9135898857160291318			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-9124738933726578350			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-9106193222192747245			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-9090396655366360064			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-9036326451069183773			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8987406218220030025			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8868651564368241096			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8829507705743697056			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8711135424320361754			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8705362163446925636			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8618416343924162790			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8493121937336985691			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8442274297240864100			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8398844943476955648			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8358493682708979079			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8325850949216802965			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8311949547825747815			
127.0.0.1	South	Up	Normal	241.51 KiB	100.00%	-8202389261199346109			

8.5. Nodetool gossipinfo:

It provides the gossip protocol related statistics.

Follow the below syntax to use this command:

nodetool [options] gossipinfo

```
:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>nodetool gossipinfo
/127.0.0.1
 generation:1735198167
 heartbeat:9476
 STATUS: 25: NORMAL, -1199880975988446116
 LOAD:9460:196256.0
 SCHEMA: 20: e84b6a60-24cf-30ca-9b58-452d92911703
 DC:9:Asia
 RACK:11:South
 RELEASE_VERSION:4:3.11.17
 INTERNAL_IP:7:127.0.0.1
 RPC ADDRESS:3:127.0.0.1
 NET_VERSION:1:11
 HOST_ID:2:a0eadcc0-2bb4-4b09-8ae3-4b0e8f81fece
 RPC_READY:28:true
 SSTABLE_VERSIONS:5:big-me
 TOKENS:24:<hidden>
 127.0.0.2
 generation:1735198829
 heartbeat:8793
 STATUS: 25: NORMAL, -104634129013279800
 LOAD:8777:196992.0
 SCHEMA: 20: e84b6a60-24cf-30ca-9b58-452d92911703
 DC:9:North America
 RACK:11:US
 RELEASE_VERSION:4:3.11.17
 INTERNAL_IP:7:127.0.0.2
 RPC_ADDRESS:3:127.0.0.2
 NET VERSION:1:11
 HOST_ID:2:cd34282f-e91c-493b-a74c-4ea11dfa24ff
 RPC_READY:36:true
 SSTABLE_VERSIONS:5:big-me
 TOKENS:24:<hidden>
D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>
```

8.6. Nodetool getlogginglevels:

It gives logging levels defined in the database for all areas

Follow the below syntax to use this command:

nodetool [options] getlogginglevels

8.7. Nodetool netstats:

This command provides the network information about the host machine.

Follow the below syntax to use this command:

nodetool [options] netstats

```
D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>nodetool netstats
Mode: NORMAL
Not sending any streams.
Read Repair Statistics:
Attempted: 0
Mismatch (Blocking): 0
Mismatch (Background): 0
                                      Pending
Pool Name
                             Active
                                                   Completed
                                                                Dropped
Large messages
                                            0
                                                           0
                                n/a
Small messages
                                n/a
                                            0
                                                          140
                                                                      0
Gossip messages
                                n/a
                                                                      0
D:\ProgramFiles\Cassandra\apache-cassandra-3.11.17\bin>
```

8.8. Nodetool tablestats:

This command provides statistics about one or more tables. The table stats are updated when SSTables change through compaction or flushing. Cassandra uses the metrics-core library to make the output more informative and easier to understand.

Follow the below syntax to use this command:

```
nodetool [options] tablestats
```

8.9. Nodetool cleanup:

This command that is required to remove data from nodes when a new node is added to a cluster and token ring is re-distributed. After cleanup it is recommended to run compact command.

Follow the below syntax to use cleanup command:

```
nodetool [connection_options] cleanup [-j num_jobs] [--]
[keyspace_name table_name [table_name ...]]
```

8.10. Nodetool compact:

This command is useful to perform compaction to merge several SSTables (data files in Cassandra) and keep the resultant SSTable with the latest updated data.

When a data update or delete operation is triggered, Cassandra does not overwrite or delete the data. In case of updates, a different timestamped version of updates is maintained and in case of deletes, the data is marked for deletion as **tombstones** and then the latest version of data is obtained post the merge of the SSTables. Therefore, it is important to perform compactions on a periodic basis in order to keep the cluster healthy.

Follow the below syntax to use compact command:

```
nodetool [options] compact [(-et <end_token> | --end-token
  <end_token>)]
[(-s | --split-output)] [(-st <start_token> | --start-token
  <start_token>)] [--] [<keyspace> [<tables>...]]
[--user-defined] <relative_path_to_SSTable file>
```

8.11. Nodetool decommission:

It decommissions the node where this command is executed, and the data of the node is streamed to the next node in the ring. It is one of the important commands that need to be executed when the cluster needs to be scaled to ensure no data loss.

Follow the below syntax to use decommission command:

```
nodetool [options] decommission
```

8.12. Nodetool drain:

It flushes all memtables (temporary tables usually on the heap) to the SSTables on disk. Once the command is executed, the node stops listening for connections from clients and other nodes. The node is marked as DS (Down/Stopped) in the cluster in the nodetool status command output. This command is usually run before any maintenance activities or when upgrading a node to a newer version of Cassandra.

Follow the below syntax to use drain command:

```
nodetool [options] drain
```

8.13. Nodetool garbagecollect:

It performs single SSTable compactions to eliminate updates or logically deleted data (Tombstones).

For each SSTable, the command creates a new SSTable with unnecessary data cleaned out. By default, <code>garbagecollect</code> removes rows or partitions that have been deleted or overwritten with newer data. It can also remove deleted or overwritten cell values when <code>-g</code> argument is specified. This command can eliminate expired tombstones which are older than <code>gc grace seconds</code>, but not fresh ones.

Note that garbagecollect with -g cell option incurs very high Disk I/O and hence it should be ensured that enough disk space is available.

Follow the below syntax to use this command:

nodetool options garbagecollect [--] keyspace name table name

8.14. Nodetool join:

It adds a new node to the cluster. When this command is executed, the new node will start to communicate with other nodes in the cluster and receive data from them. It is important to ensure that the new node has the same version of Cassandra as the existing nodes in the cluster.

Follow the below syntax to use this command:

nodetool <options> join

8.15. Nodetool removenode:

This command is useful when a node is no longer needed or when a node has failed and needs to be replaced or removed. Before removing the dead node, nodetool decommission command must be run first on the node being removed and then nodetool removenode command should be executed on the live node in the cluster.

When a node is removed, Cassandra redistributes the data that was stored on that node to the remaining nodes in the cluster. After the data has been redistributed, the node being removed will be marked as "removed" and will no longer participate in the cluster.

It is important to ensure that all data has been successfully redistributed before decommissioning or shutting down the node being removed. This can be checked using nodetool status and monitoring the "UN" (up and normal) status of all nodes in the cluster.

It is recommended to perform a full repair of the cluster after removing a node to ensure data consistency. This can be done using nodetool repair command.

Follow the below syntax to use nodetool removenode command:

nodetool [connection options] removenode -- <status> | <force> | <ID>

8.16. Nodetool assasinate:

This command is used to assassinate a node and should be performed when the nodetool removenode command fails.

Follow the below syntax to use nodetool assasinate command:

nodetool [options] assassinate <ip address>

8.17. Nodetool repair:

Since frequent data deletions and downtime in nodes may lead to data inconsistencies, nodetool repair ensures data consistency across all nodes in the cluster. It works by comparing the data on each node with the data on other nodes and resolving any inconsistencies. This is done by constructing a **merkle tree** whose leaves are the hashes of the individual keys.

Note that while nodetool repair is running, it can cause increased network traffic and disk I/O on the nodes in the cluster. This can impact the performance of other applications running on the same nodes. It can also cause temporary data unavailability during the repair process which can be mitigated by running repairs during off-peak hours or using incremental repair (new data since last repair) instead of full repair (complete data).

If nodetool repair is interrupted or fails for any reason, it can leave the cluster in an inconsistent state and so it is important to monitor the progress of nodetool repair and ensure that it completes successfully.

Follow the below syntax to use this command:

nodetool repair [-full|-inc]

Congratulations!! You have successfully installed Apache Cassandra with single node and multi-node configuration and executed database queries using CQLSH tool along with an overview of nodetool utility to monitor and manage Cassandra cluster in Windows operating system.