Contents

Alignment	2
What are closures? What are lambdas?	2
move assignment? When to use it?	2
std::move()	3
static - all the different meanings?	3
const and $mutable$	3
$volatile \text{ keyword } \dots \dots \dots \dots$	3
restrict keyword	3
in place new	3
pointers	4
typename keyword	4
What is a <i>virtual</i> function?	5
pure virtual function	5
virtual destructor - when/why?	5
virtual call in $assembly \dots \dots \dots$	5
co-variant return types	5
Cross Product	5
Dot Product	6
Matrix Determinant	7
Matrix Inverse	8
Quaternions	9
Conjugate	9
Norm	9
Inverse (or Reciprocal)	9
Multiplication	9
Unit quaternions or <i>versors</i>	9
Rotate vector example	10
SLERP	10
STL containers speed	10

common thread synchronization primitives 10
Multi-Threading problems
Race conditions
Deadlock
Livelock
Starvation
Priority inversion
Alignment general: (last mod is for offset $== 0$ to work)
<pre>new_offset = offset + padding = offset + (align - (offset mod align)) mod align</pre>
power-of-2:
<pre>new_offset = (offset + align - 1) & ~(align - 1)</pre>

What are *closures*? What are *lambdas*? Lambda = anonymous local function

Closure = lambda + reference to the environment (a table storing a reference to each of the non-local captured variables)

move assignment? When to use it? Tied to the concept of rvalue-reference (or xvalue)

The move assignment operator is called whenever it is selected by overload resolution, e.g. when an object appears on the left side of an assignment expression, where the right-hand side is an rvalue of the same or implicitly convertible type.

Move assignment operators typically "steal" the resources held by the argument (e.g. pointers to dynamically-allocated objects, file descriptors, TCP sockets, I/O streams, running threads, etc), rather than make copies of them, and leave the argument in some valid but otherwise indeterminate state. For example, move-assigning from a std::string or from a std::vector leaves the right-hand side argument empty.

 $\label{eq:more_std_org_jtc1/sc22/wg21/docs/papers/2006/n2027.} \\ \text{html}\#\text{Move_Semantics}$

std::move() Obtains an rvalue reference to its argument and converts it to an xvalue.

Code that receives such an xvalue has the opportunity to optimize away unnecessary overhead by moving data out of the argument, leaving it in a valid but unspecified state.

Basically it's just a cast:

```
template<typename _Tp>
constexpr typename std::remove_reference<_Tp>::type&& move(_Tp&& __t) noexcept
{
    return static_cast<typename std::remove_reference<_Tp>::type&&>(__t);
}
```

static - all the different meanings?

- 1. at *file scope*: signifies "internal-linkage" i.e. not shared between translation units
- 2. at function scope: variable retains value between function calls
- 3. at class scope: signifies independence of class instance

const and mutable Const member function doesn't alter the data it operates on; except the one marked as mutable

volatile keyword Depends on language and compiler. Usually marks atomicity for data (but not guarantees it): reads from threads are guaranteed to have latest; marks that variable can be modified "externally"

restrict keyword Optimisation hint to limit pointer aliasing and aid caching - it means a particular data is accessed only thru that pointer thus making optimisations like storing the ptr value in a registry for subsequent access

http://stackoverflow.com/questions/776283/what-does-the-restrict-keyword-mean-in-c

in place **new** Allows to explicitly specify the memory management of individual objects, i.e. their "placement" in memory.

new (expression) [(arguments)]; for example:

```
char buffer[] = new char[256];
string *str = new (buffer) string("Hello world");
```

there is no placement delete syntax (but both new and delete functions can be overrided to specify the in-place)

pointers

```
ptr[offset] = *(ptr + offset);
&ptr[offset] = ptr + offset;

pointer arithmetic always adds in sizeof of the element
ptr[5] = *(ptr + 5) = *(ptr + 5 * sizeof(*ptr))
```

typename keyword

- 1. alias for the class keyword when declaring template parameters
- 2. a method to indicate that a dependent name is a type

If the compiler can't tell if a dependent name (one that contains a template parameter) is a value or a type, then it will assume that it is a value.

```
template <typename T>
void foo() {
   T::bar * p; // won't compile, because without the typename prefix it will be interpreted
}
struct Gotcha {
   typedef int bar;
};
foo<Gotcha>();
```

What is a *virtual* function? A virtual function allows derived classes to replace the implementation provided by the base class.

When you refer to a derived class object using a pointer or a reference to the base class, you can call a virtual function for that object and execute the derived class's version of the function. Virtual functions ensure that the correct function is called for an object, regardless of the expression used to make the function call

pure virtual function A virtual function that is required to be implemented by a derived class.

Classes containing pure virtual methods are termed "abstract"; they cannot be instantiated directly.

virtual destructor - when/why? At the root of a class hierarchy to insure proper cleanup

virtual call in assembly

```
mov eax, dword ptr [this]
mov edx, dword ptr [eax]
mov eax, dword ptr [edx+4]
mov ecx, dword ptr [this]
call eax
```


co-variant return types http://katyscode.wordpress.com/2013/08/22/c-polymorphic-cloning-and-the-crtp-curiously-recurring-template-pattern/

Cross Product
$$\mathbf{a} \times \mathbf{b} = \|\mathbf{a}\| \|\mathbf{b}\| \sin \theta \mathbf{n}$$

$$\mathbf{A} \times \mathbf{B} = -\mathbf{B} \times \mathbf{A} = \begin{vmatrix} \mathbf{i} & \mathbf{j} & \mathbf{k} \\ A_x & A_y & A_z \\ B_x & B_y & B_z \end{vmatrix} = \mathbf{i} \begin{vmatrix} A_y & A_z \\ B_y & B_z \end{vmatrix} - \mathbf{j} \begin{vmatrix} A_x & A_z \\ B_x & B_z \end{vmatrix} + \mathbf{k} \begin{vmatrix} A_x & A_y \\ B_x & B_y \end{vmatrix}$$

$$= (A_y B_z - A_z B_y) \mathbf{i} + (A_z B_x - A_x B_z) \mathbf{j} + (A_x B_y - A_y B_x) \mathbf{k}$$


the right hand rule



 ${\bf Dot\ Product}$ $\,$ it's the sum of the vectors components multiplied - it's 0 when the vectors are perpendicular

the vectors are perpendicular
$$\mathbf{A} \cdot \mathbf{B} = \|\mathbf{A}\| \|\mathbf{B}\| \cos \theta$$
,

the projection of vector X onto Y is (where ^ denotes unit vectors):




The dot product therefore has the geometric interpretation as the length of the projection of X onto the unit vector Y when the two vectors are placed so that their tails coincide.


Matrix Determinant The determinant of a 3 x 3 matrix is defined by:

$$\begin{vmatrix} a & b & c \\ d & e & f \\ g & h & i \end{vmatrix} = a \begin{vmatrix} e & f \\ h & i \end{vmatrix} - b \begin{vmatrix} d & f \\ g & i \end{vmatrix} + c \begin{vmatrix} d & e \\ g & h \end{vmatrix}$$
$$= a(ei - fh) - b(di - fg) + c(dh - eg)$$
$$= aei + bfg + cdh - ceg - bdi - afh.$$

The area of the parallelogram is the absolute value of the determinant of the matrix formed by the vectors representing the parallelogram's sides:



The volume of this parallelepiped is the absolute value of the determinant of the matrix formed by the rows constructed from the vectors r1, r2, and r3:



Also the determinant of a 3x3 is the triple product which is the volume of the parallelepiped formed by the 3 row vectors of the matrix:

$$\mathbf{a} \cdot (\mathbf{b} \times \mathbf{c}) = \det egin{bmatrix} a_1 & a_2 & a_3 \ b_1 & b_2 & b_3 \ c_1 & c_2 & c_3 \end{bmatrix}.$$

Matrix Inverse An n x n matrix M is invertible if there exists a matrix, which we denote by M^1 , such that $MM^1 = M^1M = I$. The matrix M^1 is called the inverse of M.

Not every matrix has an inverse, and those that do not are called singular. An example of a singular matrix is any one that has a row or column consisting of all zeros.

An n x n matrix M is invertible if and only if determinant(M) != 0.

A quick formula for 3x3 matrices:
$$\mathbf{A}^{-1} = \begin{bmatrix} a & b & c \\ d & e & f \\ g & h & i \end{bmatrix}^{-1} = \frac{1}{\det(\mathbf{A})} \begin{bmatrix} A & B & C \\ D & E & F \\ G & H & I \end{bmatrix}^T = \frac{1}{\det(\mathbf{A})} \begin{bmatrix} A & D & G \\ B & E & H \\ C & F & I \end{bmatrix}$$

$$A = (ei - fh) \qquad D = -(bi - ch) \qquad G = (bf - ce)$$

$$B = -(di - fg) \qquad E = (ai - cg) \qquad H = -(af - cd)$$

$$C = (dh - eg) \qquad F = -(ah - bg) \qquad I = (ae - bd)$$

Quaternions alternative mathematical entity similar to complex number and are of the form:

$$Q = a + bi + cj + dk$$

Conjugate

$$Q* = a - bi - ck - dk$$

Norm

$$norm(Q) = sqrt(Q Q*) = sqrt(a^2 + b^2 + c^2 + d^2)$$

Inverse (or Reciprocal)

$$inv(Q) = Q* / norm(Q)^2$$

Multiplication Hamilton product:

$$A B = a1b1 - a2b2 - a3b3 - a4b4 + (a1b2 + a2b1 + a3b4 - a4b3)i + (a1b3 + a2b4 + a3b1 + a4b2)j + (a1b4 + a2b3 - a3b2 + a4b1)k$$

Quaternions can be interpreted as a scalar plus a vector by writing Q = (s, V). Multiplication is easy then:

Q V =
$$(s1, V1)$$
 $(s2 V2)$ = $(s1 s2 - V1 . V2, s1 V2 + s2 V1 + V1 x V2)$

Unit quaternions or *versors* provide a convenient mathematical notation for representing orientations and rotations of objects in three dimensions. Compared to Euler angles they are simpler to compose and avoid the problem of gimbal lock. Compared to rotation matrices they are more numerically stable and may be more efficient.

A rotation about the unit vector N by an angle *theta* can be computed using the quaternion: (due to generalized Euler formula)

Rotate vector example

- 1. Compute the matrix product of a 3x3 rotation matrix R and the original 3x1 column matrix representing v. This requires 3x (3 multiplications +2 additions) = 9 multiplications and 6 additions, the most efficient method for rotating a vector.
- 2. A rotation can be represented by a unit-length quaternion Q=(w,R) with scalar (real) part w and vector (imaginary) part R. The rotation can be applied to a 3D vector V via the formula:

$$V' = V + 2R \times (R \times V + wV)$$

This requires only 15 multiplications and 15 additions to evaluate. This yields the same result as the less efficient but more compact formula:

V' = Q V inv(Q)

 $\begin{tabular}{ll} \bf SLERP & http://run.usc.edu/cs520-s12/assign2/p245-shoemake.pdf \\ http://number-none.com/product/Understanding%20Slerp,%20Then%20Not%20Using%20It/p245-shoemake.pdf \\ http://number-none.com/product/Understanding%20Slerp,%$

Container	Implementation	Insert	Remove	Index	Find
vector	dynamic array	O(n)	O(n)	O(1)	O(log n)
list	double link list	O(1)	O(1)	-	O(n)
map	red-black b tree	$O(\log n)$	$O(\log n)$	O(1)	O(log n)
hashmap	hash table	O(1)	O(1)	O(1)	O(1)

STL containers speed

${\bf common\ thread\ } synchronization\ primitives$

- 1. CompareAndSwap instructions atomic (that is no other thread can preempt it) only writes after the compare with a known value is true
- 2. Mutex locking mechanism used to synchronize access to a resource. only one "thing" at a time can acquire the mutex and the same "thing" must release it thus OWNERSHIP property

- 3. Semaphore generalized mutex based on counting. NO ownership property, multiple threads can increase/decrease, when 0 it waits
- 4. Condition Variable used for signalling/event passing
- 5. *Memory Fence* a class of instructions that mean memory read/writes occur in the order you expect for example a 'full fence' means all read/writes before the fence are committed before those after the fence.

Multi-Threading problems

Race conditions where the output is dependent on the sequence or timing of other uncontrollable events. It becomes a bug when events don't happen in the order that the programmer intended

Deadlock a situation in which 2 or more competing threads are waiting on each other to finish, and thus neither one advances. Ex: 2 threads wait on each other to release acquired resources


Livelock similar to deadlock but instead of waiting, they change state in regard to eachother - none progressing.

A real-world example of livelock occurs when two people meet in a narrow corridor, and each tries to be polite by moving aside to let the other pass, but they end up swaying from side to side without making any progress because they both repeatedly move the same way at the same time.

Starvation is where a process is perpetually denied the necessary resources.

Starvation is often caused by errors in a scheduling algorithm, but can also be caused by resource leaks, and can be intentionally caused via a denial-of-service attack such as a fork bomb.

Priority inversion is a problematic scenario in scheduling in which a high priority task is indirectly preempted by a medium priority task effectively "inverting" the relative priorities of the two tasks.



Time