
PRACTICAL NO: 01

AIM: Configure Ip Sla Tracking And Path Control



Objectives:

Configure and verify the IP SLA feature.

Test the IP SLA tracking feature.

Verify the configuration and operation using show and debug commands.

Use IO router c7200

Step 1: Configure loopbacks and assign addresses.

Router R1

hostname R1

interface Loopback 0 description R1 LAN ip address 192.168.1.1 255.255.255.0

interface Serial3/0 description R1 \rightarrow ISP1 ip address 209.165.201.2 255.255.255.252 clock rate 128000 bandwidth 128 no shutdown

interface Serial3/1 description R1 \rightarrow ISP2 ip address 209.165.202.130 255.255.255.252 bandwidth 128 no shutdown

Router ISP1 (R2)

hostname ISP1

interface Loopback0 description Simulated Internet Web Server ip address 209.165.200.254 255.255.255.255

interface Loopback1 description ISP1 DNS Server ip address 209.165.201.30 255.255.255.255

interface Serial3/0 description ISP1 \rightarrow R1 ip address 209.165.201.1 255.255.255 bandwidth 128

no shutdown

```
R2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
 R2(config)#hostname ISP1
ISP1 (config) #
 ISP1(config)#interface Loopback0
ISP1(config-if) #description Simulated Internet Web Server
ISP1(config-if)#ip address 209.165.200.254 255.255.255.255
ISP1(config-if)#
 Mar 6 12:07:55.159: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state
 to up
ISP1(config-if)#interface Loopbackl
ISP1(config-if) #description ISP1 DNS Server
ISP1(config-if)#ip address 209.165.201.30 255.255.255.255
ISP1(config-if)#
 Mar 6 12:08:11.943: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopbackl, changed state*
 to up
ISP1(config-if)#interface Serial3/0
ISP1(config-if) #description ISP --> R1
ISP1(config-if) #ip address 209.165.201.1 255.255.255.252
ISP1(config-if)#bandwidth 128
ISP1(config-if)#no shutdown
```

interface Serial3/1 description ISP1 → ISP2 ip address 209.165.200.225 255.255.255.252 clock rate 128000 bandwidth 128 no shutdown

```
ISP1(config) #interface Serial3/1
ISP1(config-if) #description ISP1 --> ISP2
ISP1(config-if) #ip address 209.165.200.225 255.255.255.252
ISP1(config-if) #clock rate 128000
ISP1(config-if) #bandwidth 128
ISP1(config-if) #no shutdown
```

Router ISP2 (R3)

hostname ISP2 interface Loopback0 description Simulated Internet Web Server ip address 209.165.200.254 255.255.255.255

interface Loopback1 description ISP2 DNS Server ip address 209.165.202.158 255.255.255.255

interface Serial description ISP2 → R1 ip address 209.165.202.129 255.255.255.252

clock rate 128000 bandwidth 128 no shutdown

interface Serial3/1 description ISP2 \rightarrow ISP1 ip address 209.165.200.226 255.255.255.252 bandwidth 128

```
NO Shutdown

R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.

R3(config) #interface Loopback0

ISP2(config) #interface Loopback0

ISP2(config-if) #igeacription Simulated Internet Web Server

ISP2(config-if) #igeacription Simulated Internet Web Server

ISP2(config-if) #interface Loopback1

ISP2(config-if) #interface Serial #interface Loopback0, changed state to up

*Mar 6 12:14:03.697: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up

P

*Mar 6 12:14:03.895: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1, changed state to up

ISP2(config-if) #interface Serial3/0

ISP2(config-if) #description ISP2 --> R1

ISP2(config-if) #ip address 209.165.202.129 255.255.255

ISP2(config-if) #interface Serial3/0

ISP2(config-if) #interface Serial3/0

ISP2(config-if) #interface Serial3/0

ISP2(config-if) #interface Serial3/1

ISP2(config-if) #interface Serial3/1
```

Verify the configuration by using the show interfaces description command. The output from router R1 is shown here as an example.

R1# show interfaces description

All three interfaces should be active.

Step 2: Configure static routing.

a) Implement the routing policies on the respective routers. You can copy and paste the following configurations.

Router R1

R1(config)# ip route 0.0.0.0 0.0.0.0 209.165.201.1

R1(config)#

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip route 0.0.0.0 0.0.0.0 209.165.201.1
R1(config)#
```

Router ISP1 (R2)

ISP1(config-if)#router eigrp 1

ISP1(config-router)#network 209.165.200.224 0.0.0.3

ISP1(config-router)#network 209.165.201.0 0.0.0.31

ISP1(config-router)#no auto-summary

ISP1(config-router)#exit

ISP1(config)#ip route 192.168.1.0 255.255.255.0 209.165.201.2

ISP1(config)#

```
ISP1(config-if) #router eigrp 1
ISP1(config-router) #network 209.165.200.224 0.0.0.3
ISP1(config-router) #network 209.165.201.0 0.0.0.31
ISP1(config-router) #no auto-summary
ISP1(config-router) #exit
ISP1(config) #ip route 192.168.1.0 255.255.255.0 209.165.201.2
ISP1(config) #
```

Router ISP2 (R3)

ISP2(config)# router eigrp 1

ISP2(config-router)# network 209.165.200.224 0.0.0.3

ISP2(config-router)# network 209.165.202.128 0.0.0.31

ISP2(config-router)# no auto-summary

ISP2(config-router)# exit

ISP2(config)# ip route 192.168.1.0 255.255.255.0 209.165.202.130

```
ISP2(config-if) #router eigrp 1
ISP2(config-router) #network 209.165.200.224 0.0.0.3
ISP2(config-router) #network 209.165.202.128 0.0.0.31
ISP2(config-router) #no auto-summary
ISP2(config-router) #exit
ISP2(config) #ip route 192.168.1.0 255.255.255.0 209.165.202.130
ISP2(config) #
```

b) implementing the Cisco IOS SLA feature, you must verify reachability to the Internet servers. From router R1, ping the web server, ISP1 DNS server, and ISP2 DNS server to verify connectivity. You can copy the following Tcl script and paste it into R1.

```
R1#tclsh
foreach address {
209.165.200.254
209.165.201.30
209.165.202.158
} {
ping $address source 192.168.1.1
 R1#tclsh
 R1(tcl) #foreach address {
 +>(tcl)#209.165.200.254
 +>(tc1) #209.165.201.30
 +>(tc1) #209.165.202.158
 +>(tcl)#} {
 +>(tcl) #ping $address source 192.168.1.1
 +>(tcl)#}
 Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 209.165.200.254, timeout is 2 seconds:
Cacket sent with a source address of 192.168.1.1
 Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 209.165.201.30, timeout is 2 seconds:

Cacket sent with a source address of 192.168.1.1
  ccess rate is 0 percent (0/5)
 Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 209.165.202.158, timeout is 2 seconds:
Vacket sent with a source address of 192.168.1.1
  uccess rate is 0 percent (0/5)
```

c) Trace the path taken to the web server, ISP1 DNS server, and ISP2 DNS server. You can copy the following Tcl script and paste it into R1.

```
foreach address {
209.165.200.254
209.165.201.30
209.165.202.158
} {
trace $address source 192.168.1.1
```

Step 3: Configure IP SLA probes.

Create an ICMP echo probe on R1 to the primary DNS server on ISP1 using the ip slacommand, the previous ip sla monitor command. In addition, the icmp-echo commandhas replaced the type echo protocol ipIcmpEcho command.

a. Create an ICMP echo probe on R1 to the primary DNS server on ISP1 using the ip sla command.

R1(config)# ip sla 11 R1(config-ip-sla)# icmp-echo 209.165.201.30 R1(config-ip-sla-echo)# frequency 10 R1(config-ip-sla-echo)# exit

R1(config)# ip sla schedule 11 life forever start-time now

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip sla 11
R1(config-ip-sla)#icmp-echo 209.165.201.30
R1(config-ip-sla-echo)#frequency 10
R1(config-ip-sla-echo)#exit
R1(config)#ip sla schedule 11 life forever start-time now
R1(config)#
```

b. Verify the IP SLAs configuration of operation 11 using the show ip sla configuration 11 command.

R1# show ip sla configuration 11

```
l#show ip sla configuration 1
IP SLAs Infrastructure Engine-III
Entry number: 11
 wner:
 ag:
Operation timeout (milliseconds): 5000
 ype of operation to perform: icmp-echo
Type Of Service parameter: 0x0
Request size (ARR data portion): 28
 chedule:
   Operation frequency (seconds): 10 (not considered if randomly scheduled)
Next Scheduled Start Time: Start Time already passed
   Group Scheduled : FALSE
   Randomly Scheduled : FALSE
   Entry Ageout (seconds): never
   Recurring (Starting Everyday): FALSE
 Status of entry (SNMP RowStatus): Active 
Threshold (milliseconds): 5000
   Number of statistic hours kept: 2
```

b. Issue the **show ip sla statistics** command to display the number of successes, failures, and results of the latest operations.

R1# show ip sla statistics

```
Rl#show ip sla statistics
IPSLAs Latest Operation Statistics

IPSLA operation id: 11

Latest RTT: 36 milliseconds

Latest operation start time: 12:42:36 UTC Mon Mar 6 2023

Latest operation return code: OK

Number of successes: 34

Number of failures: 0

Operation time to live: Forever
```

d. Although not actually required because IP SLA session 11 alone could provide the desired fault tolerance, create a second probe, 22, to test connectivity to the second DNS server located on router ISP2.

R1(config)# ip sla 22 R1(config-ip-sla)# icmp-echo 209.165.202.158 R1(config-ip-sla-echo)# frequency 10 R1(config-ip-sla-echo)# exit R1(config)# R1(config)# ip sla schedule 22 life forever start-time now R1(config)# end

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config) #ip sla 22
R1(config-ip-sla) #icmp-echo 209.165.202.158
R1(config-ip-sla-echo) #frequency 10
R1(config-ip-sla-echo) #exit
R1(config) #ip sla schedule 22 life forever start-time now
R1(config) #end
R1#
*Mar 6 12:47:34.847: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

e. Verify the new probe using the show ip sla configuration and show ip sla statistics commands.

```
R1# show ip sla configuration 22
Rlfshow ip sla configuration 22
IP SLAS Infrastructure Engine-III
Entry number: 22
Owner:
Tag:
Operation timeout (milliseconds): 5000
Type of operation to perform: lcmp-echo
Target address/Source address: 209.165.202.158/0.0.0.0
Type of Service parameter: 0x0
Request size (ARR data portion): 28
Verify data: No
VFT Name:
Schedule:
Operation frequency (seconds): 10 (not considered if randomly scheduled)
Next Schedules fratise: Start Time already passed
Group Scheduled: FALSE
Life (seconds): Forever
Entry Ageout (seconds): never
Recurring (Starting Everyday): FALSE
Status of entry (SMMP RowStatus): Active
Threshold (milliseconds): 5000
Distribution Staristics:
Number of statistic hours kept: 2
Number of statistic interval (milliseconds): 20
Enhanced History:
History Statistics:
Number of history Lives kept: 0
Number of history Buckets kept: 15
History Filter Type: None
```

R1# show ip sla statistics 22

```
Rl#show ip sla statistics 22
IPSLAs Latest Operation Statistics

IPSLA operation id: 22
Latest RTT: 71 milliseconds
Latest operation start time: 12:51:02 UTC Mon Mar 6 2023
Clatest operation return code: OK
'Number of successes: 24
Number of failures: 0
Operation time to live: Forever
```

Step 4: Configure tracking options.

Although PBR could be used, you will configure a floating static route that appears or disappears depending on the success or failure of the IP SLA.

a. On R1, remove the current default route and replace it with a floating static route having an administrative distance of 5.

R1(config)# no ip route 0.0.0.0 0.0.0.0 209.165.201.1 **R1(config)**# ip route 0.0.0.0 0.0.0.0 209.165.201.1 5 **R1(config)**# exit

```
R1#CONF T

Enter configuration commands, one per line. End with CNTL/2.

R1(config) #no ip route 0.0.0.0 0.0.0.0 209.165.201.1

R1(config) #ip route 0.0.0.0 0.0.0.0 209.165.201.1 5

R1(config) #exit

R1#

*Mar 6 12:53:08.815: %SYS-5-CONFIG_I: Configured from console by console

R1#
```

h. Verify the routing table.

R1# show ip route

```
Rl‡show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP

+ - replicated route, % - next hop override

Gateway of last resort is 209.165.201.1 to network 0.0.0.0

S* 0.0.0.0/0 [5/0] via 209.165.201.1

192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks

C 192.168.1.0/24 is directly connected, Loopback0

L 192.168.1.1/32 is directly connected, Loopback0

209.165.201.0/24 is variably subnetted, 2 subnets, 2 masks

C 209.165.201.0/30 is directly connected, Serial3/0

L 209.165.201.2/32 is directly connected, Serial3/0

209.165.202.0/24 is variably subnetted, 2 subnets, 2 masks

C 209.165.202.128/30 is directly connected, Serial3/1

L 209.165.202.128/30 is directly connected, Serial3/1

R1‡
```

Notice that the default static route is now using the route with the administrative distance of 5. The first tracking object is tied to IP SLA object 11.

From global configuration mode on R1, use the track 1 ip sla 11 reachability command to enter the configuration mode.

R1(config)# track 1 ip sla 11 reachability **R1(config-track)**# delay down 10 up 1

R1(config-track)# exit

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#track 1 ip sla 11 reachability
R1(config-track)#delay down 10 up 1
R1(config-track)#exit
R1(config)#
```

To view routing table changes as they happen, first enable the debug ip routing command.

R1# debug ip routing

```
Rl#debug ip routing
IP routing debugging is on
Rl#
```

Configure the floating static route that will be implemented when tracking object 1 is active. Use the ip route 0.0.0.0 0.0.0.0 209.165.201.1 2 track 1 command to create a floating static default route via 209.165.201.1 (ISP1). Notice that this command references the tracking object number 1, which in turn references IP SLA operation number 11.

R1(config)# ip route 0.0.0.0 0.0.0.0 209.165.201.1 2 track 1

```
RI#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
Rl(config)#track | ip sla | 1 reachability
Rl(config)#track | ip sla | 1 reachability
Rl(config-track)#exit
Rl(config-track)#exit
Rl(config-track)#exit
Rl(config-track)#exit
Rl*
*Mar 6 | 12:59:01.551: %SYS-5-CONFIG_I: Configured from console by console
Rl#debug ip routing
IP routing debugging is on
Rl#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
Rl(config)#ip route 0.0.0.0 0.0.0.0 209.165.201.1 2 track |
Rl(config)# via 209.165.201.1 1048578

*Mar 6 | 13:00:34.871: RT: updating static 0.0.0.0/0 (0x0):
via 209.165.201.1 1048578

*Mar 6 | 13:00:34.871: RT: add 0.0.0.0/0 via 209.165.201.1, static metric [2/0]
*Mar 6 | 13:00:34.871: RT: rib updating static 0.0.0.0/0 (0x0):
via 209.165.201.1 1048578

*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
*Mar 6 | 13:00:34.871: RT: rib update return code: 17
```

Repeat the steps for operation 22, track number 2, and assign the static route an admin distance higher than track 1 and lower than 5. On R1, copy the following configuration, which sets an admin distance of 3.

R1(config)# track 2 ip sla 22 reachability

R1(config-track)# delay down 10 up 1

R1(config-track)# exit

R1(config)# ip route 0.0.0.0 0.0.0.0 209.165.202.129 3 track 2

```
Rl(config) #track 2 ip sla 22 reachability
Rl(config-track) #delay down 10 up 1
Rl(config-track) #exit
Rl(config) #ip route 0.0.0.0 0.0.0.0 209.165.202.129 3 track 2
Rl(config) #
*Mar 6 13:02:08.083: RT: updating static 0.0.0.0/0 (0x0):
    via 209.165.201.1 1048578

*Mar 6 13:02:08.087: RT: updating static 0.0.0.0/0 (0x0):
    via 209.165.201.1 1048578

*Mar 6 13:02:08.091: RT: rib update return code: 17
*Mar 6 13:02:08.095: RT: updating static 0.0.0.0/0 (0x0):
    via 209.165.202.129 1048578

*Mar 6 13:02:08.099: RT: rib update return code: 17
Rl(config) #
```

Verify the routing table again.

R1# show ip route

```
Rl#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP

+ - replicated route, % - next hop override

Gateway of last resort is 209.165.201.1 to network 0.0.0.0

S* 0.0.0.0/0 [2/0] via 209.165.201.1

192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks

192.168.1.0/24 is directly connected, LoopbackO

L 192.168.1.1/32 is directly connected, LoopbackO

209.165.201.0/24 is variably subnetted, 2 subnets, 2 masks

C 209.165.201.0/24 is variably subnetted, 2 subnets, 2 masks

C 209.165.201.0/24 is variably subnetted, 2 subnets, 2 masks

C 209.165.201.0/24 is variably subnetted, 2 subnets, 2 masks

C 209.165.202.12/32 is directly connected, Serial3/0

L 209.165.202.12/30 is directly connected, Serial3/1

L 209.165.202.12/30 is directly connected, Serial3/1

R1#
```

Although a new default route was entered, its administrative distance is not better than 2. Therefore, it does not replace the previously entered default route.

Step 5: Verify IP SLA operation.

In this step you observe and verify the dynamic operations and routing changes when tracked objects fail. The following summarizes the process:

- ☐ Disable the DNS loopback interface on ISP1 (R2).
- ☐ Observe the output of the debug command on R1.
- □ Verify the static route entries in the routing table and the IP SLA statistics of R1.
- □ Re-enable the loopback interface on ISP1 (R2) and again observe the operation of the IP SLA tracking feature.
- a. On ISP1, disable the loopback interface 1.

ISP1(config-if)# int lo1

ISP1(config-if)# shutdown

```
R1(config) #int lol

R1(config-if) #shutdown

R1(config-if) #shutdown

R1(config-if) #

*Mar 6 13:07:08.015: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopbackl, changed stat

to down

*Mar 6 13:07:08.019: %LINK-5-CHANGED: Interface Loopbackl, changed state to administratively

down

R1(config-if) #
```

R1# show ip route

```
Rlishow ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

O - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP

+ - replicated route, % - next hop override

Gateway of last resort is 209.165.201.1 to network 0.0.0.0

S* 0.0.0.0/0 [2/0] via 209.165.201.1

192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks

C 192.168.1.0/24 is directly connected, Loopback0

L 192.168.1.1/32 is directly connected, Loopback0

209.165.201.0/30 is directly connected, Serial3/0

L 209.165.201.2/32 is directly connected, Serial3/0

209.165.202.0/24 is variably subnetted, 2 subnets, 2 masks

C 209.165.202.0/24 is variably subnetted, 2 subnets, 2 masks

C 209.165.202.0/24 is variably subnetted, Serial3/0

L 209.165.202.1/30 is directly connected, Serial3/1

L 209.165.202.1/30 is directly connected, Serial3/1

L 209.165.202.1/30/32 is directly connected, Serial3/1

L 209.165.202.1/30/32 is directly connected, Serial3/1
```

Verify the IP SLA statistics.

R1# show ip sla statistics

```
RI#Show ip sla statistics
IPSLAs Latest Operation Statistics
IPSLA operation id: 11
Latest RTT: 44 milliseconds
Latest operation return code: 0K
Number of successes: 204
Number of failures: 0
Operation time to live: Forever

IPSLA operation id: 22
Latest RTT: 72 milliseconds
Latest operation start time: 13:10:52 UTC Mon Mar 6 2023
Latest operation code: 0K
Number of successes: 142
Number of successes: 142
Number of failures: 1
Operation time to live: Forever
```

R1# trace 209.165.200.254 source 192.168.1.1

```
Rl#trace 209.165.200.254 source 192.168.1.1
Type escape sequence to abort.
Tracing the route to 209.165.200.254
VRF info: (vrf in name/id, vrf out name/id)
1 209.165.201.1 20 msec 28 msec 28 msec
R1#
```

R1# (config)# int lo1

ISP1(config-if)# no shutdown

```
R1(config) #int lol

R1(config-if) #no shutdown

R1(config-if) #

*Mar 6 13:15:15.975: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopbackl, changed s

to up

R1(config-if) #

*Mar 6 13:15:15.975: %LINK-3-UPDOWN: Interface Loopbackl, changed state to up

R1(config-if) #
```

R1# show ip sla statistics

```
RI# SHOW IP SIG Statistics

IPSLAs Latest Operation Statistics

IPSLA operation id: 11

Latest RTT: 40 milliseconds

Latest operation start time: 13:18:06 UTC Mon Mar 6 2023

Latest operation return code: 0K

Number of successes: 247

Number of failures: 0

Operation time to live: Forever

IPSLA operation id: 22

Latest RTT: 68 milliseconds

Latest operation start time: 13:18:02 UTC Mon Mar 6 2023

Catest operation return code: 0K

Number of successes: 185

Number of failures: 1

Operation time to live: Forever
```

R1# show ip route

```
Rlishow ip route


Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
Nl - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
El - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
+ - replicated route, % - next hop override

Gateway of last resort is 209.165.201.1 to network 0.0.0.0

S* 0.0.0.0/0 [2/0] via 209.165.201.1
192.168.1.0/24 is directly connected, Loopback0
L 192.168.1.0/24 is directly connected, Loopback0
C 209.165.201.0/24 is directly connected, Loopback0
C 209.165.201.0/24 is directly connected, Serial3/0
L 209.165.201.0/24 is directly connected, Serial3/0
C 209.165.202.0/24 is variably subnetted, 2 subnets, 2 masks
C 209.165.202.0/24 is variably subnetted, 2 subnets, 2 masks
C 209.165.202.0/24 is variably subnetted, Serial3/0
L 209.165.202.128/30 is directly connected, Serial3/1
L 209.165.202.128/30 is directly connected, Serial3/1
L 209.165.202.130/32 is directly connected, Serial3/1
```

PRACTICAL NO: 02

AIM: Using The As_Path Attribute



Objectives:

Use BGP commands to prevent private AS numbers from being advertised to the outside world.

Use the AS_PATH attribute to filter BGP routes based on their source AS number

Step 1: Prepare the routers for the lab.

Cable the network as shown in the **Topology** diagram. Erase the startup configuration and reload each router to clear previous configurations.

Step 2: Configure the hostname and interface addresses.

You can copy and paste the following configurations into your routers to begin.

Step 1: Prepare the routers for the lab.

Cable the network as shown in the topology diagram. Erase the startup configuration and reload each router to clear previous configurations.

Step 2: Configure the hostname and interface addresses.

Router R1 (hostname SanJose)

R1#CONF T

R1(config)#hostname SanJose

SanJose(config)#interface Loopback0

SanJose(config-if)#ip address 10.1.1.1 255.255.255.0

SanJose(config-if)#interface Serial3/0

SanJose(config-if)#ip address 192.168.1.5 255.255.255.252

SanJose(config-if)#clock rate 128000

SanJose(config-if)#no shutdown

SanJose(config-if)#

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#hostname SanJose
SanJose(config)#interface Loopback0
SanJose(config-if)#ip address 10.1.1.1 255.255.255.0
SanJose(config-if)#interface Serial3/0
SanJose(config-if)#ip address 192.168.1.5 255.255.252
SanJose(config-if)#clock rate 128000
SanJose(config-if)#no shutdown
```

Router R2 (hostname ISP)

R2#CONF T

R2(config)#hostname ISP

ISP(config)#interface Loopback0

ISP(config-if)#ip address 10.2.2.1 255.255.255.0

ISP(config-if)#interface Serial3/0

ISP(config-if)#ip address 192.168.1.6 255.255.255.252

ISP(config-if)#no shutdown

ISP(config-if)#interface Serial3/1

ISP(config-if)#ip address 172.24.1.17 255.255.255.252

ISP(config-if)#clock rate 128000

ISP(config-if)#no shutdown

ISP(config-if)#

```
R2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.

R2(config) #hostname ISP
ISP(config) #interface Loopback0
ISP(config-if) #ip address 10.2.2.1 255.255.255.0
ISP(config-if) #interface Serial3/0
ISP(config-if) #ip address 192.168.1.6 255.255.252
ISP(config-if) #no shutdown
ISP(config-if) #interface Serial3/1
ISP(config-if) #interface Serial3/1
ISP(config-if) #ip address 172.24.1.17 255.255.252
ISP(config-if) #clock rate 128000
ISP(config-if) #no shutdown
*Mar 18 15:22:35.019: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up
ISP(config-if) #no shutdown
```

Router R3 (hostname CustRtr)

R3#CONF T

R3(config)#hostname CustRtr

CustRtr(config)#interface Loopback0

CustRtr(config-if)#ip address 10.3.3.1 255.255.255.0

CustRtr(config-if)#interface Serial3/1

CustRtr(config-if)#ip address 172.24.1.18 255.255.255.252

CustRtr(config-if)#no shutdown

CustRtr(config-if)#

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config) #hostname CustRtr
CustRtr(config) #interface Loopback0
CustRtr(config-if) #ip address 10.3.3.1 255.255.255.0
CustRtr(config-if) #interface Serial3/1
CustRtr(config-if) #ip address 172.24.1.18 255.255.255.252
CustRtr(config-if) #no shutdown
*Mar 18 15:27:18.447: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0
changed state to up
CustRtr(config-if) #no shutdown
```

Step 3: Configure BGP.

Configure BGP for normal operation. Enter the appropriate BGP commands on each router so that they identify their BGP neighbors and advertise their loopback networks.

SanJose(config)# router bgp 100

SanJose(config-router)# neighbor 192.168.1.6 remote-as 300

SanJose(config-router)# network 10.1.1.0 mask 255.255.255.0

```
SanJose#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
SanJose(config) #router bgp 100
SanJose(config-router) #neighbor 192.168.1.6 remote-as 300
SanJose(config-router) #network 10.1.1.0 mask 255.255.255.0
SanJose(config-router) #
```

ISP(config)# router bgp 300

ISP(config-router)# neighbor 192.168.1.5 remote-as 100

ISP(config-router)# neighbor 172.24.1.18 remote-as 65000

ISP(config-router)# network 10.2.2.0 mask 255.255.255.0

```
ISP#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
ISP(config)#router bgp 300
ISP(config-router)#neighbor 192.168.1.5 remote-as 100
ISP(config-router)#neighbor 172.24.1.18 remote-as 65000
ISP(config-router)#network 10.2.2.0 mask 255.255.255.0
```

CustRtr(config)# router bgp 65000

CustRtr(config-router)# neighbor 172.24.1.17 remote-as 300

CustRtr(config-router)# network 10.3.3.0 mask 255.255.255.0

```
CustRtr#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
CustRtr(config) #router bgp 65000
CustRtr(config-router) #neighbor 172.24.1.17 remote-as 300
CustRtr(config-router) #network 10.3.3.0 mask 255.255.255.0
CustRtr(config-router)#
```

Verify that these routers have established the appropriate neighbor relationships by issuing the show ip bgp neighbors command on each router.

ISP# show ip bgp neighbors

```
ISP#show ip bgp neighbors
*Mar 18 15:52:00.027: %SYS-5-CONFIG_I: Configured from console by console
ISP#show ip bgp neighbors
GP neighbor is 172.24.1.18, remote AS 65000, external link
 BGP version 4, remote router ID 0.0.0.0 BGP state = Idle
 Neighbor sessions:
   0 active, is not multisession capable (disabled)
    Stateful switchover support enabled: NO
 Default minimum time between advertisement runs is 30 seconds
For address family: IPv4 Unicast
 BGP table version 3, neighbor version 1/3
 Output queue size : 0
 Index 0, Advertise bit 0
 Slow-peer detection is disabled
 Slow-peer split-update-group dynamic is disabled
                                  Sent
                                             Rcvd
 Prefix activity:
    Prefixes Total:
   Implicit Withdraw:
   Explicit Withdraw:
    Used as bestpath:
    Used as multipath:
```

Step 4: Remove the private AS.

Display the SanJose routing table using the show ip route command. SanJose should have a route to both 10.2.2.0 and 10.3.3.0. Troubleshoot if necessary.

SanJose# show ip route

```
SanJose#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
O - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
+ - replicated route, % - next hop override

[Gateway of last resort is not set

10.0.0.0/8 is variably subnetted, 3 subnets, 2 masks
C 10.1.1.0/24 is directly connected, Loopback0
L 10.1.1./32 is directly connected, Loopback0
D 10.2.2.0/24 [20/0] via 192.168.1.6, 00:03:49
192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks
C 192.168.1.4/30 is directly connected, Serial3/0
L 192.168.1.5/32 is directly connected, Serial3/0
SanJose#
```

Ping again, this time as an extended ping, sourcing from the Loopback0 interface address.

```
ping 10.3.3.1 source 10.1.1.1
```

```
SanJose#ping 10.3.3.1 source 10.1.1.1

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 10.3.3.1, timeout is 2 seconds:

Packet sent with a source address of 10.1.1.1

.....

Success rate is 0 percent (0/5)

SanJose#
```

Ping again, this time as an extended ping, sourcing from the Loopback0 interface address.

SanJose# ping

Protocol [ip]:

Target IP address: 10.3.3.1

Repeat count [5]: Datagram size [100]: Timeout in seconds [2]: Extended commands [n]: y

Source address or interface: 10.1.1.1

Type of service [0]:

Set DF bit in IP header? [no]:

Validate reply data? [no]:

Data pattern [0xABCD]:

Loose, Strict, Record, Timestamp, Verbose[none]:

Sweep range of sizes [n]:

Type escape sequence to abort.

```
SanJose#ping
Protocol [ip]:
Target IP address: 10.3.3.1
Repeat count [5]:
Datagram size [100]:
Timeout in seconds [2]:
Extended commands [n]: y
Source address or interface: 10.1.1.1
Type of service [0]:
Set DF bit in IP header? [no]:
Validate reply data? [no]:
Data pattern [0xABCD]:
Loose, Strict, Record, Timestamp, Verbose[none]:
Sweep range of sizes [n]:
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.3.3.1, timeout is 2 seconds:
Packet sent with a source address of 10.1.1.1
Success rate is 0 percent (0/5)
```

Check the BGP table from SanJose by using the show ip bgp command. Note the AS path for the 10.3.3.0 network. The AS 65000 should be listed in the path to 10.3.3.0.

SanJose# show ip bgp

```
SanJose#show ip bgp
BGP table version is 3, local router ID is 10.1.1.1
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal, r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter, x best-external, a additional-path, c RIB-compressed,
Origin codes: i - IGP, e - EGP, ? - incomplete
RPKI validation codes: V valid, I invalid, N Not found

Network
Next Hop
Metric LocPrf Weight Path
*> 10.1.1.0/24
0.0.0.0
0
32768 i
*> 10.2.2.0/24
192.168.1.6
0
0 300 i
SanJose#
```

Configure ISP to strip the private AS numbers from BGP routes exchanged with SanJose using the following commands.

ISP(config)# router bgp 300

ISP(config-router)# neighbor 192.168.1.5 remove-private-as

```
ISP#CONF T
Enter configuration commands, one per line. End with CNTL/Z.

ISP(config) #router bgp 300
ISP(config-router) #neighbor 192.168.1.5 remove-private-as
ISP(config-router) #
```

After issuing these commands, use the clear ip bgp * command on ISP to reestablish the BGP relationship between the three routers. Wait several seconds and then return to SanJose to check its routing table.

SanJose# ping 10.3.3.1 source lo0

```
SanJose#ping 10.3.3.1 source lo0
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.3.3.1, timeout is 2 secon ds:
Packet sent with a source address of 10.1.1.1
.....
Success rate is 0 percent (0/5)
SanJose#
```

Now check the BGP table on SanJose. The AS_ PATH to the 10.3.3.0 network should be AS 300. It no longer has the private AS in the path.

SanJose# show ip bgp

```
SanJose#show ip bgp
BGP table version is 3, local router ID is 10.1.1.1
Status codes: s suppressed, d damped, h history, * valid, > best, i - i nternal,

r RIB-failure, S Stale, m multipath, b backup-path, f RT-
Filter,

x best-external, a additional-path, c RIB-compressed,
Origin codes: i - IGP, e - EGP, ? - incomplete
RPKI validation codes: V valid, I invalid, N Not found

Network

Next Hop

Metric LocPrf Weight Path
*> 10.1.1.0/24
0.0.0.0
0
32768 i
*> 10.2.2.0/24
192.168.1.6
0
0 300 i
```

Step 5: Use the AS_PATH attribute to filter routes.

Configure a special kind of access list to match BGP routes with an AS_PATH attribute that both begins and ends with the number 100. Enter the following commands on ISP.

ISP(config)# ip as-path access-list 1 deny ^100\$ ISP(config)# ip as-path access-list 1 permit .*

```
ISP(config)#ip as-path access-list 1 deny ^100$
ISP(config)#ip as-path access-list 1 permit .*
ISP(config)#
```

Apply the configured access list using the neighbor command with the filter-list option.

ISP(config)# router bgp 300

ISP(config-router)# neighbor 172.24.1.18 filter-list 1 out

```
ISP(config)#router bgp 300
ISP(config-router)#neighbor 172.24.1.18 filter-list 1 out
ISP(config-router)#
```

Use the clear ip bgp * command to reset the routing information. Wait several seconds and then check the routing table for ISP. The route to 10.1.1.0 should be in the routing table.

Note: To force the local router to resend its BGP table, a less disruptive option is to use the **clear ip bgp** * **out** or **clear ip bgp** * **soft** command (the second command performs both outgoing and incoming route resync).

ISP#clear ip bgp *
ISP# show ip route

Check the routing table for CustRtr. It should not have a route to 10.1.1.0 in its routing table.

CustRtr# show ip route

```
CustRtr#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
+ - replicated route, % - next hop override

Gateway of last resort is not set

10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C 10.3.3.0/24 is directly connected, Loopback0
L 10.3.3.1/32 is directly connected, Loopback0
172.24.0.0/16 is variably subnetted, 2 subnets, 2 masks
C 172.24.1.16/30 is directly connected, Serial3/1
L 172.24.1.18/32 is directly connected, Serial3/1
CustRtr#
```

Return to ISP and verify that the filter is working as intended. Issue the show ip bgp regexp ^100\$ command.

ISP# show ip bgp regexp ^100\$

ISP# tclsh

```
ISP#show ip bgp regexp ^100$
BGP table version is 3, local router ID is 10.2.2.1
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal, r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter, x best-external, a additional-path, c RIB-compressed,
Origin codes: i - IGP, e - EGP, ? - incomplete
RPKI validation codes: V valid, I invalid, N Not found

Network Next Hop Metric LocPrf Weight Path

*> 10.1.1.0/24 192.168.1.5 0 0 100 i

ISP#
```


Run the following Tcl script on all routers to verify whether there is connectivity. All pings from ISP should be successful. SanJose should not be able to ping the CustRtr loopback 10.3.3.1 or the WAN link 172.24.1.16/30. CustRtr should not be able to ping the SanJose loopback 10.1.1.1 or the WAN link 192.168.1.4/30.

```
foreach address {
10.1.1.1
10.2.2.1
10.3.3.1
192.168.1.5
192.168.1.6
172.24.1.17
172.24.1.18
} {
ping $address }
 ISP#tclsh
 SP(tcl)#foreach address {
 +>192.168.1.5
 +>ping $address }
Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 10.1.1.1, timeout is 2 seconds:
 Success rate is 100 percent (5/5), round-trip min/avg/max = 20/28/36 ms
 ending 5, 100-byte ICMP Echos to 10.2.2.1, timeout is 2 seconds:
 Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms
 Type escape sequence to abort.
 ending 5, 100-byte ICMP Echos to 10.3.3.1, timeout is 2 seconds:
 Type escape sequence to abort
 ending 5, 100-byte ICMP Echos to 192.168.1.5, timeout is 2 seconds:
 Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.1.6, timeout is 2 seconds:
 Success rate is 100 percent (5/5), round-trip min/avg/max = 52/65/72 ms
 Type escape sequence to abort.
  ending 5, 100-byte ICMP Echos to 172.24.1.17, timeout is 2 seconds:
 ending 5, 100-byte ICMP Echos to 172.24.1.18, timeout is 2 seconds:
  uccess rate is 100 percent (5/5), round-trip min/avg/max = 28/44/92 ms
 ISP(tcl)#
```

PRACTICAL NO: 03

AIM: Configuring Ibgp And Ebgp Sessions, Local Preference, And Med



Step 0: Suggested starting configurations.

Router R1

no ip domain-lookup line con 0 logging synchronous exec-timeout 0 0

```
RI#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
Rl(config) #no ip domain-lookup
Rl(config) #line con 0
Rl(config-line) #logging synchronous
Rl(config-line) #exec-timeout 0 0
Rl(config-line) #
```

Router R2

no ip domain-lookup line con 0 logging synchronous exec-timeout 0 0

```
R2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#no ip domain-lookup
R2(config)#line con 0
R2(config-line)#logging synchronous
R2(config-line)#exec-timeout 0 0
R2(config-line)#
```

Router R3

no ip domain-lookup line con 0 logging synchronous

exec-timeout 0 0

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config) #no ip domain-lookup
R3(config) #line con 0
R3(config-line) #logging synchronous
R3(config-line) #exec-timeout 0 0
R3(config-line) #
```

Step 1: Configure interface addresses.

Router R1 (hostname ISP)

R1(config)#hostname ISP
ISP(config)#interface Loopback0
ISP(config-if)#ip address 192.168.100.1 255.255.255.0
ISP(config-if)#exit
ISP(config)#interface Serial3/0
ISP(config-if)#ip address 192.168.1.5 255.255.255.252
ISP(config-if)#clock rate 128000
ISP(config-if)#no shutdown
ISP(config-if)#exit
ISP(config)#interface Serial3/1
ISP(config-if)#ip address 192.168.1.1 255.255.252
ISP(config-if)#no shutdown
ISP(config-if)#no shutdown
ISP(config-if)#no shutdown
ISP(config-if)#no shutdown

```
R1(config) #hostname ISP
ISP(config) #interface Loopback0
ISP(config-if) #ip address 192.168.100.1 255.255.255.0
ISP(config-if) #exit
ISP(config) #interface Serial3/0
ISP(config-if) #ip address 192.168.1.5 255.255.255.252
ISP(config-if) #clock rate 128000
ISP(config-if) #no shutdown
ISP(config-if) #exit
ISP(config-if) #exit
ISP(config) #interface Serial3/1
ISP(config-if) #ip address 192.168.1.1 255.255.252
ISP(config-if) #no shutdown
ISP(config-if) #no shutdown
ISP(config-if) #end
ISP#
```

Router R2 (hostname SanJose1)

R2#CONF T

R2(config)#hostname SanJose1

SanJose1(config)#interface Loopback0

SanJose1(config-if)#ip address 172.16.64.1 255.255.255.0

SanJose1(config-if)#exit

SanJose1(config)#interface Serial3/0

SanJose1(config-if)#ip address 192.168.1.6 255.255.255.252

SanJose1(config-if)#no shutdown

SanJose1(config-if)#exit

SanJose1(config)#interface Serial3/1

SanJose1(config-if)#ip address 172.16.1.1 255.255.255.0

SanJose1(config-if)#clock rate 128000

SanJose1(config-if)#no shutdown

SanJose1(config-if)#end

```
R2#CONF T
Enter configuration commands, one per line. End with CNTL/2.
R2(config) #hostname SanJosel
SanJosel(config) #interface Loopback0
SanJosel(config-if) #
"Mar 15 14:59:06.395: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0,
changed state to up
SanJosel(config-if) # address 172.16.64.1 255.255.255.0
SanJosel(config-if) #ip address 192.168.1.6 255.255.255.0
SanJosel(config-if) #in o shutdown
SanJosel(config-if) # no shutdown
SanJosel(config-if) # exit
*Mar 15 14:59:40.627: %LINK-3-UPDOWN: Interface Serial3/0, changed state to up
SanJosel(config-if) # *
*Mar 15 14:59:41.635: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0,
changed state to up
SanJosel(config-if) # interface Serial3/1
SanJosel(config-if) # address 172.16.1.1 255.255.255.0
SanJosel(config-if) # address 172.16.1.1 255.255.255.0
SanJosel(config-if) # on shutdown
SanJosel(config-if) # on shu
```

Router R3 (hostname SanJose2)

R3#CONF T

R3(config)#hostname SanJose2

SanJose2(config)#interface Loopback0

SanJose2(config-if)#ip address 172.16.32.1 255.255.255.0

SanJose2(config-if)#exit

SanJose2(config)#interface Serial3/0

SanJose2(config-if)#ip address 192.168.1.2 255.255.255.252

SanJose2(config-if)#clock rate 128000

SanJose2(config-if)#no shutdown

SanJose2(config-if)#exit

SanJose2(config)#interface Serial3/1

SanJose2(config-if)#ip address 172.16.1.2 255.255.255.0

SanJose2(config-if)#no shutdown

SanJose2(config-if)#end

```
Rajeconf T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config) #hostname SanJose2
SanJose2(config) #interface Loopback0
SanJose2(config-if) #
*Mar 15 15:02:56.415: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up
SanJose2(config-if) # paddress 172.16.32.1 255.255.255.0
SanJose2(config-if) # paddress 192.16.32.1 255.255.255.0
SanJose2(config-if) # paddress 192.16.32.2 255.255.255.255
SanJose2(config-if) # paddress 192.168.1.2 255.255.255.255
SanJose2(config-if) # paddress 192.168.1.2 255.255.255.255
SanJose2(config-if) # paddress 192.168.1.2 255.255.255.255
SanJose2(config-if) # war 15 15:03:37.571: %LINK-3-UPDOWN: Interface Serial3/0, changed state to up
SanJose2(config-if) # war 15 15:03:38.579: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
SanJose2(config-if) # paddress 172.16.1.2 255.255.255.0
SanJose2(config-if) # paddress 172.16.1.2 255.255.255.0
SanJose2(config-if) # war 15 15:04:04.475: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to down
SanJose2(config-if) # war 15 15:04:04.475: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to down
SanJose2(config-if) # end
*Mar 15 15:04:05.851: %LINK-3-UPDOWN: Interface Serial3/1, changed state to up
SanJose2(config-if) # end
*Mar 15 15:04:05.851: %LINK-3-UPDOWN: Interface Serial3/1, changed state to up
SanJose2(config-if) # end
*Mar 15 15:04:05.851: %LINK-3-UPDOWN: Interface Serial3/1, changed state to up
SanJose2(config-if) # end
```

Step 2: Configure EIGRP.

SanJose1(config)# router eigrp 1

SanJose1(config-router)# network 172.16.0.0

```
SanJosel Configuration commands, one per line. End with CNTL/Z.
SanJosel (config) #router eigrp 1
SanJosel (config-router) #network 172.16.0.0
SanJosel (config-router) #
```

SanJose2(config)# router eigrp 1

SanJose2(config-router)# network 172.16.0.0

```
SanJose2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
SanJose2(config)#router eigrp l
SanJose2(config-router)#network 172.16.0.0
SanJose2(config-router)#
```

Step 3: Configure IBGP and verify BGP neighbors.

a. Configure IBGP between the SanJose1 and SanJose2 routers. On the SanJose1 router, enter the following configuration.

SanJose1(config)# router bgp 64512 SanJose1(config-router)# neighbor 172.16.32.1 remote-as 64512 SanJose1(config-router)# neighbor 172.16.32.1 update-source lo0

```
SanJosel#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
SanJosel(config)#router bgp 64512
SanJosel(config-router)#neighbor 172.16.32.1 remote-as 64512
SanJosel(config-router)#neighbor 172.16.32.1 update-source 100
SanJosel(config-router)#
```

c. Complete the IBGP configuration on SanJose2 using the following commands.

SanJose2(config)# router bgp 64512

SanJose2(config-router)# neighbor 172.16.64.1 remote-as 64512

SanJose2(config-router)# neighbor 172.16.64.1 update-source lo0

```
SanJose2(config) #router bgp 64512
SanJose2(config-router) #neighbor 172.16.64.1 remote-as 64512
SanJose2(config-router) #neighbor 172.16.64.1 update-source 100
SanJose2(config-router) #
```

d. Verify that SanJose1 and SanJose2 become BGP neighbors by issuing the show ip bgp neighbors command on SanJose1. View the following partial output. If the BGP state is not established, troubleshoot the connection.

SanJose2# show ip bgp neighbors

```
SanJose2#show ip bgp neighbors
BGP neighbor is 172.16.64.1, remote AS 64512, internal link
BGP version 4, remote router ID 172.16.64.1
BGP version 4, remote router ID 172.16.64.1
BGP state = Established, up for 00:00:110

Last read 00:00:20, last write 00:00:17, hold time is 180, keepalive interval is 60 seconds
Neighbor sessions:
1 active, is not multisession capable (disabled)
Neighbor capabilities:
Route refresh: advertised and received(new)
Four-octets ASN Capability: advertised and received
Address family IPv4 Unicast: advertised and received
Enhanced Refresh Capability: advertised and received
Multisession Capability:
Stateful switchover support enabled: NO for session 1
Message statistics:
InQ depth is 0
OutQ depth is 0

Sent Rcvd
Opens:
Notifications:
0 0
Updates:
1 1
Notifications:
3 3
--More--
```

Step 4: Configure EBGP and verify BGP neighbors.

a. Configure ISP to run EBGP with SanJose1 and SanJose2. Enter the following commands on ISP.

ISP(config)# router bgp 200

ISP(config-router)# neighbor 192.168.1.6 remote-as 64512

ISP(config-router)# neighbor 192.168.1.2 remote-as 64512

ISP(config-router)# network 192.168.100.0

```
ISp#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
ISp(config)#hostname ISP
ISP(config) #router bgp 200
ISP(config-router) #neighbor 192.168.1.6 remote-as 64512
ISP(config-router)#neighbor 192.168.1.2 remote-as 64512
ISP(config-router) #network 192.168.100.0
ISP(config-router)#
```

Configure a discard static route for the 172.16.0.0/16 network. Any packets that do not have a more specific match (longer match) for a 172.16.0.0 subnet will be dropped instead of sent to the ISP. Later in this lab we will configure a default route to the ISP.

SanJose1(config)# ip route 172.16.0.0 255.255.0.0 null0

```
SanJosel#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
SanJosel(config) #ip route 172.16.0.0 255.255.0.0 null0
SanJosel(config)#
```

Configure SanJose1 as an EBGP peer to ISP.

SanJose1(config)# router bgp 64512

SanJose1(config-router)# neighbor 192.168.1.5 remote-as 200

SanJose1(config-router)# network 172.16.0.0

Use the show ip bgp neighbors command to verify that SanJose1 and ISP have reached the established state. Troubleshoot if necessary.

SanJose1# show ip bgp neighbors

```
andoselfshow ip beg neighbors

FF neighbor is 172.16.32.1, remote A5 64512, internal link

BGP version 4, remote router ID 172.16.32.1

BGP state = Established, up for 00:15:49

Last read 00:100:14, last write 00:00:46, hold time is 180, keepalive interval

60 seconds
Last read 00:00114, last write 00:00146, hold time is it so seconds.
Neighbor sessions:
1 active, is not multisession capable (disabled)
Neighbor capabilities:
Route refresh: advertised and received(new)
Four-octets ASN Capability: advertised and received
Address family IFP4 Unicast: advertised and received
Enhanced Refresh Capability: advertised and received
Multisession Capability:
Stateful switchover support enabled: NO for session 1
Message statistics:
InO depth is 0
OutO depth is 0
            Opens:
Notifications:
```

Configure a discard static route for 172.16.0.0/16 on SanJose2 and as an EBGP peer to ISP.

SanJose2(config)# ip route 172.16.0.0 255.255.0.0 null0

SanJose2(config)# router bgp 64512

SanJose2(config-router)# neighbor 192.168.1.1 remote-as 200

SanJose2(config-router)# network 172.16.0.0

```
SanJose2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
SanJose2(config)#ip route 172.16.0.0 255.255.0.0 null0
SanJose2(config) #router bgp 64512
SanJose2(config-router)#neighbor 192.168.1.1 remote-as 200
SanJose2(config-router)#network 172.16.0.0
SanJose2(config-router)#
```

Step 5: View BGP summary output.

SanJose2#show ip bgp summary

```
SanJose2#show ip bgp summary
BGP router identifier 172.16.32.1, local AS number 64512
BGP table version is 3, main routing table version 3
2 network entries using 288 bytes of memory
3 path entries using 240 bytes of memory
3/1 BGP path/bestpath attribute entries using 408 bytes of memory
1 BGP AS-PATH entries using 24 bytes of memory
0 BGP route-map cache entries using 0 bytes of memory
0 BGP filter-list cache entries using 0 bytes of memory
BGP using 960 total bytes of memory
BGP activity 2/0 prefixes, 3/0 paths, scan interval 60 secs
Neighbor V AS MsgRcvd MsgSent TblVer InQ OutQ Up/Down State/PfxRcd
172.16.64.1 4 64512 9 9 3 0 000:05:00 2
192.168.1.1 4 200 0 0 1 0 0 never Idle
SanJose2#
```

Step 6: Verify which path the traffic takes.

```
ISP#clear ip bgp *
```

```
ISP#clear ip bgp *
ISP#
ISP#
*Mar 16 12:54:33.471: %BGP-5-ADJCHANGE: neighbor 192.168.1.6 Down User reset
*Mar 16 12:54:33.471: %BGP_SESSION-5-ADJCHANGE: neighbor 192.168.1.6 IPv4 Unicast topology base removed from
ion User reset
*Mar 16 12:54:34.079: %BGP-5-ADJCHANGE: neighbor 192.168.1.6 Up
ISP#
ISP#
```

ISP#ping 172.16.64.1

```
ISP#ping 172.16.64.1
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.64.1, timeout is 2 seconds:
....
Success rate is 0 percent (0/5)
ISP#
```

ISP#ping 172.16.1.1

```
ISP#ping 172.16.1.1

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 172.16.1.1, timeout is 2 seconds:
!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 28/32/36 ms
ISP#
```

ISP#ping 172.16.32.1

```
ISP#ping 172.16.32.1
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.32.1, timeout is 2 seconds:
UUUUUU
Success rate is 0 percent (0/5)
ISP#
```

ISP#ping 172.16.1.2

```
ISP#ping 172.16.1.2
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.1.2, timeout is 2 seconds:
.....
Success rate is 0 percent (0/5)
ISP#
```

ISP#show ip bgp

```
ISP#show ip bgp
BGP table version is 3, local router ID is 192.168.100.1
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal, r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter, x best-external, a additional-path, c RIB-compressed,
Origin codes: i - IGP, e - EGP, ? - incomplete
RPKI validation codes: V valid, I invalid, N Not found

Network Next Hop Metric LocPrf Weight Path
*> 172.16.0.0 192.168.1.6 0 0 64512 i
*> 192.168.100.0 0.0.0.0 0 32768 i
TSP#
```

```
ISP#ping 172.16.1.1 source 192.168.100.1
ISP#ping 172.16.1.1 source 192.168.100.1
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.1.1, timeout is 2 seconds:
Packet sent with a source address of 192.168.100.1
Success rate is 100 percent (5/5), round-trip min/avg/max = 20/28/36 ms
ISP#
ISP#ping 172.16.32.1 source 192.168.100.1
ISP#ping 172.16.32.1 source 192.168.100.1
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.32.1, timeout is 2 seconds:
Packet sent with a source address of 192.168.100.1
010101010
Success rate is 0 percent (0/5)
ISP#
ISP#ping 172.16.1.2 source 192.168.100.1
ISP#ping 172.16.1.2 source 192.168.100.1
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.1.2, timeout is 2 seconds:
Packet sent with a source address of 192.168.100.1
Success rate is 0 percent (0/5)
ISP#
ISP#ping 172.16.64.1 source 192.168.100.1
ISP#ping 172.16.64.1 source 192.168.100.1
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.64.1, timeout is 2 seconds:
Packet sent with a source address of 192.168.100.1
Success rate is 100 percent (5/5), round-trip min/avg/max = 20/30/40 ms
ISP#
You can also use the extended ping dialogue to specify the source address, as shown in this example.
ISP# ping
Protocol [ip]:
Target IP address: 172.16.64.1
Repeat count [5]:
Datagram size [100]:
Timeout in seconds [2]:
Extended commands [n]: y
Source address or interface: 192.168.100.1
Type of service [0]:
Set DF bit in IP header? [no]:
Validate reply data? [no]:
Data pattern [0xABCD]:
Loose, Strict, Record, Timestamp, Verbose[none]:
Sweep range of sizes [n]:
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.64.1, timeout is 2 seconds:
Packet sent with a source address of 192.168.100.1
Success rate is 100 percent (5/5), round-trip min/avg/max = 20/20/24 ms
ISP#
```

```
ISP#ping
Protocol [ip]:
Target IP address: 172.16.64.1
Repeat count [5]:
Datagram size [100]:
Timeout in seconds [2]:
Extended commands [n]: y
Source address or interface: 192.168.100.1
Type of service [0]:
Set DF bit in IP header? [no]:
Validate reply data? [no]:
Data pattern [0xABCD]:
Loose, Strict, Record, Timestamp, Verbose[none]:
Sweep range of sizes [n]:
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.64.1, timeout is 2 seconds:
Packet sent with a source address of 192.168.100.1
Success rate is 100 percent (5/5), round-trip min/avg/max = 28/31/32 ms
ISP#
```

Step 7: Configure the BGP next-hop-self feature.

a. Issue the following commands on the ISP router.

ISP(config)# router bgp 200

ISP(config-router)# network 192.168.1.0 mask 255.255.255.252

ISP(config-router)# network 192.168.1.4 mask 255.255.255.252

```
ISP#CONF T
Enter configuration commands, one per line. End with CNTL/2.
ISP(config) #router bgp 200
ISP(config-router) #network 192.168.1.0 mask 255.255.255.252
ISP(config-router) #network 192.168.1.4 mask 255.255.255.252
ISP(config-router) #
```

Issue the show ip bgp command to verify that the ISP is correctly injecting its own WAN links into BGP. ISP# show ip bgp

32768 i

```
ISP#snow ip bgp
BGP table version is 4, local router ID is 192.168.100.1
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal, r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter, x best-external, a additional-path, c RIB-compressed,
Origin codes: i - IGP, e - EGP, ? - incomplete
RPKI validation codes: V valid, I invalid, N Not found

Network Next Hop Metric LocPrf Weight Path

*> 172.16.0.0 192.168.1.6 0 0 64512 i

*> 192.168.1.4/30 0.0.0.0 0 32768 i
```

SanJose2# show ip route

```
SanJose2#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP

+ - replicated route, % - next hop override

Gateway of last resort is not set

172.16.0.0/16 is variably subnetted, 5 subnets, 3 masks

S 172.16.0.0/16 is directly connected, Null0

C 172.16.1.0/24 is directly connected, Serial3/1

L 172.16.1.2/32 is directly connected, Serial3/1

C 172.16.32.0/24 is directly connected, Loopback0

L 172.16.32.1/32 is directly connected, Loopback0

SanJose2#
```

ISP(config)# router bgp 200

```
ISP(config-router)# no network 192.168.1.0 mask 255.255.255.252
ISP(config-router)# no network 192.168.1.4 mask 255.255.255.252
ISP(config-router)# exit
ISP(config)# interface serial 3/1
ISP(config-if)# shutdown
```

```
ISP#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
ISP(config) #router bgp 200
ISP(config-router) #no network 192.168.1.0 mask 255.255.255.252
ISP(config-router) #no network 192.168.1.4 mask 255.255.255.252
ISP(config-router) #exit
ISP(config) #interface serial 3/1
ISP(config-if) #shutdown
ISP(config-if) #
```

SanJose2# show ip bgp

SanJose2# show ip route

```
SanJose2#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP

+ - replicated route, % - next hop override

Gateway of last resort is not set

172.16.0.0/16 is variably subnetted, 5 subnets, 3 masks

S 172.16.0.0/16 is directly connected, Null0

C 172.16.1.0/24 is directly connected, Serial3/1

L 172.16.32.0/24 is directly connected, Loopback0

L 172.16.32.1/32 is directly connected, Loopback0

SanJose2#
```

Issue the next-hop-self command on SanJose1 and SanJose2 to advertise themselves as the next hop to their IBGP peer.

```
SanJose1(config)# router bgp 64512
SanJose1(config-router)# neighbor 172.16.32.1 next-hop-self
SanJose2(config)# router bgp 64512
SanJose2(config-router)# neighbor 172.16.64.1 next-hop-self
```

```
SanJosel#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
SanJosel(config)#router bgp 64512
SanJosel(config-router)#neighbor 172.16.32.1 next-hop-self
SanJosel(config-router)#router bgp 64512
SanJosel(config-router)#neighbor 172.16.64.1 next-hop-self
```

Reset BGP operation on either router with the clear ip bgp * command.

```
SanJose1# clear ip bgp *
SanJose1#
SanJosel#clear ip bgp *
SanJosel#
*Mar 17 12:22:40.999: %BGP-5-ADJCHANGE: neighbor 192.168.1.5 Down User reset
*Mar 17 12:22:41.003: %BGP_SESSION-5-ADJCHANGE: neighbor 192.168.1.5 IPv4 Unicas
 t topology base removed from session. User reset
*Mar 17 12:22:41.179: %BGP-5-ADJCHANGE: neighbor 192.168.1.5 Up
SanJosel#
SanJose2# clear ip bgp *
SanJose2#
SanJose2#clear ip bgp *
SanJose2#
SanJose2# show ip bgp
SanJose2#show ip bgp
BGP table version is 2, local router ID is 172.16.32.1
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal,
               r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter,
               \boldsymbol{x} best-external, a additional-path, c RIB-compressed,
Origin codes: i - IGP, e - EGP, ? - incomplete
RPKI validation codes: V valid, I invalid, N Not found
     Network
                        Next Hop
                                             Metric LocPrf Weight Path
                                                              32768 i
SanJose2#
SanJose2# show ip route
SanJose2#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2 E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
       + - replicated route, % - next hop override
Gateway of last resort is not set
      172.16.0.0/16 is variably subnetted, 5 subnets, 3 masks
          172.16.0.0/16 is directly connected, Null0
          172.16.1.0/24 is directly connected, Serial3/1
          172.16.1.2/32 is directly connected, Serial3/1
         172.16.32.0/24 is directly connected, Loopback0
          172.16.32.1/32 is directly connected, Loopback0
 SanJose2#
ISP(config)# interface serial 3/1
ISP(config-if)# no shutdown
ISP(config-if)#
ISP(config)#interface serial 3/1
ISP(config-if) #no shutdown
ISP(config-if)#
```

SanJose2# show ip route

```
SanJose2#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

El - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP

+ - replicated route, % - next hop override

Gateway of last resort is not set

172.16.0.0/16 is variably subnetted, 5 subnets, 3 masks

S 172.16.0.0/16 is directly connected, Null0

C 172.16.1.0/24 is directly connected, Serial3/1

L 172.16.1.2/32 is directly connected, Serial3/1

C 172.16.32.0/24 is directly connected, Loopback0

L 172.16.32.1/32 is directly connected, Loopback0

SanJose2#
```

Step 8: Set BGP local preference.

a. Because the local preference value is shared between IBGP neighbors, configure a simple route map that references the local preference value on SanJose1 and SanJose2. This policy adjusts outbound traffic to prefer the link off the SanJose1 router instead of the metered T1 off SanJose2.

SanJose1(config)# route-map PRIMARY_T1_IN permit 10

SanJose1(config-route-map)# set local-preference 150

SanJose1(config-route-map)# exit

SanJose1(config)# router bgp 64512

SanJose1(config-router)# neighbor 192.168.1.5 route-map PRIMARY_T1_IN in

```
SanJosel#CONF T
Enter configuration commands, one per line. End with CNTL/Z.

SanJosel(config)#route-map PRIMARY T1_IN permit 10

SanJosel(config-route-map)#set local-preference 150

SanJosel(config-route-map)#exit

SanJosel(config)#router bgp 64512

SanJosel(config-router)#neighbor 192.168.1.5 route-map PRIMARY_T1_IN in

SanJosel(config-router)#
```

SanJose2(config)# route-map SECONDARY_T1_IN permit 10

SanJose2(config-route-map)# set local-preference 125

SanJose1(config-route-map)# exit

SanJose2(config)# router bgp 64512

SanJose2(config-router)# neighbor 192.168.1.1 route-map SECONDARY T1 IN in

```
SanJose2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
SanJose2(config)#route-map SECONDARY_T1_IN permit 10
SanJose2(config-route-map)#set local-preference 125
SanJose2(config-route-map)#exit
SanJose2(config)#router bgp 64512
SanJose2(config-router)#neighbor 192.168.1.1 route-map SECONDARY_T1_IN in
SanJose2(config-router)#
```

Use the clear ip bgp * soft command after configuring this new policy. When the conversations have been reestablished, issue the show ip bgp command on SanJose1 and SanJose2.

SanJose1# clear ip bgp * soft

SanJose1#clear ip bgp * soft

SanJose2#
SanJose2# clear ip bgp * soft

SanJose2#clear ip bgp * soft

SanJose2#

SanJose1# show ip bgp

```
SanJosel#show ip bgp
BGP table version is 4, local router ID is 172.16.64.1
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal,
              r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter,
              x best-external, a additional-path, c RIB-compressed,
Origin codes: i - IGP, e - EGP, ? - incomplete
RPKI validation codes: V valid, I invalid, N Not found
     Network
                      Next Hop
                                          Metric LocPrf Weight Path
    172.16.0.0
                      0.0.0.0
                                                         32768 i
    192.168.100.0
                      192.168.1.5
                                                    150
                                                             0 200 i
SanJosel#
```

SanJose2# show ip bgp

```
SanJose2#show ip bgp

BGP table version is 2, local router ID is 172.16.32.1

Status codes: s suppressed, d damped, h history, * valid, > best, i - internal, r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter, x best-external, a additional-path, c RIB-compressed,

Origin codes: i - IGP, e - EGP, ? - incomplete

RPKI validation codes: V valid, I invalid, N Not found

Network Next Hop Metric LocPrf Weight Path

*> 172.16.0.0 0.0.0.0 0 32768 i

SanJose2#
```

Step 9: Set BGP MED.

In the previous step we saw that SanJose1 and SanJose2 will route traffic for 192.168.100.0/24 using the link between SanJose1 and ISP. Examine what the return path ISP takes to reach AS 64512. Notice that the return path is different from the original path. This is known as asymmetric routing and is not necessarily an unwanted trait.

```
ISP# show ip bgp
```

```
ISP#show ip bgp

BGP table version is 7, local router ID is 192.168.100.1

Status codes: s suppressed, d damped, h history, * valid, > best, i - internal, r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter, x best-external, a additional-path, c RIB-compressed,

Origin codes: i - IGP, e - EGP, ? - incomplete

RPKI validation codes: V valid, I invalid, N Not found

Network Next Hop Metric LocPrf Weight Path

*> 172.16.0.0 192.168.1.6 0 0 64512 i

*> 192.168.100.0 0.0.0.0 0 32768 i

ISP#
```

ISP# show ip route

Use an extended ping command to verify this situation. Specify the record option and compare your output to the following. Notice the return path using the exit interface 192.168.1.1 to SanJose2.

SanJose2# ping

Protocol [ip]:

Target IP address: 192.168.100.1
Repeat count [5]:
Datagram size [100]:
Timeout in seconds [2]:
Extended commands [n]: y
Source address or interface: 172.16.32.1
Type of service [0]:
Set DF bit in IP header? [no]:
Validate reply data? [no]:
Data pattern [0xABCD]:
Loose, Strict, Record, Timestamp, Verbose[none]: record
Number of hops [9]:
Loose, Strict, Record, Timestamp, Verbose[RV]:
Sweep range of sizes [n]:
Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 192.168.100.1, timeout is 2 seconds:

Packet sent with a source address of 172.16.32.1

Packet has IP options: Total option bytes= 39, padded length=40

Create a new policy to force the ISP router to return all traffic via SanJose1. Create a second route map utilizing the MED (metric) that is shared between EBGP neighbors.

SanJose1(config)#route-map PRIMARY_T1_MED_OUT permit 10

SanJose1(config-route-map)#set Metric 50

SanJose1(config-route-map)#exit

SanJose1(config)#router bgp 64512

SanJose1(config-router)#neighbor 192.168.1.5 route-map PRIMARY_T1_MED_OUT out

```
SanJosel#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
SanJosel(config)#route-map PRIMARY_T1_MED_OUT permit 10
SanJosel(config-route-map)#set Metric 50
SanJosel(config-route-map)#exit
SanJosel(config)#router bgp 64512
SanJosel(config-router)#neighbor 192.168.1.5 route-map PRIMARY_T1_MED_OUT out
SanJosel(config-router)#
```

SanJose2(config)#route-map SECONDARY T1 MED OUT permit 10

SanJose2(config-route-map)#set Metric 75

SanJose2(config-route-map)#exit

SanJose2(config)#router bgp 64512

SanJose2(config-router)#neighbor 192.168.1.1 route-map SECONDARY_T1_MED_OUT out

```
SanJose2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
SanJose2(config) #route-map SECONDARY_T1_MED_OUT permit 10
SanJose2(config-route-map) #set Metric 75
SanJose2(config-route-map) #exit
SanJose2(config) #router bgp 64512
SanJose2(config-router) #$2.168.1.1 route-map SECONDARY_T1_MED_OUT out
SanJose2(config-router) #
```

Use the clear ip bgp * soft command after issuing this new policy. Issuing the show ip bgp command as follows on SanJose1 or SanJose2 does not indicate anything about this newly defined policy.

```
SanJose1# clear ip bgp * soft
SanJose1#clear ip bgp * soft
SanJose2#
SanJose2# clear ip bgp * soft
SanJose2#clear ip bgp * soft
SanJose2#clear ip bgp * soft
```

SanJose1# show ip bgp

```
SanJosel#show ip bgp

BGP table version is 4, local router ID is 172.16.64.1

Status codes: s suppressed, d damped, h history, * valid, > best, i - internal, r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter, x best-external, a additional-path, c RIB-compressed,

Origin codes: i - IGP, e - EGP, ? - incomplete

RPKI validation codes: V valid, I invalid, N Not found

Network Next Hop Metric LocPrf Weight Path

*> 172.16.0.0 0.0.0.0 0 32768 i

*> 192.168.100.0 192.168.1.5 0 150 0 200 i

SanJosel#
```

SanJose2# show ip bgp

Reissue an extended ping command with the record command. Notice the change in return path using the exit interface 192.168.1.5 to SanJose1.

SanJose2# **ping** Protocol [ip]:

Target IP address: 192.168.100.1

Repeat count [5]:
Datagram size [100]:
Timeout in seconds [2]:
Extended commands [n]: y

Source address or interface: 172.16.32.1

Type of service [0]:

Set DF bit in IP header? [no]: Validate reply data? [no]:

Data pattern [0xABCD]:

Loose, Strict, Record, Timestamp, Verbose[none]: record

Number of hops [9]:

Loose, Strict, Record, Timestamp, Verbose[RV]:

```
Sweep range of sizes [n]:
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.100.1, timeout is 2 seconds:
Packet sent with a source address of 172.16.32.1
Packet has IP options: Total option bytes= 39, padded length=40
Record route: <*&gt;
(0.0.0.0)
(0.0.0.0)
(0.0.0.0)
(0.0.0.0)
(0.0.0.0)
(0.0.0.0)
(0.0.0.0)
(0.0.0.0)
(0.0.0.0)
 SanJose2#ping
 Protocol [ip]:
Target IP address: 192.168.100.1
Target IP address: 192.168.100.1
Repeat count [5]:
Datagram size [100]:
Timeout in seconds [2]:
Extended commands [n]: y
Source address or interface: 172.16.32.1
Type of service [0]:
Set DF bit in IP header? [no]:
Validate reply data? [no]:
Data pattern [0xABCD]:
Loose, Strict, Record, Timestamp, Verbose[none]: record
Number of hops [ 9 ]:
Loose, Strict, Record, Timestamp, Verbose[RV]:
Sweep range of sizes [n]:
  Sweep range of sizes [n]:

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 192.168.100.1, timeout is 2 seconds:
  acket sent with a source address of 172.16.32.1
acket has IP options: Total option bytes= 39, padded length=40
  Request 1 timed out
Request 2 timed out
Request 3 timed out
Request 4 timed out
              rate is 0 percent (0/5)
```

ISP# show ip bgp

```
ISP#show ip bgp

BGP table version is 8, local router ID is 192.168.100.1

Status codes: s suppressed, d damped, h history, * valid, > best, i - internal, r RIB-failure, S Stale, m multipath, b backup-path, f RT-Filter, x best-external, a additional-path, c RIB-compressed,

Origin codes: i - IGP, e - EGP, ? - incomplete

RPKI validation codes: V valid, I invalid, N Not found

Network Next Hop Metric LocPrf Weight Path

*> 172.16.0.0 192.168.1.6 50 0 64512 i

*> 192.168.100.0 0.0.0.0 0 32768 i

ISP#
```

Step 10: Establish a default route.

Configure ISP to inject a default route to both SanJose1 and SanJose2 using BGP using the default-originate command. This command does not require the presence of 0.0.0.0 in the ISP router. Configure the 10.0.0.0/8 network which will not be advertised using BGP. This network will be used to test the default route on SanJose1 and SanJose2.

ISP(config)# router bgp 200

ISP(config-router)# neighbor 192.168.1.6 default-originate ISP(config-router)# neighbor 192.168.1.2 default-originate ISP(config-router)# exit ISP(config)# interface loopback 10 ISP(config-if)# ip address 10.0.0.1 255.255.255.0 ISP(config-if)#

```
ISP#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
ISP(config) #router bgp 200
ISP(config-router) #neighbor 192.168.1.6 default-originate
ISP(config-router) #neighbor 192.168.1.2 default-originate
ISP(config-router) #exit
ISP(config) #interface loopback 10
ISP(config-if) #ip address 10.0.0.1 255.255.255.0
*Mar 17 12:59:38.343: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback10, changed state to up
ISP(config-if) #ip address 10.0.0.1 255.255.255.0
ISP(config-if) #ip address 10.0.0.1 255.255.255.0
```

SanJose1# show ip route

```
SamJosel#show ip Toute

SamJosel#show ip route

Codes: L - local, C - connected, S - static, R - RIF, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP

+ - replicated route, % - next hop override

Gateway of last resort is not set

172.16.0.0/16 is variably subnetted, 5 subnets, 3 masks

S 172.16.0.0/16 is directly connected, Null0

C 172.16.1.0/24 is directly connected, Serial3/1

L 172.16.1.1/32 is directly connected, Loopback0

L 172.16.64.1/32 is directly connected, Loopback0

192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks

192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks

192.168.1.4/30 is directly connected, Serial3/0

L 192.168.1.6/32 is directly connected, Serial3/0

B 192.168.1.6/32 is directly connected, Serial3/0

E 192.168.1.00.0/24 [20/0] via 192.168.1.5, 00:23:38

SamJosel#
```

SanJose2# show ip route

```
SanJose2#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

O - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP

+ - replicated route, % - next hop override

Gateway of last resort is not set

172.16.0.0/16 is variably subnetted, 5 subnets, 3 masks

S 172.16.0.0/16 is directly connected, Null0

C 172.16.1.0/24 is directly connected, Serial3/1

L 172.16.1.2/32 is directly connected, Serial3/1

C 172.16.32.0/24 is directly connected, Loopback0

L 172.16.32.1/32 is directly connected, Loopback0

SanJose2#
```

SanJose2# show ip bgp

```
SanJose2#show ip bgp
BGP table version is 2, local router ID is 172.16.32.1
Next Hop
                          Metric LocPrf Weight Path
                                   32768 i
SanJose2#
```

SanJose2# traceroute 10.0.0.1

ISP(config)# interface serial 3/0

ISP(config-if)# shutdown

```
SP(config-if) #shutdown
ISP(config-if)#
*Mar 17 13:02:36.151: %BGP-5-NBR RESET: Neighbor 192.168.1.6 reset (Interface fl
ap)
*Mar 17 13:02:36.167: %BGP-5-ADJCHANGE: neighbor 192.168.1.6 Down Interface flap
*Mar 17 13:02:36.167: %BGP_SESSION-5-ADJCHANGE: neighbor 192.168.1.6 IPv4 Unicas
t topology base removed from session Interface flap
ISP(config-if)#
*Mar 17 13:02:38.127: %LINK-5-CHANGED: Interface Serial3/0, changed state to adm
inistratively down
ISP(config-if)#
```

SanJose1# show ip route

```
elfshow ip route

L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static rout

o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
Sateway of last resort is 192.168.1.5 to network 0.0.0.0
                   172.16.0.0/16 is variably subnetted, 5 subnets, 3 masks 172.16.0.0/16 is directly connected, Null0
                             172.16.1.0/24 is directly connected, Serial3/1
172.16.1.1/24 is directly connected, Serial3/1
172.16.6.4.0/24 is directly connected, Loopback0
172.16.64.1/32 is directly connected, Loopback0
                  192.168.1.0/24 is directly connected, Loopbacku
192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks
192.168.1.4/30 is directly connected, Serial3/0
192.168.1.6/32 is directly connected, Serial3/0
192.168.100.0/24 [20/0] via 192.168.1.5, 00:26:36
```

SanJose2# show ip route

```
SanJose2#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

El - OSPF external type 1, E2 - OSPF external type 2
             i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level ia - IS-IS inter area, * - candidate default, U - per-user static r
             o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
             + - replicated route, % - next hop override
           172.16.0.0/16 is variably subnetted, 5 subnets, 3 masks 172.16.0.0/16 is directly connected, Null0
                172.16.1.0/24 is directly connected, Serial3/1 172.16.1.2/32 is directly connected, Serial3/1
                172.16.32.0/24 is directly connected, Loopback0
                172.16.32.1/32 is directly connected, Loopback0
SanJose2#
```

SanJose1# trace 10.0.0.1

```
SanJosel# trace 10.0.0.1

SanJosel#trace 10.0.0.1

Type sescape sequence to abort.


Tracing the route to 10.0.0.1

VRF info: (vrf in name/id, vrf out name/id)

1 * * *
2 * * *
3 * * * *
4 * * *
5 * * *
6 * * *
7 * * *
8 * * *
9 * * *
10 * *
11 * * *
11 * *
12 * * *
13 * * *
14 * * *
15 * * *
16 * * *
17 * * *
18 * * *
19 * * *
20 * * *
21 * * *
22 * * *
23 * * *
24 * * *
                  26
27
28
29
```

PRACTICAL NO: 04

AIM: Secure The Management Plane



Objective:

- Secure management access.
- Configure enhanced username password security.
- Enable AAA RADIUS authentication.
- Enable secure remote management.

Required Resourse

- 3 routers (Cisco IOS Release 15.2 or comparable)
- Serial and Ethernet cables

Step 1: Configure loopbacks and assign addresses.

Cable the network as shown in the topology diagram. Erase the startup configuration and reload each router to clear previous configurations. Using the addressing scheme in the diagram, apply the IP addresses to the interfaces on the R1, R2, and R3 routers.

Router R1

R1#CONF T

R1(config)#hostname R1

R1(config)#interface Loopback 0

R1(config-if)#description R1 LAN

R1(config-if)#ip address 192.168.1.1 255.255.255.0

R1(config-if)#

R1(config-if)#EXIT

R1(config)#interface Serial3/0

R1(config-if)#description R1 --> R2

```
R1(config-if)#ip address 10.1.1.1 255.255.255.252
R1(config-if)#clock rate 128000
```

R1(config-if)#no shutdown R1(config-if)#exit

R1(config)#end

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
Rl(config)#hostname Rl
Rl(config)#interface Loopback 0
Rl(config-if)#description Rl LAN
Rl(config-if)#ip address 192.168.1.1 255.255.255.0
R1(config-if)#
*Mar 20 12:28:52.843: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0,
 changed state to up
Rl(config-if)#EXIT
R1(config)#interface Serial3/0
R1(config-if) #description R1 --> R2
R1(config-if) #ip address 10.1.1.1 255.255.255.252
Rl(config-if)#clock rate 128000
Rl(config-if)#no shutdown
Rl(config-if)#exit
Rl(config)#end
 Mar 20 12:29:22.243: %LINK-3-UPDOWN: Interface Serial3/0, changed state to up
 R1 (config) #end
```

Router R2

R2#CONF T

R2(config)#hostname R2

R2(config)#interface Serial3/0

R2(config-if)#description R2 --> R1

R2(config-if)#ip address 10.1.1.2 255.255.255.252

R2(config-if)#no shutdown

R2(config-if)#exit

R2(config)#interface Serial3/1

R2(config-if)#description R2 --> R3

R2(config-if)#ip address 10.2.2.1 255.255.255.252

R2(config-if)#clock rate 128000

R2(config-if)#no shutdown

R2(config-if)#exit

R2(config)#end

```
R2#CONF T
Enter configuration commands, one per line.
                                             End with CNTL/Z.
R2(config)#hostname R2
R2(config)#interface Serial3/0
R2(config-if)#description R2 --> R1
R2(config-if)#ip address 10.1.1.2 255.255.255.252
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#interface Serial3/1
R2(config-if)#description R2 --> R3
R2(config-if)#ip address 10.2.2.1 255.255.255.252
R2(config-if)#clock rate 128000
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#end
R2#
```

Router R3

R3#CONF T

R3(config)#hostname R3

R3(config)#interface Loopback0

R3(config-if)#description R3 LAN

R3(config-if)#ip address 192.168.3.1 255.255.255.0

R3(config-if)#exit

R3(config)#interface Serial3/1

```
R3(config-if)#description R3 --> R2
```

R3(config-if)#ip address 10.2.2.2 255.255.255.252

R3(config-if)#no shutdown

R3(config-if)#exit

R3(config)#end

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#hostname R3
R3(config)#interface Loopback0
R3(config-if)#description R3 LAN
R3(config-if)#ip address 192.168.3.1 255.255.255.0
R3(config-if)#exit
R3(config)#interface Serial3/1
R3(config-if) #description R3 --> R2
R3(config-if)#ip address 10.2.2.2 255.255.255.252
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#end
Mar 20 12:39:35.323: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0
changed state to up
R3(config)#end
```

Step 2: Configure static routes.

a. On R1, configure a default static route to ISP.

R1(config)# ip route 0.0.0.0 0.0.0.0 10.1.1.2

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip route 0.0.0.0 0.0.0.0 10.1.1.2
R1(config)#
```

b. On R3, configure a default static route to ISP.

R3(config)# ip route 0.0.0.0 0.0.0.0 10.2.2.1

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#ip route 0.0.0.0 0.0.0.0 10.2.2.1
R3(config)#
```

c. On R2, configure two static routes.

R2(config)# ip route 192.168.1.0 255.255.255.0 10.1.1.1

R2(config)# ip route 192.168.3.0 255.255.255.0 10.2.2.2

```
R2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip route 192.168.1.0 255.255.255.0 10.1.1.1
R2(config)#ip route 192.168.3.0 255.255.255.0 10.2.2.2
R2(config)#
```

d. From the R1 router, run the following Tcl script to verify connectivity.

R1#tclsh

R1(tcl)#foreach address {

- +>(tcl)#192.168.1.1
- +>(tcl)#10.1.1.1
- +>(tcl)#10.1.1.2
- +>(tcl)#10.2.2.1
- +>(tcl)#10.2.2.2
- +>(tcl)#192.168.3.1
- +>(tcl)#} { ping \$address }

Step 3: Secure management access.

a. On R1, use the security passwords command to set a minimum password length of 10 characters. R1(config)# security passwords min-length 10

b. Configure the enable secret encrypted password on both routers.

R1(config)# enable secret class12345

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config) #security passwords min-length 10
R1(config) #enable secret class12345
R1(config) #
```

c. Configure a console password and enable login for routers. For additional security, the exec-timeout command causes the line to log out after 5 minutes of inactivity. The logging synchronous command prevents console messages from interrupting command entry.

R1(config)# line console 0

R1(config-line)# password ciscoconpass

R1(config-line)# exec-timeout 5 0

R1(config-line)# login

R1(config-line)# logging synchronous

R1(config-line)# exit

R1(config)#

```
R1(config) #line console 0
R1(config-line) #password ciscoconpass
R1(config-line) #exec-timeout 5 0
R1(config-line) #login
R1(config-line) #logging synchronous
R1(config-line) #exit
R1(config) #
```

d. Configure the password on the vty lines for router R1.

R1(config)# line vty 0 4

R1(config-line)# password ciscovtypass

R1(config-line)# exec-timeout 5 0

R1(config-line)# login

R1(config-line)# exit

R1(config)#

```
R1(config)#line vty 0 4
R1(config-line)#password ciscovtypass
R1(config-line)#exec-timeout 5 0
R1(config-line)#login
R1(config-line)#exit
```

e. The aux port is a legacy port used to manage a router remotely using a modem and is hardly ever used. Therefore, disable the aux port.

```
R1(config)# line aux 0
R1(config-line)# no exec
R1(config-line)# end
R1(config) # line aux 0
R1(config-line) # no exec
R1(config-line) # no exec
```

Use the service password-encryption command to encrypt the line console and vty passwords.

R1(config)# service password-encryption

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#service password-encryption
R1(config)#
```

Configure a warning to unauthorized users with a message-of-the-day (MOTD) banner using the banner motd command. When a user connects to one of the routers, the MOTD banner appears before the login prompt. In this example, the dollar sign (\$) is used to start and end the message.

R1(config)# banner motd \$Unauthorized access strictly prohibited!\$

R1(config)# exit

Step 4: Configure enhanced username password security.

To increase the encryption level of console and VTY lines, it is recommended to enable authentication using the local database. The local database consists of usernames and password combinations that are created locally on each device. The local and VTY lines are configured to refer to the local database when authenticating a user.

a. To create local database entry encrypted to level 4 (SHA256), use the username name secret password global configuration command. In global configuration mode, enter the following command:

R1(config)# username JR-ADMIN secret class12345 R1(config)# username ADMIN secret class54321

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config) #username JR-ADMIN secret class12345
R1(config) #username ADMIN secret class54321
R1(config)#
```

b. Set the console line to use the locally defined login accounts.

```
R1(config)# line console 0
R1(config-line)# login local
```

R1(config-line)# exit

```
R1(config)#line console 0
R1(config-line)#login local
R1(config-line)#exit
R1(config)#
```

c. Set the vty lines to use the locally defined login accounts.

R1(config)# line vty 0 4 R1(config-line)# login local R1(config-line)# end

```
R1(config)#
R1(config)#line vty 0 4
R1(config-line)#login local
R1(config-line)#end
R1#
```

d. To create local database entry encrypted to level 4 (SHA256), use the username name secret password global configuration command. In global configuration mode, enter the following command:

R3(config)# username JR-ADMIN secret class12345

R3(config)# username ADMIN secret class54321

```
R3(config)#username JR-ADMIN secret class12345
R3(config)#username ADMIN secret class54321
R3(config)#
```

Set the console line to use the locally defined login accounts.

R3(config)# line console 0 R3(config-line)# login local

R3(config-line)# exit

```
R3(config)#line console 0
R3(config-line)#login local
R3(config-line)#exit
R3(config)#
```

Set the vty lines to use the locally defined login accounts.

R3(config)# line vty 0 4 R3(config-line)# login local R3(config-line)# end

R3(config-line)# end

```
R3(config)#line vty 0 4
R3(config-line)#login local
R3(config-line)#end
R3#
```

e. To verify the configuration, telnet to R3 from R1 and login using the ADMIN local database account.

R1# telnet 10.2.2.2

Trying 10.2.2.2 ... Open

Unauthorized access strictly prohibited!

User Access Verification Username: ADMIN

Password: R3>

```
Rl#telnet 10.2.2.2
Trying 10.2.2.2 ... Open

User Access Verification

Username: ADMIN
Password:
% Login invalid

Username: ADMIN
Password:
R3>
```

Step 5: Enabling AAA RADIUS Authentication with Local User for Backup.

Authentication, authorization, and accounting (AAA) is a standards-based framework that can be implemented to control who is permitted to access a network (authenticate), what they can do on that network (authorize), and audit what they did while accessing the network (accounting).

a. Always have local database accounts created before enabling AAA. Since we created two local database accounts in the previous step, then we can proceed and enable AAA on R1.

R1(config)# aaa new-model

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config) #aaa new-model
R1(config) #
```

b. Configure the specifics for the first RADIUS server located at 192.168.1.101. Use RADIUS-1-pa55w0rd as the server password.

R1(config)# radius server RADIUS-1

R1(config-radius-server)# address ipv4 192.168.1.101

R1(config-radius-server)# key RADIUS-1-pa55w0rd

R1(config-radius-server)# exit

```
Rl(config) #radius server RADIUS-1
Rl(config-radius-server) #address ipv4 192.168.1.101
Rl(config-radius-server) #key RADIUS-1-pa55w0rd
Rl(config-radius-server) #exit
Rl(config) #
```

c. Configure the specifics for the second RADIUS server located at 192.168.1.102. Use RADIUS-2-pa55w0rd as the server password.

R1(config)# radius server RADIUS-2

R1(config-radius-server)# address ipv4 192.168.1.102

R1(config-radius-server)# key RADIUS-2-pa55w0rd

R1(config-radius-server)# exit

```
R1(config) #radius server RADIUS-2
R1(config-radius-server) #address ipv4 192.168.1.102
R1(config-radius-server) #key RADIUS-2-pa55w0rd
R1(config-radius-server) #exit
R1(config) #
```

d. Assign both RADIUS servers to a server group.

R1(config)# aaa group server radius RADIUS-GROUP

R1(config-sg-radius)# server name RADIUS-1

R1(config-sg-radius)# server name RADIUS-2

R1(config-sg-radius)# exit

```
Rl(config) #aaa group server radius RADIUS-GROUP
Rl(config-sg-radius) #server name RADIUS-1
Rl(config-sg-radius) #server name RADIUS-2
Rl(config-sg-radius) #exit
Rl(config) #
```

e. Enable the default AAA authentication login to attempt to validate against the server group. If they are not available, then authentication should be validated against the local database..

R1(config)# aaa authentication login default group RADIUS-GROUP local

```
Rl(config) #aaa authentication login default group RADIUS-GROUP local
Rl(config) #
```

f. Enable the default AAA authentication Telnet login to attempt to validate against the server group. If they are not available, then authentication should be validated against a case sensitive local database. R1(config)# aaa authentication login TELNET-LOGIN group RADIUS-GROUP local-case

```
Rl(config)#$ication login TELNET-LOGIN group RADIUS-GROUP local-case
Rl(config)#
```

g. Alter the VTY lines to use the TELNET-LOGIN AAA authentiaito0n method.

R1(config)# line vty 0 4

R1(config-line)# login authentication TELNET-LOGIN

R1(config-line)# exit

```
Rl(config)#line vty 0 4
Rl(config-line)#login authentication TELNET-LOGIN
Rl(config-line)#exit
Rl(config)#
```

h. Always have local database accounts created before enabling AAA. Since we created two local database accounts in the previous step, then we can proceed and enable AAA on R1.

R3(config)# aaa new-model

```
R3#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#aaa new-model
```

Configure the specifics for the first RADIUS server located at 192.168.1.101. Use RADIUS-1-pa55w0rd as the server password.

R3(config)# radius server RADIUS-1

R3(config-radius-server)# address ipv4 192.168.1.101

R3(config-radius-server)# key RADIUS-1-pa55w0rd

R3(config-radius-server)# exit

```
R3(config) #aaa new-model
R3(config) #radius server RADIUS-1
R3(config-radius-server) #address ipv4 192.168.1.101
R3(config-radius-server) #key RADIUS-1-pa55w0rd
R3(config-radius-server) #exit
R3(config) #
```

Configure the specifics for the second RADIUS server located at 192.168.1.102. Use RADIUS-2-pa55w0rd as the server password.

R3(config)# radius server RADIUS-2

R3(config-radius-server)# address ipv4 192.168.1.102

R3(config-radius-server)# key RADIUS-2-pa55w0rd

R3(config-radius-server)# exit

```
R3(config) #radius server RADIUS-2
R3(config-radius-server) #address ipv4 192.168.1.102
R3(config-radius-server) #key RADIUS-2-pa55w0rd
R3(config-radius-server) #exit
R3(config) #
```

Assign both RADIUS servers to a server group.

R3(config)# aaa group server radius RADIUS-GROUP

R3(config-sg-radius)# server name RADIUS-1

R3(config-sg-radius)# server name RADIUS-2

R3(config-sg-radius)# exit

```
R3(config) #aaa group server radius RADIUS-GROUP
R3(config-sg-radius) #server name RADIUS-1
R3(config-sg-radius) #server name RADIUS-2
R3(config-sg-radius) #exit
R3(config) #
```

Enable the default AAA authentication login to attempt to validate against the server group. If they are not available, then authentication should be validated against the local database..

R3(config)# aaa authentication login default group RADIUS-GROUP local

```
R3(config) #aaa authentication login default group RADIUS-GROUP local
R3(config) #
```

Enable the default AAA authentication Telnet login to attempt to validate against the server group. If they are not available, then authentication should be validated against a case sensitive local database.

R3(config)# aaa authentication login TELNET-LOGIN group RADIUS-GROUP local-case

```
R3(config)#$ication login TELNET-LOGIN group RADIUS-GROUP local-case
R3(config)#
```

Alter the VTY lines to use the TELNET-LOGIN AAA authentiaito0n method.

R3(config)# line vty 0 4

R3(config-line)# login authentication TELNET-LOGIN

R3(config-line)# exit

```
R3(config)#line vty 0 4
R3(config-line)#login authentication TELNET-LOGIN
R3(config-line)#exit
```

i. To verify the configuration, telnet to R3 from R1 and login using the ADMIN local database account.

R1# telnet 10.2.2.2 Username: ADMIN Password: class54321

```
R1#telnet 10.2.2.2
Trying 10.2.2.2 ... Open
User Access Verification
Username: ADMIN
Password:
% Authentication failed
Username: ADMIN
Password:
R3>
```

Step 6: Enabling secure remote management using SSH.

Traditionally, remote access on routers was configured using Telnet on TCP port 23. However, Telnet was developed in the days when security was not an issue; therefore, all Telnet traffic is forwarded in plaintext. Secure Shell (SSH) is a network protocol that establishes a secure terminal emulation connection to a router or other networking device. SSH encrypts all information that passes over the network link and provides authentication of the remote computer. SSH is rapidly replacing Telnet as the remote login tool of choice for network professionals.

a. SSH requires that a device name and a domain name be configured. Since the router already has a name assigned, configure the domain name.

```
R1(config)# ip domain-name ccnasecurity.com
```

```
Rl#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Rl(config)#ip domain-name conasecurity.com
Rl(config)#
```

b. The router uses the RSA key pair for authentication and encryption of transmitted SSH data. Although optional it may be wise to erase any existing key pairs on the router.

R1(config)# crypto key zeroize rsa

```
Rl(config)#crypto key zeroize rsa
% No Signature Keys found in configuration.
```

c. Generate the RSA encryption key pair for the router. Configure the RSA keys with 1024 for the number of modulus bits. The default is 512, and the range is from 360 to 2048.

R1(config)# crypto key generate rsa general-keys modulus 1024

```
R1(config) #crypto key generate rsa general-keys modulus 1024
The name for the keys will be: R1.ccnasecurity.com

% The key modulus size is 1024 bits
% Generating 1024 bit RSA keys, keys will be non-exportable...
[OK] (elapsed time was 1 seconds)

R1(config) #

*Mar 21 12:42:14.439: %SSH-5-ENABLED: SSH 1.99 has been enabled
R1(config) #
```

d. Cisco routers support two versions of SSH:

R1(config)# ip ssh version 2

```
Rl(config)#ip ssh version 2
Rl(config)#<mark>|</mark>
```

e. Configure the vty lines to use only SSH connections.

R1(config)# line vty 0 4

R1(config-line)# transport input ssh

R1(config-line)# end

```
Rl(config)#line vty 0 4
Rl(config-line)#transport input ssh
Rl(config-line)#end
Rl#
```

f. Verify the SSH configuration using the show ip ssh command.

R1# show ip ssh

```
Rl#show ip ssh

SSH Enabled - version 2.0

Authentication timeout: 120 secs; Authentication retries: 3

Minimum expected Diffie Hellman key size : 1024 bits

IOS Keys in SECSH format(ssh-rsa, base64 encoded):

ssh-rsa AAAAB3NzaClyc2EAAAADAQABAAAAgQDLPSfbpHMLEQXjxJDwWSoQ/NKG0DlNaDNCGPaldg14

U/kGKDOT1WDLGbPewfqoeWTcLeL6VDyXcAX8XWJ3WffBn0/ywecW4gihhX8kqp7QuGEW0Vrb0iFCczIu

Tzv8o5TKbnmpgGDjzpnuOGClLGHqgVO1ZXpDLdTL2q31NDAOsw==

R1#
```

g. SSH requires that a device name and a domain name be configured. Since the router already has a name assigned, configure the domain name.

R3(config)# ip domain-name ccnasecurity.com

```
R3(config) #ip domain-name conasecurity.com
```

The router uses the RSA key pair for authentication and encryption of transmitted SSH data. Although optional it may be wise to erase any existing key pairs on the router.

R3(config)# crypto key zeroize rsa

```
R3(config)#crypto key zeroize rsa
% No Signature Keys found in configuration.
```

Generate the RSA encryption key pair for the router. Configure the RSA keys with 1024 for the number of modulus bits. The default is 512, and the range is from 360 to 2048.

R3(config)# crypto key generate rsa general-keys modulus 1024

```
R3(config) #crypto key generate rsa general-keys modulus 1024
The name for the keys will be: R3.ccnasecurity.com

% The key modulus size is 1024 bits
% Generating 1024 bit RSA keys, keys will be non-exportable...
[OK] (elapsed time was 0 seconds)

R3(config) #

*Mar 21 12:50:29.823: %SSH-5-ENABLED: SSH 1.99 has been enabled
R3(config)#
```

Cisco routers support two versions of SSH:

R3(config)# ip ssh version 2

```
R3(config)#ip ssh version 2
R3(config)#
```

Configure the vty lines to use only SSH connections.

R3(config)# line vty 0 4

R3(config-line)# transport input ssh

R3(config-line)# end

```
R3(config)#line vty 0 4
R3(config-line)#transport input ssh
R3(config-line)#end
R3#
```

Verify the SSH configuration using the show ip ssh command.

R3# show ip ssh

```
R3#show ip ssh

SSH Enabled - version 2.0

Authentication timeout: 120 secs; Authentication retries: 3

Minimum expected Diffie Hellman key size : 1024 bits

IOS Keys in SECSH format(ssh-rsa, base64 encoded):

ssh-rsa AAAAB3NzaClyc2EAAAADAQABAAAAgQCUllXlGjSlihj+LunLsKM28wu4RQOSUNqJ6i3

Tf6I0

8L5Z3dv2wnJkxkQ45s/3u3mv5Os5OF7nZ42filU+pGd5CrHxIytdNBuak/dbxFRPy76bW/bq14q

BLhcS

IAq3shHDd7vel3G2CPiK44ZHC41G5xxq85Al8BQR9GoV+8/rvw==
```

h. Although a user can SSH from a host using the SSH option of TeraTerm of PuTTY, a router can also SSH to another SSH enabled device. SSH to R3 from R1.

R1# ssh -1 ADMIN 10.2.2.2

Password:

R3>

R3>en

% Error in authentication.

R3>

```
R1#ssh -1 ADMIN 10.2.2.2
Password:
R3>
R3>en
% Error in authentication.
```

Router R1

R1#CONF T

R1(config)#service password-encryption

R1(config)#hostname R1

R1(config)#security passwords min-length 10

R1(config)#enable secret 5 \$1\$t6eK\$FZ.JdmMLj8QSgNkpChyZz.

R1(config)#aaa new-model

R1(config)#aaa group server radius RADIUS-GROUP

R1(config-sg-radius)#server name RADIUS-1

R1(config-sg-radius)#server name RADIUS-2

R1(config-sg-radius)#\$ication login default group RADIUS-GROUP local

R1(config)#\$ication login TELNET-LOGIN group RADIUS-GROUP local-case

R1(config)#ip domain name ccnasecurity.com

R1(config)#username JR-ADMIN secret 5 \$1\$0u0q\$lwimCZIAuQtV4C1ezXL1S0

R1(config)#username ADMIN secret 5 \$1\$NSVD\$/YjzB7Auyes1sAt4qMfpd.

R1(config)#ip ssh version 2

R1(config)#interface Loopback0

R1(config-if)#description R1 LAN

R1(config-if)#ip address 192.168.1.1 255.255.255.0

R1(config-if)#interface Serial3/0

R1(config-if)#description R1 --> R2

R1(config-if)#ip address 10.1.1.1 255.255.255.252

R1(config-if)#no fair-queue

R1(config-if)#ip route 0.0.0.0 0.0.0.0 10.1.1.2

R1(config)#radius server RADIUS-1

R1(config-radius-server)#\$4 192.168.1.101 auth-port 1645 acct-port 1646

R1(config-radius-server)#key 7 107C283D2C2221465D493A2A717D24653017

R1(config-radius-server)#radius server RADIUS-2

R1(config-radius-server)#\$4 192.168.1.102 auth-port 1645 acct-port 1646

R1(config-radius-server)#key 7 03367A2F2F3A12011C44090442471C5C162E

R1(config-radius-server)#\$ ^CUnauthorized access strictly prohibited!^C

R1(config)#line con 0

R1(config-line)#exec-timeout 5 0

R1(config-line)#password 7 070C285F4D061A0A19020A1F17

R1(config-line)#logging synchronous

R1(config-line)#line aux 0

R1(config-line)#no exec

R1(config-line)#password 7 060506324F411F0D1C0713181F

R1(config-line)#login authentication TELNET-LOGIN

R1(config-line)#transport input ssh

R1(config-line)#end

```
RI#CONF T

Enter configuration commands, one per line. End with CNTL/Z.

RI(config) #service password-encryption
RI(config) #hostname RI
RI(config) #security passwords min-length 10
(RI(config) #enable secret 5 $1$t6eK$FZ.JdmMLj8Q$GNkpChyZz.
RI(config) #aaa new-model
RI(config) #aaa group server radius RADIUS-GROUP
RI(config-sq-radius) #server name RADIUS-1
RI(config-sq-radius) #server name RADIUS-1
RI(config-sq-radius) #server name RADIUS-1
RI(config) #jo domain name consecurity.com
RI(config) #security domain name consecurity.com
RI(config) #sername ADMIN secret 5 $1$0u0q$lwimcZIAuqtV4ClezXLISO
RI(config-if) #inderes 10.1.1.1 255.255.255.255.2
RI(config-if) #inderes 10.1.1.1 255.255.255.2
RI(config-if) #inderes 10.1.1.1 255.255.255.2
RI(config-if) #inderes 10.1.1.1 255.255.255.2
RI(config-if) #inderes 10.1.1.1 255.255.255.2
RI(config-radius-server) #sq 192.168.1.101 auth-port 1645 acct-port 1646
RI(config-radius-server) #sq 192.168.1.102 auth-port 1645 acct-port 1646
RI(config-radius-server) #sq 7 070c285F4D61A0A19020A1F17
RI(config-radius-server) #sq 7 070c285F4D61A0A19020A1F17
RI(config-li
```

Router R2

R2(config)#hostname R2

R2(config)#enable secret 5 \$1\$DJS7\$xvJDW87zLs8pSJDFUlCPB1

R2(config)#interface Serial3/0

R2(config-if)#description R2 --> R1

R2(config-if)#ip address 10.1.1.2 255.255.255.252

R2(config-if)#no fair-queue

R2(config-if)#clock rate 2000000

R2(config-if)#interface Serial3/1

R2(config-if)#description R2 --> R3

R2(config-if)#ip address 10.2.2.1 255.255.255.252

R2(config-if)#clock rate 128000

R2(config-if)#ip route 192.168.1.0 255.255.255.0 10.1.1.1

R2(config)#ip route 192.168.3.0 255.255.255.0 10.2.2.2

R2(config)#line con 0

R2(config-line)#exec-timeout 0 0

R2(config-line)#logging synchronous

R2(config-line)#line vty 0 4

R2(config-line)#password cisco

R2(config-line)#login

R2(config-line)#end

```
R2(config)#hostname R2
R2(config)#enable secret 5 $1$DJS7$xvJDW87zLs8pSJDFUlCPB1
R2(config)#interface Serial3/0
R2(config-if)#description R2 --> R1
R2(config-if)#ip address 10.1.1.2 255.255.255.252
R2(config-if)#no fair-queue
  Invalid input detected at '^' marker.
R2(config-if)#clock rate 2000000
%Clockrate bestfitted (rounded) to 2016000
R2(config-if)#interface Serial3/1
R2(config-if)#description R2 --> R3
R2(config-if)#ip address 10.2.2.1 255.255.255.252
R2(config-if)#clock rate 128000
R2(config-if)#ip route 192.168.1.0 255.255.255.0 10.1.1.1
R2(config) #ip route 192.168.3.0 255.255.255.0 10.2.2.2
R2(config)#line con 0
R2(config-line)#exec-timeout 0 0
R2(config-line)#logging synchronous
R2(config-line)#line vty 0 4
R2(config-line)#password cisco
R2(config-line)#login
R2(config-line)#end
```

Router R3

R3(config)#service password-encryption

R3(config)#hostname R3

R3(config)#security passwords min-length 10

R3(config)#enable secret 5 \$1\$5OY4\$4J6VFlvGNKjwQ8XtajgUk1

R3(config)#aaa new-model

R3(config)#aaa group server radius RADIUS-GROUP

R3(config-sg-radius)#server name RADIUS-1

R3(config-sg-radius)#server name RADIUS-2

R3(config-sg-radius)#\$ication login default group RADIUS-GROUP local

OUP local R3(config)#\$ication login R3(config)#ip domain name cenasecurity.com

TELNET-LOGIN group RADIUS-GROUP local-case R3(config)#ip don R3(config)#username JR-ADMIN secret 5 \$1\$b4m1\$RVmjL9S3gxKh1xr8qzNqr/

R3(config)#username ADMIN secret 5 \$1\$zGV7\$pVgSEbinvXQ7f7uyxeKBj0

R3(config)#ip ssh version 2

R3(config)#interface Loopback0

R3(config-if)#description R3 LAN

R3(config-if)#ip address 192.168.3.1 255.255.255.0

R3(config-if)#interface Serial3/1

R3(config-if)#description R3 --> R2

R3(config-if)#ip address 10.2.2.2 255.255.255.252

R3(config-if)#ip route 0.0.0.0 0.0.0.0 10.2.2.1

R3(config)#radius server RADIUS-1

R3(config-radius-server)#\$4 192.168.1.101 auth-port 1645 acct-port 1646

R3(config-radius-server)#key 7 01212720723E354270015E084C5000421908

R3(config-radius-server)#radius server RADIUS-2

R3(config-radius-server)#\$4 192.168.1.102 auth-port 1645 acct-port 1646

R3(config-radius-server)#key 7 003632222D6E384B5D6C5C4F5C4C1247000F

R3(config-radius-server)#\$ ^CUnauthorized access strictly prohibited!^C

R3(config)#line con 0

R3(config-line)#exec-timeout 5 0

R3(config-line)#password 7 104D000A0618110402142B3837

R3(config-line)#logging synchronous

R3(config-line)#line aux 0

R3(config-line)#no exec

R3(config-line)#line vty 0 4

R3(config-line)#exec-timeout 5 0

R3(config-line)#password 7 070C285F4D060F110E020A1F17

R3(config-line)#login authentication TELNET-LOGIN


R3(config-line)#transport input ssh

R3(config-line)#end

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config) #service password-encryption
R3(config) #service passwords min-length 10
R3(config) #security passwords min-length 10
R3(config) #seaurity passwords min-length 10
R3(config) #seaurity passwords min-length 10
R3(config) #seau new-model
R3(config) #seau new-model
R3(config) #seaurity passwords mane RADIUS-GROUP
R3(config-sq-radius) #server name RADIUS-1
R3(config-sq-radius) #server name RADIUS-2
R3(config-sq-radius) #server name RADIUS-2
R3(config-sq-radius) #server name RADIUS-GROUP local
R3(config) #sication login TELNET-LOGIN group RADIUS-GROUP local
R3(config) #sication login TELNET-LOGIN group RADIUS-GROUP local-case
R3(config) #sication login TELNET-LOGIN R3(config) #sication login TELNET-LOGIN R3(config) #sication login TELNET-LOGIN
R3(config-if) #sication login TELNET-LOGIN
R3(config-radius-server) #sication login TELNET-LOGIN
R3(config-line) #password 7 0700285F4D060F110E020A1F17
R3(config-line) #transport input ssh
R3(config-line) #transport input ssh
R3(config-line) #transport input ssh
```

PRACTICAL NO: 05

AIM: Configure And Verify Path Control Using Pbr



Step 1: Configure loopbacks and assign addresses.

a. Cable the network as shown in the topology diagram. Erase the startup configuration, and reload each router to clear previous configurations.

b. Using the addressing scheme in the diagram, create the loopback interfaces and apply IP addresses to these and the serial interfaces on R1, R2, R3, and R4. On the serial interfaces connecting R1 to R3 and R3 to R4, specify the bandwidth as 64 Kb/s and set a clock rate on the DCE using the clock rate 64000 command. On the serial interfaces connecting R1 to R2 and R2 to R3, specify the bandwidth as 128 Kb/s and set a clock rate on the DCE using the clock rate 128000 command.

Router R1

R1#CONF T

R1(config)#hostname R1

R1(config)#interface Lo1

R1(config-if)#description R1 LAN

R1(config-if)#ip address 192.168.1.1 255.255.255.0

R1(config-if)#interface Serial3/0

R1(config-if)#description R1 --> R2

R1(config-if)#ip address 172.16.12.1 255.255.255.248

R1(config-if)#clock rate 128000

R1(config-if)#bandwidth 128

R1(config-if)#no shutdown

R1(config-if)#interface Serial3/1

R1(config-if)#description R1 --> R3

R1(config-if)#ip address 172.16.13.1 255.255.255.248

R1(config-if)#bandwidth 64

R1(config-if)#no shutdown

R1(config-if)#end

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#hostname R1
R1(config)#interface Lo1
R1(config-if)#description R1 LAN
R1(config-if)#ip address 192.168.1.1 255.255.255.0
R1(config-if)#interface Serial3/0
R1(config-if)#description R1 --> R2
R1(config-if)#ip address 172.16.12.1 255.255.255.248
R1(config-if)#clock rate 128000
R1(config-if)#bandwidth 128
R1(config-if)#no shutdown
R1(config-if)#interface Serial3/1
R1(config-if)#description R1 --> R3
R1(config-if)#description R1 --> R3
R1(config-if)#bandwidth 64
R1(config-if)#no shutdown
R1(config-if)#no shutdown
R1(config-if)#no shutdown
R1(config-if)#no shutdown
R1(config-if)#no shutdown
R1(config-if)#no shutdown
```

Router R2

R2#CONF T

R2(config)#hostname R2

R2(config)#interface Lo2

R2(config-if)#description R2 LAN

R2(config-if)#ip address 192.168.2.1 255.255.255.0

R2(config-if)#interface Serial3/0

R2(config-if)#description R2 --> R1

R2(config-if)#ip address 172.16.12.2 255.255.255.248

R2(config-if)#bandwidth 128

R2(config-if)#no shutdown

R2(config-if)#interface Serial3/1

R2(config-if)#description R2 --> R3

R2(config-if)#ip address 172.16.23.2 255.255.255.248

R2(config-if)#clock rate 128000

R2(config-if)#bandwidth 128

R2(config-if)#no shutdown

R2(config-if)#end

```
R2#CONF 7
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#hostname R2
R2(config)#interface Lo2
R2(config-if)#description R2 LAN
R2(config-if)#ip address 192.168.2.1 255.255.255.0
R2(config-if)#interface Serial3/0
R2(config-if)#description R2 --> R1
R2(config-if)#ip address 172.16.12.2 255.255.255.248
R2(config-if)#bandwidth 128
R2(config-if)#no shutdown
R2(config-if)#interface Serial3/1
R2(config-if)#description R2 --> R3
R2(config-if)#ip address 172.16.23.2 255.255.255.248
R2(config-if)#clock rate 128000
R2(config-if)#bandwidth 128
R2(config-if)#no shutdown
R2(config-if)#end
```

Router R3

R3#CONF T

R3(config)#hostname R3

R3(config)#interface Lo3

R3(config-if)#description R3 LAN

R3(config-if)#ip address 192.168.3.1 255.255.255.0

R3(config-if)#interface Serial3/0

R3(config-if)#description R3 --> R1

R3(config-if)#ip address 172.16.13.3 255.255.255.248

R3(config-if)#clock rate 64000

R3(config-if)#bandwidth 64

R3(config-if)#no shutdown

R3(config-if)#interface Serial3/1

R3(config-if)#description R3 --> R2

R3(config-if)#ip address 172.16.23.3 255.255.255.248

R3(config-if)#bandwidth 128

R3(config-if)#no shutdown

R3(config-if)#interface Serial3/2

R3(config-if)#description R3 --> R4

R3(config-if)#ip address 172.16.34.3 255.255.255.248

R3(config-if)#clock rate 64000

R3(config-if)#bandwidth 64

R3(config-if)#no shutdown

R3(config-if)#end

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#hostname R3
R3(config)#interface Lo3
R3(config-if)#description R3 LAN
R3(config-if)#ip address 192.168.3.1 255.255.255.0
R3(config-if)#ip address 192.16.13.3 255.255.255.248
R3(config-if)#ap address 172.16.13.3 255.255.255.248
R3(config-if)#lp address 172.16.13.3 255.255.255.248
R3(config-if)#lock rate 64000
R3(config-if)#bandwidth 64
R3(config-if)#hon shutdown
R3(config-if)#description R3 --> R2
R3(config-if)#description R3 --> R2
R3(config-if)#p address 172.16.23.3 255.255.255.248
R3(config-if)#p address 172.16.23.3 255.255.255.248
R3(config-if)#hon shutdown
R3(config-if)#hon shutdown
R3(config-if)#description R3 --> R4
R3(config-if)#description R3 --> R4
R3(config-if)#jp address 172.16.34.3 255.255.255.248
R3(config-if)#bandwidth 64
R3(config-if)#bandwidth 64
R3(config-if)#bandwidth 64
R3(config-if)#bandwidth 64
R3(config-if)#no shutdown
R3(config-if)#no shutdown
R3(config-if)#no shutdown
R3(config-if)#no shutdown
```

Router R4

R4#CONF T

Enter configuration commands, one per line. End with CNTL/Z.

R4(config)#hostname R4

R4(config)#interface Lo4

R4(config-if)#description R4 LAN A

R4(config-if)#ip address 192.168.4.1 255.255.255.128

R4(config-if)#interface Lo5

R4(config-if)#description R4 LAN B

R4(config-if)#ip address 192.168.4.129 255.255.255.128

R4(config-if)#interface Serial3/2

R4(config-if)#description R4 --> R3

R4(config-if)#ip address 172.16.34.4 255.255.255.248

R4(config-if)#bandwidth 64

R4(config-if)#no shutdown

R4(config-if)#end

```
R4#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R4(config)#hostname R4
R4(config)#interface Lo4
R4(config-if)#description R4 LAN A
R4(config-if)#ip address 192.168.4.1 255.255.255.128
R4(config-if)#interface Lo5
R4(config-if)#description R4 LAN B
R4(config-if)#ip address 192.168.4.129 255.255.255.128
R4(config-if)#interface Serial3/2
R4(config-if)#description R4 --> R3
R4(config-if)#description R4 --> R3
R4(config-if)#interface Serial3/2
R4(config-if)#bandwidth 64
R4(config-if)#bandwidth 64
R4(config-if)#no shutdown
R4(config-if)#end
```

c. Verify the configuration with the show ip interface brief, show protocols, and show interfaces description commands. The output from router R3 is shown here as an example.

```
R3# show ip interface brief
Interface IP-Address
GigabitEthernet2/0 unassigned YES unset administratively down down
Serial3/0 172.16.13.3 YES manual up up
Serial3/2 172.16.34.3 YES manual up up
Serial3/3 unassigned YES unset administratively down down
FastEthernet4/0 unassigned YES unset administratively down down
FastEthernet4/1 unassigned YES unset administratively down down
Ethernet5/1 unassigned YES unset administratively down down
Ethernet5/2 unassigned YES unset administratively down down
Ethernet6/0 unassigned YES unset administratively down down
Ethernet6/1 unassigned YES unset administratively down down
Ethernet6/2 unassigned YES unset administratively down down
Ethernet6/3 unassigned YES unset administratively down down
Ethernet6/4 unassigned YES unset administratively down down
Ethernet6/5 unassigned YES unset administratively down down
Ethernet6/6 unassigned YES unset administratively down down
Ethernet6/7 unassigned YES unset administratively down down
Ethernet6/6 unassigned YES unset administratively down down
Ethernet6/7 unassigned YES unset administratively down down
Ethernet6/8 unassigned YES unset administratively down down
Ethernet6/9 unassigned YES unset administratively down down
Ethernet6/9 unassigned YES unset administratively down down
```

R3# show protocols

```
R3#show protocols
Global values:
    Internet Protocol routing is enabled
FastEthernet0/0 is administratively down, line protocol is down
GigabitEthernet2/0 is administratively down, line protocol is down
Serial3/0 is up, line protocol is up
    Internet address is 172.16.13.3/29
Serial3/1 is up, line protocol is up
    Internet address is 172.16.23.3/29
Serial3/2 is up, line protocol is up
    Internet address is 172.16.34.3/29
Serial3/3 is administratively down, line protocol is down
FastEthernet4/0 is administratively down, line protocol is down
Ethernet5/0 is administratively down, line protocol is down
Ethernet5/1 is administratively down, line protocol is down
Ethernet5/3 is administratively down, line protocol is down
Ethernet6/0 is administratively down, line protocol is down
Ethernet6/1 is administratively down, line protocol is down
Ethernet6/1 is administratively down, line protocol is down
Ethernet6/1 is administratively down, line protocol is down
Ethernet6/2 is administratively down, line protocol is down
Ethernet6/3 is administratively down, line protocol is down
Ethernet6/3 is administratively down, line protocol is down
Ethernet6/3 is administratively down, line protocol is down
Ethernet6/5 is administratively down, line protocol is down
```

R3# show interfaces description

```
        R3#show interfaces description

        Interface
        Status
        Protocol
        Description

        Fa0/0
        admin down
        down

        6i2/0
        admin down
        down

        Se3/0
        up
        up
        R3 --> R1

        Se3/1
        up
        up
        R3 --> R4

        Se3/2
        up
        up
        R3 --> R4

        Se3/3
        admin down
        down
        Admin down
        down

        Fa4/0
        admin down
        down
        Admin down
        down

        Fa5/2
        admin down
        down
        Admin down
        down

        Et5/2
        admin down
        down
        Admin down
        down

        Et6/3
        admin down
        down
        Admin down
        down

        Et6/2
        admin down
        down
        Admin down
        Adwin down

        Et6/5
        admin down
        down
        Admin down
        Adwin down

        Et6/6
        admin down
        down
        Admin down
        Adwin down

        Et6/6
        admin down
        down
        Admin down
        Adwin down

        Et6/6<
```

Step 3: Configure basic EIGRP.

a. Implement EIGRP AS 1 over the serial and loopback interfaces as you have configured it for the other EIGRP labs.

d. Advertise networks 172.16.12.0/29, 172.16.13.0/29, 172.16.23.0/29, 172.16.34.0/29, 192.168.1.0/24, 192.168.2.0/24, 192.168.3.0/24, and 192.168.4.0/24 from their respective routers.

R1(config)#router eigrp 1

R1(config-router)#network 192.168.1.0

R1(config-router)#network 172.16.12.0 0.0.0.7

R1(config-router)#network 172.16.13.0 0.0.0.7

R1(config-router)#no auto-summary

```
R1(config)#router eigrp 1
R1(config-router)#network 192.168.1.0
R1(config-router)#network 172.16.12.0 0.0.0.7
R1(config-router)#network 172.16.13.0 0.0.0.7
R1(config-router)#no auto-summary
R1(config-router)#
```

R2#conf t

R2(config)#router eigrp 1

R2(config-router)#network 192.168.2.0

R2(config-router)#network 172.16.12.0 0.0.0.7

R2(config-router)#network 172.16.23.0 0.0.0.7

R2(config-router)#no auto-summary

```
R2(config)#router eigrp 1
R2(config-router)#network 192.168.2.0
R2(config-router)#network 172.16.12.0 0.0.0.7
R2(config-router)#network 172.16.23.0 0.0.0.7
R2(config-router)#no auto-summary
```

R3(config)#router eigrp 1

R3(config-router)#network 192.168.3.0

R3(config-router)#network 172.16.13.0 0.0.0.7

R3(config-router)#network 172.16.23.0 0.0.0.7

R3(config-router)#network 172.16.34.0 0.0.0.7

R3(config-router)#no auto-summary

```
R3(config)#router eigrp 1
R3(config-router)#network 192.168.3.0
R3(config-router)#network 172.16.13.0 0.0.0.7
R3(config-router)#network 172.16.23.0 0.0.0.7
R3(config-router)#network 172.16.34.0 0.0.0.7
R3(config-router)#no auto-summary
```

R4#conf t

R4(config)#router eigrp 1

R4(config-router)#network 192.168.4.0

R4(config-router)#network 172.16.34.0 0.0.0.7

R4(config-router)#no auto-summary

```
R4(config)#router eigrp 1
R4(config-router)#network 192.168.4.0
R4(config-router)#network 172.16.34.0 0.0.0.7
R4(config-router)#no auto-summary
```

Step 4: Verify EIGRP connectivity.

a. Verify the configuration by using the show ip eigrp neighbors command to check which routers have EIGRP adjacencies.

R1# show ip eigrp neighbors

R1#9	show ip eigrp neighbors RP-IPv4 Neighbors for AS	(1)				
Н	Address	Interface	Hold Uptime	SRTT	RTO	Q
Seq						
			(sec)	(ms)		Cnt
Num						
1	172.16.13.3	Se3/1	12 00:01:09	58	2340	0
10						
0	172.16.12.2	Se3/0	11 00:01:49	60	1170	0
9						
R1#						

R2# show ip eigrp neighbors

```
R2#show ip eigrp neighbors
EIGRP-IPv4 Neighbors for AS(1)
    Address
                            Interface
                                                    Hold Uptime
                                                                  SRTT
                                                                         RTO Q
Seq
                                                    (sec)
                                                                              Cnt
                                                                   (ms)
Num
   172.16.23.3
                            Se3/1
                                                      12 00:01:55
                                                                        1170 0
11
                                                      10 00:02:35
   172.16.12.1
                            Se3/0
                                                                    45 1170 0
11
```

R3# show ip eigrp neighbors

	show ip eigrp neighbors RP-IPv4 Neighbors for AS	(1)					
Н	Address	Interface	Hold Uptime	SRTT	RTO	Q	Se
q 			(sec)	(ms)		Cnt	Nu
m 2	172.16.34.4	Se3/2	10 00:02:08	73	2340	0	3
1	172.16.23.2	Se3/1	14 00:02:38	48	1170	0	8
0	172.16.13.1	Se3/0	10 00:02:38	54	2340	0	10
R3#							

```
R4# show ip eigrp neighbors
```

```
R4#show ip eigrp neighbors
EIGRP-IPv4 Neighbors for AS(1)
                             Interface
                                                     Hold Uptime
    Address
Seq
                                                      (sec)
                                                                     (ms)
    172.16.34.3
                             Se3/2
                                                       10 00:02:40
                                                                          2340
```

a. Run the following Tcl script on all routers to verify full connectivity.

```
R1# tclsh
foreach address {
172.16.12.1
172.16.12.2
172.16.13.1
172.16.13.3
172.16.23.2
172.16.23.3
172.16.34.3
172.16.34.4
192.168.1.1
192.168.2.1
```

} { ping \$address }

192.168.3.1 192.168.4.1 192.168.4.129

```
(tcl)#10reacn addi
(tcl)#172.16.12.1
(tcl)#172.16.12.2
(tcl)#172.16.13.3
(tcl)#172.16.13.3
(tcl)#172.16.23.2
(tcl)#172.16.23.3
(tcl)#172.16.23.3
   (tcl)#192.168.1.1
(tcl)#192.168.2.1
 (tcl)#192.168.4.1
>(tcl)#192.168.4.129
 (tcl)#} { ping $address }
 ype escape sequence to abort.
ending 5, 100-byte ICMP Echos to 172.16.12.1, timeout is 2 seconds:
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.16.12.2, timeout is 2 seconds:
Success rate is 100 percent (5/5), round-trip min/avg/max = 36/56/72 ms
ending 5, 100-byte ICMP Echos to 172.16.13.3, timeout is 2 seconds:
```

Step 5: Verify the current path.

Before you configure PBR, verify the routing table on R1.

a. On R1, use the show ip route command. Notice the next-hop IP address for all networks discovered by EIGRP. R1# show ip route

```
R1#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP

+ - replicated route, % - next hop override

Gateway of last resort is not set

172.16.0.0/16 is variably subnetted, 6 subnets, 2 masks

C 172.16.12.0/29 is directly connected, Serial3/0

L 172.16.13.0/29 is directly connected, Serial3/1

L 172.16.13.1/32 is directly connected, Serial3/1

D 172.16.23.0/29 [90/21024000] via 172.16.12.2, 00:05:36, Serial3/1

192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks

C 192.168.1.0/24 is directly connected, Loopback1

D 192.168.2.0/24 [90/20640000] via 172.16.12.2, 00:05:36, Serial3/0

--More--
```

e. On R4, use the traceroute command to the R1 LAN address and source the ICMP packet from R4 LAN A and LAN B.

R4# traceroute 192.168.1.1 source 192.168.4.1

```
R4#traceroute 192.168.1.1 source 192.168.4.1
tType escape sequence to abort.
Tracing the route to 192.168.1.1
tVRF info: (vrf in name/id, vrf out name/id)
1 172.16.34.3 16 msec 28 msec 64 msec
2 172.16.23.2 84 msec 148 msec 116 msec
3 172.16.12.1 164 msec 156 msec 164 msec
```

R4# traceroute 192.168.1.1 source 192.168.4.129

f. On R3, use the show ip route command and note that the preferred route from R3 to R1 LAN 192.168.1.0/24 is via R2 using the R3 exit interface S0/0/1.

R3# show ip route

```
R3#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
+ - replicated route, % - next hop override

Gateway of last resort is not set

172.16.0.0/16 is variably subnetted, 7 subnets, 2 masks
D 172.16.12.0/29 [90/21024000] via 172.16.23.2, 00:07:39, Serial3/1
C 172.16.13.3/29 is directly connected, Serial3/0
L 172.16.23.3/32 is directly connected, Serial3/1
C 172.16.23.3/32 is directly connected, Serial3/1
L 172.16.34.0/29 is directly connected, Serial3/1
C 172.16.34.3/32 is directly connected, Serial3/2
L 172.16.34.3/32 is directly connected, Serial3/2
D 192.168.1.0/24 [90/21152000] via 172.16.23.2, 00:07:39, Serial3/1
D 192.168.2.0/24 [90/20640000] via 172.16.23.2, 00:07:39, Serial3/1
192.168.3.0/24 is variably subnetted, 2 subnets, 2 masks
--More--
```

g. On R3, use the show interfaces serial 0/0/0 and show interfaces s0/0/1 commands. R3# show interfaces serial3/2

```
R3# show interfaces serial3/2

R3#show interfaces serial3/2

Serial3/2 is up, line protocol is up
Hardware is M4T

Description: R3 --> R4

Internet address is 172.16.34.3/29

MTU 1500 bytes, BW 64 Kbit/sec, DLY 20000 usec,
    reliability 255/255, txload 1/255, rxload 1/255

Encapsulation HDLC, crc 16, loopback not set
Keepalive set (10 sec)
Restart-Delay is 0 secs
Last input 00:00:03, output 00:00:04, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: weighted fair
Output queue: 0/1000/64/0 (size/max total/threshold/drops)
    Conversations 0/1/256 (active/max active/max total)
    Reserved Conversations 0/0 (allocated/max allocated)
    Available Bandwidth 48 kilobits/sec

5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
313 packets input, 22504 bytes, 0 no buffer
Received 147 broadcasts (0 IP multicasts)
    0 runts, 0 giants, 0 throttles
    0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
--More--
```

R3# show interfaces serial3/0

```
R3#show interfaces serial3/0
Serial3/0 is up, line protocol is up
Hardware is MAT
Description: R3 --> R1
Internet address is 172.16.13.3/29
MTU 1500 bytes, BW 64 Kbit/sec, DLY 20000 usec,
    reliability 255/255, txload 1/255, rxload 1/255
Encapsulation HDLC, crc 16, loopback not set
Keepalive set (10 sec)
Restart-Delay is 0 secs
Last input 00:00:00, output 00:00:01, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: weighted fair
Output queue: 0/1000/64/0 (size/max total/threshold/drops)
    Conversations 0/1/256 (active/max active/max total)
    Reserved Conversations 0/0 (allocated/max allocated)
    Available Bandwidth 48 kilobits/sec
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
364 packets input, 27064 bytes, 0 no buffer
    Received 145 broadcasts (0 IP multicasts)
0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
--More--
```

R3# show interfaces serial3/1

```
R3#show interfaces serial3/1
Serial3/1 is up, line protocol is up
Hardware is M4T
Description: R3 --> R2
Internet address is 172.16.23.3/29
MTU 1500 bytes, BW 128 Kbit/sec, DLY 20000 usec,
    reliability 255/255, txload 1/255, rxload 1/255
Encapsulation HDLC, crc 16, loopback not set
Keepalive set (10 sec)
Restart-Delay is 0 secs
Last input 00:00:03, output 00:00:03, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
Queueing strategy: weighted fair
Output queue: 0/1000/64/0 (size/max total/threshold/drops)
    Conversations 0/1/256 (active/max active/max total)
    Reserved Conversations 0/0 (allocated/max allocated)
    Available Bandwidth 96 kilobits/sec
5 minute input rate 0 bits/sec, 0 packets/sec
5 minute output rate 0 bits/sec, 0 packets/sec
348 packets input, 25420 bytes, 0 no buffer
    Received 162 broadcasts (0 IP multicasts)
0 runts, 0 giants, 0 throttles
0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
--More--
```

h. Confirm that R3 has a valid route to reach R1 from its serial 0/0/0 interface using the show ip eigrp topology 192.168.1.0 command.

R3# show ip eigrp topology 192.168.1.0

```
R3#show ip eigrp topology 192.168.1.0
EIGRP-IPv4 Topology Entry for AS(1)/ID(192.168.3.1) for 192.168.1.0/24
State is Passive, Query origin flag is 1, 1 Successor(s), FD is 21152000
Descriptor Blocks:
172.16.23.2 (Serial3/1), from 172.16.23.2, Send flag is 0x0
Composite metric is (21152000/20640000), route is Internal
Vector metric:
Minimum bandwidth is 128 Kbit
Total delay is 45000 microseconds
Reliability is 255/255
Load is 1/255
Minimum MTU is 1500
Hop count is 2
Originating router is 192.168.1.1
172.16.13.1 (Serial3/0), from 172.16.13.1, Send flag is 0x0
Composite metric is (40640000/128256), route is Internal
Vector metric:
Minimum bandwidth is 64 Kbit
Total delay is 25000 microseconds
Reliability is 255/255
Load is 1/255
Minimum MTU is 1500
Hop count is 1
--More--
```

Step 6: Configure PBR to provide path control.

Now you will deploy source-based IP routing by using PBR. You will change a default IP routing decision based on the EIGRP-acquired routing information for selected IP source-to-destination flows and apply a different next-hop router.

Recall that routers normally forward packets to destination addresses based on information in their routing table. By using PBR, you can implement policies that selectively cause packets to take different paths based on source address, protocol type, or application type. Therefore, PBR overrides the router's normal routing behavior. Configuring PBR involves configuring a route map with match and set commands and then applying the route map to the interface.

The steps required to implement path control include the following:

- Choose the path control tool to use. Path control tools manipulate or bypass the IP routing table. For PBR, route-map commands are used.
- Implement the traffic-matching configuration, specifying which traffic will be manipulated. The match commands are used within route maps.
- Define the action for the matched traffic using set commands within route maps.
- Apply the route map to incoming traffic.

As a test, you will configure the following policy on router R3:

- All traffic sourced from R4 LAN A must take the R3 --> R2 --> R1 path.
- All traffic sourced from R4 LAN B must take the R3 --> R1 path.

.

a. On router R3, create a standard access list called PBR-ACL to identify the R4 LAN B network.

R3(config)# ip access-list standard PBR-ACL

R3(config-std-nacl)# remark ACL matches R4 LAN B traffic

R3(config-std-nacl)# permit 192.168.4.128 0.0.0.127

R3(config-std-nacl)# exit

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#ip access-list standard PBR-ACL
R3(config-std-nacl)#remark ACL matches R4 LAN B traffic
R3(config-std-nacl)#permit 192.168.4.128 0.0.0.127
R3(config-std-nacl)#exit
R3(config)#
```

i. Create a route map called R3-to-R1 that matches PBR-ACL and sets the next-hop interface to the R1 serial 0/0/1 interface.

R3(config)# route-map R3-to-R1 permit

R3(config-route-map)# description RM to forward LAN B traffic to R1

R3(config-route-map)# match ip address PBR-ACL

R3(config-route-map)# set ip next-hop 172.16.13.1

R3(config-route-map)# exit

```
R3(config)#route-map R3-to-R1 permit
R3(config-route-map)#description RM to forward LAN B traffic to R1
R3(config-route-map)#match ip address PBR-ACL
R3(config-route-map)#set ip next-hop 172.16.13.1
R3(config-route-map)#exit
```

j. Apply the R3-to-R1 route map to the serial interface on R3 that receives the traffic from R4. Use the ip policy route-map command on interface S3/2

R3(config)# interface s03/2

R3(config-if)# ip policy route-map R3-to-R1

R3(config-if)# end

```
R3(config)#interface s3/2
R3(config-if)#ip policy route-map R3-to-R1
R3(config-if)#end
R3#
```

k. On R3, display the policy and matches using the show route-map command.

R3# show route-map

```
R3#show route-map
route-map R3-to-R1, permit, sequence 10
Match clauses:
   ip address (access-lists): PBR-ACL
Set clauses:
   ip next-hop 172.16.13.1
Policy routing matches: 0 packets, 0 bytes
```

Step 7: Test the policy.

Now you are ready to test the policy configured on R3. Enable the debug ip policy command on R3 so that you can observe the policy decision-making in action. To help filter the traffic, first create a standard ACL that identifies all traffic from the R4 LANs.

a. On R3, create a standard ACL which identifies all of the R4 LANs.

R3# conf t

R3(config)# access-list 1 permit 192.168.4.0 0.0.0.255

R3(config)# exit

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#access-list 1 permit 192.168.4.0 0.0.0.255
R3(config)#exit
```

l. Enable PBR debugging only for traffic that matches the R4 LANs.

R3# debug ip policy?

```
R3#debug ip policy ?
<1-199> Access list
dynamic dynamic PBR
early Early PBR
<cr>
```

R3# debug ip policy 1

```
R3#debug ip policy 1
Policy routing debugging is on for access list 1
R3#
```

Policy routing debugging is on for access list 1 m. Test the policy from R4 with the traceroute command, using R4 LAN A as the source network.

R4# traceroute 192.168.1.1 source 192.168.4.1

```
R4#traceroute 192.168.1.1 source 192.168.4.1
Type escape sequence to abort.
Tracing the route to 192.168.1.1
VRF info: (vrf in name/id, vrf out name/id)
1 172.16.34.3 52 msec 24 msec 52 msec
2 172.16.23.2 104 msec 108 msec 104 msec
3 172.16.12.1 84 msec 68 msec 128 msec
```

n. Test the policy from R4 with the traceroute command, using R4 LAN B as the source network. R4# traceroute 192.168.1.1 source 192.168.4.129

```
R4#traceroute 192.168.1.1 source 192.168.4.129
Type escape sequence to abort.
Tracing the route to 192.168.1.1
VRF info: (vrf in name/id, vrf out name/id)
1 172.16.34.3 40 msec 76 msec 52 msec
2 172.16.13.1 132 msec 140 msec 128 msec
```

o. On R3, display the policy and matches using the show route-map command.

R3# show route-map


```
R3#show route-map
route-map R3-to-R1, permit, sequence 10
Match clauses:
   ip address (access-lists): PBR-ACL
Set clauses:
   ip next-hop 172.16.13.1
Nexthop tracking current: 0.0.0.0
172.16.13.1, fib_nh:0,oce:0,status:0


Policy routing matches: 6 packets, 192 bytes
```

PRACTICAL NO: 06


AIM: Inter-Vlan Routing

1) Assing the Address to PCs









2) Configure within the switch

- VLAN
- Assign the specified interfaces to the specific VLANs
- Define Access ports and Trunk Ports

Switch(config)# VLAN 10 Switch(config)# exit Switch(config)# VLAN 20 Switch(config)# exit Switch(config)# VLAN 30 Switch(config)# exit

Switch#show vlan brief

VLAN Name	Status Ports
 1 default	active Fa0/1, Fa0/2, Fa0/3, Fa0/4
	Fa0/5, Fa0/6, Fa0/7, Fa0/8
	Fa0/9, Fa0/10, Fa0/11, Fa0/12
	Fa0/13, Fa0/14, Fa0/15, Fa0/16
	Fa0/17, Fa0/18, Fa0/19, Fa0/20
	Fa0/21, Fa0/22, Fa0/23, Fa0/24
	Gig0/1, Gig0/2
10 VLAN0010	active
20 VLAN0020	active
30 VLAN0030	active
1002 fddi-default	active
1003 token-ring-default	active
1004 fddinet-default	active
1005 trnet-default	active

Switch# configure terminal

Enter configuration commands, one per line. End with CNTL/Z. Switch(config)#interface fastethernet 0/1
Switch(config-if)#switchport access vlan 10
Switch(config-if)#switchport mode access
Switch(config-if)#exit
Switch(config)#
Switch(config)#

Switch(config-if)#switchport access vlan 20
Switch(config-if)#switchport mode access
Switch(config-if)#exit
Switch(config)#
Switch(config)#interface fastethernet 0/3
Switch(config-if)#switchport access vlan 10
Switch(config-if)#switchport mode access
Switch(config-if)#end
Switch#
%SYS-5-CONFIG_I: Configured from console by console

Switch#show vlan brief

LAN Name	Status Ports		
default	active Fa0/4, Fa0/5, Fa0/6, Fa0/7		
	Fa0/8, Fa0/9, Fa0/10, Fa0/11		
	Fa0/12, Fa0/13, Fa0/14, Fa0/15		
	Fa0/16, Fa0/17, Fa0/18, Fa0/19		
	Fa0/20, Fa0/21, Fa0/22, Fa0/23		
	Fa0/24, Gig0/1, Gig0/2		
0 VLAN0010	active Fa0/1		
0 VLAN0020	active Fa0/2		
0 VLAN0030	active Fa0/3		
002 fddi-default	active		
003 token-ring-default	active		
004 fddinet-default	active		
005 trnet-default	active		

Switch#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Switch(config)#interface gigabitethernet 0/1

Switch(config-if)#no shutdown

Switch(config-if)#

Switch(config-if)#switchport mode trunk

Switch(config-if)#**exit** Switch(config)#**exit**

Switch#

%SYS-5-CONFIG_I: Configured from console by console

Switch#show run

```
Switch#show run
Building configuration...
Current configuration: 1256 bytes
version 15.0
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
hostname Switch
spanning-tree mode pyst
spanning-tree extend system-id
interface FastEthernet0/1
switchport access ylan 10
switchport mode access
interface FastEthernet0/2
switchport access ylan 20
switchport mode access
interface FastEthernet0/3
switchport access ylan 30
switchport mode access
interface FastEthernet0/4
interface FastEthernet0/5
```

```
interface FastEthernet0/6
interface FastEthernet0/7
interface FastEthernet0/8
interface FastEthernet0/9
interface FastEthernet0/10
interface FastEthernet0/11
interface FastEthernet0/12
interface FastEthernet0/13
interface FastEthernet0/14
interface FastEthernet0/15
interface FastEthernet0/16
interface FastEthernet0/17
interface FastEthernet0/18
interface FastEthernet0/19
interface FastEthernet0/20
interface FastEthernet0/21
interface FastEthernet0/22
interface FastEthernet0/23
interface FastEthernet0/24
```

```
interface GigabitEthernet0/1
switchport mode trunk
interface GigabitEthernet0/2
interface Vlan1
no ip address
shutdown
!
1
line con 0
line yty 0 4
login
line vty 5 15
login
ļ
ļ
!
end
```

Switch#copy running-config startup-config


Destination filename [startup-config]? Building configuration...

[OK]

Switch#

3) Configure router with dot1Q encapsulation by making each of sub-interfaces

Go to the Router0 and go to CLI tab and type no



Router>enable

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface gigabitEthernet 0/0

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

Router(config-if)#exit

Router(config)#interface gigabitEthernet 0/0.10

Router(config-subif)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0.10, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0.10, changed state to up

Router(config-subif)#encapsulation dot1Q 10

Router(config-subif)#ip address 192.168.10.1 255.255.255.0

Router(config-subif)#exit

Router(config)#interface gigabitEthernet 0/0.20

Router(config-subif)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0.20, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0.20, changed state to up

Router(config-subif)#encapsulation dot1Q 20

Router(config-subif)#ip address 192.168.20.1 255.255.255.0

Router(config-subif)#exit

Router(config)#interface gigabitEthernet 0/0.30

Router(config-subif)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0.30, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0.30, changed state to up

Router(config-subif)#encapsulation dot1Q 30

Router(config-subif)#ip address 192.168.30.1 255.255.255.0

Router(config-subif)#

Router(config-subif)#encapsulation dot1Q 10

%Configuration of multiple subinterfaces of the same main

interface with the same VID (10) is not permitted.

This VID is already configured on GigabitEthernet0/0.10.

Router(config-subif)#shutdown

Router(config-subif)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0.30, changed state to administratively down

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0.30, changed state to down

Router(config-subif)#

Router(config-subif)#exit

Router(config)#no interface gigabitethernet 0/0.30

Router(config)#end

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#show run

```
Router#show run
Building configuration...
Current configuration : 875 bytes
version 15.1
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
hostname Router
ip cef
no ipv6 cef
license udi pid CISCO2911/K9 sn FTX1524JG2W-
spanning-tree mode pvst
interface GigabitEthernet0/0
no ip address
duplex auto
 speed auto
interface GigabitEthernet0/0.10
 encapsulation dot1Q 10
ip address 192.168.10.1 255.255.255.0
interface GigabitEthernet0/0.20
encapsulation dot1Q 20
 ip address 192.168.20.1 255.255.255.0
```

```
interface GigabitEthernet0/0
 no ip address
 duplex auto
 speed auto
interface GigabitEthernet0/0.10
 encapsulation dot1Q 10
 ip address 192.168.10.1 255.255.255.0
interface GigabitEthernet0/0.20
 encapsulation dot1Q 20
 ip address 192.168.20.1 255.255.255.0
interface GigabitEthernet0/1
 no ip address
 duplex auto
 speed auto
 shutdown
interface GigabitEthernet0/2
 no ip address
 duplex auto
 speed auto
 shutdown
interface Vlanl
no ip address
 shutdown
ip classless
ip flow-export version 9
line con 0
line aux 0
line vty 0 4
login
end
```

Router#show ip route

```
Router#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

192.168.10.0/24 is variably subnetted, 2 subnets, 2 masks

C 192.168.10.0/24 is directly connected, GigabitEthernet0/0.10

192.168.20.0/24 is variably subnetted, 2 subnets, 2 masks

C 192.168.20.0/24 is directly connected, GigabitEthernet0/0.10

192.168.20.0/24 is directly connected, GigabitEthernet0/0.20

L 192.168.20.1/32 is directly connected, GigabitEthernet0/0.20
```

Switch>enable

Switch#show vlan brief

Switch> Switch>enable Switch#show vlan brief			
VLAN	Name	Status	Ports
1	default	active	Fa0/4, Fa0/5, Fa0/6, Fa0/7 Fa0/8, Fa0/9, Fa0/10, Fa0/11 Fa0/12, Fa0/13, Fa0/14, Fa0/15 Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/21, Fa0/22, Fa0/23 Fa0/24, Gig0/2
10	VLAN0010	active	Fa0/1, Fa0/3
20	VLAN0020	active	Fa0/2
30	VLAN0030	active	
1002	fddi-default	active	
1003	token-ring-default	active	
1004	fddinet-default	active	
1005	trnet-default	active	
Swite	eh#		

Switch#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Switch(config)#vlan 30

Switch(config-vlan)#exit

Switch(config)#

Switch(config)#interface fastethernet 0/3

Switch(config-if)#switchport access vlan 30

Switch(config-if)#switchport mode access

Switch(config-if)#exit

Switch(config)#exit

Switch#

Switch#show vlan brief

Swite	Switch#show vlan brief				
VLAN	Name	Status	Ports		
1	default	active	Fa0/4, Fa0/5, Fa0/6, Fa0/7 Fa0/8, Fa0/9, Fa0/10, Fa0/11		
			Fa0/12, Fa0/13, Fa0/14, Fa0/15		
			Fa0/16, Fa0/17, Fa0/18, Fa0/19		
			Fa0/20, Fa0/21, Fa0/22, Fa0/23		
			Fa0/24, Gig0/2		
10	VLAN0010	active	Fa0/1		
20	VLAN0020	active	Fa0/2		
30	VLAN0030	active	Fa0/3		
1002	fddi-default	active			
1003	token-ring-default	active			
1004	fddinet-default	active			
1005	trnet-default	active			
Swite	ch#				

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface gigabitethernet 0/0.30

Router(config-subif)#

Router(config-subif)#encapsulation dot1Q 30

Router(config-subif)#ip address 192.168.30.1 255.255.255.0

Router(config-subif)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route

```
Router#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

192.168.10.0/24 is variably subnetted, 2 subnets, 2 masks
C 192.168.10.0/24 is directly connected, GigabitEthernet0/0.10
192.168.20.0/24 is directly connected, GigabitEthernet0/0.10
192.168.20.0/24 is variably subnetted, 2 subnets, 2 masks
C 192.168.20.0/24 is directly connected, GigabitEthernet0/0.20
L 192.168.30.0/24 is directly connected, GigabitEthernet0/0.20
192.168.30.0/24 is variably subnetted, 2 subnets, 2 masks
C 192.168.30.0/24 is directly connected, GigabitEthernet0/0.30
L 192.168.30.1/32 is directly connected, GigabitEthernet0/0.30
L 192.168.30.1/32 is directly connected, GigabitEthernet0/0.30
```

Switch#copy running-config startup-config


```
Switch#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
Switch#
```

PRACTICAL NO: 07

AIM: Simulating Mpls Environment

Step 1 – IP addressing of MPLS Core and OSPF

First bring 3 routers into your topology R1, R2, R3 position them as below. We are going to address the routers and configure ospf to ensure loopback to loopback connectivity between R1 and R3



Router R1

R1#conf t

R1(config)#int lo0

R1(config-if)#ip add 1.1.1.1 255.255.255.255

R1(config-if)#ip ospf 1 area 0

R1(config-if)#int f0/0

R1(config-if)#ip add 10.0.0.1 255.255.255.0

R1(config-if)#no shut

R1(config-if)#ip ospf 1 area 0

```
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#int lo0
R1(config-if)#ip add 1.1.1.1 255.255.255
R1(config-if)#ip ospf 1 area 0
R1(config-if)#int f0/0
R1(config-if)#ip add 10.0.0.1 255.255.255.0
R1(config-if)#ip ospf 1 area 0
```

Router R2

R2#CONF T

R2(config)#int lo0

R2(config-if)#ip add 2.2.2.2 255.255.255.255

R2(config-if)#ip ospf 1 area 0

R2(config-if)#

R2(config-if)#int f0/0

R2(config-if)#ip add 10.0.0.2 255.255.255.0

R2(config-if)#no shut

R2(config-if)#ip ospf 1 area 0

R2(config)#int f0/1

R2(config-if)#ip add 10.0.1.2 255.255.255.0

R2(config-if)#no shut

```
R2(config-if)#ip ospf 1 area 0
```

```
R2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#int lo0
R2(config-if)#ip add 2.2.2.2 255.255.255
R2(config-if)#ip ospf 1 area 0
R2(config-if)#
R2(config-if)#int f0/0
R2(config-if)#ip add 10.0.0.2 255.255.255.0
R2(config-if)#no shut
R2(config-if)#ip ospf 1 area 0
R2(config-if)#
R2(config-if)#
R2(config-if)#int f0/1
R2(config-if)#int f0/1
R2(config-if)#ip add 10.0.1.2 255.255.255.0
R2(config-if)#ip ospf 1 area 0
```

Router R3

R3(config)#CONF T

R3(config)#int lo0

R3(config-if)#ip add 3.3.3.3 255.255.255.255

R3(config-if)#ip ospf 1 area 0

R3(config-if)#

R3(config-if)#int f0/0

R3(config-if)#ip add 10.0.1.3 255.255.255.0

R3(config-if)#no shut

R3(config-if)#ip ospf 1 area 0

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#int lo0
R3(config-if)#ip add 3.3.3.3 255.255.255
R3(config-if)#ip ospf 1 area 0
R3(config-if)#
R3(config-if)#
R3(config-if)#int f0/0
R3(config-if)#ip add 10.0.1.3 255.255.255.0
R3(config-if)#no shut
R3(config-if)#ip ospf 1 area 0
```

R1#ping 3.3.3.3 source lo0

```
Rl#ping 3.3.3.3 source 100

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 3.3.3.3, timeout is 2 seconds:

Packet sent with a source address of 1.1.1.1

!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 60/62/64 ms
Rl#
```

Step 2 - Configure LDP on all the interfaces in the MPLS Core

In order to run MPLS you need to enable it, there are two ways to do this.

- ☐ At each interface enter the mpls ip command
- ☐ Under the ospf process use the mpls ldp autoconfig command For this tutorial we will be using the second option, so go int the ospf process and enter mpls ldp autoconfig this will enable mpls label distribution protocol on every interface running ospf under that specific Process.

Router R1

R1#conf t

Enter configuration commands, one per line. End with CNTL/Z. R1(config)#router ospf 1

R1(config-router)#mpls ldp autoconfig

```
Rl#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Rl(config) #router ospf l
Rl(config-router) #mpls ldp autoconfig
Rl(config-router) #
```

Router R2

R2(config)#router ospf 1

R2(config-router)#mpls ldp autoconfig

```
R2#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#router ospf l
R2(config-router)#mpls ldp autoconfig
R2(config-router)#
```

Router R3

R3(config)#router ospf 1

R3(config-router)#mpls ldp autoconfig

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#router ospf l
R3(config-router)#mpls ldp autoconfig
R3(config-router)#
```

You should see log messages coming up showing the LDP neighbors are up.

```
*Mar 1 00:14:42.787: %LDP-5-NBRCHG: LDP Neighbor 1.1.1.1:0 (1) is UP
R2(config-router)#
R2#
*Mar 1 00:14:57.659: %SYS-5-CONFIG_I: Configured from console by console
R2#
*Mar 1 00:15:28.615: %LDP-5-NBRCHG: LDP Neighbor 3.3.3.3:0 (2) is UP
R2#
```

To verify the mpls interfaces the command is very simple – sh mpls Interface This is done on R2 and you can see that both interfaces are running mpls and using LDP

```
R2#sh mpls interface
Interface IP Tunnel Operational
FastEthernet0/0 Yes (ldp) No Yes
FastEthernet0/1 Yes (ldp) No Yes
R2#
```

You can also verify the LDP neighbors with the sh mpls ldp neighbors command. R2#sh mpls ldp neigh

```
R2#sh mpls ldp neigh
    Peer LDP Ident: 1.1.1.1:0; Local LDP Ident 2.2.2.2:0
        TCP connection: 1.1.1.1.646 - 2.2.2.2.37982
        State: Oper; Msgs sent/rcvd: 13/12; Downstream
       Up time: 00:04:31
        LDP discovery sources:
         FastEthernet0/0, Src IP addr: 10.0.0.1
        Addresses bound to peer LDP Ident:
         10.0.0.1
                         1.1.1.1
    Peer LDP Ident: 3.3.3.3:0; Local LDP Ident 2.2.2.2:0
        TCP connection: 3.3.3.3.34804 - 2.2.2.2.646
        State: Oper; Msgs sent/rcvd: 12/12; Downstream
        Up time: 00:03:45
        LDP discovery sources:
         FastEthernet0/1, Src IP addr: 10.0.1.3
        Addresses bound to peer LDP Ident:
          10.0.1.3
                          3.3.3.3
```

One more verification to confirm LDP is running ok is to do a trace between R1 and R3 and verify if you get MPLS Labels show up in the trace. R1#trace 3.3.3.3

```
RI#trace 3.3.3.3

Type escape sequence to abort.
Tracing the route to 3.3.3.3

1 10.0.0.2 [MPLS: Label 17 Exp 0] 52 msec 64 msec 60 msec 2 10.0.1.3 64 msec 68 msec 68 msec RI#
```

As you can see the trace to R2 used an MPLS Label in the path, as this is a very small MPLS core only one label was used as R3 was the final hop. So to review we have now configured IP addresses on the MPLS core, enabled OSPF and full IP connectivity between all routers and finally enabled mpls on all the interfaces in the core and have established ldp neighbors between all routers. The next step is to configure MP-BGP between R1 and R3 This is when you start to see the layer 3 vpn configuration come to life

Step 3 – MPLS BGP Configuration between R1 and R3

We need to establish a Multi Protocol BGP session between R1 and R3 this is done by configuring the vpnv4 address family as below

```
R1(config)#router bgp 1
```

R1(config-router)#neighbor 3.3.3.3 remote-as 1

R1(config-router)#neighbor 3.3.3.3 update-source Loopback0

R1(config-router)#no auto-summary

R1(config-router)#address-family vpnv4

R1(config-router-af)#neighbor 3.3.3.3 activate

```
Rl#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
Rl(config) #router bgp 1
Rl(config-router) #neighbor 3.3.3.3 remote-as 1
Rl(config-router) #neighbor 3.3.3.3 update-source Loopback0
Rl(config-router) #no auto-summary
Rl(config-router) #address-family vpnv4
Rl(config-router-af) #neighbor 3.3.3.3 activate
Rl(config-router-af) #
```

R3(config)#router bgp 1

R3(config-router)#neighbor 1.1.1.1 remote-as 1

R3(config-router)#neighbor 1.1.1.1 update-source Loopback0

R3(config-router)#no auto-summary

R3(config-router)#address-family vpnv4

R3(config-router-af)#neighbor 1.1.1.1 activate

```
R3#CONF T

Enter configuration commands, one per line. End with CNTL/Z.
R3(config) #router bgp 1
R3(config-router) #neighbor 1.1.1.1 remote-as 1
R3(config-router) #neighbor 1.1.1.1 update-source Loopback0
R3(config-router) #no auto-summary
R3(config-router) #address-family vpnv4
R3(config-router-af) #neighbor 1.1.1.1 activate
R3(config-router-af) # *Mar 1 00:24:35.327: %BGP-5-ADJCHANGE: neighbor 1.1.1.1 Up
R3(config-router-af) #
```

To verify the BGP session between R1 and R3 issue the command sh bgp vpnv4 unicast all summary

R1#sh bgp vpnv4 unicast all summary

```
Rl#sh bgp vpnv4 unicast all summary
BGP router identifier 1.1.1.1, local AS number 1
BGP table version is 1, main routing table version 1


Neighbor V AS MsgRcvd MsgSent TblVer InQ OutQ Up/Down State/PfxRcd
3.3.3.3 4 1 4 4 1 0 0 00:01:28 0
R1#
```

You can see here that we do have a bgp vpnv4 peering to R3 – looking at the PfxRcd you can see it says 0 this is because we have not got any routes in BGP. We are now going to add two more routers to the topology. These will be the customer sites connected to R1 and R3. We will then create a VRF on each router and put the interfaces connected to each site router into that VRF.

Step 4 – Add two more routers, create VRFs

We will add two more routers into the topology so it now looks like the final Topology

Router 4 will peer OSPF using process number 2 to a VRF configured on R1. It will use the local site addressing of 192.168.1.0/24.



R4#conf t
R4(config)#int lo0
R4(config-if)#ip add 4.4.4.4 255.255.255.255
R4(config-if)#ip ospf 2 area 2
R4(config-if)#int f0/0
R4(config-if)#ip add 192.168.1.4 255.255.255.0
R4(config-if)#ip ospf 2 area 2
R4(config-if)#no shut

```
R4#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R4(config)#int lo0
R4(config-if)#ip add 4.4.4.4 255.255.255.255
R4(config-if)#ip ospf 2 area 2
R4(config-if)#int f0/0
R4(config-if)#ip add 192.168.1.4 255.255.255.0
R4(config-if)#ip ospf 2 area 2
R4(config-if)#no shut
R1#conf t
R1(config)#int f0/1
R1(config-if)#no shut
R1(config-if)#ip add 192.168.1.1 255.255.255.0
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#int f0/1
R1(config-if)#no shut
R1(config-if)#ip add 192.168.1.1 255.255.255.0
R1(config)#ip vrf RED
R1(config-vrf)#rd 4:4
R1(config-vrf)#route-target both 4:4
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip vrf RED
R1(config-vrf)#rd 4:4
R1(config-vrf)#route-target both 4:4
R1(config)#int f0/1
R1(config-if)#ip vrf forwarding RED
R1(config-if)#ip vrf fo
R1(config-if)#ip vrf forwarding RED
R1(config)#int f0/1
Rl(config-if) #ip vrf forwarding RED
% Interface FastEthernet0/1 IP address 192.168.1.1 removed due to enabling VRF
R1(config)#int f0/1
R1(config-if)#ip address 192.168.1.1 255.255.255.0
R1(config)#int f0/1
R1(config-if)#ip address 192.168.1.1 255.255.255.0
R1#sh run int f0/1
Rl#sh run int f0/1
Building configuration...
Current configuration : 119 bytes
interface FastEthernet0/1
 ip vrf forwarding RED
 ip address 192.168.1.1 255.255.255.0
```

duplex auto speed auto

end

R1#sh ip route

```
Rlish ip route

Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

1.00.0/32 is subnetted, 1 subnets

C 1.1.1.1 is directly connected, Loopback0

2.0.0.0/32 is subnetted, 1 subnets

0 2.2.2.2 [110/11] via 10.0.0.2, 00:17:49, FastEthernet0/0

3.0.0.0/32 is subnetted, 1 subnets

0 3.3.3.3 [110/21] via 10.0.0.2, 00:17:23, FastEthernet0/0

10.0.0.0/24 is subnetted, 2 subnets

C 10.0.0.0 is directly connected, FastEthernet0/0

10.0.1.0 [110/20] via 10.0.0.2, 00:17:33, FastEthernet0/0
```

R1#sh ip route vrf red

```
Rl#sh ip route vrf red
% IP routing table red does not exist
Rl#
```

R1#sh ip route vrf RED

```
Routing Table: RED

Routing Table: RED

Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

C 192.168.1.0/24 is directly connected, FastEthernet0/1

R1#
```

R1(config)#int f0/1

R1(config-if)#ip ospf 2 area 2

```
Rl#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
Rl(config)#int f0/1
Rl(config-if)#ip ospf 2 area 2
Rl(config-if)#
*Mar 1 00:23:14.423: %OSPF-5-ADJCHG: Process 2, Nbr 4.4.4.4 on FastEthernet0/1 from LOADING to FULL, Loading Done
Rl(config-if)#
Rl#
*Mar 1 00:23:36.811: %SYS-5-CONFIG_I: Configured from console by console
Rl#
```

R1#sh ip route vrf RED

```
Rl#sh ip route vrf RED

Routing Table: RED

Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

O - ODR, P - periodic downloaded static route

Gateway of last resort is not set

4.0.0.0/32 is subnetted, 1 subnets

O 4.4.4.4 [110/11] via 192.168.1.4, 00:01:18, FastEthernet0/1

C 192.168.1.0/24 is directly connected, FastEthernet0/1

Rl#
```

R5(config)#int lo0

```
R5(config-if)#ip add 6.6.6.6 255.255.255.255
R5(config-if)#ip ospf 2 area 2
R5(config-if)#int f0/0
R5(config-if)#ip add 192.168.2.6 255.255.255.0
R5(config-if)#ip ospf 2 area 2
R5(config-if)#no shut
R5#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R5(config)#int lo0
R5(config-if)#ip add 6.6.6.6 255.255.255.255
R5(config-if)#ip ospf 2 area 2
R5(config-if)#int f0/0
R5(config-if) #ip add 192.168.2.6 255.255.255.0
R5(config-if)#ip ospf 2 area 2
R5(config-if)#no shut
R3(config)#int f0/1
R3(config-if)#no shut
R3(config-if)#ip add 192.168.2.3 255.255.255.0
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#int f0/1
R3(config-if)#no shut
R3(config-if)#ip add 192.168.2.3 255.255.255.0
R3(config)#ip vrf RED
R3(config-vrf)#rd 4:4
R3(config-vrf)#route-target both 4:4
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#ip vrf RED
R3(config-vrf) #rd 4:4
R3(config-vrf) #route-target both 4:4
R3(config)#int f0/1
R3(config-if)#ip vrf forwarding RED
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#int f0/1
R3(config-if)#ip vrf forwarding RED
% Interface FastEthernet0/1 IP address 192.168.2.3 removed due to enabling VRF R
ED
R3(config-if)#
R3(config)#int f0/1
R3(config-if)#ip address 192.168.2.1 255.255.255.0
R3#CONF T
Enter configuration commands, one per line.
                                                         End with CNTL/Z.
```

R3#sh run int f0/1

R3(config)#int f0/1

R3(config-if)#

R3(config-if)#ip address 192.168.2.1 255.255.255.0

```
R3#sh run int f0/1
Building configuration...

Current configuration : 119 bytes
!
interface FastEthernet0/1
ip vrf forwarding RED
ip address 192.168.2.1 255.255.255.0
duplex auto
speed auto
end

R3#
```

R3(config)#int f0/1

R3(config-if)#ip ospf 2 area 2

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config) #int f0/1
¿R3(config-if) #ip ospf 2 area 2
R3(config-if) #
```

R3#sh ip route vrf RED

```
Routing Table: RED

Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

6.0.0.0/32 is subnetted, 1 subnets

O 6.6.6.6 [110/11] via 192.168.2.6, 00:00:37, FastEthernet0/1

C 192.168.2.0/24 is directly connected, FastEthernet0/1

R3#
```

R4#sh ip route

```
R4#sh ip route

Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

4.0.0.0/32 is subnetted, 1 subnets

C 4.4.4.4 is directly connected, Loopback0

C 192.168.1.0/24 is directly connected, FastEthernet0/0

R4#
```

R1#sh ip route

```
Rl#sh ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route
Gateway of last resort is not set
     1.0.0.0/32 is subnetted, 1 subnets
        1.1.1.1 is directly connected, Loopback0
     2.0.0.0/32 is subnetted, 1 subnets
        2.2.2.2 [110/11] via 10.0.0.2, 00:32:11, FastEthernet0/0
     3.0.0.0/32 is subnetted, 1 subnets
        3.3.3.3 [110/21] via 10.0.0.2, 00:31:45, FastEthernet0/0
     10.0.0.0/24 is subnetted, 2 subnets
        10.0.0.0 is directly connected, FastEthernet0/0
        10.0.1.0 [110/20] via 10.0.0.2, 00:31:55, FastEthernet0/0
```

R1#sh ip route vrf RED

```
Routing Table: RED

Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

0 - ODR, P - periodic downloaded static route

Gateway of last resort is not set

4.0.0.0/32 is subnetted, 1 subnets

0 4.4.4.4 [110/11] via 192.168.1.4, 00:12:27, FastEthernet0/1

C 192.168.1.0/24 is directly connected, FastEthernet0/1

R1#
```

R1(config)#router bgp 1

R1(config-router)#address-family ipv4 vrf RED

R1(config-router-af)#redistribute ospf 2

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config) #router bgp 1
R1(config-router) #address-family ipv4 vrf RED
R1(config-router-af) #redistribute ospf 2
```

R3(config)#router bgp 1

R3(config-router)#address-family ipv4 vrf RED

R3(config-router-af)#redistribute ospf 2

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/2.
R3(config) #router bgp 1
R3(config-router) #address-family ipv4 vrf RED
R3(config-router-af) #redistribute ospf 2
```

R1#sh ip bgp vpnv4 vrf RED

```
Rl#sh ip bgp vpnv4 vrf RED
BGP table version is 9, local router ID is 1.1.1.1
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal,
              r RIB-failure, S Stale
Origin codes: i - IGP, e - EGP, ? - incomplete
                                        Metric LocPrf Weight Path
   Network
                    Next Hop
Route Distinguisher: 4:4 (default for vrf RED)
                                                        32768 ?
                    192.168.1.4
*> 4.4.4.4/32
                    3.3.3.3
                                                           0 2
*>i6.6.6.6/32
                                                   100
*> 192.168.1.0
                   0.0.0.0
                                                        32768 ?
*>i192.168.2.0
                    3.3.3.3
                                                            0 ?
R1#
```

R3#sh ip bgp vpnv4 vrf RED

```
R3#sh ip bgp vpnv4 vrf RED
BGP table version is 9, local router ID is 3.3.3.3
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal,
              r RIB-failure, S Stale
Origin codes: i - IGP, e - EGP, ? - incomplete
                   Next Hop
                                        Metric LocPrf Weight Path
   Network
Route Distinguisher: 4:4 (default for vrf RED)
*> 6.6.6.6/32
                    192.168.2.6
                                                       32768 ?
*>i192.168.1.0
*> 192.168.2.0
                   0.0.0.0
                                                       32768 ?
R3#
```

R1(config)#router ospf 2

R1(config-router)#redistribute bgp 1 subnets

```
R1#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R1(config) #router ospf 2
R1(config-router) #redistribute bgp 1 subnets
```

R3(config)#router ospf 2

R3(config-router)#redistribute bgp 1 subnets

```
R3#CONF T
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#router ospf 2
R3(config-router)#redistribute bgp l subnets
```

R4#sh ip route

```
R4#sh ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       {\tt E1} - OSPF external type 1, {\tt E2} - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route
Gateway of last resort is not set
     4.0.0.0/32 is subnetted, 1 subnets
        4.4.4.4 is directly connected, Loopback0
     6.0.0.0/32 is subnetted, 1 subnets
       6.6.6.6 [110/21] via 192.168.1.1, 00:01:28, FastEthernet0/0
O IA
     192.168.1.0/24 is directly connected, FastEthernet0/0
C
O IA 192.168.2.0/24 [110/11] via 192.168.1.1, 00:01:28, FastEthernet0/0
R4#
```

R5#sh ip route

```
R5#sh ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       {\tt N1} - OSPF NSSA external type 1, {\tt N2} - OSPF NSSA external type 2
       {\tt E1} - OSPF external type 1, {\tt E2} - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route
Gateway of last resort is not set
     4.0.0.0/32 is subnetted, 1 subnets
O IA
       4.4.4.4 [110/21] via 192.168.2.1, 00:01:13, FastEthernet0/0
     6.0.0.0/32 is subnetted, 1 subnets
       6.6.6.6 is directly connected, Loopback0
O IA 192.168.1.0/24 [110/11] via 192.168.2.1, 00:01:13, FastEthernet0/0
     192.168.2.0/24 is directly connected, FastEthernet0/0
```

R4#ping 6.6.6.6

```
R4#ping 6.6.6.6

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 6.6.6.6, timeout is 2 seconds:

!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 124/128/140 ms

.R4#
```

R4#trace 6.6.6.6

```
R4#trace 6.6.6.6

Type escape sequence to abort.

Tracing the route to 6.6.6.6

1 192.168.1.1 32 msec 16 msec 44 msec
2 10.0.0.2 [MPLS: Labels 17/19 Exp 0] 124 msec 128 msec 124 msec
3 192.168.2.1 [MPLS: Label 19 Exp 0] 88 msec 96 msec 92 msec
4 192.168.2.6 128 msec 124 msec 124 msec

R4#
```

83