root

Go Up

Table of Contents

LinearRegression	
LogisticRegression	
ML_Core	
PBblas	

LinearRegression

Go Up

Table of Contents

OLS.ecl

Ordinary Least Squares (OLS) Linear Regression aka Ordinary Linear Regression Regression learns a function that maps a set of input data (independents) to one or more output variables (dependents)

LinearRegression/ OLS

Go Up

IMPORTS

ML_Core | ML_Core.Types | PBblas | PBblas.Types | PBblas.Converted | PBblas.MatUtils | ML_Core.Math |

DESCRIPTIONS

MODULE OLS

OLS

(DATASET(NumericField) X=empty_data, DATASET(NumericField) Y=empty_data)

Ordinary Least Squares (OLS) Linear Regression aka Ordinary Linear Regression Regression learns a function that maps a set of input data (independents) to one or more output variables (dependents). The resulting learned function is known as the model. That model can then be used repetitively to predict (i.e. estimate) the output value(s) based on new input data. Two major use cases are supported: 1) Learn and return a model 2) Use an existing (e.g. persisted) model to predict new values for Y Of course, both can be done in a single run. Alternatively, the model can be persisted and used indefinitely for prediction of Y values, as long as the record format has not changed, and the original training data remains representative of the population. OLS supports any number of independent variables (Multiple Regression) and multiple dependent variables (Multivariate Regression). In this way, multiple variables' values can be predicted from the same input (i.e. independent) data. Training data is presented as parameters to this module. When using a previously persisted model (use case 2 above), these parameters should be omitted. This module provides a rich set of analytics to assess the usefulness of the resulting linear regression model, and to determine the best subset of independent variables to include in the model. These include: For the whole model: - Analysis of Variance (ANOVA) - R-squared - Adjusted R-squared - F-Test - Akaike Information Criterion (AIC) For each coefficient: - Standard Error (SE) -

- **PARAMETER** X The independent variable training data in DATASET(NumericField) format. Each observation (e.g. record) is identified by 'id', and each feature is identified by field number (i.e. 'number'). Omit this parameter when predicting from a persisted model.
- **PARAMETER** Y The dependent variable training data in DATASET(NumericField) format. Each observation (e.g. record) is identified by 'id', and each feature is identified by field number. Omit this parameter when predicting from a persisted model.

Children

- 1. GetModel: GetModel Returns the learned model that maps X's to Y's
- 2. Betas: Return raw Beta values as numeric fields Extracts Beta values from the model
- 3. Predict: Predict the dependent variable values (Y) for any set of independent variables (X)
- 4. makeRSQ
- 5. RSquared : RSquared Calculate the R-Squared Metric used to assess the fit of the regression line to the training data
- 6. AnovaRec
- 7. calcAnova
- 8. Anova: ANOVA (Analysis of Variance) report Analyzes the sources of variance
- 9. SE: Standard Error of the Regression Coefficients Describes the variability of the regression error for each coefficient
- 10. TStat: T-Statistic The T-statistic identifies the significance of the value of each regression coefficient
- 11. AdjRSquared : Adjusted R2 Calculate Adjusted R Squared which is a scaled version of R Squared that does not arbitrarily increase with the number of features
- 12. AICRec
- 13. AIC : Akaike Information Criterion (AIC) Information theory based criterion for assessing Goodness of Fit (GOF)
- 14. RangeVec
- 15. DistributionBase
- 16. TDistribution
- 17. FDistribution
- 18. NormalDistribution

- 19. pVal: P-Value Calculate the P-value for each coefficient, which is the probability that the coefficient is insignificant (i.e
- 20. ConfintRec
- 21. ConfInt: Confidence Interval The Confidence Interval determines the upper and lower bounds of each estimated coefficient given a confidence level (level) that is required
- 22. FTestRec
- 23. FTest: F-Test Calculate the P-value for the full regression, which is the probability that all of the coefficients are insignificant (i.e

ATTRIBUTE GetModel

OLS \

DATASET(Layout_Model) GetModel

GetModel Returns the learned model that maps X's to Y's. In the case of OLS, the model represents a set of Betas which are the coefficients of the linear model: Beta0 * 1 + Beta1 * Field1 + Beta2 * Field2 ... The ID of each model record specifies to which Y variable the coefficient applies. The Field Number ('number') indicates to which field of X the beta is to be applied. Field number 1 provides the intercept portion of the linear model and is always multiplied by 1. Note that if multiple work-items are provided within X and Y, there will be multiple models returned. The models can be separated by their work item id (i.e. 'wi'). A single model can be extracted from a myriad model by using e.g., model(wi=myWI_id). GetModel should not be called when predicting using a previously persisted model (i.e. when training data was not passed to the module.

RETURN Model in DATASET(Layout_Model) format

SEE ML_core/Types.Layout_Model

OVERRIDE True

FUNCTION Betas

OLS \

DATASET(NumericField) Betas (DATASET(Layout_Model) model=GetModel)

Return raw Beta values as numeric fields Extracts Beta values from the model. Can be used during training and prediction phases. For use during training phase, the 'model' parameter can be omitted. GetModel will be called to retrieve the model based on the training data. For use during prediction phase, a previously persisted model should be provided. The 'number' field of the returned NumericField records specifies to which Y the coefficient applies. The 'id' field of the returned record indicates the position of the Beta value. ID = 1 provides the Beta for the constant term (i.e. the Y intercept) while subsequent values reflect the Beta for each correspondingly numbered X feature. Feature 1 corresponds to Beta with 'id' = 2 and so on. If 'model' contains multiple work-items, Separate sets of Betas will be returned for each of the 'myriad' models (distinguished by 'wi').

PARAMETER <u>model</u> Optional parameter provides a model that was previously retrieved using GetModel. If omitted, GetModel will be used as the model.

RETURN DATASET(NumericField) containing the Beta values.

FUNCTION Predict

OLS \

DATASET(NumericField) Predict (DATASET(NumericField) newX, DATASET(Layout_Model) model=GetModel)

Predict the dependent variable values (Y) for any set of independent variables (X). Returns a predicted Y values for each observation (i.e. record) of X. This supports the 'myriad' style interface in that multiple independent work items may be present in 'newX', and multiple independent models may be provided in 'model'. The resulting predicted values will also be separable by work item (i.e. wi).

PARAMETER <u>newX</u> The set of observations of independent variables in DATASET(NumericField) format.

PARAMETER model Optional. A model that was previously returned from GetModel (above). Note that a model from a previous run will only be valid if the field numbers in X are the same as when the model was learned. If this parameter is omitted, the current model will be used.

RETURN An estimation of the corresponding Y value for each observation of newX. Returned in DATASET(NumericField) format with field number (i.e. 'number') indicating the dependent variable that is predicted.



TRANSFORM makeRSQ

OLS \

R2Rec makeRSQ (CoCoRec coco)

ATTRIBUTE RSquared

OLS \

DATASET(R2Rec) RSquared

RSquared Calculate the R-Squared Metric used to assess the fit of the regression line to the training data. Since the regression has chosen the best (i.e. least squared error) line matching the data, this can be thought of as a measurement of the linearity of the training data. R Squared generally varies between 0 and 1, with 1 indicating an exact linear fit, and 0 indicating that a linear fit will have no predictive power. Negative values are possible under certain conditions, and indicate that the mean(Y) will be more predictive than any linear fit. Moderate values of R squared (e.g. .5) may indicate that the relationship of $X \rightarrow Y$ is non-linear, or that the measurement error is high relative to the linear correlation (e.g. many outliers). In the former case, increasing the dimensionality of X, such as by using polynomial variants of the features, may yield a better fit. R squared always increases when additional independent variables are added, so it should not be used to determine the optimal set of X variables to include. For that purpose, use Adjusted R Squared (below) which penalizes larger numbers of variables. Note that the result of this call is only meaningful during training phase (use case 1 above) as it is an analysis based on the training data which is not provided during a prediction-only phase.

RETURN DATASET(R2Rec) with one record per dependent variable, per work-item. The number field indicates the dependent variable and coresponds to the number field of the dependent (Y) variable to which it applies.

RECORD AnovaRec

OLS \

AnovaRec

TRANSFORM calcAnova

OLS \

(tmpRec le)

AnovaRec calcAnova

ATTRIBUTE Anova

OLS \

Anova

ANOVA (Analysis of Variance) report Analyzes the sources of variance. Basic ANOVA equality: Model + Error = Total Determines how much of the variance of Y is explained by the regression model, versus how much is due to the error term (i.e. unexplained variance). This attribute is only meaningful during the training phase. Provides one record per work-item. Each record provides the following statistics: - Total_SS - Total Sum of Squares (SS) variance of the dependent data - Model_SS - The SS variance represented within the model - Error_SS - The SS variance not reflected by the model (i.e. Total_SS - Error_SS) - Total_DF - The total degrees of freedom within the dependent data - Model_DF - Degrees of freedom of the model - Error_DF - Degrees of freedom of the error component - Total_MS - The Mean Square (MS) variance represented within the model - Error_MS - The MS variance not reflected by the model - Model_F - The F-Test statistic: Model_MS / Error_MS

RETURN DATASET(AnovaRec), one per work-item per dependent (Y) variable The number field indicates the dependent variable to which the analysis applies.

ATTRIBUTE SE

OLS \

DATASET(NumericField)

SE

Standard Error of the Regression Coefficients Describes the variability of the regression error for each coefficient. Only meaningful during the training phase.

RETURN DATASET(NumericField), one record per Beta coefficient per dependent variable per work-item. The 'id' field is the coefficient number, with 1 being the Y intercept, 2 being the coefficient for the first feature, etc. The 'number' field indicates the dependent variable to which the coefficient applies.

ATTRIBUTE TStat

OLS \

DATASET(NumericField) | TStat

T-Statistic The T-statistic identifies the significance of the value of each regression coefficient. Its calculation is simply the value of the coefficient divided by the Standard Error of the coefficient. A larger absolute value of the T-statistic indicates that the coefficient is more significant. Only meaningful during the training phase.

RETURN DATSET(NumericField), one record per Beta coefficient per dependent variable per work-item. The 'id' field is the coefficient number, with 1 being the Y intercept, 2 being the coefficient for the first feature, etc. The number field indicates the dependent variable to which the coefficient applies.

ATTRIBUTE AdjRSquared

OLS \

DATASET(R2Rec)

 ${\bf AdjRS quared}$

Adjusted R2 Calculate Adjusted R Squared which is a scaled version of R Squared that does not arbitrarily increase with the number of features. Adjusted R2, rather than R2 should always be used when trying to determine the best set of features to include in a model. When adding features, R2 will always increase, whether or not it improves the predictive power of the model. Adjusted R2, however, will only increase with the predictive power of the model.

RETURN DATASET(R2Rec), one record per dependent variable per work-item. The number field indicates the dependent variable and corresponds to the number field of the dependent (Y) variable to which it applies.

RECORD AICRec

OLS \

AICRec

ATTRIBUTE AIC

OLS \

DATASET(AICRec) AIC

Akaike Information Criterion (AIC) Information theory based criterion for assessing Goodness of Fit (GOF). Lower values mean better fit.

RETURN DATASET(AICRec), one record per dependent variable per work-item. The number field indicates the dependent variable and corresponds to the number field of the dependent (Y) variable to which it applies.

RECORD RangeVec

OLS \

Rar	igeVec	
Luui		

MODULE DistributionBase

OLS \

DistributionBase

(t_Count Nranges = 10000)

Children

- 1. Low
- 2. High
- 3. Density
- 4. RangeWidth
- 5. DensityV
- 6. CumulativeV
- 7. Cumulative
- 8. NTile
- 9. InvDensity
- 10. Discrete

ATTRIBUTE Low

OLS \setminus DistributionBase \setminus

Low

ATTRIBUTE High

OLS \ DistributionBase \

High

FUNCTION Density

OLS \ DistributionBase \

t_FieldReal Density

(t_FieldReal t)

ATTRIBUTE RangeWidth

OLS \ DistributionBase \

RangeWidth

FUNCTION DensityV

OLS \ DistributionBase \

DATASET(RangeVec) DensityV
()

FUNCTION CumulativeV

OLS \ DistributionBase \

	CumulativeV
(

FUNCTION Cumulative

OLS \ DistributionBase \

t_FieldReal	Cumulative
(t_FieldReal	t)

FUNCTION NTile

OLS \setminus DistributionBase \setminus

```
t_FieldReal NTile
(t_FieldReal Pc)
```

FUNCTION InvDensity

OLS \ DistributionBase \

	InvDensity
(t_FieldReal delta)

ATTRIBUTE Discrete

OLS \ DistributionBase \

Discrete

MODULE TDistribution

OLS \

TDistribution

(t_Discrete v_in,t_Count NRanges = 10000)

Children

- 1. DensityV
- 2. NTile
- 3. Discrete
- 4. InvDensity
- 5. High
- 6. Low
- 7. RangeWidth
- 8. Density
- 9. CumulativeV
- 10. Cumulative

FUNCTION DensityV

OLS \ TDistribution \

DATASET(RangeVec) DensityV

()

OVERRIDE True

FUNCTION NTile

OLS \ TDistribution \

t_FieldReal NTile
(t_FieldReal Pc)

OVERRIDE True

ATTRIBUTE Discrete

OLS \ TDistribution \

Discrete

INHERITED True

FUNCTION InvDensity

OLS \ TDistribution \

InvDensity

(t_FieldReal delta)



ATTRIBUTE High

OLS \ TDistribution \

High

OVERRIDE True

ATTRIBUTE Low

 $OLS \setminus TDistribution \setminus$

Low

INHERITED True

ATTRIBUTE RangeWidth

OLS \ TDistribution \

 ${\bf RangeWidth}$

FUNCTION Density

OLS \ TDistribution \

t_FieldReal Density
(t_FieldReal t)

OVERRIDE True

FUNCTION CumulativeV

OLS \ TDistribution \

CumulativeV ()

OVERRIDE True

FUNCTION Cumulative

OLS \ TDistribution \

t_FieldReal Cumulative (t_FieldReal t)

MODULE FDistribution

OLS \

FDistribution

(t_Discrete d1_in, t_Discrete d2_in, t_Count NRanges = 10000)

Children

- 1. DensityV
- 2. CumulativeV
- 3. Cumulative
- 4. NTile
- 5. InvDensity
- 6. Discrete
- 7. Low
- 8. High
- 9. RangeWidth
- 10. Density

FUNCTION DensityV

OLS \ FDistribution \

DATASET(RangeVec)	DensityV
()	

FUNCTION CumulativeV

OLS \ FDistribution \

CumulativeV ()

OVERRIDE True

FUNCTION Cumulative

OLS \ FDistribution \

t_FieldReal Cumulative
(t_FieldReal t)

OVERRIDE True

FUNCTION NTile

OLS \ FDistribution \

t_FieldReal NTile
(t_FieldReal Pc)

FUNCTION InvDensity

OLS \ FDistribution \

InvDensity

(t FieldReal delta)

INHERITED True

ATTRIBUTE Discrete

OLS \ FDistribution \

Discrete

INHERITED

ATTRIBUTE Low

OLS \ FDistribution \

Low

INHERITED True

ATTRIBUTE High

OLS \ FDistribution \

High **OVERRIDE** True **ATTRIBUTE** RangeWidth OLS \ FDistribution \ RangeWidth OVERRIDE True **FUNCTION** Density OLS \ FDistribution \ t_FieldReal Density (t FieldReal t) **OVERRIDE** True

MODULE NormalDistribution

OLS \

NormalDistribution
(t_Count NRanges)

Children

1.	Low
2.	High
3.	RangeWidth
4.	DensityV
5.	CumulativeV
6.	Cumulative
7.	NTile
8.	InvDensity
9.	Discrete
10.	Density
ΔΤΊ	TRIBUTE Low
,	
OLS	\ NormalDistribution \
L	ow
INH	ERITED True
ATT	TRIBUTE High
OI G	
OLS	\ NormalDistribution \
Н	igh
INH	ERITED True

ATTRIBUTE RangeWidth

OLS \setminus NormalDistribution \setminus

RangeWidth

OVERRIDE True

FUNCTION DensityV

OLS \ NormalDistribution \

DATASET(RangeVec) DensityV

()

OVERRIDE True

FUNCTION CumulativeV

OLS \ NormalDistribution \

CumulativeV

()

OVERRIDE True

FUNCTION Cumulative

OLS \ NormalDistribution \

Cumulative t_FieldReal (t_FieldReal t) **OVERRIDE** True **FUNCTION** NTile $OLS \setminus NormalDistribution \setminus$ t_FieldReal NTile (t_FieldReal Pc) **OVERRIDE** True **FUNCTION** InvDensity $OLS \setminus NormalDistribution \setminus$ InvDensity (t_FieldReal delta) INHERITED True **ATTRIBUTE** Discrete

OLS \ NormalDistribution \

Discrete



FUNCTION Density

OLS \ NormalDistribution \

t_FieldReal | Density

(t_FieldReal t)

OVERRIDE True

ATTRIBUTE pVal

OLS \

pVal

P-Value Calculate the P-value for each coefficient, which is the probability that the coefficient is insignificant (i.e. actually zero). A low P-value (e.g. .05) provides evidence that the coefficient is significant in the model. A high P-value indicates that the coefficient value should, in fact, be zero. P-value is related to the T-Statistic, and can be thought of as a normalized version of the T-Statistic. Only meaningful during the training phase.

RETURN DATSET(NumericField), one record per Beta coefficient per dependent variable per work-item. The 'id' field is the coefficient number, with 1 being the Y intercept, 2 being the coefficient for the first feature, etc. The number field indicates the dependent variable and corresponds to the number field of the dependent (Y) variable to which it applies.

RECORD ConfintRec

OLS \

ConfintRec				
------------	--	--	--	--

FUNCTION Confint

OLS \

ConfInt

(Types.t fieldReal level)

Confidence Interval The Confidence Interval determines the upper and lower bounds of each estimated coefficient given a confidence level (level) that is required. For example, one could say that there is a 95% probability (level) that the coefficient of the first independent variable is between 2.05 and 3.62. This allows error margins to be determined with the desired confidence level. If the confidence interval spans zero, it implies that the coefficient may not be significant at the specified confidence level.

PARAMETER <u>level</u> The level of confidence required, expressed as a percentage from 0.0 to 100.0

RETURN DATASET(ConfintRec) with one record per coefficient per dependent variable per work-item. The 'id' field is the coefficient number, with 1 being the Y intercept, 2 being the coefficient for the first feature, etc. The number field indicates the dependent variable and corresponds to the number field of the dependent (Y) variable to which it applies.

RECORD FTestRec

OLS \

FTestRec

ATTRIBUTE FTest

OLS \

DATASET(FTestRec)

FTest

F-Test Calculate the P-value for the full regression, which is the probability that all of the coefficients are insignificant (i.e. actually zero). A low P-value (e.g. .05) provides evidence that at least one coefficient is significant. A high P-value indicates that all the coefficient values should in fact be zero, implying that the regression has no statistically significant predictive power. P-value is related to the ANOVA F-Statistic, and can be thought of as a standardized version of the ANOVA F-Statistic. The F-Test and T-Test are similar, except that the T-test is used to test the significance of each coefficient, while the F-Test is used to test the significance of the entire regression. For simple linear regression (i.e. only one independent variable, the T-Test and F-Test are equivalent.

RETURN DATASET(FTestRec), one record per dependent variable per work-item. The number field indicates the dependent variable and corresponds to the number field of the dependent (Y) variable to which it applies.

LogisticRegression

Go Up

Table of Contents

т	١		1.4	\sim	- (•	•	1
н	⋖	inomi	വ	٠,	ont	711	-101	പരവ
┸	,	inomi	aιν	ر	om	. ua	וטוכ	1.001

Binomial confusion matrix

BinomialLogisticRegression.ecl

Binomial logistic regression using iteratively re-weighted least squares

Confusion.ecl

Detail confusion records to compare actual versus predicted response variable values

Constants.ecl

DataStats.ecl

Information about the datasets

Deviance_Analysis.ecl

Compare deviance information for an analysis of deviance

Deviance Detail.ecl

Detail deviance for each observation

dimm.ecl

Matrix multiply when either A or B is a diagonal and is passed as a vector

Distributions.ecl

ExtractBeta.ecl

Extract the beta values form the model dataset

ExtractBeta CI.ecl

Extract the beta values form the model dataset

ExtractBeta_pval.ecl

Extract the beta values form the model dataset

ExtractReport.ecl

Extract Report records from model

LogitPredict.ecl

Predict the category values with the logit function and the supplied beta coefficients

 ${\bf Logit Score. ecl}$

Calculate the score using the logit function and the the supplied beta coefficients

Model_Deviance.ecl

Model Deviance

Null_Deviance.ecl

Deviance for the null model, that is, a model with only an intercept

Types.ecl

LogisticRegression/

BinomialConfusion

Go Up

IMPORTS

LogisticRegression | LogisticRegression.Types | ML_Core.Types |

DESCRIPTIONS

FUNCTION BinomialConfusion

DATASET(Types.Binomial_Confusion_Summary)	BinomialConfusion
(DATASET(Core_Types.Confusion_Detail) d)	

Binomial confusion matrix. Work items with multinomial responses are ignored by this function. The higher value lexically is considered to be the positive indication.

PARAMETER $\underline{\mathbf{d}}$ confusion detail for the work item and classifier

RETURN confusion matrix for a binomial classifier

LogisticRegression/

${\bf Binomial Logistic Regression}$

Go Up

IMPORTS

LogisticRegression | LogisticRegression.Constants | ML_Core.Interfaces | ML_Core.Types |

DESCRIPTIONS

MODULE BinomialLogisticRegression

BinomialLogisticRegression

(UNSIGNED max_iter=200, REAL8 epsilon=Constants.default_epsilon, REAL8 ridge=Constants.default ridge)

Binomial logistic regression using iteratively re-weighted least squares.

PARAMETER <u>max_iter</u> maximum number of iterations to try

PARAMETER epsilon the minimum change in the Beta value estimate to continue

PARAMETER <u>ridge</u> a value to populate a diagonal matrix that is added to a matrix help assure that the matrix is invertible.

Children

1. GetModel: Calculate the model to fit the observation data to the observed classes

- 2. Classify: Classify the observations using a model
- 3. Report: Report the confusion matrix for the classifier and training data

FUNCTION GetModel

BinomialLogisticRegression \

```
DATASET(Types.Layout_Model) GetModel

(DATASET(Types.NumericField) observations,
DATASET(Types.DiscreteField) classifications)
```

Calculate the model to fit the observation data to the observed classes.

PARAMETER <u>observations</u> the observed explanatory values

PARAMETER <u>classifications</u> the observed classification used to build the model

RETURN the encoded model

OVERRIDE True

FUNCTION Classify

BinomialLogisticRegression \

```
DATASET(Types.Classify_Result) Classify

(DATASET(Types.Layout_Model) model,
DATASET(Types.NumericField) new_observations)
```

Classify the observations using a model.

PARAMETER model The model, which must be produced by a corresponding getModel function.

PARAMETER new_observations observations to be classified

RETURN Classification with a confidence value



FUNCTION Report

BinomialLogisticRegression \

```
DATASET(Types.Confusion_Detail) Report

(DATASET(Types.Layout_Model) model,
DATASET(Types.NumericField) observations,
DATASET(Types.DiscreteField) classifications)
```

Report the confusion matrix for the classifier and training data.

PARAMETER model the encoded model

PARAMETER observations the explanatory values.

PARAMETER <u>classifications</u> the classifications associated with the observations

RETURN the confusion matrix showing correct and incorrect results

LogisticRegression/

Confusion

Go Up

IMPORTS

ML_Core | ML_Core.Types | LogisticRegression | LogisticRegression.Types |

DESCRIPTIONS

FUNCTION Confusion

DATASET(Confusion_Detail)	Confusion
(DATASET(DiscreteField) de predicts)	pendents, DATASET(DiscreteField)

Detail confusion records to compare actual versus predicted response variable values.

PARAMETER dependents the original response values

PARAMETER predicts the predicted responses

RETURN confusion counts by predicted and actual response values.

LogisticRegression/

Constants

Go Up

DESCRIPTIONS

MODULE Constants

Constants

Children

- 1. limit_card
- 2. default_epsilon
- 3. default_ridge
- 4. local_cap
- 5. id_base
- 6. id_iters
- 7. id_delta
- 8. id_correct
- 9. id_incorrect
- $10. \ id_stat_set$
- 11. id_betas
- 12. id_betas_coef
- 13. id_betas_SE
- 14. base_builder
- 15. base_max_iter

16. base_e	epsilon
17. base_i	nd _vars
18. base_c	lep_vars
19. base_c	obs — — — — — — — — — — — — — — — — — — —
20. builder	·_irls_local
21. builder	·_irls_global
22. builder	_softmax
ATTRIBU	JTE limit_card
Constants \	
UNSIGNED2	limit_card
ONSTGNEDZ	mmt_card
ATTRIBL	JTE default_epsilon
Constants \	
REAL8 de	fault_epsilon
ATTRIBU	JTE default_ridge

Constants \setminus

REAL8 default_ridge

ATTRIBUTE local_cap Constants \ UNSIGNED4 local_cap ATTRIBUTE id_base Constants \ id_base ATTRIBUTE id_iters Constants \setminus id_iters ATTRIBUTE id_delta

id_delta

Constants \

ATTRIBUTE id_correct

Constants \

id_correct	
ATTRIBUTE id_incorrect	
Constants \	
id_incorrect	
ATTRIBUTE id_stat_set	
Constants \	
id_stat_set	
ATTRIBUTE id_betas	
Constants \	
id_betas	
ATTRIBUTE id_betas_coef	
MINDOILE IN SCHOOL COCK	
Constants \	
id_betas_coef	

ATTRIBUTE id_betas_SE Constants \ id_betas_SE **ATTRIBUTE** base_builder Constants \ base_builder **ATTRIBUTE** base_max_iter Constants \ base_max_iter **ATTRIBUTE** base_epsilon Constants \ base_epsilon

ATTRIBUTE base_ind_vars

Constants \

base_ind_vars	
	_
ATTRIBUTE base_dep_vars	
Constants \	
base_dep_vars	
	_
ATTRIBUTE base_obs	
Constants \	
base_obs	
	—
ATTRIBUTE builder_irls_local	
Constants \	
builder_irls_local	
ATTRIBUTE builder_irls_global	
Constants	
Constants \	
builder_irls_global	

ATTRIBUTE builder_softmax

						١
	α r	10	ta:	nt	C	١
$\mathbf{\circ}$	$\mathbf{o}_{\mathbf{I}}$	\mathbf{r}	υcu.	ш	JID.	

builder_softmax

DataStats

Go Up

IMPORTS

LogisticRegression | LogisticRegression.Types | LogisticRegression.Constants | ML_Core.Types |

DESCRIPTIONS

FUNCTION DataStats

DATASET(Types.Data_Info) DataStats

(DATASET(Core_Types.NumericField) indep,
DATASET(Core_Types.DiscreteField) dep, BOOLEAN
field_details=FALSE)

Information about the datasets. Without details the range for the x and y (independent and dependent) columns. Note that a column of all zero values cannot be distinguished from a missing column. When details are requested, the cardinality, minimum, and maximum values are returned. A zero cardinality is returned when the field cardinality exceeds the Constants.limit_card value.

PARAMETER indep data set of independent variables

PARAMETER dep data set of dependent variables

PARAMETER field details Boolean directive to provide field level info

Deviance_Analysis

Go Up

IMPORTS

LogisticRegression | LogisticRegression. Types |

DESCRIPTIONS

FUNCTION Deviance_Analysis

DATASET(Types.AOD_Record) Deviance_Analysis

(DATASET(Types.Deviance_Record) proposed,
DATASET(Types.Deviance_Record) base)

Compare deviance information for an analysis of deviance.

PARAMETER proposed the proposed model

PARAMETER <u>base</u> the base model for comparison

RETURN the comparison of the deviance between the models

Deviance_Detail

Go Up

IMPORTS

ML_Core | ML_Core.Types | LogisticRegression | LogisticRegression.Types |

DESCRIPTIONS

FUNCTION Deviance_Detail

DATASET(Types.Observation_Deviance) Deviance_Detail

(DATASET(Core_Types.DiscreteField) dependents,
DATASET(Types.Raw_Prediction) predicts)

Detail deviance for each observation.

PARAMETER dependents original dependent records for the model

PARAMETER predicts the predicted values of the response variable

RETURN the deviance information by observation and the log likelihood of the predicted result.

dimm

Go Up

IMPORTS

std.BLAS | std.BLAS.Types |

DESCRIPTIONS

EMBED dimm

```
Types.matrix_t dimm

(BOOLEAN transposeA, BOOLEAN transposeB, BOOLEAN diagonalA, BOOLEAN diagonalB, Types.dimension_t m, Types.dimension_t n,

Types.dimension_t k, Types.value_t alpha, Types.matrix_t A,

Types.matrix_t B, Types.value_t beta=0.0, Types.matrix_t C=[])
```

Matrix multiply when either A or B is a diagonal and is passed as a vector. alpha*op(A) op(B) + beta*C where op() is transpose

PARAMETER transpose true when transpose of A is used

PARAMETER transpose true when transpose of B is used

PARAMETER diagonal true when A is the diagonal matrix

PARAMETER diagonal true when B is the diagonal matrix

PARAMETER m number of rows in product

PARAMETER n number of columns in product

PARAMETER <u>k</u> number of columns/rows for the multiplier/multiplicand

PARAMETER alpha scalar used on A

PARAMETER <u>A</u> matrix A

PARAMETER B matrix B

PARAMETER beta scalar for matrix C

PARAMETER <u>C</u> matrix C or empty

Distributions

Go Up

IMPORTS

ML_Core.Constants | ML_Core.Math |

DESCRIPTIONS

MODULE Distributions

Distributions

Children

- 1. Normal_CDF: Cumulative Distribution of the standard normal distribution, the probability that a normal random variable will be smaller than x standard deviations above or below the mean
- 2. Normal_PPF: Normal Distribution Percentage Point Function
- 3. T CDF: Students t distribution integral evaluated between negative infinity and x
- 4. T_PPF: Percentage point function for the T distribution
- 5. Chi2 CDF: The cumulative distribution function for the Chi Square distribution
- 6. Chi2_PPF: The Chi Squared PPF function

FUNCTION Normal_CDF

Distributions \

REAL8	Normal_CDF
(REAL8	(x)

Cumulative Distribution of the standard normal distribution, the probability that a normal random variable will be smaller than x standard deviations above or below the mean. Taken from C/C++ Mathematical Algorithms for Scientists and Engineers, n. Shammas, McGraw-Hill, 1995

PARAMETER $\underline{\mathbf{x}}$ the number of standard deviations

FUNCTION Normal_PPF

Distributions \

REAL8	Normal_PPF
(REAL8	(X)

Normal Distribution Percentage Point Function. Translated from C/C++ Mathematical Algorithms for Scientists and Engineers, N. Shammas, McGraw-Hill, 1995

PARAMETER <u>x</u> probability

FUNCTION T_CDF

Distributions \

```
REAL8 T_CDF

(REAL8 x, REAL8 df)
```

Students t distribution integral evaluated between negative infinity and x. Translated from NIST SEL DATAPAC Fortran TCDF.f source

 $\begin{array}{c} \textbf{PARAMETER} & \underline{\mathbf{x}} \text{ value of the evaluation} \\ \\ \textbf{PARAMETER} & \underline{\mathbf{df}} \text{ degrees of freedom} \\ \end{array}$

FUNCTION T_PPF

Distributions \

```
REAL8 T_PPF

(REAL8 x, REAL8 df)
```

Percentage point function for the T distribution. Translated from NIST SEL DATAPAC Fortran TPPF.f source

FUNCTION Chi2_CDF

Distributions \

```
REAL8 Chi2_CDF

(REAL8 x, REAL8 df)
```

The cumulative distribution function for the Chi Square distribution. the CDF for the specified degrees of freedom. Translated from the NIST SEL DATAPAC Fortran subroutine CHSCDF.

FUNCTION Chi2_PPF

Distributions \

```
REAL8 Chi2_PPF

(REAL8 x, REAL8 df)
```

The Chi Squared PPF function. Translated from the NIST SEL DATAPAC Fortran subroutine CHSPPF.

ExtractBeta

Go Up

IMPORTS

LogisticRegression | LogisticRegression.Types | ML_Core.Types |

DESCRIPTIONS

FUNCTION ExtractBeta

ExtractBeta

(DATASET(Core_Types.Layout_Model) mod_ds)

Extract the beta values form the model dataset.

PARAMETER mod_ds the model dataset

RETURN a beta values as Model Coefficient records, zero as the constant term.

ExtractBeta_CI

Go Up

IMPORTS

LogisticRegression | LogisticRegression.Types | ML_Core.Types |

DESCRIPTIONS

FUNCTION ExtractBeta_CI

DATASET(Types.Confidence_Model_Coef)	ExtractBeta_CI
<pre>(DATASET(Core_Types.Layout_Model) mod level)</pre>	_ds, REAL8

Extract the beta values form the model dataset.

PARAMETER mod_ds the model dataset

PARAMETER <u>level</u> the significance value for the intervals

RETURN the beta values with confidence intervals term.

ExtractBeta_pval

Go Up

IMPORTS

LogisticRegression | LogisticRegression.Types | ML_Core.Types |

DESCRIPTIONS

FUNCTION ExtractBeta_pval

DATASET(Types.pval_Model_Coef)	ExtractBeta_pval
(DATASET(Core_Types.Layout_Mode	l) mod_ds)

Extract the beta values form the model dataset.

PARAMETER mod_ds the model dataset

RETURN the beta values with p-values as Model Coefficient records, zero as the constant term.

ExtractReport

Go Up

IMPORTS

LogisticRegression | LogisticRegression.Types | LogisticRegression.Constants | ML_Core.Types |

DESCRIPTIONS

FUNCTION ExtractReport

DATASET(Types.Model_Report) ExtractReport

(DATASET(Core_Types.Layout_Model) mod_ds)

Extract Report records from model

PARAMETER mod_ds the model dataset

RETURN the model report dataset

LogitPredict

Go Up

IMPORTS

LogisticRegression | LogisticRegression.Types | ML_Core.Types |

DESCRIPTIONS

FUNCTION LogitPredict

DATASET(Classify_Result)	LogitPredict
(DATASET(Model_Coef) coef independents)	, DATASET(NumericField)

Predict the category values with the logit function and the supplied beta coefficients.

PARAMETER <u>coef</u> the model beta coefficients

PARAMETER independents the observations

RETURN the predicted category values and a confidence score

LogitScore

Go Up

IMPORTS

LogisticRegression | LogisticRegression.Types | ML_Core.Types |

DESCRIPTIONS

FUNCTION LogitScore

DATASET(Raw_Prediction) LogitScore

(DATASET(Model_Coef) coef, DATASET(NumericField)
independents)

Calculate the score using the logit function and the supplied beta coefficients.

PARAMETER coef the model beta coefficients

PARAMETER independents the observations

RETURN the raw prediction value

Model_Deviance

Go Up

IMPORTS

LogisticRegression | LogisticRegression. Types |

DESCRIPTIONS

FUNCTION Model_Deviance

DATASET(Types.Deviance_Record) Model_Deviance

(DATASET(Types.Observation_Deviance) od,
DATASET(Types.Model_Coef) mod)

Model Deviance.

PARAMETER od observation deviance record

PARAMETER <u>mod</u> model co-efficients

RETURN model deviance

$\frac{{\bf Logistic Regression}/}{{\bf Null_Deviance}}$

Go Up

IMPORTS

LogisticRegression | LogisticRegression. Types |

DESCRIPTIONS

FUNCTION Null_Deviance

DATASET(Types.Deviance_Record)	Null_Deviance
(DATASET(Types.Observation_Devi	ance) od)

Deviance for the null model, that is, a model with only an intercept.

PARAMETER <u>od</u> Observation Deviance record set.

RETURN a data set of the null model deviances for each work item and classifier.

Types

Go Up

IMPORTS

ML_Core.Types |

DESCRIPTIONS

MODULE Types

Types

Children

- 1. t_Universe
- 2. Field_Desc
- 3. Data_Info
- 4. NumericField_U
- 5. DiscreteField_U
- 6. Layout_Column_Map
- 7. Classifier_Stats
- 8. Model_Report
- 9. Binomial_Confusion_Summary
- 10. Model_Coef

11. Confidence_Model_Coef	
12. pval_Model_Coef	
13. Raw_Prediction	
14. Observation_Deviance	
15. Deviance_Record	
16. AOD_Record	
ATTRIBUTE t_Universe	
Types \	
t_Universe	
RECORD Field_Desc	
RECORD Field_Desc	
Types \	
Field_Desc	
Field_Desc	
Field_Desc	
RECORD Data_Info	
RECORD Data_Info	
RECORD Data_Info Types \	

RECORD NumericField_U
Types \
NumericField_U
RECORD DiscreteField_U
Types \
DiscreteField_U
RECORD Layout_Column_Map
Types \
Layout_Column_Map
Layout_Column_Map
Layout_Column_Map
Layout_Column_Map RECORD Classifier_Stats
RECORD Classifier_Stats
RECORD Classifier_Stats Types \
RECORD Classifier_Stats Types \
RECORD Classifier_Stats Types \

Model_Report
RECORD Binomial_Confusion_Summary
Types \
Binomial_Confusion_Summary
RECORD Model_Coef
MECOND Model_Coci
Types \
Model_Coef
Woder_Coer
DECORD Confidence Model Conf
RECORD Confidence_Model_Coef
Types \
Confidence_Model_Coef
RECORD pval_Model_Coef
Types \
pval_Model_Coef

RECORD Raw_Prediction
Types \
Raw_Prediction
RECORD Observation_Deviance
$\mathrm{Types} \setminus$
Observation_Deviance
RECORD Deviance_Record
Types \
Deviance_Record
RECORD AOD_Record
Types \
AOD_Record

ML_Core

Go Up

Table of Contents

AppendID.ecl
AppendSeqID.ecl
Config.ecl
Constants.ecl
Useful constants
${ m FieldAggregates.ecl}$
FromField.ecl
Generate.ecl
ToField.ecl
Γypes.ecl
Interfaces
Math
Γests
Utils

$\begin{array}{c} {\rm ML_Core/} \\ {\bf AppendID} \end{array}$

Go Up

DESCRIPTIONS

MACRO AppendID

	AppendID
(dIn,idfield,dOut)

${\bf AppendSeqID}$

Go Up

DESCRIPTIONS

MACRO AppendSeqID

AppendSeqID (dIn,idfield,dOut)

$\frac{\mathrm{ML_Core}}{Config}$

Go Up

DESCRIPTIONS

MODULE Config

Config

Children

- 1. MaxLookup
- 2. Discrete
- 3. RoundingError

ATTRIBUTE MaxLookup

Config \

MaxLookup

ATTRIBUTE Discrete

Config \

Discrete

ATTRIBUTE RoundingError

Config \

 ${\bf Rounding Error}$

ML_Core/ Constants

Go Up

DESCRIPTIONS

MODULE Constants

Constants

Useful constants

Children

- 1. Pi: Constant PI
- 2. Root_2 : Constant square root of 2

ATTRIBUTE Pi

Constants \

 \mathbf{Pi}

Constant PI

ATTRIBUTE Root_2

Constants \

Constant square root of 2

$\frac{\mathrm{ML_Core}/}{\mathbf{FieldAggregates}}$

Go Up

IMPORTS

 $\operatorname{ML_Core} \mid \operatorname{ML_Core}.\operatorname{Types} \mid \operatorname{ML_Core}.\operatorname{Utils} \mid \operatorname{std.system}.\operatorname{ThorLib} \mid$

DESCRIPTIONS

MODULE FieldAggregates

FieldAggregates

(DATASET(Types.NumericField) d)

Children

- 1. Simple
- 2. SimpleRanked
- 3. Medians
- 4. MinMedNext
- 5. Buckets
- 6. BucketRanges
- 7. Modes
- 8. Cardinality
- 9. RankedInput

11. NTileRanges
ATTRIBUTE Simple
${\sf FieldAggregates} \setminus$
Simple
ATTRIBUTE SimpleRanked
${ m FieldAggregates} \setminus$
SimpleRanked
ATTRIBUTE Medians
${ m FieldAggregates} \setminus$
Medians
ATTRIBUTE MinMedNext
${ m FieldAggregates} \setminus$
MinMedNext

10. NTiles

FUNCTION Buckets

FieldAggregates \
Buckets
(Types.t_Discrete n)
FUNCTION BucketRanges
FieldAggregates \
BucketRanges
(Types.t_Discrete n)
ATTRIBUTE Modes
FieldAggregates \
Modes
ATTRIBUTE Cardinality
FieldAggregates \
Cardinality

ATTRIBUTE RankedInput

FieldAggregates \

 ${\bf Ranked Input}$

FUNCTION NTiles

FieldAggregates \

NTiles

(Types.t_Discrete n)

FUNCTION NTileRanges

FieldAggregates \

NTileRanges

(Types.t_Discrete n)

$\begin{array}{c} \text{ML_Core/} \\ \textbf{FromField} \end{array}$

 ${\rm Go}\ {\rm Up}$

DESCRIPTIONS

MACRO FromField

FromField

(dIn,10ut,dOut,dMap=")

$rac{ ext{ML_Core}/}{ ext{Generate}}$

Go Up

IMPORTS

ML_Core | ML_Core.Types |

DESCRIPTIONS

MODULE Generate

Generate

Children

- 1. tp_Method
- 2. MethodName
- 3. ToPoly

ATTRIBUTE tp_Method

Generate \

 tp_Method

FUNCTION MethodName

Generate \setminus

MethodName

(tp_Method x)

FUNCTION ToPoly

$Generate \ \backslash$

ToPoly

(DATASET(Types.NumericField) seedCol, UNSIGNED maxN=6)

$\begin{array}{c} \text{ML_Core/} \\ \textbf{ToField} \end{array}$

 ${\rm Go}\ {\rm Up}$

DESCRIPTIONS

MACRO ToField

ToField

(dIn,dOut,idfield=", wifield=", wivalue=",datafields=")

$\frac{\mathrm{ML_Core}}{Types}$

Go Up

DESCRIPTIONS

MODULE Types

Types

Children

- 1. t_RecordID
- $2. \ t_FieldNumber$
- $3. t_FieldReal$
- 4. t_FieldSign
- 5. t_Discrete
- 6. t_Item
- 7. t_Count
- 8. t_Work_Item
- 9. AnyField
- 10. NumericField
- 11. DiscreteField
- 12. Layout_Model
- 13. Classify_Result
- 14. l_result
- 15. Confusion_Detail

17. t_node	
18. t_level	
19. NodeID	
ATTRIBUTE t_RecordID	
ATTRIBUTE I_Recordib	
Types \	
t_RecordID	
ATTRIBUTE t_FieldNumber	
Types \	
t_FieldNumber	
ATTRIBUTE t_FieldReal	
Types \	
Types \	
t_FieldReal	
ATTRIBUTE t_FieldSign	
ATTRIBOTE (_I leidəlgii	
Types \	

16. ItemElement

t_FieldSign	
ATTRIBUTE t_Discrete	
Types \	
t_Discrete	
ATTRIBUTE t_ltem	
Types \	
t_Item	
ATTRIBUTE t_Count	
Types \	
t_Count	
ATTRIBUTE t_Work_Item	
Types \	
t_Work_Item	

RECORD AnyField	
Types \	
AnyField	
RECORD NumericField	
Types \	
NumericField	
RECORD DiscreteField	
Types \	
DiscreteField	
RECORD Layout_Model	
Types \	
Layout_Model	
RECORD Classify_Result	
Types \	

Classify_Result	
RECORD I_result	
Types \	
l_result	
RECORD Confusion_Detail	
$\mathrm{Types} \setminus$	
Types \	
Confusion_Detail	
RECORD ItemElement	
$\mathrm{Types} \setminus$	
ItemElement	
ATTRIBUTE t_node	
$\mathrm{Types} \setminus$	
t_node	

ATTRIBUTE t_level Types \

t_level

RECORD NodelD

Types \setminus

NodeID

Interfaces

Go Up

Table of Contents

IClassify.ecl

Interface definition for Classification

IRegression.ecl

Interface Definition for Regression Modules Regression learns a function that maps a set of input data to one or more output variables

ML_Core/ Interfaces/ IClassify

Go Up

IMPORTS

ML_Core | ML_Core.Types |

DESCRIPTIONS

MODULE IClassify

IClassify

Interface definition for Classification. Actual implementation modules will probably take parameters.

Children

- 1. GetModel: Calculate the model to fit the observation data to the observed classes
- 2. Classify: Classify the observations using a model
- 3. Report: Report the confusion matrix for the classifier and training data

FUNCTION GetModel

IClassify \

DATASET(Types.Layout_Model) GetModel (DATASET(Types.NumericField) observations, DATASET(Types.DiscreteField) classifications)

Calculate the model to fit the observation data to the observed classes.

PARAMETER observations the observed explanatory values

PARAMETER <u>classifications</u> the observed classification used to build the model

RETURN the encoded model

FUNCTION Classify

IClassify \

```
DATASET(Types.Classify_Result) Classify

(DATASET(Types.Layout_Model) model,

DATASET(Types.NumericField) new_observations)
```

Classify the observations using a model.

PARAMETER model The model, which must be produced by a corresponding getModel function.

PARAMETER new_observations observations to be classified

RETURN Classification with a confidence value

FUNCTION Report

IClassify \

```
DATASET(Types.Confusion_Detail) Report

(DATASET(Types.Layout_Model) model,
DATASET(Types.NumericField) observations,
DATASET(Types.DiscreteField) classifications)
```

Report the confusion matrix for the classifier and training data.

PARAMETER model the encoded model

PARAMETER observations the explanatory values.

PARAMETER classifications the classifications associated with the observations

RETURN the confusion matrix showing correct and incorrect results

ML_Core/ Interfaces/

IRegression

Go Up

IMPORTS

ML_Core | ML_Core.Types |

DESCRIPTIONS

MODULE IRegression

IRegression

(DATASET(NumericField) X=empty data, DATASET(NumericField) Y=empty data)

Interface Definition for Regression Modules Regression learns a function that maps a set of input data to one or more output variables. The resulting learned function is known as the model. That model can then be used repetitively to predict (i.e. estimate) the output value(s) based on new input data.

PARAMETER X The independent data in DATASET(NumericField) format. Each statistical unit (e.g. record) is identified by 'id', and each feature is identified by field number (i.e. 'number').

PARAMETER Y The dependent variable(s) in DATASET(NumericField) format. Each statistical unit (e.g. record) is identified by 'id', and each feature is identified by field number (i.e. 'number').

Children

- 1. GetModel: Calculate and return the 'learned' model The model may be persisted and later used to make predictions using 'Predict' below
- 2. Predict: Predict the output variable(s) based on a previously learned model

ATTRIBUTE GetModel

IRegression \

DATASET(Layout_Model) GetModel

Calculate and return the 'learned' model The model may be persisted and later used to make predictions using 'Predict' below.

RETURN DATASET(LayoutModel) describing the learned model parameters

FUNCTION Predict

IRegression \

DATASET(NumericField) Predict

(DATASET(NumericField) newX, DATASET(Layout_Model) model)

Predict the output variable(s) based on a previously learned model

PARAMETER <u>newX</u> DATASET(NumericField) containing the X values to b predicted.

RETURN DATASET(NumericField) containing one entry per observation (i.e. id) in newX. This represents the predicted values for Y.

Math

Go Up

Table of Contents

Beta.ecl

Return the beta value of two positive real numbers, x and y

Distributions.ecl

DoubleFac.ecl

The 'double' factorial is defined for ODD n and is the product of all the odd numbers up to and including that number

Fac.ecl

Factorial function

gamma.ecl

Return the value of gamma function of real number x A wrapper for the standard C tgamma function

log_gamma.ecl

Return the value of the log gamma function of the absolute value of X

lowerGamma.ecl

Return the lower incomplete gamma value of two real numbers,

NCK.ecl

Poly.ecl

Evaluate a polynomial from a set of co-effs

StirlingFormula.ecl

Stirling's formula

upperGamma.ecl

Return the upper incomplete gamma value of two real numbers, x and y

$\begin{array}{c} \mathrm{ML_Core/\ Math/} \\ Beta \end{array}$

Go Up

IMPORTS

ML_Core.Math |

DESCRIPTIONS

FUNCTION Beta

Beta

(REAL8 x, REAL8 y)

Return the beta value of two positive real numbers, **x** and **y**

PARAMETER $\underline{\mathbf{x}}$ the value of the first number

PARAMETER $\underline{\mathbf{y}}$ the value of the second number

RETURN the beta value

ML_Core/ Math/ Distributions

Go Up

IMPORTS

ML_Core.Constants | ML_Core.Math |

DESCRIPTIONS

MODULE Distributions

Distributions

Children

- 1. Normal_CDF: Cumulative Distribution of the standard normal distribution, the probability that a normal random variable will be smaller than x standard deviations above or below the mean
- 2. Normal_PPF: Normal Distribution Percentage Point Function
- 3. T CDF: Students t distribution integral evaluated between negative infinity and x
- 4. T_PPF: Percentage point function for the T distribution
- 5. Chi2 CDF: The cumulative distribution function for the Chi Square distribution
- 6. Chi2_PPF: The Chi Squared PPF function

FUNCTION Normal_CDF

Distributions \

REAL8	Normal_CDF
(REAL8 x)	

Cumulative Distribution of the standard normal distribution, the probability that a normal random variable will be smaller than x standard deviations above or below the mean. Taken from C/C++ Mathematical Algorithms for Scientists and Engineers, n. Shammas, McGraw-Hill, 1995

PARAMETER $\underline{\mathbf{x}}$ the number of standard deviations

FUNCTION Normal_PPF

Distributions \

REAL8	Normal_PPF
(REAL8 x)	

Normal Distribution Percentage Point Function. Translated from C/C++ Mathematical Algorithms for Scientists and Engineers, N. Shammas, McGraw-Hill, 1995

PARAMETER <u>x</u> probability

FUNCTION T_CDF

Distributions \

```
REAL8 T_CDF

(REAL8 x, REAL8 df)
```

Students t distribution integral evaluated between negative infinity and x. Translated from NIST SEL DATAPAC Fortran TCDF.f source

 $\begin{array}{c} \textbf{PARAMETER} & \underline{\mathbf{x}} \text{ value of the evaluation} \\ \\ \textbf{PARAMETER} & \underline{\mathbf{df}} \text{ degrees of freedom} \\ \end{array}$

FUNCTION T_PPF

Distributions \

```
REAL8 T_PPF

(REAL8 x, REAL8 df)
```

Percentage point function for the T distribution. Translated from NIST SEL DATAPAC Fortran TPPF.f source

FUNCTION Chi2_CDF

Distributions \

```
REAL8 Chi2_CDF

(REAL8 x, REAL8 df)
```

The cumulative distribution function for the Chi Square distribution. the CDF for the specified degrees of freedom. Translated from the NIST SEL DATAPAC Fortran subroutine CHSCDF.

FUNCTION Chi2_PPF

Distributions \

```
REAL8 Chi2_PPF

(REAL8 x, REAL8 df)
```

The Chi Squared PPF function. Translated from the NIST SEL DATAPAC Fortran subroutine CHSPPF.

ML_Core/ Math/ DoubleFac

Go Up

DESCRIPTIONS

EMBED DoubleFac

REAL8	DoubleFac
(INTEGER2 i)	

The 'double' factorial is defined for ODD n and is the product of all the odd numbers up to and including that number. We are extending the meaning to even numbers to mean the product of the even numbers up to and including that number. Thus DoubleFac(8) = 8*6*4*2 We also defend against i < 2 (returning 1.0)

 $\begin{array}{c} \textbf{PARAMETER} & \underline{\mathbf{i}} \text{ the value used in the calculation} \\ \end{array}$

RETURN the factorial of the sequence, declining by 2

$\frac{\mathrm{ML_Core}/\ \mathrm{Math}/}{Fac}$

Go Up

DESCRIPTIONS

EMBED Fac

REAL8	Fac
(UNSIGNED2 i)	

Factorial function

PARAMETER $\underline{\mathbf{i}}$ the value used, $(\mathbf{i})(\mathbf{i}-1)(\mathbf{i}-2)\dots(2)$

RETURN the factorial i!

$\frac{\mathrm{ML_Core}/\mathrm{\ Math}/}{gamma}$

Go Up

DESCRIPTIONS

EMBED gamma

REAL8	gamma
(REAL8 x)	

Return the value of gamma function of real number x A wrapper for the standard C tgamma function.

PARAMETER $\underline{\mathbf{x}}$ the input x

RETURN the value of GAMMA evaluated at x

$\frac{\mathrm{ML_Core/\ Math/}}{log_gamma}$

Go Up

DESCRIPTIONS

EMBED log_gamma

REAL8	log_gamma
(REAL8 x)	

Return the value of the log gamma function of the absolute value of X. A wrapper for the standard C lgamma function. Avoids the race condition found on some platforms by taking the absolute value of the of the input argument.

PARAMETER $\underline{\mathbf{x}}$ the input x

RETURN the value of the log of the GAMMA evaluated at ABS(x)

$\frac{\mathrm{ML_Core}/\ \mathrm{Math}/}{lowerGamma}$

Go Up

DESCRIPTIONS

EMBED lowerGamma

REAL8	lowerGamma
(REAL8 x, REAL8 y)	

Return the lower incomplete gamma value of two real numbers, x and y

PARAMETER $\underline{\mathbf{x}}$ the value of the first number

PARAMETER $\underline{\mathbf{y}}$ the value of the second number

RETURN the lower incomplete gamma value

$\frac{\mathrm{ML_Core}/\ \mathrm{Math}/}{\mathrm{NCK}}$

Go Up

IMPORTS

 $\operatorname{ML_Core.Math} \mid$

DESCRIPTIONS

FUNCTION NCK

REAL8 NCK

(INTEGER2 N, INTEGER2 K)

$\begin{array}{c} \mathrm{ML_Core/\ Math/} \\ \mathbf{Poly} \end{array}$

Go Up

DESCRIPTIONS

EMBED Poly

REAL8	Poly
(REAL8	x, SET OF REAL8 Coeffs)

Evaluate a polynomial from a set of co-effs. Co-effs 1 is assumed to be the HIGH order of the equation. Thus for ax^2+bx+c - the set would need to be Coef := [a,b,c];

PARAMETER $\underline{\mathbf{x}}$ the value of x in the polynomial

PARAMETER Coeffs a set of coefficients for the polynomial. The ALL set is considered to be all zero values

RETURN value of the polynomial at x

$\frac{\mathrm{ML_Core/\ Math/}}{StirlingFormula}$

Go Up

IMPORTS

ML_Core.Math | ML_Core.Constants |

DESCRIPTIONS

FUNCTION StirlingFormula

StirlingFormula

(REAL x)

Stirling's formula

PARAMETER $\underline{\mathbf{x}}$ the point of evaluation

RETURN evaluation result

$\begin{array}{c} {\rm ML_Core/\ Math/} \\ upperGamma \end{array}$

Go Up

DESCRIPTIONS

EMBED upperGamma

REAL8	upperGamma
(REAL8	x, REAL8 y)

Return the upper incomplete gamma value of two real numbers, ${\bf x}$ and ${\bf y}$.

PARAMETER $\underline{\mathbf{x}}$ the value of the first number

PARAMETER y the value of the second number

RETURN the upper incomplete gamma value

Tests

Go Up

Table of Contents

Check_Dist.ecl	
field_aggregates.ecl	
generate.ecl	
test_appends.ecl	
test_discrete.ecl	
to_from.ecl	
Validate_Betas.ecl	
Validate_Gammas.ecl	



Go Up

IMPORTS

ML_Core.Math.Distributions | ML_Core | python |

DESCRIPTIONS

ATTRIBUTE Check_Dist

Check_Dist

$\begin{array}{c} {\rm ML_Core/\ Tests/} \\ \\ field_aggregates \end{array}$

Go Up

IMPORTS

ML_Core | ML_Core.Types |

DESCRIPTIONS

ATTRIBUTE field_aggregates

 $field_aggregates$

ML_Core/ Tests/ generate

Go Up

IMPORTS

ML_Core |

DESCRIPTIONS

ATTRIBUTE generate

generate

$\begin{array}{c} \text{ML_Core/ Tests/} \\ test_appends \end{array}$

Go Up

IMPORTS

ML_Core | std.system.thorlib |

DESCRIPTIONS

ATTRIBUTE test_appends

 $test_appends$

$\begin{array}{c} \text{ML_Core/ Tests/} \\ test__discrete \end{array}$

Go Up

IMPORTS

ML_Core | ML_Core.Types |

DESCRIPTIONS

ATTRIBUTE test_discrete

test_discrete

$$\frac{\mathrm{ML_Core/\ Tests/}}{to_from}$$

Go Up

IMPORTS

ML_Core | ML_Core.Types |

DESCRIPTIONS

ATTRIBUTE to_from

to_from

$\begin{array}{c} {\rm ML_Core/\ Tests/} \\ {\bf Validate_Betas} \end{array}$

Go Up

IMPORTS

ML_Core | ML_Core.Math | python |

DESCRIPTIONS

ATTRIBUTE Validate_Betas

Validate_Betas

$\begin{array}{c} {\rm ML_Core/\ Tests/} \\ {\bf Validate_Gammas} \end{array}$

Go Up

IMPORTS

ML_Core | ML_Core.Math | python |

DESCRIPTIONS

ATTRIBUTE Validate_Gammas

 $Validate_Gammas$

Utils

Go Up

Table of Contents

Fat.ecl

Will take a potentially sparse file d and fill in the missing

FatD.ecl

Will take a potentially sparse file d and fill in the missing

Gini.ecl

Creates a file of pivot/target pairs with a Gini impurity value

SequenceInField.ecl

Given a file which is sorted by the work item identifier and INFIELD (and possibly other values), add sequence numbers within the range of each infield

ML_Core/ Utils/ Fat

Go Up

IMPORTS

ML_Core.Types |

DESCRIPTIONS

FUNCTION Fat

DATASET(Types.NumericField)	Fat
(DATASET(Types.NumericField)	d0, Types.t_FieldReal v=0)

Will take a potentially sparse file d and fill in the missing with value v for Numeric Field datasets

PARAMETER <u>d0</u> They myriad format Numeric Field dataset to be filled

PARAMETER $\underline{\mathbf{v}}$ The value to assign missing records

RETURN A full Numeric Field dataset with every field populated

ML_Core/ Utils/ FatD

Go Up

IMPORTS

ML_Core.Types |

DESCRIPTIONS

FUNCTION FatD

DATASET(Types.DiscreteField)	FatD
(DATASET(Types.DiscreteField)	d0, Types.t_Discrete v=0)

Will take a potentially sparse file d and fill in the missing with value v for Discrete Field datasets

PARAMETER <u>d0</u> They myriad format Discrete Field dataset to be filled

PARAMETER $\underline{\mathbf{v}}$ The value to assign missing records

RETURN A full Discrete Field dataset with every field populated

ML_Core/ Utils/ Gini

Go Up

DESCRIPTIONS

MACRO Gini

Gini
(infile, pivot, target, wi_name='wi')

Creates a file of pivot/target pairs with a Gini impurity value.

PARAMETER infile the input file, any type with a work item field

PARAMETER pivot the name of the pivot field

PARAMETER target the name of the field used as the target

PARAMETER wi_name the name of the work item field, default is "wi" return A table by Work Item and Pivot value giving count and Gini impurity value

$\begin{array}{c} {\rm ML_Core/\ Utils/} \\ {\bf SequenceInField} \end{array}$

Go Up

DESCRIPTIONS

MACRO SequenceInField

SequenceInField

(infile,infield,seq,wi_name='wi')

Given a file which is sorted by the work item identifier and INFIELD (and possibly other values), add sequence numbers within the range of each infield. Slighly elaborate code is to avoid having to partition the data to one value of infield per node and to work with very large numbers of records where a global count project would be inappropriate. This is useful for assigning rank positions with the groupings.

PARAMETER <u>infile</u> the input file, any type

PARAMETER <u>infield</u> field name of grouping field

PARAMETER seq name of the field to receive the sequence number

PARAMETER wi_name work item field name, default is wi

RETURN a file of the same type with sequence numbers applied

PBblas

Go Up

Table of Contents

Apply2Elements.ecl

Apply a function to each element of the matrix Use PBblas. IElementFunc as the prototype function

asum.ecl

Absolute sum – the "Entrywise" 1-norm

axpy.ecl

Implements alpha*X + Y

Constants.ecl

Converted.ecl

Module to convert between ML_Core/Types Field layouts (i.e

ExtractTri.ecl

Extract the upper or lower triangle from the composite output from getrf (LU Factorization)

gemm.ecl

Extended Parallel Block Matrix Multiplication Module Implements: Result = alpha * op(A)op(B) + beta * C

getrf.ecl

LU Factorization Splits a matrix into Lower and Upper triangular factors Produces composite LU matrix for the diagonal blocks

HadamardProduct.ecl

Element-wise multiplication of X * Y

IElementFunc.ecl

Function prototype for a function to apply to each element of the

MatUtils.ecl

Provides various utility attributes for manipulating cell-based matrixes

potrf.ecl

Implements Cholesky factorization of A = U**T * U if Triangular. Upper requested or A = L * L**T if Triangualr. Lower is requested

scal.ecl

Scale a matrix by a constant Result is alpha * X This supports a "myriad" style interface in that X may be a set of independent matrices separated by different work-item ids

tran.ecl

Transpose a matrix and sum into base matrix

trsm.ecl

Partitioned block parallel triangular matrix solver

Types.ecl

Types for the Parallel Block Basic Linear Algebra Sub-programs support WARNING: attributes marked with WARNING can not be changed without making corresponding changes to the C++ attributes

Vector2Diag.ecl

Convert a vector into a diagonal matrix

PBblas/ Apply2Elements

Go Up

IMPORTS

PBblas | PBblas.Types | std.BLAS |

DESCRIPTIONS

FUNCTION Apply2Elements

DATASET(Layout_Cell)	Apply2Elements
(DATASET(Layout_Cell)	X, IElementFunc f)

Apply a function to each element of the matrix Use PBblas.IElementFunc as the prototype function. Input and ouput may be a single matrix, or myriad matrixes with different work item ids.

PARAMETER X A matrix (or multiple matrices) in Layout_Cell form

PARAMETER $\underline{\mathbf{f}}$ A function based on the IElementFunc prototype

RETURN A matrix (or multiple matrices) in Layout_Cell form

SEE PBblas/IElementFunc

SEE PBblas/Types.Layout_Cell

PBblas/

asum

Go Up

IMPORTS

PBblas.Types | PBblas.internal | PBblas.internal.Types | PBblas.internal.MatDims | PBblas.internal.Converted | std.BLAS |

DESCRIPTIONS

FUNCTION asum

DATASET(Layout_Norm)	asum
(DATASET(Layout_Cell)	X)

Absolute sum – the "Entrywise" 1-norm Compute SUM(ABS(X))

PARAMETER X Matrix or set of matrices in Layout_Cell format

RETURN DATASET(Layout_Norm) with one record per work item

SEE PBblas/Types.Layout_Cell

PBblas/ axpy

Go Up

IMPORTS

PBblas | PBblas.Types |

DESCRIPTIONS

FUNCTION axpy

DATASET(Layout_Cell)	axpy
(value_t alpha, DATAS	<pre>ET(Layout_Cell) X, DATASET(Layout_Cell) Y)</pre>

Implements alpha*X + Y X and Y must have same shape

PARAMETER alpha Scalar multiplier for the X matrix

PARAMETER X X matrix in DATASET(Layout_Cell) form

RETURN Matrix in DATASET(Layout_Cell) form

SEE PBblas/Types.layout_cell

PBblas/

Constants

Go Up

DESCRIPTIONS

MODULE Constants

Constants

Children

- 1. Block_Minimum
- 2. Block_NoSplit
- 3. Block_Maximum
- 4. Block_Vec_Rows
- 5. Dimension_Incompat
- 6. Dimension_IncompatZ
- 7. Distribution_Error
- 8. Distribution_ErrorZ
- 9. Not_Square
- 10. Not_SquareZ
- 11. Not_PositiveDef
- 12. Not_PositiveDefZ
- 13. Not_Single_Block
- 14. Not_Single_BlockZ
- 15. Not_Block_Vector

ATTRIBUTE Block_Minimum	
Constants \	
Block_Minimum	
ATTRIBUTE Block_NoSplit	
Constants \	
Block_NoSplit	
ATTRIBUTE Block_Maximum	
Constants \	
Block_Maximum	
ATTRIBUTE Block_Vec_Rows	
Constants \	
Block Vec Rows	

ATTRIBUTE Dimension_Incompat Constants \ Dimension_Incompat ATTRIBUTE Dimension_IncompatZ Constants \ Dimension_IncompatZ **ATTRIBUTE** Distribution_Error Constants \ Distribution_Error **ATTRIBUTE** Distribution_ErrorZ Constants \ Distribution ErrorZ **ATTRIBUTE** Not_Square Constants \

Not_Square	
ATTRIBUTE Not_SquareZ	
Constants \	
Not_SquareZ	
ATTRIBUTE Not_PositiveDef	
Constants \	
N. A. D. C.	
Not_PositiveDef	
ATTRIBUTE Not_PositiveDefZ	
ATTRIBUTE NOL_POSITIVEDEIZ	
Constants	
Constants \	
Not_PositiveDefZ	
ATTRIBUTE Not_Single_Block	
Constants \	
Not_Single_Block	

ATTRIBUTE Not_Single_BlockZ Constants \ Not_Single_BlockZ ATTRIBUTE Not_Block_Vector Constants \ Not_Block_Vector ATTRIBUTE Not_Block_VectorZ Constants \ $Not_Block_VectorZ$

PBblas/ Converted

Go Up

IMPORTS

PBblas | PBblas.Types | ML_Core.Types |

DESCRIPTIONS

MODULE Converted

Converted

Module to convert between ML_Core/Types Field layouts (i.e. NumericField and DiscreteField) and PBblas matrix layout (i.e. Layout_Cell)

Children

- 1. NFToMatrix : Convert NumericField dataset to Matrix
- 2. DFToMatrix: Convert DiscreteField dataset to Matrix
- 3. MatrixToNF: Convert Matrix to NumericField dataset
- 4. MatrixToDF: Convert Matrix to DiscreteField dataset

FUNCTION NFToMatrix

Converted \

DATASET(Layout_Cell)	NFToMatrix
(DATASET(NumericField) recs)

Convert NumericField dataset to Matrix

PARAMETER recs Record Dataset in DATASET(NumericField) format

RETURN Matrix in DATASET(Layout_Cell) format

SEE PBblas/Types.Layout_Cell

SEE ML_Core/Types.NumericField

FUNCTION DFToMatrix

Converted \

DATASET(Layout_Cell)	DFToMatrix
(DATASET(DiscreteField) recs)	

Convert DiscreteField dataset to Matrix

PARAMETER recs Record Dataset in DATASET(DiscreteField) format

RETURN Matrix in DATASET(Layout_Cell) format

SEE PBblas/Types.Layout_Cell

SEE ML_Core/Types.DiscreteField

FUNCTION MatrixToNF

Converted \

DATASET(NumericField)	MatrixToNF
(DATASET(Layout Cell)	mat)

Convert Matrix to NumericField dataset

PARAMETER <u>mat</u> Matrix in DATASET(Layout_Cell) format

RETURN NumericField Dataset

SEE PBblas/Types.Layout_Cell

SEE ML_Core/Types.NumericField

FUNCTION MatrixToDF

Converted \

DATASET(DiscreteField)	MatrixToDF
(DATASET(Layout_Cell) mat)	

Convert Matrix to DiscreteField dataset

PARAMETER <u>mat</u> Matrix in DATASET(Layout_Cell) format

RETURN DiscreteField Dataset

SEE PBblas/Types.Layout_Cell

SEE ML_Core/Types.DiscreteField

PBblas/ ExtractTri

Go Up

IMPORTS

PBblas | std.BLAS | PBblas.Types | PBblas.internal | PBblas.internal.Types | PBblas.internal.MatDims | PBblas.internal.Converted |

DESCRIPTIONS

FUNCTION ExtractTri

DATASET(Layout_Cell)	ExtractTri
(Triangle tri, Diagon	al dt, DATASET(Layout_Cell) A)

Extract the upper or lower triangle from the composite output from getrf (LU Factorization).

PARAMETER <u>tri</u> Triangle type: Upper or Lower (see Types.Triangle)

PARAMETER dt Diagonal type: Unit or non unit (see Types.Diagonal)

PARAMETER <u>A</u> Matrix of cells. See Types.Layout_Cell

RETURN Matrix of cells in Layout_Cell format representing a triangular matrix (upper or lower)

SEE Std.PBblas.Types

PBblas/

gemm

Go Up

IMPORTS

PBblas.Types | PBblas.internal | PBblas.internal.Types | std.BLAS | PBblas.internal.MatDims | std.system.Thorlib |

DESCRIPTIONS

FUNCTION gemm

```
DATASET(Layout_Cell) gemm

(BOOLEAN transposeA, BOOLEAN transposeB, value_t alpha,
DATASET(Layout_Cell) A_in, DATASET(Layout_Cell) B_in,
DATASET(Layout_Cell) C_in=emptyC, value_t beta=0.0)
```

Extended Parallel Block Matrix Multiplication Module Implements: Result = alpha * op(A)op(B) + beta * C. op is No Transpose or Transpose. Multiplies two matrixes A and B, with an optional pre-multiply transpose for each Optionally scales the product by the scalar "alpha". Then adds an optional C matrix to the product after scaling C by the scalar "beta". A, B, and C are specified as DATASET(Layout_Cell), as is the Resulting matrix. Layout_Cell describes a sparse matrix stored as a list of x, y, and value. This interface also provides a "Myriad" capability allowing multiple similar operations to be performed on independent sets of matrixes in parallel. This is done by use of the work-item id (wi_id) in each cell of the matrixes. Cells with the same wi_id are considered part of the same matrix. In the myriad form, each input matrix A, B, and (optionally) C can contain many independent matrixes. The wi_ids are matched up such that each operation involves the A, B, and C with the same wi_id. A and B must therefore contain the same set of wi_ids, while C is optional for any wi_id. The same parameters: alpha, beta, transposeA, and transposeB are used for all work-items. The result will contain cells from all provided work-items. Result has same shape as C if provided. Note that matrixes are not explicitly

dimensioned. The shape is determined by the highest value of x and y for each work-item.

PARAMETER transposeA Boolean indicating whether matrix A should be transposed before multiplying

PARAMETER transposeB Same as above but for matrix B

PARAMETER alpha Scalar multiplier for alpha * A * B

PARAMETER A_in 'A' matrix (multiplier) in Layout_Cell format

PARAMETER B_in Same as above for the 'B' matrix (multiplicand)

PARAMETER C_in Same as above for the 'C' matrix (addend). May be omitted.

PARAMETER beta A scalar multiplier for beta * C, scales the C matrix before addition. May be omitted.

RETURN Result matrix in Layout_Cell format.

SEE PBblas/Types.Layout_Cell

PBblas/ getrf

Go Up

IMPORTS

PBblas.Types | PBblas.internal | PBblas.internal.Types | std.BLAS | PBblas.internal.MatDims | std.system.Thorlib |

DESCRIPTIONS

FUNCTION getrf

DATASET(Layout_Cell)	getrf
(DATASET(Layout_Cell)	A)

LU Factorization Splits a matrix into Lower and Upper triangular factors Produces composite LU matrix for the diagonal blocks. Iterates through the matrix a row of blocks and column of blocks at a time. Partition A into M block rows and N block columns. The A11 cell is a single block. A12 is a single row of blocks with N-1 columns. A21 is a single column of blocks with M-1 rows. A22 is a sub-matrix of M-1 x N-1 blocks. | A11 A12 | | L11 0 | | U11 U12 | | A21 A22 | == | L21 L22 | * | 0 U22 | | L11*U11 L11*U12 | == | L21*U11 L21*U12 + L22*U22 | Based upon PB-BLAS: A set of parallel block basic linear algebra subprograms by Choi and Dongarra This module supports the "Myriad" style interface, allowing many independent problems to be worked on at once. The A matrix can contain multiple matrixes to be factored, indicated by different values for work-item id (wi_id). Note: The returned matrix includes both the upper and lower factors. This matrix can be used directly by trsm which will only use the part indicated by trsm's 'triangle' parameter (i.e. upper or lower). To extract the upper or lower triangle explicitly for other purposes, use the ExtractTri function. When passing the Lower matrix to the triangle solver (trsm), set the "Diagonal" parameter to "UnitTri". This is necessary because both triangular matrixes returned from this function are packed into a square matrix with only one diagonal. By convention, The Lower triangle is assumed to be a Unit Triangle (diagonal all ones), so the diagonal

contained in the returned matrix is for the Upper factor and must be ignored (i.e. assumed to be all ones) when referencing the Lower triangle.

PARAMETER A The input matrix in Types.Layout_Cell format

RETURN Resulting factored matrix in Layout_Cell format

SEE Types.Layout_Cell

SEE ExtractTri

$\frac{\text{PBblas}/}{\textbf{HadamardProduct}}$

Go Up

IMPORTS

PBblas.internal | PBblas.internal.MatDims | PBblas.Types | PBblas.internal.Types | PBblas.internal.Converted | std.BLAS | std.system.Thorlib |

DESCRIPTIONS

FUNCTION HadamardProduct

DATASET(Layout_Cell)	HadamardProduct
(DATASET(Layout_Cell)	X, DATASET(Layout_Cell) Y)

Element-wise multiplication of X * Y. Supports the "myriad" style interface - X and Y may contain multiple separate matrixes. Each X will be multiplied by the Y with the same work-item id. Note: This performs element-wise multiplication. For dot-product matrix multiplication, use PBblas.gemm.

PARAMETER X A matrix (or multiple matrices) in Layout_Cell form

PARAMETER Y A matrix (or multiple matrices) in Layout_Cell form

RETURN A matrix (or multiple matrices) in Layout_Cell form

SEE PBblas/Types.Layout Cell

PBblas/ IElementFunc

Go Up

IMPORTS

PBblas |

DESCRIPTIONS

FUNCTION IElementFunc

```
value_t | IElementFunc
(value_t v, dimension_t r, dimension_t c)
```

Function prototype for a function to apply to each element of the distributed matrix Base your function on this prototype:

PARAMETER <u>v</u> Input value

PARAMETER $\underline{\mathbf{r}}$ Row number (1 based)

PARAMETER <u>c</u> Column number (1 based)

RETURN Output value

SEE PBblas/Apply2Elements

$\frac{\mathrm{PBblas}/}{MatUtils}$

Go Up

IMPORTS

PBblas | PBblas.Types | PBblas.internal | PBblas.internal.Types | PBblas.internal.MatDims |

DESCRIPTIONS

MODULE MatUtils

MatUtils

Provides various utility attributes for manipulating cell-based matrixes

SEE Std/PBblas/Types.Layout_Cell

Children

- 1. GetWorkItems: Get a list of work-item ids from a matrix containing one or more work items
- 2. InsertCols: Insert one or more columns of a fixed value into a matrix
- 3. Transpose: Transpose a matrix This attribute supports the myriad interface

FUNCTION GetWorkItems

MatUtils \

```
DATASET(Layout_WI_ID) GetWorkItems

(DATASET(Layout_Cell) cells)
```

Get a list of work-item ids from a matrix containing one or more work items

PARAMETER cells A matrix in Layout_Cell format

RETURN DATASET(Layout_WI_ID), one record per work-item

SEE PBblas/Types.Layout_Cell

SEE PBblas/Types.Layout_WI_ID

FUNCTION InsertCols

MatUtils \

```
DATASET(Layout_Cell) InsertCols

(DATASET(Layout_Cell) M, UNSIGNED cols_to_insert=1, value_t insert_val=1)
```

Insert one or more columns of a fixed value into a matrix. Columns are inserted before the first original column. This attribute supports the myriad interface. Multiple independent matrixes can be represented by M.

PARAMETER $\underline{\mathbf{M}}$ the input matrix

PARAMETER cols_to_insert the number of columns to insert, default 1

PARAMETER insert val the value for each cell of the new column(s), default 0

RETURN matrix in Layout_Cell format with additional column(s)

FUNCTION Transpose

MatUtils \

DATASET(Layout_Cell)	Transpose
(DATASET(Layout_Cell) M)	

Transpose a matrix This attribute supports the myriad interface. Multiple independent matrixes can be represented by M.

PARAMETER M A matrix represented as DATASET(Layout_Cell)

RETURN Transposed matrix in Layout_Cell format

SEE PBblas/Types.Layout_Cell

PBblas/ potrf

Go Up

IMPORTS

PBblas.Types | std.BLAS | PBblas.internal | PBblas.internal.Types | PBblas.internal.MatDims | PBblas.internal.Converted | std.system.Thorlib |

DESCRIPTIONS

FUNCTION potrf

```
DATASET(Layout_Cell) potrf

(Triangle tri, DATASET(Layout_Cell) A_in)
```

Implements Cholesky factorization of $A = U^{**}T^*U$ if Triangular. Upper requested or $A = L^*L^{**}T$ if Triangular. Lower is requested. The matrix A must be symmetric positive definite.

So, use Cholesky on the first block to get L11. L21 = A21*L11** T^{**} -1 which can be found by dtrsm on each column block A22' is A22 - L21*L21**T

Based upon PB-BLAS: A set of parallel block basic linear algebra subprograms by Choi and Dongarra

This module supports the "Myriad" style interface, allowing many independent problems to be worked on at once. The A matrix can contain multiple matrixes to be factored, indicated by different values for work-item id (wi id).

PARAMETER <u>tri</u> Types. Triangle enumeration indicating whether we are looking for the Upper or the Lower factor

PARAMETER A_in The matrix or matrixes to be factored in Types.Layout_Cell format

RETURN Triangular matrix in Layout_Cell format

SEE Std.PBblas.Types.Layout_Cell

SEE Std.PBblas.Types.Triangle

PBblas/ scal

Go Up

IMPORTS

PBblas | PBblas.Types |

DESCRIPTIONS

FUNCTION scal

DATASET(Layout_Cell)	scal
(value_t alpha, DATASET(Layout_Cell) X)	

Scale a matrix by a constant Result is alpha * X This supports a "myriad" style interface in that X may be a set of independent matrices separated by different work-item ids.

PARAMETER <u>alpha</u> A scalar multiplier

PARAMETER $\underline{\mathbf{X}}$ The matrix(es) to be scaled in Layout_Cell format

RETURN Matrix in Layout_Cell form, of the same shape as X

SEE PBblas/Types.Layout_Cell

PBblas/

tran

Go Up

IMPORTS

PBblas.Types | PBblas.internal | PBblas.internal.Types | PBblas.internal.MatDims | PBblas.internal.Converted | std.BLAS | std.system.Thorlib |

DESCRIPTIONS

FUNCTION tran

```
DATASET(Layout_Cell) tran

(value_t alpha, DATASET(Layout_Cell) A, value_t beta=0,
DATASET(Layout_Cell) C=empty_c)
```

Transpose a matrix and sum into base matrix result \leq = alpha * A**t + beta * C, A is n by m, C is m by n A**T (A Transpose) and C must have same shape

PARAMETER alpha Scalar multiplier for the A**T matrix

PARAMETER A A matrix in DATASET(Layout_Cell) form

PARAMETER <u>beta</u> Scalar multiplier for the C matrix

PARAMETER C C matrix in DATASET(Layout_Call) form

RETURN Matrix in DATASET(Layout_Cell) form alpha * A**T + beta * C

SEE PBblas/Types.layout_cell

145

PBblas/

trsm

Go Up

IMPORTS

PBblas.Types | std.BLAS | PBblas.internal | PBblas.internal.Types | PBblas.internal.MatDims | PBblas.internal.Converted | std.system.Thorlib |

DESCRIPTIONS

FUNCTION trsm

```
DATASET(Layout_Cell) trsm

(Side s, Triangle tri, BOOLEAN transposeA, Diagonal diag, value_t alpha, DATASET(Layout_Cell) A_in, DATASET(Layout_Cell) B_in)
```

Partitioned block parallel triangular matrix solver. Solves for X using: AX = B or XA = B A is is a square triangular matrix, X and B have the same dimensions. A may be an upper triangular matrix (UX = B or XU = B), or a lower triangular matrix (LX = B or XL = B). Allows optional transposing and scaling of A. Partially based upon an approach discussed by MJ DAYDE, IS DUFF, AP CERFACS. A Parallel Block implementation of Level-3 BLAS for MIMD Vector Processors ACM Tran. Mathematical Software, Vol 20, No 2, June 1994 pp 178-193 and other papers about PB-BLAS by Choi and Dongarra This module supports the "Myriad" style interface, allowing many independent problems to be worked on at once. Corresponding A and B matrixes are related by a common work-item identifier (wi_id) within each cell of the matrix. The returned X matrix will contain cells for the same set of work-items as specified for the A and B matrices.

PARAMETER $\underline{\mathbf{s}}$ Types. Side enumeration indicating whether we are solving AX = B or XA = B

PARAMETER <u>tri</u> Types. Triangle enumeration indicating whether we are solving an Upper or Lower triangle.

PARAMETER solving Eranspose Boolean indicating whether or not to transpose the A matrix before

PARAMETER diag Types. Diagonal enumeration indicating whether A is a unit matrix or not. This is primarily used after factoring matrixes using getrf (LU factorization). That module produces a factored matrix stored within the same space as the original matrix. Since the diagonal is used by both factors, by convention, the Lower triangle has a unit matrix (diagonal all 1's) while the Upper triangle uses the diagonal cells. Setting this to UnitTri, causes the contents of the diagonal to be ignored, and assumed to be 1. NotUnitTri should be used for most other cases.

PARAMETER alpha Multiplier to scale A

PARAMETER A_in The A matrix in Layout_Cell format

PARAMETER B_in The B matrix in Layout_Cell format

RETURN X solution matrix in Layout_Cell format

SEE Types.Layout_Cell

SEE Types.Triangle

SEE Types.Side

PBblas/ Types

Go Up

IMPORTS

ML_Core | ML_Core.Types |

DESCRIPTIONS

MODULE Types

Types

Types for the Parallel Block Basic Linear Algebra Sub-programs support WARNING: attributes marked with WARNING can not be changed without making corresponding changes to the C++ attributes.

Children

- 1. dimension_t : Type for matrix dimensions
- 2. partition_t : Type for partition id only supports up to 64K partitions
- 3. work_item_t: Type for work-item id only supports up to 64K work items
- 4. value_t : Type for matrix cell values
- 5. m_label_t: Type for matrix label
- 6. Triangle: Enumeration for Triangle type
- 7. Diagonal: Enumeration for Diagonal type
- 8. Side: Enumeration for Side type

- 9. t_mu_no: Type for matrix universe number
- 10. Layout_Cell: Layout for Matrix Cell Main representation of Matrix cell at interface to all PBBlas functions
- 11. Layout_Norm: Layout for Norm results

ATTRIBUTE dimension_t

Types \

 $dimension_t$

Type for matrix dimensions. Uses UNSIGNED four as matrixes are not designed to support more than 4 B rows or columns.

ATTRIBUTE partition_t

Types \

partition_t

Type for partition id – only supports up to 64K partitions

ATTRIBUTE work_item_t

Types \setminus

 ${\bf work_item_t}$

Type for work-item id – only supports up to 64K work items

ATTRIBUTE value_t

Types \

 $value_t$

Type for matrix cell values WARNING: type used in C++ attribute

ATTRIBUTE m_label_t

Types \

 m_label_t

Type for matrix label. Used for Matrix dimensions (see Layout_Dims) and for partitions (see Layout_Part)

ATTRIBUTE Triangle

Types \

Triangle

Enumeration for Triangle type WARNING: type used in C++ attribute

ATTRIBUTE Diagonal

Types \

Diagonal

Enumeration for Diagonal type WARNING: type used in C++ attribute

ATTRIBUTE Side

Types \

Side

Enumeration for Side type WARNING: type used in C++ attribute

ATTRIBUTE t_mu_no

Types \

t_mu_no

Type for matrix universe number Allow up to 64k matrices in one universe

RECORD Layout_Cell

Types \

Layout Cell

Layout for Matrix Cell Main representation of Matrix cell at interface to all PBBlas functions. Matrixes are represented as DATASET(Layout_Cell), where each cell describes the row and column position of the cell as well as its value. Only the non-zero cells need to be contained in the dataset in order to describe the matrix since all unspecified cells are considered to have a value of zero. The cell also contains a work-item number that allows multiple separate matrixes to be carried in the same dataset. This supports the "myriad" style interface that allows the same operations to be performed on many different sets of data at once. Note that these matrixes do not have an explicit size. They are sized implicitly, based on the maximum row and column presented in the data. A matrix can be converted to an explicit dense form (see matrix_t) by using the utility module MakeR8Set. This module should only be used for known small matrixes (< 1M cells) or for partitions of a larger matrix. The Converted module provides utility functions to convert to and from a set of partitions (See Layout_parts).

- **FIELD** <u>wi_id</u> Work Item Number An identifier from 1 to 64K-1 that separates and identifies individual matrixes
- **FIELD** $\underline{\mathbf{x}}$ 1-based row position within the matrix
- FIELD y 1-based column position within the matrix
- FIELD <u>v</u> Real value for the cell
- SEE matrix_t
- SEE Std/PBblas/MakeR8Set.ecl
- SEE Std/PBblas/Converted.ecl WARNING: Used as C++ attribute. Do not change without corresponding changes to MakeR8Set.

RECORD Layout_Norm

Types \

Layout_Norm

Layout for Norm results.

- **FIELD** wi_id Work Item Number An identifier from 1 to 64K-1 that separates and identifies individual matrixes
- **FIELD v** Real value for the norm

${\bf Vector 2 Diag}$

Go Up

IMPORTS

PBblas.internal | PBblas.internal.MatDims | PBblas.Types | PBblas.internal.Types | PBblas.Constants |

DESCRIPTIONS

FUNCTION Vector2Diag

DATASET(Layout_Cell)	Vector2Diag
(DATASET(Layout_Cell) X)	

Convert a vector into a diagonal matrix. The typical notation is D = diag(V). The input X must be a 1 x N column vector or an N x 1 row vector. The resulting matrix, in either case will be N x N, with zero everywhere except the diagonal.

PARAMETER X A row or column vector (i.e. N x 1 or 1 x N) in Layout_Cell format

RETURN An N x N matrix in Layout_Cell format

SEE PBblas/Types.Layout_cell