MIPS Architecture and Assembly Language Overview

Adapted from: http://edge.mcs.dre.g.el.edu/GICL/people/sevy/architecture/MIPSRef(SPIM).html

[Register Description] [I/O Description]

Data Types and Literals

Data types:

- Instructions are all 32 bits
- byte(8 bits), halfword (2 bytes), word (4 bytes)
- a character requires 1 byte of storage
- an integer requires 1 word (4 bytes) of storage

Literals:

- numbers entered as is. <u>e.g.</u> 4
- characters enclosed in single quotes. e.g. 'b'
- strings enclosed in double quotes. e.g. "A string"

Registers

- 32 general-purpose registers
- register preceded by \$ in assembly language instruction two formats for addressing:
 - o using register number e.g. \$0 through \$31
 - o using equivalent names <u>e.g.</u> \$t1, \$sp
- special registers Lo and Hi used to store result of multiplication and division
 - o not directly addressable; contents accessed with special instruction mfhi ("move from Hi") and mflo ("move from Lo")
- stack grows from high memory to low memory

This is from Figure 9.9 in the Goodman&Miller text

Register Number	Alternative Name	Description	
0	zero	the value 0	
1	\$at	(assembler temporary) reserved by the assembler	

2-3	\$v0 - \$v1	(values) from expression evaluation and function results		
4-7	\$a0 - \$a3	(arguments) First four parameters for subroutine. Not preserved across procedure calls		
8-15	\$t0 - \$t7	(temporaries) Caller saved if needed. Subroutines can use w/out saving. Not preserved across procedure calls		
16-23	\$s0 - \$s7	(saved values) - Callee saved. A subroutine using one of these must save original and restore it before exiting. Preserved across procedure calls		
24-25	\$t8 - \$t9	(temporaries) Caller saved if needed. Subroutines can use w/out saving. These are in addition to \$t0 - \$t7 above. Not preserved across procedure calls.		
26-27	\$k0 - \$k1	reserved for use by the interrupt/trap handler		
28	\$gp	global pointer. Points to the middle of the 64K block of memory in the static data segment.		
29	\$sp	stack p ointer Points to last location on the stack.		
30	\$s8/\$fp	saved value / frame pointer Preserved across procedure calls		
31	\$ra	return address		

See also Britton section 1.9, Sweetman section 2.21, Larus Appendix section A.6

Program Structure

- just plain text file with data declarations, program code (name of file should end in suffix .s to be used with SPIM simulator)
- data declaration section followed by program code section

Data Declarations

- placed in section of program identified with assembler directive .data
- declares variable names used in program; storage allocated in main memory (RAM)

Code

• placed in section of text identified with assembler directive .text

- contains program code (instructions)
- starting point for code e.g.ecution given label main:
- ending point of main code should use exit system call (see below under System Calls)

Comments

- anything following # on a line
 # This stuff would be considered a comment
- Template for a MIPS assembly language program:

```
# Comment giving name of program and description of function
# Template.s
# Bare-bones outline of MIPS assembly language program

. data  # variable declarations follow this
line
# ...

. text  # instructions follow this line

main:  # indicates start of code (first instruction to execute)

# ...

# End of program, leave a blank line afterwards to make SPIM happy
```

Data Declarations

format for declarations:

```
name: storage_type value(s)
```

- o create storage for variable of specified type with given name and specified value
- o value(s) usually gives initial value(s); for storage type .space, gives number of spaces to be allocated

Note: labels always followed by colon (:)

```
example
                              # create a single integer variable with initial
var1:
               .word
value 3
                       'a','b' # create a 2-element character array with
array1:
               .byte
elements initialized
                                  to a and b
               .space 40
                              # allocate 40 consecutive bytes, with storage
array2:
uninitialized
                                  could be used as a 40-element character
array, or a
```

Load / Store Instructions

- RAM access only allowed with load and store instructions
- all other instructions use register operands

load:

store word:

```
sw register_source, RAM_destination

#store word in source register into RAM destination

sb register_source, RAM_destination
```

#store byte (low-order) in source register into RAM destination

load immediate:

```
li register_destination, value #load immediate value into destination register
```

```
example:
       .data
                             # declare storage for var1; initial value is 23
var1:
       .word
              23
       .text
 _start:
       lw
              $t0, var1
                                    # load contents of RAM location into
register $t0:
              $t0 = var1
            $t1, 5
                             # $t1 = 5
                                        ("load immediate")
       li
                                    # store contents of register $t1 into
              $t1, var1
       SW
RAM: var1 = $t1
```

Indirect and Based Addressing

done

• Used only with load and store instructions

load address:

```
la $t0, var1
```

• copy RAM address of var1 (presumably a label defined in the program) into register \$t0

indirect addressing:

```
lw $t2, ($t0)
```

• load word at RAM address contained in \$t0 into \$t2

```
sw $t2, ($t0)
```

• store word in register \$t2 into RAM at address contained in \$t0

based or indexed addressing:

```
lw $t2, 4($t0)
```

- load word at RAM address (\$t0+4) into register \$t2
- "4" gives offset from address in register \$t0

```
sw $t2, -12($t0)
```

- store word in register \$t2 into RAM at address (\$t0 12)
- negative offsets are fine

Note: based addressing is especially useful for:

- arrays; access elements as offset from base address
- stacks; easy to access elements at offset from stack pointer or frame pointer

example

```
.data
                                   # declare 12 bytes of storage to hold
array1:
              .space 12
array of 3 integers
              .text
 start:
              la
                     $t0, array1
                                             load base address of array
into register $t0
                     $t1, 5
                                   # $t1 = 5 ("load immediate")
              li
              sw $t1, ($t0)
                                 # first array element set to 5;
indirect addressing
              li $t1, 13
                                      $t1 = 13
                              # second array element set to 13
              sw $t1, 4($t0)
              li $t1, -7
                                      $t1 = -7
                                   #
              sw $t1, 8($t0)
                                   # third array element set to -7
              done
```

Arithmetic Instructions

- most use 3 operands
- all operands are registers; no RAM or indirect addressing
- operand size is word (4 bytes)

```
add $t0,$t1,$t2  # $t0 = $t1 + $t2; add as signed (2's complement) integers sub $t2,$t3,$t4  # $t2 = $t3 \div $t4
```

```
addi
                       $t2,$t3, 5
                                      # $t2 = $t3 + 5; "add immediate" (no
sub immediate)
                       $t1,$t6,$t7
                                      # $t1 = $t6 + $t7;
                                                            add as unsigned
               addu
integers
               subu
                       $t1,$t6,$t7
                                      # $t1 = $t6 + $t7;
                                                            subtract as
unsigned integers
                                         multiply 32-bit quantities in $t3
               mult
                       $t3,$t4
and $t4, and store 64-bit
                                         result in special registers Lo and
Hi: (Hi, Lo) = $t3 * $t4
                       $t5,$t6
               div
                                      #
                                         Lo = $t5 / $t6
                                                          (integer quotient)
                                         Hi = $t5 \mod $t6
                                                            (remainder)
                                         move quantity in special register Hi
               mfhi
                       $t0
to $t0:
          $t0 = Hi
                                      # move quantity in special register Lo
               mflo
                       $t1
          $t1 = Lo
to $t1:
                                         used to get at result of product or
quotient
               move
                       $t2,$t3 # $t2 = $t3
```

Control Structures

Branches

• comparison for conditional branches is built into instruction

```
target
                                         unconditional branch to program
               b
label target
                       $t0,$t1,target # branch to target if
                                                               $t0 = $t1
               beq
               blt
                       $t0,$t1,target #
                                         branch to target if
                                                               $t0 < $t1
               ble
                       $t0,$t1,target #
                                         branch to target if
                                                              $t0 <= $t1
               bqt
                       $t0,$t1,target #
                                         branch to target if
                                                               $t0 > $t1
                                                              $t0 >= $t1
               bge
                       $t0,$t1,target # branch to target if
               bne
                       $t0,$t1,target # branch to target if
                                                              $t0 <> $t1
<u>Jumps</u>
               j
                       target # unconditional jump to program label target
                                      # jump to address contained in $t3
               jr
                       $t3
("jump register")
```

Subroutine Calls

subroutine call: "jump and link" instruction

```
jal sub_label # "jump and link"
```

- copy program counter (return address) to register \$ra (return address register)
- jump to program statement at sub_label

subroutine return: "jump register" instruction

```
jr $ra # "jump register"
```

• jump to return address in \$ra (stored by jal instruction)

Note: return address stored in register \$ra; if subroutine will call other subroutines, or is recursive, return address should be copied from \$ra onto stack to preserve it, since jal always places return address in this register and hence will overwrite previous value

System Calls and I/O (SPIM Simulator)

- used to read or print values or strings from input/output window, and indicate program end
- use **syscall** operating system routine call
- first supply appropriate values in registers \$v0 and \$a0-\$a1
- result value (if any) returned in register \$v0

The following table lists the possible **syscall** services.

Service	Code in \$v0	Arguments	Results
print_int	1	\$a0 = integer to be printed	
print_float	2	f12 = float to be printed	
print_doubl e	3	\$f12 = double to be printed	
print_string	4	\$a0 = address of string in memory	
read_int	5		integer returned in \$v0
read_float	6		float returned in \$v0
read_double	7		double returned in \$v0
read_string	8	\$a0 = memory address of string input buffer \$a1 = length of string buffer (n)	
sbrk	9	\$a0 = amount	address in \$v0
exit	10		

- o The print_string service expects the address to start a null-terminated character string. The directive **.asciiz** creates a null-terminated character string.
- o The read_int, read_float and read_double services read an entire line of input up to and including the newline character.
- The read_string service has the same semantices as the UNIX library routine fgets.

- It reads up to n-1 characters into a buffer and terminates the string with a null character.
- If fewer than n-1 characters are in the current line, it reads up to and including the newline and terminates the string with a null character.
- o The sbrk service returns the address to a block of memory containing n additional bytes. This would be used for dynamic memory allocation.
- o The exit service stops a program from running.
- e.g. Print out integer value contained in register \$t2

```
li $v0, 1  # load appropriate system call code into register $v0;  # code for printing integer is 1 move $a0, $t2  # move integer to be printed into $a0: $a0 = $t2  # call operating system to perform operation # call operating system to
```

e.g. Read integer value, store in RAM location with label int_value (presumably declared in data section)

e.g. Print out string (useful for prompts)

.data

```
string1 .asciiz "Print this.\n"  # declaration for string variable,  # .asciiz directive makes string null terminated  .text
```

 $\underline{\text{e.g.}}$ To indicate end of program, use **exit** system call; thus last lines of program should be:

```
li $v0, 10  # system call code for exit = 10
syscall  # call operating sys
```