

ECMP Load Balancing

Equal-cost multi-path routing (ECMP) is a routing strategy where next-hop packet forwarding to a single destination can occur over multiple "best paths" which tie for top place in routing metric calculations. Multipath routing can be used in conjunction with most routing protocols, since it is a per-hop decision that is limited to a single router. It potentially offers substantial increases in bandwidth by load-balancing traffic over multiple paths.

Various routing protocols, including Open Shortest Path First (OSPF), Intermediate System to Intermediate System (ISIS), Enhanced Interior Gateway Routing Protocol (EIGRP), and Border Gateway Protocol (BGP) allow ECMP routing.

Load balancing between ECMP paths is performed on IOS-XE based CEF object called loadbalance.

ECMP Per-Flow Load Balancing


Load balancing is a forwarding mechanism that distributes traffic over multiple links based on certain parameters. ECMP Per-Flow Load Balancing distributes packets across multiple links based on Layer 3 routing information. If the router discovers multiple paths to a destination, the routing table is updated with multiple entries for that destination. Per-flow load balancing allows the router to use multiple paths to achieve load sharing across multiple source-destination host pairs. Packets for a given source-destination host pair are guaranteed to take the same path, even if multiple paths are available. Traffic streams destined for different pairs tend to take different paths.

Benefits of Per-Flow Load Balancing

• Incoming data traffic is evenly distributed over multiple equal-cost connections.

 Incoming data traffic is evenly distributed over multiple equal-cost connections member links within a bundle interface.

Figure 1: ECMP Load Balancing with MPLS Enabled



- Finding Feature Information, page 2
- Restrictions for ECMP Load Balancing, page 2
- Configuring ECMP Load Balancing, page 3
- Configuration Examples for ECMP Load Balancing, page 4

Finding Feature Information

Your software release may not support all the features documented in this module. For the latest caveats and feature information, see Bug Search Tool and the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the feature information table.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Restrictions for ECMP Load Balancing

- Both 4 ECMP and 8 ECMP paths are supported.
- Load balancing is supported on global IPv4 and IPv6 traffic. For global IPv4 and IPv6 traffic, the traffic distribution can be equal among the available 8 links.
- Per packet load balancing is not supported.
- Label load balancing is supported.
- BGP multi-path is *not* supported with ECMP.

- BGP multi-path with PIC Edge is not supported
- When BGP PIC is configured, the L3VPN prefixes scale reduces by 1/4th of the supported value (Supported scale value/4), for better convergence value at the PIC core. For example, for RSP1A the supported L3VPN scale is 2000, if 4 ECMP path with PIC is enabled, then the maximum supported scale value is reduced to 5000 (20000/4).

Configuring ECMP Load Balancing

Perform the following steps to configure ECMP load balancing.

SUMMARY STEPS

- 1. enable
- 2. configure terminal
- 3. platform loadbalance max-paths δ
- 4 exi

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable	Enables privileged EXEC mode.
	<pre>Example: Device> enable</pre>	Enter your password if prompted.
Step 2	configure terminal	Enters global configuration mode.
	Example: Device# configure terminal	
Step 3	platform loadbalance max-paths 8	Configures the loadbalance maximum paths. Select Yes to save the configuration and reload the router.
	<pre>Example: Device(config)# platform loadbalance max-paths 8</pre>	Note ISIS by default supports only 4 paths. To increase ISIS max-paths, use the command config-maximum-paths 8 under router ISIS. IGP by default supports only 4 paths. To increase IGP max-paths, use the command config-maximum-paths 8 under respective IGP (OSPF and ISIS) process.
Step 4	exit	Returns to privileged EXEC mode.
	Example: Device(config)#exit	

Configuration Examples for ECMP Load Balancing

This section shows sample configurations for ECMP load balancing.

Example: Configuring ECMP Load balancing

```
The following is a sample configuration for ECMP load balancing
Router# show run-configuration | in platform loadbalance
platform loadbalance max-paths 8
         show ip cef 200.0.0.0 detail
200.0.0.0/24, epoch 2, per-destination sharing local label info: global/266
  nexthop 21.1.1.2 GigabitEthernet0/1/3 label 141
  nexthop 21.1.6.1 GigabitEthernet0/0/0 label 269
  nexthop 21.2.1.2 GigabitEthernet0/1/0 label 141
  nexthop 21.2.6.1 GigabitEthernet0/0/1 label 269
  nexthop\ 21.3.1.2\ GigabitEthernet0/1/1\ label\ 141
  nexthop 21.3.6.1 GigabitEthernet0/0/2 label 269
  nexthop 21.4.1.2 GigabitEthernet0/0/4 label 141
  nexthop 21.4.6.1 GigabitEthernet0/0/7 label 269
Router#
Router# show interface GigabitEthernet 0/1/3 | in output rate
  5 minute output rate 548000 bits/sec, 1009 packets/sec
Router# show interface GigabitEthernet 0/0/0 | in output rate
  5 minute output rate 547000 bits/sec, 1008 packets/sec
Router# show interface GigabitEthernet 0/1/0 | in output rate
  5 minute output rate 539000 bits/sec, 992 packets/sec
Router# show interface GigabitEthernet 0/0/1 | in output rate
  5 minute output rate 539000 bits/sec, 991 packets/sec
Router# show interface GigabitEthernet 0/1/1 | in output rate
  5 minute output rate 540000 bits/sec, 993 packets/sec
Router# show interface GigabitEthernet 0/0/2 | in output rate
  5 minute output rate 540000 bits/sec, 993 packets/sec
Router# show interface GigabitEthernet 0/0/4 | in output rate
5 minute output rate 548000 bits/sec, 1009 packets/sec Router# show interface GigabitEthernet 0/0/7 | in output rate
  5 minute output rate 548000 bits/sec, 1009 packets/sec
```

Verifying ECMP Load Balancing

Use the following commands to verify ECMP load balancing.

```
Building configuration...

Current configuration: 10710 bytes!! Last configuration change at 00:29:01 IST Sat Jan 17 2015! version 15.5 no service pad service timestamps debug datetime msec service timestamps log datetime msec platform loadbalance max-paths 8 no platform punt-keepalive disable-kernel-core platform bfd-debug-trace 1 platform tcam-parity-error enable platform shell! hostname RM-PE1!
```

```
boot-start-marker
boot-end-marker
vrf definition Mgmt-intf
address-family ipv4
exit-address-family
address-family ipv6
exit-address-family
no aaa new-model
clock timezone IST 5\ 30
facility-alarm critical exceed-action shutdown
no ip routing protocol purge interface
ip vrf test
rd 100:100
route-target export 1000:1000
route-target import 1000:1000
no ip domain lookup
mpls label protocol ldp
mpls ldp explicit-null
mpls ldp session protection
mpls ldp discovery targeted-hello accept
multilink bundle-name authenticated
license udi pid ASR-903 sn FOX1551P04E
license accept end user agreement
license boot level metroaggrservices
sdm prefer default
redundancy
mode sso
transceiver type all
monitoring
ip tftp source-interface GigabitEthernet0
interface Loopback0
ip address 100.111.14.1 255.255.255.255
```

```
interface Loopback101
ip address 65.1.101.1 255.255.255.255
interface Loopback102
ip address 65.1.102.1 255.255.255.255
interface Loopback103
ip address 65.1.103.1 255.255.255.255
interface Loopback104
ip address 65.1.104.1 255.255.255.255
interface Loopback105
ip address 65.1.105.1 255.255.255.255
interface Loopback106
ip address 65.1.106.1 255.255.255.255
interface Loopback107
ip address 65.1.107.1 255.255.255.255
interface Loopback108
ip address 65.1.108.1 255.255.255.255
interface Loopback109
ip address 65.1.109.1 255.255.255.255
interface Loopback110
ip address 65.1.110.1 255.255.255.255
interface Loopback111
ip address 65.1.111.1 255.255.255.255
interface Loopback112
ip address 65.1.112.1 255.255.255.255
interface Loopback113
ip address 65.1.113.1 255.255.255.255
interface Loopback114
ip address 65.1.114.1 255.255.255.255
interface Loopback115
ip address 65.1.115.1 255.255.255.255
interface Loopback116
ip address 65.1.116.1 255.255.255.255
interface Loopback117
ip address 65.1.117.1 255.255.255.255
interface Loopback118
ip address 65.1.118.1 255.255.255.255
interface Loopback119
ip address 65.1.119.1 255.255.255.255
interface Loopback120
ip address 65.1.120.1 255.255.255.255
interface Loopback121
ip address 65.1.121.1 255.255.255.255
interface Loopback122
ip address 65.1.122.1 255.255.255.255
interface Loopback123
ip address 65.1.123.1 255.255.255.255
interface Loopback124
ip address 65.1.124.1 255.255.255.255
```

```
interface Loopback125
ip address 65.1.125.1 255.255.255.255
interface Loopback126
ip address 65.1.126.1 255.255.255.255
interface Loopback127
ip address 65.1.127.1 255.255.255.255
interface Loopback128
ip address 65.1.128.1 255.255.255.255
interface Loopback129
ip address 65.1.129.1 255.255.255.255
interface Loopback130
ip address 65.1.130.1 255.255.255.255
interface Loopback131
ip address 65.1.131.1 255.255.255.255
interface Loopback132
ip address 65.1.132.1 255.255.255.255
interface Loopback133
ip address 65.1.133.1 255.255.255.255
interface Loopback134
ip address 65.1.134.1 255.255.255.255
interface Loopback135
ip address 65.1.135.1 255.255.255.255
interface Loopback136
ip address 65.1.136.1 255.255.255.255
interface Loopback137
ip address 65.1.137.1 255.255.255.255
interface Loopback138
ip address 65.1.138.1 255.255.255.255
interface Loopback139
ip address 65.1.139.1 255.255.255.255
interface Loopback140
ip address 65.1.140.1 255.255.255.255
interface Loopback141
ip address 65.1.141.1 255.255.255.255
interface Loopback142
ip address 65.1.142.1 255.255.255.255
interface Loopback143
ip address 65.1.143.1 255.255.255.255
interface Loopback144
ip address 65.1.144.1 255.255.255.255
interface Loopback145
ip address 65.1.145.1 255.255.255.255
interface Loopback146
ip address 65.1.146.1 255.255.255.255
interface Loopback147
ip address 65.1.147.1 255.255.255.255
interface Loopback148
ip address 65.1.148.1 255.255.255.255
interface Loopback149
```

```
ip address 65.1.149.1 255.255.255.255
interface Loopback150
ip address 65.1.150.1 255.255.255.255
interface Loopback151
ip address 65.1.151.1 255.255.255.255
interface Loopback152
ip address 65.1.152.1 255.255.255.255
interface Loopback153
ip address 65.1.153.1 255.255.255.255
interface Loopback154
ip address 65.1.154.1 255.255.255.255
interface Loopback155
ip address 65.1.155.1 255.255.255.255
interface Loopback156
ip address 65.1.156.1 255.255.255.255
interface Loopback157
ip address 65.1.157.1 255.255.255.255
interface Loopback158
ip address 65.1.158.1 255.255.255.255
interface Loopback159
ip address 65.1.159.1 255.255.255.255
interface Loopback160
ip address 65.1.160.1 255.255.255.255
interface GigabitEthernet0/0/0
ip address 21.1.6.2 255.255.255.0
ip router isis core-agg
negotiation auto
mpls ip
interface GigabitEthernet0/0/1
ip address 21.2.6.2 255.255.255.0
ip router isis core-agg
negotiation auto
mpls ip
interface GigabitEthernet0/0/2
ip address 21.3.6.2 255.255.255.0
ip router isis core-agg
negotiation auto
mpls ip
interface GigabitEthernet0/0/3
no ip address
shutdown
negotiation auto
interface GigabitEthernet0/0/4
ip address 21.4.1.1 255.255.255.0
ip router isis core-agg
shutdown
negotiation auto
mpls ip
interface GigabitEthernet0/0/5
no ip address
shutdown
negotiation auto
interface GigabitEthernet0/0/6
ip address 51.1.0.1 255.255.255.0
negotiation auto
```

```
interface GigabitEthernet0/0/7
ip address 21.4.6.2 255.255.255.0
ip router isis core-agg
shutdown
negotiation auto
mpls ip
interface GigabitEthernet0/1/0
ip address 21.2.1.1 255.255.255.0
ip router isis core-agg
negotiation auto
mpls ip
interface GigabitEthernet0/1/1
ip address 21.3.1.1 255.255.255.0
ip router isis core-agg
negotiation auto
mpls ip
interface GigabitEthernet0/1/2
no ip address
shutdown
negotiation auto
interface GigabitEthernet0/1/3
ip address 21.1.1.1 255.255.255.0
ip router isis core-agg
negotiation auto
mpls ip
interface GigabitEthernet0/1/4
no ip address
shutdown
negotiation auto
interface GigabitEthernet0/1/5
no ip address
shutdown
negotiation auto
interface GigabitEthernet0/1/6
no ip address
shutdown
negotiation auto
interface GigabitEthernet0/1/7
no ip address
shutdown
negotiation auto
interface GigabitEthernet0
vrf forwarding Mgmt-intf
ip address 7.43.21.101 255.255.0.0
shutdown
negotiation auto
router isis core-agg
net 49.0000.0000.1111.00
is-type level-1
metric-style wide
fast-flood 10
ip route priority high tag 10000
set-overload-bit on-startup 360
max-lsp-lifetime 65535
lsp-refresh-interval 65000
spf-interval 5 50 200
prc-interval 5 50 200
lsp-gen-interval 5 50 200
log-adjacency-changes
passive-interface Loopback0
passive-interface Loopback101
passive-interface Loopback102
```

```
passive-interface Loopback103
passive-interface Loopback104
passive-interface Loopback105
passive-interface Loopback106
passive-interface Loopback107
passive-interface Loopback108
passive-interface Loopback109
passive-interface Loopback110
passive-interface Loopback111
passive-interface Loopback112
passive-interface Loopback113
passive-interface Loopback114
passive-interface Loopback115
passive-interface Loopback116
passive-interface Loopback117
passive-interface Loopback118
passive-interface Loopback119
passive-interface Loopback120
passive-interface Loopback121
passive-interface Loopback122
passive-interface Loopback123
passive-interface Loopback124
passive-interface Loopback125
passive-interface Loopback126
passive-interface Loopback127
passive-interface Loopback128
passive-interface Loopback129
passive-interface Loopback130
passive-interface Loopback131
passive-interface Loopback132
passive-interface Loopback133
passive-interface Loopback134
passive-interface Loopback135
passive-interface Loopback136
passive-interface Loopback137
passive-interface Loopback138
passive-interface Loopback139
passive-interface Loopback140
passive-interface Loopback141
passive-interface Loopback142
passive-interface Loopback143
passive-interface Loopback144
passive-interface Loopback145
passive-interface Loopback146
passive-interface Loopback147
passive-interface Loopback148
passive-interface Loopback149
passive-interface Loopback150
passive-interface Loopback151
passive-interface Loopback152
passive-interface Loopback153
passive-interface Loopback154
passive-interface Loopback155
passive-interface Loopback156
passive-interface Loopback157
passive-interface Loopback158
passive-interface Loopback159
passive-interface Loopback160
maximum-paths 8
mpls ldp sync
router bgp 100
bgp router-id 100.111.14.1
bgp log-neighbor-changes
neighbor ABR peer-group
neighbor ABR remote-as 100
neighbor ABR update-source Loopback0
neighbor 100.111.10.1 peer-group ABR
neighbor 100.111.10.1 shutdown
neighbor 100.111.10.2 peer-group ABR
neighbor 100.111.10.2 shutdown
address-family ipv4
```

```
bgp additional-paths install
  network 100.111.14.1 mask 255.255.255.255 route-map set-PAN-comm
  neighbor ABR send-community both
  neighbor ABR next-hop-self all
  neighbor ABR route-map deny-PAN-loopbacks in
  neighbor ABR send-label
  neighbor 100.111.10.1 activate
 neighbor 100.111.10.2 activate
exit-address-family
address-family vpnv4
  neighbor ABR send-community both
  neighbor 100.111.10.1 activate
 neighbor 100.111.10.2 activate
exit-address-family
address-family ipv4 vrf test
 redistribute connected
exit-address-family
ip forward-protocol nd
ip bgp-community new-format
ip community-list 1 permit 100:100
no ip http server
no ip http secure-server
ip route vrf Mgmt-intf 10.0.0.0 255.0.0.0 7.43.0.1
ip route vrf Mgmt-intf 202.153.144.0 255.255.255.0 7.43.0.1
route-map set-service-nh permit 10
route-map deny-PAN-loopbacks deny 10
match community 1
route-map deny-PAN-loopbacks permit 20
route-map set-PAN-comm permit 10
set community 100:100
mpls ldp router-id Loopback0
control-plane
alias exec psh reques plat soft sys shell
alias exec shpp6 sh platform hard pp act fea cef da ipv6 \,
alias exec shpp sh platform hard pp act fea cef da ipv4
line con 0
exec-timeout 0 0
logging synchronous
stopbits 1
line aux 0
stopbits 1
line vty 0
exec-timeout 0 0
password lab
login
line vty 1 4
login
end
```

Verifying ECMP Load Balancing