


Introduction to Operating Systems

3. Interprocess communication

Manuel - Fall 2019

Chapter organisation



Independent threads:

- Cannot affect/be affected by anything
- State not shared with other threads
- Input state determines the output
- Reproducible
- No side effect when stopping/resuming

Where difficulties start:

- Single-tasking: run a thread to completion and start next one
- Multi-tasking:
 - One core shared among several threads
 - Several cores run several threads in parallel
- A thread runs on one core at a time
- A thread can run on different cores at different times
- For threads no difference between one or more cores

Setup:

- Threads sharing a state
- Behavior depends on the execution sequence
- Behavior may seem random/irreproducible

Setup:

- Threads sharing a state
- Behavior depends on the execution sequence
- Behavior may seem random/irreproducible

Major problems:

- 1 How can threads/processes share information?
- 2 How to prevent them for getting in each other's way?
- 3 How to handle sequencing?



6

Operation that either happens in its entirety or not at all:

- Atomic operation cannot be created
- Atomic operations are hardware level
- Central to the question of parallel programming

Operation that either happens in its entirety or not at all:

- Atomic operation cannot be created
- Atomic operations are hardware level
- Central to the question of parallel programming


Example.

Most basic atomic operation, A=B:

- Read a clean value for B
- Set a clean value for A


Race conditions






Practical example:

- Process A wants to queue a file, reads next_free_slot=7
- Interrupt occurs, Process B reads next_free_slot=7
- Process B queues its file in slot 7, and update next_free_slot=8
- Process A resumes using next_free_slot=7
- Game over






































































9:00 am 9:15 am

9:30 am

9:45 am




Chapter organisation



Part of the program where shared memory is accessed:

- No two processes can be in a critical region at the same time
- No assumption on speed/number of CPU
- No process outside a critical region can block other processes
- No process waits forever to enter its critical region



```
if(no milk && no note) {
leave note;
milk the cow;
remove note;
}
```

John

```
if(no milk && no note) {
leave note;
milk the cow;
remove note;
}
```

```
if(no milk && no note) {
leave note;
milk the cow;
remove note;
}
```

John

```
if(no milk && no note) {
leave note;
milk the cow;
remove note;
}
```

Result: too much milk

```
1 leave note Frank;
2 if(no note John) {
3   if(no milk){
4    milk the cow;
5   }
6 }
7 remove note Frank;
```

John

```
1 leave note John;
2 if(no note Frank) {
3   if(no milk) {
4    milk the cow;
5   }
6 }
7 remove note John;
```

```
leave note Frank;
if(no note John) {
  if(no milk) {
    milk the cow;
}
}
remove note Frank;
```

John

```
leave note John;
if(no note Frank) {
  if(no milk) {
    milk the cow;
}
}
remove note John;
```

Result: no milk

```
leave note Frank;
while(note John) {
nothing;
};
if(no milk) {
milk the cow;
}
remove note Frank;
```

John

```
1 leave note John;
2 if(no note Frank) {
3   if(no milk) {
4    milk the cow;
5   }
6 }
7 remove note John;
```

```
1 leave note Frank;
2 while(note John) {
3    nothing;
4 }
5    if(no milk) {
6     milk the cow;
7 }
8    remove note Frank;
```

John

```
1 leave note John;
2 if(no note Frank) {
3   if(no milk) {
4    milk the cow;
5   }
6 }
7 remove note John;
```

Result: just enough milk

Comments on the solution:

- Solution is correct
- Complicated
- Asymmetrical
- Busy wait, CPU time wasted

Simple strategy:

- Assume two processes
- Two functions:
 - enter_region: show process is interested and wait for its turn
 - leave_region: indicates departure from critical region
- Solution is correct
- Drawback: busy wait

Simple strategy:

- Assume two processes
- Two functions:
 - enter_region: show process is interested and wait for its turn
 - leave_region: indicates departure from critical region
- Solution is correct
- Drawback: busy wait

Exercise.

Write the pseudo C code for Peterson's idea using two processes represented by the integers 0 and 1

```
int turn;
   int interested[2];
   void enter_region(int p) {
     int other;
     other=1-p;
     interested(p)=TRUE;
     turn=p;
9
     while(turn==p && interested[other]==TRUE)
10
11
   void leave_region(int p) {
     interested(p)=FALSE;
```

Side effects of Peterson's idea:

- Two processes: L, low priority, and H, high priority
- L enters in a critical region
- H becomes ready
- H has higher priority so the scheduler switches to H
- L has lower priority so is not rescheduled as long as H is busy
- H loops forever

19

Disabling interrupts, good or bad:

Disabling interrupts, good or bad:

- Case 1: block interrupts for the whole computer
 - Interrupts could be disabled for a while (too long?)
 - This gives a lot of power to the programmer
- Case 2: block interrupts for only one CPU
 - No effect on other processors
 - Another CPU can access the variable between read and write

A simple atomic operation:

- Test and Set Lock (TSL)
- Hardware level, requires assembly
- Task: copy lock to register and set lock to 1
- Atomic operation

A simple atomic operation:

- Test and Set Lock (TSL)
- Hardware level, requires assembly
- Task: copy lock to register and set lock to 1
- Atomic operation

```
1 enter_region:
2  TSL REGISTER,LOCK
3  CMP REGISTER,#0
4  JNE enter_region
5  RET
6
7 leave_region:
8  MOVE LOCK,#0
9  RET
```

A simple atomic operation:

- Test and Set Lock (TSL)
- Hardware level, requires assembly
- Task: copy lock to register and set lock to 1
- Atomic operation

```
1 enter_region:
2  TSL REGISTER,LOCK
3  CMP REGISTER,#0
4  JNE enter_region
5  RET
6
7 leave_region:
8  MOVE LOCK,#0
9  RET
```

Note: TSL displays the same side-effect as Peterson's solution when dealing with processes having different priorities

```
int count=0;
    void producer() {
      int item:
      while(1) {
 6
        item=produce_item();
        if(count==N) sleep();
        insert_item(item); count++;
        if(count==1) wakeup(consumer);
 9
10
    void consumer() {
12
      int item;
13
      while(1) {
14
        if(count==0) sleep();
16
        item=remove_item(); count--;
        if(count==N-1) wakeup(producer);
18
        consume_item(item);
19
20
```

Assume the buffer is empty:

- Consumer reads count == 0
- Scheduler stops the consumer and starts the producer
- Producer adds one item
- Producer wakes up the consumer
- Consumer not yet asleep, signal is lost
- Consumer goes asleep
- When the buffer is full the producer falls asleep
- Both consumer and producer sleep forever

Basics:

- 1965, Edseger Dijkstra
- Simple hardware based solution
- Basis of all contemporary OS synchronization mechanisms

Basics:

- 1965, Edseger Dijkstra
- Simple hardware based solution
- Basis of all contemporary OS synchronization mechanisms

A semaphore s in a non-negative variable that can only be changed or tested by two atomic actions:

```
1 down(s) {
2  while(s==0) wait();
3  s--;
4 }
```

```
up(s) {
s++;
}
```



Semaphore and processes

The down operation

Check if the value is > 0

- True: decrement the value and continues
- False: sleep, do not complete the down

Only one single atomic action

The up operation

- Increment the value of the semaphore
- If one or more processes were asleep, randomly choose one to wakeup (complete its down)

Only one single atomic action

Semaphores MUST be implemented in an indivisible way:

- Up and down are implemented using system calls
- OS disables all interrupts while testing, updating the semaphore and putting process to sleep
- When dealing with more than one CPU, semaphores are protected using the TSL instruction

Note: a semaphore operation only takes a few microseconds

Hiding interrupts using semaphores:

- Each I/O device gets a semaphore initialised to 0
- Managing process applies a down when starting an I/O device
- Process is blocked
- Interrupt handler applies an up when receiving an interrupt
- Process is ready to run again

MUTual EXclusion:

- Simplified semaphore
- Takes values 0 (unlocked) or 1 (locked)

On a mutex-lock request:

- If mutex is currently unlocked, lock it; thread can enter in critical region
- If mutex is currently locked, block the calling thread until thread in critical regions is done and calls mutex-unlock
- Randomly chose which thread acquires the lock if more than one are waiting

Mutexes can be implemented in user-space using TSL

```
mutex-lock:
     TSL REGISTER, MUTEX
     CMP REGISTER, #0
     JNE ok
     CALL thread_yield
     JMP mutex-lock
   ok: RET
   mutex-unlock:
     MOVE MUTEX, #0
10
     RET
11
```

Questions.

- What differences were introduced compared to enter_region (3.20)?
- In user-space what happens if a thread tries to acquire lock through busy-waiting?
- Why is thread_yield used?


consumer_producer.c

```
#include <stdio.h>
 2 3 4 5 6 7 8 9
     #include <pthread.h>
     #define MAX 1000
     pthread_mutex_t m; pthread_cond_t cc, cp; int buf=0;
     void *prod() {
       for(int i=1;i<MAX;i++) {</pre>
         pthread_mutex_lock(&m); while(buf!=0) pthread_cond_wait(&cp,&m);
         buf=1; pthread_cond_signal(&cc); pthread_mutex_unlock(&m);
10
        pthread exit(0):
11
12
     void *cons() {
13
      for(int i=1:i<MAX:i++) {
14
         pthread_mutex_lock(&m); while(buf==0) pthread_cond_wait(&cc,&m);
15
         buf=0; pthread_cond_signal(&cp); pthread_mutex_unlock(&m);
16
17
       pthread_exit(0);
18
10
     int main() {
20
      pthread_t p, c;
21
       pthread_mutex_init(&m,0); pthread_cond_init(&cc,0); pthread_cond_init(&cp,0);
22
       pthread_create(&c,0,cons,0); pthread_create(&p,0,prod,0);
23
       pthread_join(p,0); pthread_join(c,0);
24
       pthread cond destroy(&cc); pthread cond destroy(&cp); pthread mutex destroy(&m);
25
```

Alter the previous program such as:

- To display information on the consumer and producer
- To increase the buffers to 100
- To have two consumers and one producer. In this case also print which consumer is active.

Chapter organisation



```
mutex mut = 0; semaphore empty = 100; semaphore full = 0;
    void producer() {
      while(TRUE) {
 4
        item = produce_item();
        mutex-lock(&mut);
 6
        down(&empty);
       insert_item(item);
        mutex-unlock(&mut);
 9
        up(&full);
10
    void consumer() {
12
      while(TRUE) {
13
        down(&full);
14
        mutex-lock(&mut);
16
       item = remove_item();
        mutex-unlock(&mut);
18
        up(&empty); consume_item(item);
19
20
```

In the previous code:

- What is the behavior of the producer when the buffer is full?
- What about the consumer?
- What is the final result for this program?
- How to fix it?

As semaphores and mutexes are sometimes risky *monitors* were introduced:

- Monitors are higher level, cleaner and less risky solution
- A monitor is composed of
 - Procedures/functions
 - Structures
- Only one process can be active within a monitor at a time
- Monitors are a programming concept, compiler must know them
- Mutual exclusion handled by the compiler not the programmer

Basics on monitors:

- Monitors are easy to use for mutual exclusion
- Offer a condition to block "properly" when the buffer is full
- A signal on the condition variable can wake up a blocked process
- Only one process can be active in the monitor
- As soon as the signal on the condition is sent, exit the monitor
- Other process can resume

```
(36)
```

```
monitor ProducerConsumer {
      condition full, empty;
      int count:
      void insert(item) {
        if (count == N) wait(full);
        insert_item(item);
        count++:
        if (count==1) signal(empty);
g
      void remove() {
10
        if (count==0) wait(empty);
        removed = remove_item;
13
        count--:
        if (count==N-1) signal(full);
14
16
      count:= 0:
```

```
void ProducerConsumer::producer() {
      while (TRUE) {
        item = produce_item();
        ProducerConsumer.insert(item);
 5
    void ProducerConsumer::consumer() {
8
      while (TRUE) {
        item=ProducerConsumer.remove():
        consume item(item)
10
```

Limitation of semaphores and monitors: processes need to share some part of the memory. Distributed systems over a network consist of multiple CPU each with its own private memory

Message passing:

- send(destination, &message)
- receive(source,&message), can either block or exit if nothing is received

Potential issues:

- Message lost (sending/acknowledging reception)
- No possible confusion on process names
- Security (authentication, traffic)
- Performance





Useful for problems where several processes must complete before the next phase can start

- Why is thread communication essential?
- What is a critical region?
- Do software solutions exist?
- What is an atomic operation?
- What are the two best and most common solutions?



Thank you!