

Sun Cluster 3.1 Data Service for Oracle Guide

Sun Microsystems, Inc. 4150 Network Circle Santa Clara, CA 95054 U.S.A.

Part No: 817–3306–10 October 2003, Revision A Copyright 2003 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

This product or document is protected by copyright and distributed under licenses restricting its use, copying, distribution, and decompilation. No part of this product or document may be reproduced in any form by any means without prior written authorization of Sun and its licensors, if any. Third-party software, including font technology, is copyrighted and licensed from Sun suppliers.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, docs.sun.com, AnswerBook, AnswerBook2, Solstice DiskSuite, SunPlex, and Solaris are trademarks, registered trademarks, or service marks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc.

The OPEN LOOK and Sun^{TM} Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

Federal Acquisitions: Commercial Software-Government Users Subject to Standard License Terms and Conditions.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright 2003 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Ce produit ou document est protégé par un copyright et distribué avec des licences qui en restreignent l'utilisation, la copie, la distribution, et la décompilation. Aucune partie de ce produit ou document ne peut être reproduite sous aucune forme, par quelque moyen que ce soit, sans l'autorisation préalable et écrite de Sun et de ses bailleurs de licence, s'il y en a. Le logiciel détenu par des tiers, et qui comprend la technologie relative aux polices de caractères, est protégé par un copyright et licencié par des fournisseurs de Sun.

Des parties de ce produit pourront être dérivées du système Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, docs.sun.com, AnswerBook, AnswerBook2, Solstice DiskSuite, SunPlex, et Solaris sont des marques de fabrique ou des marques déposées, ou marques de service, de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc.

L'interface d'utilisation graphique OPEN LOOK et SunTM a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui en outre se conforment aux licences écrites de Sun.

CETTE PUBLICATION EST FOURNIE "EN L'ETAT" ET AUCUNE GARANTIE, EXPRESSE OU IMPLICITE, N'EST ACCORDEE, Y COMPRIS DES GARANTIES CONCERNANT LA VALEUR MARCHANDE, L'APTITUDE DE LA PUBLICATION A REPONDRE A UNE UTILISATION PARTICULIERE, OU LE FAIT QU'ELLE NE SOIT PAS CONTREFAISANTE DE PRODUIT DE TIERS. CE DENI DE GARANTIE NE S'APPLIQUERAIT PAS, DANS LA MESURE OU IL SERAIT TENU JURIDIQUEMENT NUL ET NON AVENU.





Contents

Preface 5

Installing and Configuring Sun Cluster HA for Oracle 9
Overview of the Installation and Configuration Process for Sun Cluster HA for Oracle 10
Planning the Sun Cluster HA for Oracle Installation and Configuration 11
Configuration Requirements 11
Configuration Planning Questions 11
Preparing the Nodes and Disks 12
▼ How to Prepare the Nodes 12
▼ How to Configure Oracle Database Access With Solstice DiskSuite 13
 ▼ How to Configure Oracle Database Access With VERITAS Volume Manager 14
Installing the Oracle Software 15
▼ How to Install the Oracle Software 15
Verifying the Oracle Installation and Configuration 16
▼ How to Verify the Oracle Installation 16
Creating an Oracle Database 16
▼ How to Create an Oracle Database 16
Setting Up Oracle Database Permissions 17
▼ How to Set Up Oracle Database Permissions 18
Installing the Sun Cluster HA for Oracle Packages 21
 ▼ How to Install the Sun Cluster HA for Oracle Packages by Using the Web Start Program 21
▼ How to Install the Sun Cluster HA for Oracle Packages by Using the scinstall Utility 23
Registering and Configuring Sun Cluster HA for Oracle 23

Sun Cluster HA for Oracle Extension Properties	23
lacktriangle How to Register and Configure Sun Cluster HA	for Oracle 27
Where to Go From Here 32	
Verifying the Sun Cluster HA for Oracle Installation	32
▼ How to Verify the Sun Cluster HA for Oracle Ins	stallation 33
Oracle Clients 33	
Location of Sun Cluster HA for Oracle Log Files	34
Understanding the Sun Cluster HA for Oracle Fault M	onitor 34
Oracle Server Fault Monitor 34	
Oracle Listener Fault Monitor 36	
Customizing the Sun Cluster HA for Oracle Server Fau	ılt Monitor 37
Defining Custom Behavior for Errors 38	
Propagating a Custom Action File to All Nodes in	a Cluster 46
Specifying the Custom Action File That a Server Fa	ault Monitor Should Use 46
Upgrading the SUNW.oracle_server Resource Type	47
Information for Registering the New Resource Typ	e Version 47
Information for Migrating Existing Instances of the	e Resource Type 48

A Preset Actions for Database Management System (DBMS) Errors and Logged Alerts 49

Index 57

Preface

Sun Cluster 3.1 Data Service for Oracle Guide explains how to install and configure Sun™ Cluster HA for Oracle on your Sun Cluster nodes.

This document is intended for system administrators with extensive knowledge of Sun software and hardware. Do not use this document as a planning or presales guide. Before reading this document, you should have already determined your system requirements and purchased the appropriate equipment and software.

The instructions in this document assume knowledge of the Solaris $^{\text{TM}}$ operating environment and expertise with the volume manager software that is used with Sun Cluster.

UNIX Commands

This document contains information about commands that are specific to installing and configuring Sun Cluster data services. The document does *not* contain comprehensive information about basic UNIX® commands and procedures, such as shutting down the system, booting the system, and configuring devices. Information about basic UNIX commands and procedures is available from the following sources:

- Online documentation for the Solaris software environment
- Solaris operating environment man pages
- Other software documentation that you received with your system

Typographic Conventions

The following table describes the typographic changes used in this book.

TABLE P-1 Typographic Conventions

Typeface or Symbol	Meaning	Example
AaBbCc123	The names of commands, files, and directories; on-screen computer output	Edit your .login file. Use ls -a to list all files. machine_name% you have mail.
AaBbCc123	What you type, contrasted with on-screen computer output	machine_name% su Password:
AaBbCc123	Command-line placeholder: replace with a real name or value	To delete a file, type rm filename.
AaBbCc123	Book titles, new words, or terms, or words to be emphasized.	Read Chapter 6 in <i>User's Guide</i> . These are called <i>class</i> options. You must be <i>root</i> to do this.

Shell Prompts in Command Examples

The following table shows the default system prompt and superuser prompt for the C shell, Bourne shell, and Korn shell.

TABLE P-2 Shell Prompts

Shell	Prompt
C shell prompt	machine_name%
C shell superuser prompt	machine_name#
Bourne shell and Korn shell prompt	ş
Bourne shell and Korn shell superuser prompt	#

Related Documentation

Information about related Sun Cluster topics is available in the documentation that is listed in the following table.

Topic	Title	Part Number
Data service administration	Sun Cluster 3.1 Data Service Planning and Administration Guide	817-3305
	Sun Cluster 3.1 10/03 Data Services Collection at http://docs.sun.com/db/coll/573.11	
Concepts	Sun Cluster 3.1 10/03 Concepts Guide	817-0519
Software installation	Sun Cluster 3.1 10/03 Software Installation Guide	817-0518
System administration	Sun Cluster 3.1 10/03 System Administration Guide	817-0516
Hardware	Sun Cluster 3.1 Hardware Administration Manual	817-0168
administration	Sun Cluster 3.x Hardware Administration Collection at http://docs.sun.com/db/coll/1024.1	
Data service development	Sun Cluster 3.1 10/03 Data Services Developer's Guide	817-0520
Error messages	Sun Cluster 3.1 10/03 Error Messages Guide	817-0521
Command and function reference	Sun Cluster 3.1 10/03 Reference Manual	817-0522
Release	Sun Cluster 3.1 Data Services 10/03 Release Notes	817-3324
information	Sun Cluster 3.1 10/03 Release Notes	817-0638
	Sun Cluster 3.x Release Notes Supplement	816-3381

Accessing Sun Documentation Online

The docs.sun.comSM Web site enables you to access Sun technical documentation online. You can browse the docs.sun.com archive or search for a specific book title or subject. The URL is http://docs.sun.com.

Ordering Sun Documentation

Sun Microsystems offers select product documentation in print. For a list of documents and how to order them, see "Buy printed documentation" at http://docs.sun.com.

Help

If you have problems installing or using Sun Cluster, contact your service provider and provide the following information:

- Your name and email address (if available)
- Your company name, address, and phone number
- The model and serial numbers of your systems
- The release number of the operating environment (for example, Solaris 8)
- The release number of Sun Cluster (for example, Sun Cluster 3.0)

Use the following commands to gather information about each node on your system for your service provider.

Command	Function
prtconf -v	Displays the size of the system memory and reports information about peripheral devices
psrinfo -v	Displays information about processors
showrev -p	Reports which patches are installed
prtdiag -v	Displays system diagnostic information
scinstall -pv	Displays Sun Cluster release and package version information

Also have available the contents of the /var/adm/messages file.

Installing and Configuring Sun Cluster HA for Oracle

This chapter contains the following procedures.

- "How to Prepare the Nodes" on page 12
- "How to Configure Oracle Database Access With Solstice DiskSuite" on page 13
- "How to Configure Oracle Database Access With VERITAS Volume Manager" on page 14
- "How to Install the Oracle Software" on page 15
- "How to Verify the Oracle Installation" on page 16
- "How to Create an Oracle Database" on page 16
- "How to Set Up Oracle Database Permissions" on page 18
- "How to Install the Sun Cluster HA for Oracle Packages by Using the Web Start Program" on page 21
- "How to Install the Sun Cluster HA for Oracle Packages by Using the scinstall Utility" on page 23
- "How to Register and Configure Sun Cluster HA for Oracle" on page 27
- "How to Verify the Sun Cluster HA for Oracle Installation" on page 33
- "How to Specify the Custom Action File That a Server Fault Monitor Should Use" on page 47

Note – You can use $SunPlex^{TM}$ Manager to install and configure this data service. See the SunPlex Manager online help for details.

Overview of the Installation and Configuration Process for Sun Cluster HA for Oracle

The following table summarizes the tasks for installing and configuring Sun Cluster HA for Oracle. The table also provides cross-references to detailed instructions for performing the tasks. Perform these tasks in the order that they are listed.

TABLE 1-1 Task Map: Installing and Configuring HA for Oracle

Task	Cross-Reference
Plan the Sun Cluster HA for Oracle installation and configuration	"Planning the Sun Cluster HA for Oracle Installation and Configuration" on page 11
Prepare the nodes and disks	"Preparing the Nodes and Disks" on page 12
Install the Oracle software	"How to Install the Oracle Software" on page 15
Verify the Oracle installation	"How to Verify the Oracle Installation" on page 16
Create an Oracle database	"How to Create an Oracle Database" on page 16
Set up Oracle database permissions	"How to Set Up Oracle Database Permissions" on page 18
Install the Sun Cluster HA for Oracle packages	"Installing the Sun Cluster HA for Oracle Packages" on page 21
Register and configure Sun Cluster HA for Oracle	"How to Register and Configure Sun Cluster HA for Oracle" on page 27
Verify the Sun Cluster HA for Oracle installation	"How to Verify the Oracle Installation" on page 16
Understand Sun Cluster HA for Oracle fault monitor	"Understanding the Sun Cluster HA for Oracle Fault Monitor" on page 34
(Optional) Customize the Sun Cluster HA for Oracle server fault monitor	"Customizing the Sun Cluster HA for Oracle Server Fault Monitor" on page 37
(Optional) Upgrade the SUNW.oracle_server resource type	"Upgrading the SUNW.oracle_server Resource Type" on page 47

Planning the Sun Cluster HA for Oracle Installation and Configuration

This section contains the information that you need to plan your Sun Cluster HA for Oracle installation and configuration.

Configuration Requirements



Caution – Your data service configuration might not be supported if you do not adhere to these requirements.

Use the requirements in this section to plan the installation and configuration of Sun Cluster HA for Oracle. These requirements apply to Sun Cluster HA for Oracle only. You must meet these requirements before you proceed with your Sun Cluster HA for Oracle installation and configuration.

For requirements that apply to all data services, see "Identifying Data Service Special Requirements" on page 3.

- Oracle application files These files include Oracle binaries, configuration files, and parameter files. You can install these files either on the local file system, the highly available local file system, or on the cluster file system.
 - See "Configuration Guidelines for Sun Cluster Data Services" in *Sun Cluster 3.1 Data Service Planning and Administration Guide* for the advantages and disadvantages of placing the Oracle binaries on the local file system, highly available local file system, and the cluster file system.
- Database-related files These files include the control file, redo logs, and data files. You must install these files on the highly available local file system or the cluster file system as either raw devices or regular files.

Configuration Planning Questions

Use the questions in this section to plan the installation and configuration of Sun Cluster HA for Oracle. Write the answers to these questions in the space that is provided on the data service worksheets in "Configuration Worksheets" in *Sun Cluster 3.1 Data Service Planning and Administration Guide.*

■ What resource groups will you use for network addresses and application resources and the dependencies between them?

- What is the logical hostname (for failover services) or shared address (for scalable services) for clients that will access the data service?
- Where will the system configuration files reside?

See "Configuration Guidelines for Sun Cluster Data Services" in Sun Cluster 3.1 Data Service Planning and Administration Guide for the advantages and disadvantages of placing the Oracle binaries on the local file system rather than the cluster file system.

Preparing the Nodes and Disks

This section contains the procedures that you need to prepare the nodes and disks.

How to Prepare the Nodes

Use this procedure to prepare for the installation and configuration of Oracle software.



Caution – Perform all of the steps in this section on all of the nodes. If you do not perform all of the steps on all of the nodes, the Oracle installation is incomplete. An incomplete Oracle installation causes Sun Cluster HA for Oracle to fail during startup.

Note – Consult the Oracle documentation before you perform this procedure.

The following steps prepare your nodes and install the Oracle software.

- 1. Become superuser on all of the cluster members.
- 2. Configure the /etc/nsswitch.conf files as follows so that the data service starts and stops correctly if a switchover or failover occurs.

On each node that can master the logical host that runs Sun Cluster HA for Oracle, include one of the following entries for group in the /etc/nsswitch.conf file.

```
group:
                   files [NOTFOUND=return] nis
group:
                   files [NOTFOUND=return] nisplus
group:
```

Sun Cluster HA for Oracle uses the su *user* command to start and stop the database node. The network information name service might become unavailable when a cluster node's public network fails. Adding one of the preceding entries for group

ensures that the su(1M) command does not refer to the NIS/NIS+ name services if the network information name service is unavailable.

3. Configure the cluster file system for Sun Cluster HA for Oracle.

If raw devices contain the databases, configure the global devices for raw device access. See the *Sun Cluster 3.1 10/03 Software Installation Guide* for information about how to configure global devices.

If you use the Solstice DiskSuite™/Solaris Volume Manager software, configure the Oracle software to use UNIX file system (UFS) logging on mirrored metadevices or raw-mirrored metadevices. See the Solstice DiskSuite/Solaris Volume Manager documentation for more information about how to configure raw-mirrored metadevices.

4. Prepare the \$ORACLE HOME directory on a local or multihost disk.

Note – If you install the Oracle binaries on a local disk, use a separate disk if possible. Installing the Oracle binaries on a separate disk prevents the binaries from overwrites during operating environment reinstallation.

5. On each node, create an entry for the database administrator (DBA) group in the /etc/group file, and add potential users to the group.

You typically name the DBA group *dba*. Verify that the root and *oracle* users are members of the *dba* group, and add entries as necessary for other DBA users. Ensure that the group IDs are the same on all of the nodes that run Sun Cluster HA for Oracle, as the following example illustrates.

```
dba: *:520:root, oracle
```

You can create group entries in a network name service (for example, NIS or NIS+). If you create group entries in this way, add your entries to the local /etc/inet/hosts file to eliminate dependency on the network name service.

6. On each node, create an entry for the Oracle user ID (oracle).

You typically name the Oracle user ID *oracle*. The following command updates the /etc/passwd and /etc/shadow files with an entry for the Oracle user ID.

```
# useradd -u 120 -g dba -d /Oracle-home oracle
```

Ensure that the *oracle* user entry is the same on all of the nodes that run Sun Cluster HA for Oracle.

▼ How to Configure Oracle Database Access With Solstice DiskSuite

Use this procedure to configure the Oracle database with Solstice DiskSuite volume manager.

1. Configure the disk devices for the Solstice DiskSuite software to use.

See the Sun Cluster 3.1 10/03 Software Installation Guide for information about how to configure the Solstice DiskSuite software.

2. If you use raw devices to contain the databases, run the following commands to change each raw-mirrored metadevice's owner, group, and mode.

If you do not use raw devices, do not perform this step.

a. If you create raw devices, run the following commands for each device on each node that can master the Oracle resource group.

```
# chown oracle /dev/md/metaset/rdsk/dn
# chgrp dba /dev/md/metaset/rdsk/dn
# chmod 600 /dev/md/metaset/rdsk/dn
metaset
             Specifies the name of the diskset
/rdsk/dn
             Specifies the name of the raw disk device within the metaset
```

diskset

b. Verify that the changes are effective.

ls -lL /dev/md/metaset/rdsk/dn

▼ How to Configure Oracle Database Access With **VERITAS Volume Manager**

Use this procedure to configure the Oracle database with VERITAS Volume Manager software.

1. Configure the disk devices for the VxVM software to use.

See the Sun Cluster 3.1 10/03 Software Installation Guide for information about how to configure VERITAS Volume Manager.

2. If you use raw devices to contain the databases, run the following commands on the current disk-group primary to change each device's owner, group, and mode.

If you do not use raw devices, do not perform this step.

a. If you create raw devices, run the following command for each raw device.

```
# vxedit -g diskgroup set user=oracle group=dba mode=600 volume
diskgroup
             Specifies the name of the disk group
volume
             Specifies the name of the raw volume within the disk group
```

b. Verify that the changes are effective.

```
# ls -lL /dev/vx/rdsk/diskgroup/volume
```

c. Reregister the disk device group with the cluster to keep the VxVM namespace consistent throughout the cluster.

scconf -c -D name=diskgroup

Installing the Oracle Software

This section contains the procedure that you need to install Oracle software.

How to Install the Oracle Software

- 1. Become superuser on a cluster member.
- 2. Note the Oracle installation requirements.

Install Oracle binaries on one of the following locations.

- Local disks of the cluster nodes
- Highly available local file system
- Cluster file system

Note – Before you install the Oracle software on the cluster file system, start the Sun Cluster software and become the owner of the disk device group.

See "Preparing the Nodes and Disks" on page 12 for more information about installation locations.

3. Install the Oracle software.

Regardless of where you install the Oracle software, modify each node's /etc/system files as you would in standard Oracle installation procedures. Then reboot.

Log in as oracle to ensure ownership of the entire directory before you perform this step. See the appropriate Oracle installation and configuration guides for instructions about how to install Oracle software.

Verifying the Oracle Installation and Configuration

This section contains the procedure that you need to verify the Oracle installation and configuration.

▼ How to Verify the Oracle Installation

This procedure does not verify that your application is highly available because you have not yet installed your data service.

- 1. Verify that the *oracle* user and the *dba* group own the \$ORACLE HOME/bin/oracle directory.
- 2. Verify that the \$ORACLE HOME/bin/oracle permissions are set as follows.

-rwsr-s--x

3. Verify that the listener binaries exist in the \$ORACLE HOME/bin directory.

Where to Go From Here

When you have completed the work in this section, go to "Creating an Oracle Database" on page 16.

Creating an Oracle Database

This section contains the procedure to configure and create the initial Oracle database in a Sun Cluster environment. If you create and configure additional databases, omit the procedure "How to Create an Oracle Database" on page 16.

▼ How to Create an Oracle Database

1. Prepare database configuration files.

Place all of the database-related files (data files, redo log files, and control files) on either shared raw global devices or on the cluster file system. See "Preparing the Nodes and Disks" on page 12 for information about installation locations.

Within the init\$ORACLE_SID.ora or config\$ORACLE_SID.ora file, you might need to modify the assignments for control_files and background_dump_dest to specify the locations of the control files and alert files.

Note – If you use Solaris authentication for database logins, set the remote os authent variable in the init\$ORACLE SID.ora file to True.

2. Create the database.

Start the Oracle installer and select the option to create a database. Alternatively, depending on your Oracle version, you can use the Oracle svrmgrl(1M) command to create the database.

During creation, ensure that all of the database-related files are placed in the appropriate location, either on shared global devices or on the cluster file system.

3. Verify that the file names of your control files match the file names in your configuration files.

4. Create the v\$sysstat view.

Run the catalog scripts that create the v\$sysstat view. The Sun Cluster HA for Oracle fault monitor uses this view.

Where to Go From Here

When you have completed the work in this section, go to "Setting Up Oracle Database Permissions" on page 17.

Setting Up Oracle Database Permissions

Perform the procedure in this section to set up Oracle database permissions for Oracle 8i and Oracle 9i.

▼ How to Set Up Oracle Database Permissions

- 1. Enable access for the user and password to be used for fault monitoring.
 - To use the Oracle authentication method For all of the supported Oracle releases, type the following script at the sqlplus prompt.

■ To use the Solaris authentication method – Grant permission for the database to use Solaris authentication.

Note – The user for which you enable Solaris authentication is the user who owns the files under the \$ORACLE_HOME directory. The following code sample shows that the user *oracle* owns these files.

2. Configure NET8 for the Sun Cluster software.

The listener. ora file must be accessible from all of the nodes that are in the cluster. Place these files either under the cluster file system or in the local file system of each node that can potentially run the Oracle resources.

Note – If you place the listener.ora file in a location other than the /var/opt/oracle directory or the \$ORACLE_HOME/network/admin directory, you must specify the TNS_ADMIN variable or an equivalent Oracle variable in a user-environment file. For information about Oracle variables, see the Oracle documentation. You must also run the scrgadm(1M) command to set the resource extension parameter User_env, which sources the user-environment file. See Table 1–2 or Table 1–3 for format details.

Sun Cluster HA for Oracle imposes no restrictions on the listener name—it can be any valid Oracle listener name.

The following code sample identifies the lines in listener.ora that are updated.

```
LISTENER =
    (ADDRESS LIST =
             (ADDRESS =
                 (PROTOCOL = TCP)
                     (HOST = logical-hostname) <- use logical hostname
                 (PORT = 1527)
            )
SID LIST LISTENER =
                         (SID_NAME = SID) < - Database name,
default is ORCL
                   The following code sample identifies the lines in tnsnames.ora that are updated
                   on client machines.
service name =
                          (ADDRESS =
                                  (PROTOCOL = TCP)
                                  (HOST = logicalhostname) <- logical hostname
```

(SID = <SID>)) <- database name, default is ORCL
The following example shows how to update the listener.ora and
tnsnames.ora files for the following Oracle instances.</pre>

(CONNECT_DATA =

Instance	Logical Host	Listener
ora8	hadbms3	LISTENER-ora8

(PORT = 1527) <- must match port in LISTENER.ORA

Instance	Logical Host	Listener
ora9	hadbms4	LISTENER-ora9

The corresponding listener.ora entries are the following entries.

```
LISTENER-ora9 =
    (ADDRESS_LIST =
            (ADDRESS =
                (PROTOCOL = TCP)
                (HOST = hadbms4)
                (PORT = 1530)
       )
SID LIST LISTENER-ora9 =
    (SID_LIST =
            (SID DESC =
               (SID NAME = ora9)
        )
LISTENER-ora8 =
  (ADDRESS LIST =
    (ADDRESS= (PROTOCOL=TCP) (HOST=hadbms3) (PORT=1806))
SID_LIST_LISTENER-ora8 =
  (SID LIST =
     (SID DESC =
            (SID_NAME = ora8)
```

The corresponding tnsnames.ora entries are the following entries.

```
ora8 =
(DESCRIPTION =
   (ADDRESS_LIST =
            (ADDRESS = (PROTOCOL = TCP)
            (HOST = hadbms3)
            (PORT = 1806))
    (CONNECT_DATA = (SID = ora8))
)
ora9 =
(DESCRIPTION =
  (ADDRESS_LIST =
        (ADDRESS =
                (PROTOCOL = TCP)
                (HOST = hadbms4)
                (PORT = 1530))
 )
      (CONNECT DATA = (SID = ora9))
```

3. Verify that the Sun Cluster software is installed and running on all of the nodes.

Where to Go From Here

Go to "Installing the Sun Cluster HA for Oracle Packages" on page 21 to install the Sun Cluster HA for Oracle packages.

Installing the Sun Cluster HA for Oracle Packages

If you did not install the Sun Cluster HA for Oracle packages during your initial Sun Cluster installation, perform this procedure to install the packages. Perform this procedure on each cluster node where you are installing the Sun Cluster HA for Oracle packages. To complete this procedure, you need the Sun Cluster Agents CD-ROM.

If you are installing more than one data service simultaneously, perform the procedure in "Installing the Software" in Sun Cluster 3.1 10/03 Software Installation Guide.

Install the Sun Cluster HA for Oracle packages by using one of the following installation tools:

- The Web Start program
- The scinstall utility

Note – The Web Start program is *not* available in releases earlier than Sun Cluster 3.1 Data Services 10/03.

▼ How to Install the Sun Cluster HA for Oracle Packages by Using the Web Start Program

You can run the Web Start program with a command-line interface (CLI) or with a graphical user interface (GUI). The content and sequence of instructions in the CLI and the GUI are similar. For more information about the Web Start program, see the installer(1M) man page.

1. On the cluster node where you are installing the Sun Cluster HA for Oracle packages, become superuser.

- 2. (Optional) If you intend to run the Web Start program with a GUI, ensure that your DISPLAY environment variable is set.
- 3. Load the Sun Cluster Agents CD-ROM into the CD-ROM drive.

If the Volume Management daemon vold(1M) is running and configured to manage CD-ROM devices, it automatically mounts the CD-ROM on the /cdrom/scdataservices 3 1 vb directory.

4. Change to the Sun Cluster HA for Oracle component directory of the CD-ROM.

The Web Start program for the Sun Cluster HA for Oracle data service resides in this directory.

```
# cd /cdrom/scdataservices 3 1 vb/\
components/SunCluster_HA_Oracle_3.1
```

- 5. Start the Web Start program.
 - # ./installer
- 6. When you are prompted, select the type of installation.
 - To install only the C locale, select Typical.
 - To install other locales, select Custom.
- 7. Follow instructions on the screen to install the Sun Cluster HA for Oracle packages on the node.

After the installation is finished, the Web Start program provides an installation summary. This summary enables you to view logs that the Web Start program created during the installation. These logs are located in the /var/sadm/install/logs directory.

- 8. Exit the Web Start program.
- 9. Unload the Sun Cluster Agents CD-ROM from the CD-ROM drive.
 - a. To ensure that the CD-ROM is not being used, change to a directory that does not reside on the CD-ROM.
 - b. Eject the CD-ROM.
 - # eject cdrom

Where to Go From Here

See "Registering and Configuring Sun Cluster HA for Oracle" on page 23 to register Sun Cluster HA for Oracle and to configure the cluster for the data service.

▼ How to Install the Sun Cluster HA for Oracle Packages by Using the scinstall Utility

- 1. Load the Sun Cluster Agents CD-ROM into the CD-ROM drive.
- 2. Run the scinstall utility with no options.

This step starts the scinstall utility in interactive mode.

3. Choose the menu option, Add Support for New Data Service to This Cluster Node.

The scinstall utility prompts you for additional information.

4. Provide the path to the Sun Cluster Agents CD-ROM.

The utility refers to the CD as the "data services cd."

5. Specify the data service to install.

The scinstall utility lists the data service that you selected and asks you to confirm your choice.

- 6. Exit the scinstall utility.
- 7. Unload the CD from the drive.

Where to Go From Here

See "Registering and Configuring Sun Cluster HA for Oracle" on page 23 to register Sun Cluster HA for Oracle and to configure the cluster for the data service.

Registering and Configuring Sun Cluster HA for Oracle

This section contains the procedures that you need to configure Sun Cluster HA for Oracle.

Sun Cluster HA for Oracle Extension Properties

Use the extension properties in Table 1–2 to create your resources. Use the command scrgadm -x parameter=value to configure extension properties when you create your resource. Use the procedure in "Administering Data Service Resources" in *Sun Cluster 3.1 Data Service Planning and Administration Guide* to configure the extension

properties if you have already created your resources. You can update some extension properties dynamically. You can update others, however, only when you create or disable a resource. The Tunable entries indicate when you can update each property. See "Standard Properties" in *Sun Cluster 3.1 Data Service Planning and Administration Guide* for details about all Sun Cluster properties.

TABLE 1-2 Sun Cluster HA for Oracle Listener Extension Properties

Name/Data Type	Description
LISTENER_NAME	The name of the Oracle listener.
(string)	Default: LISTENER
	Range: None
	Tunable: When disabled
ORACLE_HOME	The path to the Oracle home directory.
(string)	Default: None
	Range: Minimum = 1
	Tunable: When disabled
User_env (string)	A file that contains environment variables to be set before listener startup and shutdown. Those environment variables that have values that differ from Oracle defaults must be defined in this file.
	For example, a user's listener.ora file might not reside under the /var/opt/oracle directory or the \$ORACLE_HOME/network/admin. directory. In this situation, the TNS_ADMIN environment variable should be defined.
	The definition of each environment variable that is defined must follow the format VARIABLE_NAME=VARIABLE_VALUE. Each of these environment variables must be specified, one per line in the environment file.
	Default: ""
	Range: None
	Tunable: Any time

Table 1–3 describes the extension properties that you can set for the Oracle server. For the Oracle server, you are required to set only the following extension properties:

- ORACLE HOME
- ORACLE SID
- Alert_log_file
- Connect_string

 TABLE 1-3 Sun Cluster HA for Oracle Server Extension Properties

Name/Data Type	Description
Alert_log_file (string)	Oracle alert log file.
	Default: None
	Range: Minimum = 1
	Tunable: Any time
Auto_End_Bkp (Boolean)	 Specifies whether the following recovery actions are performed if an Oracle relational database management system (RDBMS) hot backup is interrupted. Recognizing when a database fails to open because of files that remain in hot backup mode. This verification process occurs when Sun Cluster HA for Oracle starts. Identifying and releasing all files that remain in hot backup mode. Opening the database for use.
	 The permitted values for this property are as follows: False – Specifies that the recovery actions are <i>not</i> performed. This value is the default. True – Specifies that the recovery actions are performed.
	Default: False
	Range: None
	Tunable: Any time
Connect_cycle (integer)	The number of probe cycles that the server fault monitor performs before disconnecting from the database.
	Default: 5
	Range: 0 – 99, 999
	Tunable: Any time
Connect_string (string)	The Oracle user and password that the server fault monitor uses to connect to the database.
	Default: None
	Range: Minimum = 1
	Tunable: Any time

TABLE 1–3 Sun Cluster HA for Oracle Server Extension Properties (Continued)

Name/Data Type	Description
Custom_action_file (string)	The absolute path of the file that defines the custom behavior of the Sun Cluster HA for Oracle server fault monitor.
	Default: ""
	Range: None
	Tunable: Any time
	Introduced in release: 3.1 10/03
Debug_level (integer)	The level to which Sun Cluster HA for Oracle debug messages are logged.
	Default: 1
	Range: 1–100
	Tunable: Any time
ORACLE_HOME (string)	The path to the Oracle home directory.
	Default: None
	Range: Minimum = 1
	Tunable: When disabled
ORACLE_SID (string)	The Oracle system identifier.
	Default: None
	Range: Minimum = 1
	Tunable: When disabled
Parameter_file (string)	The Oracle parameter file. If the Oracle parameter file is not specified this property defaults to Oracle's default.
	Default: ""
	Range: Minimum = 0
	Tunable: Any time
Probe_timeout (integer)	The time-out value (in seconds) that the server fault monitor uses to probe an Oracle server instance.
	Default: 60
	Range: 0 – 99, 999
	Tunable: Any time

TABLE 1-3 Sun Cluster HA for Oracle Server Extension Properties (Continued)

Name/Data Type	Description
Restart_type (string)	Specifies the entity that the server fault monitor restarts when the response to a fault is restart. The permitted values for this property are as follows: RESOURCE_GROUP_RESTART – Specifies that all resources in the resource group that contains this resource are restarted RESOURCE_RESTART – Specifies that only this resource is restarted
	Default: RESOURCE_GROUP_RESTART
	Range: None
	Tunable: Any time
User_env (string)	A file that contains environment variables to be set before server startup and shutdown. Those environment variables that have values that differ from Oracle defaults must be defined in this file.
	For example, a user's listener.ora file might not reside under the /var/opt/oracle directory or the \$ORACLE_HOME/network/admin. directory. In this situation, the TNS_ADMIN environment variable should be defined.
	The definition of each environment variable that is defined must follow the format VARIABLE_NAME=VARIABLE_VALUE. Each of these environment variables must be specified, one per line in the environment file.
	Default: NULL
	Range: None
	Tunable: Any time
Wait_for_online (Boolean)	Wait in the START method until the database is online.
	Default: True
	Range: None
	Tunable: Any time

How to Register and Configure Sun Cluster HA for Oracle

Use this procedure to configure Sun Cluster HA for Oracle as a failover data service. This procedure assumes that you installed the data service packages during your initial Sun Cluster installation. If you did not install the Sun Cluster HA for Oracle

packages as part of your initial Sun Cluster installation, go to "Installing the Sun Cluster HA for Oracle Packages" on page 21 to install the data service packages. Otherwise, use this procedure to configure the Sun Cluster HA for Oracle.

You must have the following information to perform this procedure.

- The names of the cluster nodes that master the data service.
- The network resource that clients use to access the data service. Normally, you set up this IP address when you install the cluster. See the *Sun Cluster 3.1 10/03 Concepts Guide* for details about network resources.
- The path to the Oracle application binaries for the resources that you plan to configure.
- 1. Become superuser on a cluster member.
- 2. Run the scrgadm command to register the resource types for the data service.

For Sun Cluster HA for Oracle, you register two resource types, SUNW.oracle server and SUNW.oracle listener, as follows.

```
# scrgadm -a -t SUNW.oracle_server
# scrgadm -a -t SUNW.oracle listener
```

-a Adds the data service resource type.

-t SUNW.oracle_type Specifies the predefined resource type name for your data service.

3. Create a failover resource group to hold the network and application resources.

You can optionally select the set of nodes on which the data service can run with the -h option, as follows.

```
# scrgadm -a -g resource-group [-h nodelist]
```

-g *resource-group* Specifies the name of the resource group. This name can be

your choice but must be unique for resource groups within

the cluster.

-h nodelist Specifies an optional comma-separated list of physical node

names or IDs that identify potential masters. The order here determines the order in which the nodes are considered as

primary during failover.

Note – Use the -h option to specify the order of the node list. If all of the nodes that are in the cluster are potential masters, you do not need to use the -h option.

4. Verify that all of the network resources that you use have been added to your name service database.

You should have performed this verification during the Sun Cluster installation.

Note - Ensure that all of the network resources are present in the server's and client's /etc/inet/hosts file to avoid any failures because of name service lookup.

5. Add a network resource to the failover resource group.

scrgadm -a -L -g resource-group -1 logical-hostname [-n netiflist]

-1 logical-hostname

Specifies a network resource. The network resource is the logical hostname or shared address (IP address) that clients

use to access Sun Cluster HA for Oracle.

[-n netiflist]

Specifies an optional, comma-separated list that identifies the IP Networking Multipathing groups that are on each node. Each element in netiflist must be in the form of netif@node. netif can be given as an IP Networking Multipathing group name, such as sc ipmp0. The node can be identified by the node name or node ID, such as sc_ipmp0@1 or sc_ipmp@phys-schost-1.

Note – Sun Cluster does not currently support the use of the adapter name for netif.

6. Register the SUNW.HAStoragePlus resource type with the cluster.

```
# scrgadm -a -t SUNW.HAStoragePlus
```

7. Create the resource oracle-hastp-rs of type SUNW.HAStoragePlus.

```
# scrgadm -a -j oracle-hastp-rs -g oracle-rg -t SUNW.HAStoragePlus \
[If your database is on a raw device, specify the global device path.]
-x GlobalDevicePaths=ora-set1,/dev/global/dsk/dl \
[If your database is on a Cluster File Service, specify
the global file system and local file system mount points.]
-x FilesystemMountPoints=/global/ora-inst,/global/ora-data/logs,/
local/ora-data \
[Set AffinityOn to true.]
-x AffinityOn=TRUE
```

Note - AffinityOn must be set to TRUE and the local file system must reside on global disk groups to be failover.

8. Run the scswitch command to complete the following tasks and bring the resource group oracle-rg online on a cluster node.



Caution – Be sure to switch only at the resource group level. Switching at the device group level confuses the resource group, causing it to fail over.

- Move the resource group into a MANAGED state.
- Bring the resource group online.

This node is made the primary for device group ora-set1 and raw device /dev/global/dsk/d1. Device groups that are associated with file systems such as /global/ora-inst and /global/ora-data/logs are also made primaries on this node.

```
# scswitch -Z -g oracle-rg
```

- 9. Create Oracle application resources in the failover resource group.
 - Oracle server resource:

```
# scrgadm -a -j resource -g resource-group \
-t SUNW.oracle_server \
-x Connect_string=user/passwd \
-x ORACLE_SID=instance \
-x ORACLE_HOME=Oracle-home \
-x Alert_log_file=path-to-log \
-x Restart_type=entity-to-restart
-y resource_dependencies=storageplus-resource
```

Oracle listener resource:

```
# scrgadm -a -j resource -g resource-group \
-t SUNW.oracle_listener \
-x LISTENER_NAME=listener \
-x ORACLE_HOME=Oracle-home
-y resource dependencies=storageplus-resource
```

- j resource

Specifies the name of the resource to add.

-g resource-group

Specifies the name of the resource group into which the resources are to be placed.

- -t SUNW.oracle_server/listener Specifies the type of the resource to add.
- -x Alert_log_file=path-to-log
 Sets the path under \$ORACLE_HOME for the server message log.
- -x Connect_string=user/passwd
 Specifies the user and password that the fault monitor uses to connect to the database. These settings must agree with the permissions that you set up in

"How to Set Up Oracle Database Permissions" on page 18. If you use Solaris authorization, type a slash (/) instead of the user name and password.

- -x ORACLE_SID=*instance*Sets the Oracle system identifier.
- -x LISTENER_NAME=*listener*Sets the name of the Oracle listener instance. This name must match the corresponding entry in listener.ora.
- -x ORACLE_HOME=Oracle-home
 Sets the path to the Oracle home directory.
- -x Restart_type=entity-to-restart Specifies the entity that the server fault monitor restarts when the response to a fault is restart. Set entity-to-restart as follows:
 - To specify that all resources in the resource group that contains this resource are restarted, set *entity-to-restart* to RESOURCE_GROUP_RESTART. By default, the resource group that contains this resource is restarted.
 - If you set *entity-to-restart* to RESOURCE_GROUP_RESTART, all other resources (such as Apache or DNS) in the resource group are restarted, even if they are not faulty. Therefore, include in the resource group only the resources that you require to be restarted when the Oracle server resource is restarted.
 - To specify that only this resource is restarted, set *entity-to-restart* to RESOURCE RESTART.

Note – Optionally, you can set additional extension properties that belong to the Oracle data service to override their default values. See "Sun Cluster HA for Oracle Extension Properties" on page 23 for a list of extension properties.

10. Enable the resource and fault monitoring.

- # scswitch -Z -g resource-group
- -Z Enables the resource and monitor, moves the resource group

to the MANAGED state, and brings it online.

-g resource-group Specifies the name of the resource group.

Example—Registering Sun Cluster HA for Oracle

The following example shows how to register Sun Cluster HA for Oracle on a two-node cluster.

Cluster Information Node names: phys-schost-1, phys-schost-2 Logical Hostname: schost-1

```
Resource group: resource-group-1 (failover resource group)
Oracle Resources: oracle-server-1, oracle-listener-1
Oracle Instances: ora-lsnr (listener), ora-srvr (server)
(Add the failover resource group to contain all of the resources.)
# scrgadm -a -g resource-group-1
(Add the logical hostname resource to the resource group.)
# scrgadm -a -L -g resource-group-1 -l schost-1
(Register the Oracle resource types.)
# scrgadm -a -t SUNW.oracle server
# scrgadm -a -t SUNW.oracle_listener
(Add the Oracle application resources to the resource group.)
# scrgadm -a -j oracle-server-1 -g resource-group-1 \
-t SUNW.oracle server -x ORACLE HOME=/global/oracle \
-x Alert log file=/global/oracle/message-log \
-x ORACLE_SID=ora-srvr -x Connect_string=scott/tiger
# scrgadm -a -j oracle-listener-1 -g resource-group-1 \
-t SUNW.oracle listener -x ORACLE HOME=/global/oracle \
-x LISTENER NAME=ora-lsnr
(Bring the resource group online.)
# scswitch -Z -g resource-group-1
```

Where to Go From Here

Go to "Verifying the Sun Cluster HA for Oracle Installation" on page 32 after you register and configure Sun Cluster HA for Oracle.

Verifying the Sun Cluster HA for Oracle Installation

Perform the following verification tests to make sure that you have correctly installed Sun Cluster HA for Oracle.

These sanity checks ensure that all of the nodes that run Sun Cluster HA for Oracle can start the Oracle instance and that the other nodes in the configuration can access the Oracle instance. Perform these sanity checks to isolate any problems in starting the Oracle software from Sun Cluster HA for Oracle.

How to Verify the Sun Cluster HA for Oracle Installation

- 1. Log in as *oracle* to the node that currently masters the Oracle resource group.
- 2. Set the environment variables ORACLE SID and ORACLE HOME.
- 3. Confirm that you can start the Oracle instance from this node.
- 4. Confirm that you can connect to the Oracle instance.

Use the sqlplus command with the user/password variable that is defined in the connect string property.

sqlplus user/passwd@tns_service

5. Shut down the Oracle instance.

The Sun Cluster software restarts the Oracle instance because the Oracle instance is under Sun Cluster control.

6. Switch the resource group that contains the Oracle database resource to another cluster member.

The following example shows how to complete this step.

```
# scswitch -z -g resource-group -h node
```

- 7. Log in as *oracle* to the node that now contains the resource group.
- 8. Repeat Step 3 and Step 4 to confirm interactions with the Oracle instance.

Oracle Clients

Clients must always refer to the database by using the network resource, not the physical hostname. The network resource is an IP address that can move between physical nodes during failover. The physical hostname is a machine name.

For example, in the tnsnames . ora file, you must specify the network resource as the host on which the database instance is running. The network resource is a logical hostname or a shared address. See "How to Set Up Oracle Database Permissions" on page 18.

Note – Oracle client-server connections cannot survive a Sun Cluster HA for Oracle switchover. The client application must be prepared to handle disconnection and reconnection or recovery as appropriate. A transaction monitor might simplify the application. Further, Sun Cluster HA for Oracle node recovery time is application dependent.

Location of Sun Cluster HA for Oracle Log Files

Each instance of the Sun Cluster HA for Oracle data service maintains log files in subdirectories of the /var/opt/SUNWscor directory.

- The /var/opt/SUNWscor/oracle_server directory contains log files for the Oracle server.
- The /var/opt/SUNWscor/oracle_listener directory contains log files for the Oracle listener.

These files contain information about actions that the Sun Cluster HA for Oracle data service performs. Refer to these files to obtain diagnostic information for troubleshooting your configuration or to monitor the behavior of the Sun Cluster HA for Oracle data service.

Understanding the Sun Cluster HA for Oracle Fault Monitor

The two fault monitors for Sun Cluster HA for Oracle are a server and a listener monitor.

Oracle Server Fault Monitor

The fault monitor for the Oracle server uses a request to the server to query the health of the server.

The server fault monitor is started through pmfadm to make the monitor highly available. If the monitor is killed for any reason, the Process Monitor Facility (PMF) automatically restarts the monitor.

Server Fault Monitor Processes

The server fault monitor consists of the following processes.

- A main fault monitor process, which performs error lookup and scha_control actions
- A database client fault probe, which performs database transactions

Operation of the Main Fault Monitor

The main fault monitor determines that an operation is successful if the database is online and no errors are returned during the transaction.

Operation of the Database Client Fault Probe

The database client fault probe queries the dynamic performance view v\$sysstat to obtain database performance statistics. Changes to these statistics indicate that the database is operational. If these statistics remain unchanged between consecutive queries, the fault probe performs database transactions to determine if the database is operational. These transactions involve the creation, updating, and dropping of a table in the user table space.

The database client fault probe performs all its transactions as the Oracle user. The ID of this user is specified during the preparation of the nodes as explained in "How to Prepare the Nodes" on page 12.

The probe uses the time-out value that is set in the resource property Probe_timeout to determine how much time to allocate to successfully probe Oracle.

Actions by the Server Fault Monitor in Response to a Database Transaction Failure

If a database transaction fails, the server fault monitor performs an action that is determined by the error that caused the failure. To change the action that the server fault monitor performs, customize the server fault monitor as explained in "Customizing the Sun Cluster HA for Oracle Server Fault Monitor" on page 37.

If the action requires an external program to be run, the program is run as a separate process in the background.

Possible actions are as follows:

■ **Ignore.** The server fault monitor ignores the error.

- Stop monitoring. The server fault monitor is stopped without shutting down the database.
- **Restart.** The server fault monitor stops and restarts the entity that is specified by the value of the Restart type extension property:
 - If the Restart_type extension property is set to RESOURCE_GROUP_RESTART, the server fault monitor restarts the database server resource group. By default, the server fault monitor restarts the database server resource group.
 - If the Restart_type extension property is set to RESOURCE_RESTART, the server fault monitor restarts the database server resource.

Note – The number of attempts to restart might exceed the value of the Retry_count resource property within the time that the Retry_interval resource property specifies. If this situation occurs, the server fault monitor attempts to switch over the resource group to another node.

■ **Switch over.** The server fault monitor switches over the database server resource group to another node. If no nodes are available, the attempt to switch over the resource group fails. If the attempt to switch over the resource group fails, the database server is restarted.

Scanning of Logged Alerts by the Server Fault Monitor

The Oracle software logs alerts in an alert log file. The absolute path of this file is specified by the alert_log_file extension property of the SUNW.oracle_server resource. The server fault monitor scans the alert log file for new alerts at the following times:

- When the server fault monitor is started
- Each time that the server fault monitor queries the health of the server

If an action is defined for a logged alert that the server fault monitor detects, the server fault monitor performs the action in response to the alert.

Preset actions for logged alerts are listed in Table A–2. To change the action that the server fault monitor performs, customize the server fault monitor as explained in "Customizing the Sun Cluster HA for Oracle Server Fault Monitor" on page 37.

Oracle Listener Fault Monitor

The Oracle listener fault monitor checks the status of an Oracle listener.

If the listener is running, the Oracle listener fault monitor considers a probe successful. If the fault monitor detects an error, the listener is restarted.

The listener probe is started through pmfadm to make the probe highly available. If the probe is killed, PMF automatically restarts the probe.

If a problem occurs with the listener during a probe, the probe tries to restart the listener. The value that is set in the resource property Retry_count determines the maximum number of times that the probe attempts the restart. If, after trying for the maximum number of times, the probe is still unsuccessful, the probe stops the fault monitor and does not switch over the resource group.

Customizing the Sun Cluster HA for Oracle Server Fault Monitor

Customizing the Sun Cluster HA for Oracle server fault monitor enables you to modify the behavior of the server fault monitor as follows:

- Overriding the preset action for an error
- Specifying an action for an error for which no action is preset



Caution – Before you customize the Sun Cluster HA for Oracle server fault monitor, consider the effects of your customizations, especially if you change an action from restart or switch over to ignore or stop monitoring. If errors remain uncorrected for long periods, the errors might cause problems with the database. If you encounter problems with the database after customizing the Sun Cluster HA for Oracle server fault monitor, revert to using the preset actions. Reverting to the preset actions enables you to determine if the problem is caused by your customizations.

Customizing the Sun Cluster HA for Oracle server fault monitor involves the following activities:

- 1. Defining custom behavior for errors
- 2. Propagating a custom action file to all nodes in a cluster
- 3. Specifying the custom action file that a server fault monitor should use

Defining Custom Behavior for Errors

The Sun Cluster HA for Oracle server fault monitor detects the following types of errors:

- DBMS errors that occur during a probe of the database by the server fault monitor
- Alerts that Oracle logs in the alert log file
- Timeouts that result from a failure to receive a response within the time that is set by the Probe_timeout extension property

To define custom behavior for these types of errors, create a custom action file.

Custom Action File Format

A custom action file is a plain text file. The file contains one or more entries that define the custom behavior of the Sun Cluster HA for Oracle server fault monitor. Each entry defines the custom behavior for a single DBMS error, a single time-out error, or several logged alerts. A maximum of 1024 entries is allowed in a custom action file.

Note – Each entry in a custom action file overrides the preset action for an error, or specifies an action for an error for which no action is preset. Create entries in a custom action file *only* for the preset actions that you are overriding or for errors for which no action is preset. Do *not* create entries for actions that you are not changing.

An entry in a custom action file consists of a sequence of keyword-value pairs that are separated by semicolons. Each entry is enclosed in braces.

The format of an entry in a custom action file is as follows:

```
{
    [ERROR_TYPE=DBMS_ERROR|SCAN_LOG|TIMEOUT_ERROR;]
    ERROR=error-spec;
    [ACTION=SWITCH|RESTART|STOP|NONE;]
    [CONNECTION_STATE=co|di|on|*;]
    [NEW_STATE=co|di|on|*;]
    [MESSAGE="message-string"]
}
```

White space may be used between separated keyword-value pairs and between entries to format the file.

The meaning and permitted values of the keywords in a custom action file are as follows:

ERROR TYPE

Indicates the type of the error that the server fault monitor has detected. The following values are permitted for this keyword:

being blind between specifics that the circles a being circle.	DBMS ERROR	Specifies that the error is a DBMS error.
--	------------	---

SCAN_LOG Specifies that the error is an alert that is logged in the alert log

file.

TIMEOUT ERROR Specifies that the error is a timeout.

The ERROR_TYPE keyword is optional. If you omit this keyword, the error is assumed to be a DBMS error.

ERROR

Identifies the error. The data type and the meaning of *error-spec* are determined by the value of the ERROR_TYPE keyword as shown in the following table.

ERROR_TYPE	Data Type	Meaning
DBMS_ERROR	Integer	The error number of a DBMS error that is generated by Oracle
SCAN_LOG	Quoted regular expression	A string in an error message that Oracle has logged to the Oracle alert log file
TIMEOUT_ERROR	Integer	The number of consecutive timed-out probes since the server fault monitor was last started or restarted

You must specify the ERROR keyword. If you omit this keyword, the entry in the custom action file is ignored.

ACTION

Specifies the action that the server fault monitor is to perform in response to the error. The following values are permitted for this keyword:

NONE	Specifies that the server fault monitor ignores the error.
STOP	Specifies that the server fault monitor is stopped.
RESTART	Specifies that the server fault monitor stops and restarts the entity that is specified by the value of the Restart_type extension property of the SUNW.oracle_server resource.
SWITCH	Specifies that the server fault monitor switches over the database server resource group to another node.

The ACTION keyword is optional. If you omit this keyword, the server fault monitor ignores the error.

CONNECTION STATE

Specifies the required state of the connection between the database and the server fault monitor when the error is detected. The entry applies only if the connection is in the required state when the error is detected. The following values are permitted for this keyword:

- Specifies that the entry always applies, regardless of the state of the connection.
- co Specifies that the entry applies only if the server fault monitor is attempting to connect to the database.
- on Specifies that the entry applies only if the server fault monitor is online. The server fault monitor is online if it is connected to the database.
- di Specifies that the entry applies only if the server fault monitor is disconnecting from the database.

The CONNECTION_STATE keyword is optional. If you omit this keyword, the entry always applies, regardless of the state of the connection.

NEW STATE

Specifies the state of the connection between the database and the server fault monitor that the server fault monitor must attain after the error is detected. The following values are permitted for this keyword:

- * Specifies that the state of the connection must remain unchanged.
- co Specifies that the server fault monitor must disconnect from the database and reconnect immediately to the database.
- di Specifies that the server fault monitor must disconnect from the database. The server fault monitor reconnects when it next probes the database.

The NEW_STATE keyword is optional. If you omit this keyword, the state of the database connection remains unchanged after the error is detected.

MESSAGE

Specifies an additional message that is printed to the resource's log file when this error is detected. The message must be enclosed in double quotes. This message is additional to the standard message that is defined for the error.

The MESSAGE keyword is optional. If you omit this keyword, no additional message is printed to the resource's log file when this error is detected.

Changing the Response to a DBMS Error

The action that the server fault monitor performs in response to each DBMS error is preset as listed in Table A–1. To determine whether you need to change the response to a DBMS error, consider the effect of DBMS errors on your database to determine if the preset actions are appropriate. For examples, see the subsections that follow.

To change the response to a DBMS error, create an entry in a custom action file in which the keywords are set as follows:

- ERROR TYPE is set to DBMS ERROR.
- ERROR is set to the error number of the DBMS error.
- ACTION is set to the action that you require.

Responding to an Error the Effects of Which Are Major

If an error that the server fault monitor ignores affects more than one session, action by the server fault monitor might be required to prevent a loss of service.

For example, no action is preset for Oracle error 4031: unable to allocate *num-bytes* bytes of shared memory. However, this Oracle error indicates that the shared global area (SGA) has insufficient memory, is badly fragmented, or both states apply. If this error affects only a single session, ignoring the error might be appropriate. However, if this error affects more than one session, consider specifying that the server fault monitor restart the database.

The following example shows an entry in a custom action file for changing the response to a DBMS error to restart.

EXAMPLE 1–1 Changing the Response to a DBMS Error to Restart

```
{
    ERROR_TYPE=DBMS_ERROR;
    ERROR=4031;
    ACTION=restart;
    CONNECTION_STATE=*;
    NEW_STATE=*;
    MESSAGE="Insufficient memory in shared pool.";
}
```

This example shows an entry in a custom action file that overrides the preset action for DBMS error 4031. This entry specifies the following behavior:

- In response to DBMS error 4031, the action that the server fault monitor performs is restart.
- This entry applies regardless of the state of the connection between the database and the server fault monitor when the error is detected.
- The state of the connection between the database and the server fault monitor must remain unchanged after the error is detected.
- The following message is printed to the resource's log file when this error is detected:

Insufficient memory in shared pool.

Ignoring an Error the Effects of Which Are Minor

If the effects of an error to which the server fault monitor responds are minor, ignoring the error might be less disruptive than responding to the error.

For example, the preset action for Oracle error 4030: out of process memory when trying to allocate *num-bytes* bytes is restart. This Oracle error indicates that the server fault monitor could not allocate private heap memory. One possible cause of this error is that insufficient memory is available to the operating system. If this error affects more than one session, restarting the database might be appropriate. However, this error might not affect other sessions because these sessions do not require further private memory. In this situation, consider specifying that the server fault monitor ignore the error.

The following example shows an entry in a custom action file for ignoring a DBMS error.

EXAMPLE 1–2 Ignoring a DBMS Error

```
{
    ERROR_TYPE=DBMS_ERROR;
    ERROR=4030;
    ACTION=none;
    CONNECTION_STATE=*;
    NEW_STATE=*;
    MESSAGE="";
}
```

This example shows an entry in a custom action file that overrides the preset action for DBMS error 4030. This entry specifies the following behavior:

- The server fault monitor ignores DBMS error 4030.
- This entry applies regardless of the state of the connection between the database and the server fault monitor when the error is detected.
- The state of the connection between the database and the server fault monitor must remain unchanged after the error is detected.
- No additional message is printed to the resource's log file when this error is detected.

Changing the Response to Logged Alerts

The Oracle software logs alerts in a file that is identified by the Alert_log_file extension property. The server fault monitor scans this file and performs actions in response to alerts for which an action is defined.

Logged alerts for which an action is preset are listed in Table A–2. Change the response to logged alerts to change the preset action, or to define new alerts to which the server fault monitor responds.

To change the response to logged alerts, create an entry in a custom action file in which the keywords are set as follows:

- ERROR TYPE is set to SCAN LOG.
- ERROR is set to a quoted regular expression that identifies a string in an error message that Oracle has logged to the Oracle alert log file.
- ACTION is set to the action that you require.

The server fault monitor processes the entries in a custom action file in the order in which the entries occur. Only the first entry that matches a logged alert is processed. Later entries that match are ignored. If you are using regular expressions to specify actions for several logged alerts, ensure that more specific entries occur before more general entries. Specific entries that occur after general entries might be ignored.

For example, a custom action file might define different actions for errors that are identified by the regular expressions ORA-65 and ORA-6. To ensure that the entry that contains the regular expression ORA-65 is not ignored, ensure that this entry occurs before the entry that contains the regular expression ORA-6.

The following example shows an entry in a custom action file for changing the response to a logged alert.

EXAMPLE 1-3 Changing the Response to a Logged Alert

```
{
ERROR_TYPE=SCAN_LOG;
ERROR="ORA-00600: internal error";
ACTION=RESTART;
}
```

This example shows an entry in a custom action file that overrides the preset action for logged alerts about internal errors. This entry specifies the following behavior:

- In response to logged alerts that contain the text ORA-00600: internal error, the action that the server fault monitor performs is restart.
- This entry applies regardless of the state of the connection between the database and the server fault monitor when the error is detected.
- The state of the connection between the database and the server fault monitor must remain unchanged after the error is detected.
- No additional message is printed to the resource's log file when this error is detected.

Changing the Maximum Number of Consecutive Timed-Out Probes

By default, the server fault monitor restarts the database after the second consecutive timed-out probe. If the database is lightly loaded, two consecutive timed-out probes should be sufficient to indicate that the database is hanging. However, during periods

of heavy load, a server fault monitor probe might time out even if the database is functioning correctly. To prevent the server fault monitor from restarting the database unnecessarily, increase the maximum number of consecutive timed-out probes.



Caution – Increasing the maximum number of consecutive timed-out probes increases the time that is required to detect that the database is hanging.

To change the maximum number of consecutive timed-out probes allowed, create one entry in a custom action file for each consecutive timed-out probe that is allowed *except* the first timed-out probe.

Note – You are not required to create an entry for the first timed-out probe. The action that the server fault monitor performs in response to the first timed-out probe is preset.

For the last allowed timed-out probe, create an entry in which the keywords are set as follows:

- ERROR TYPE is set to TIMEOUT ERROR.
- ERROR is set to the maximum number of consecutive timed-out probes that are allowed.
- ACTION is set to RESTART.

For each remaining consecutive timed-out probe except the first timed-out probe, create an entry in which the keywords are set as follows:

- ERROR TYPE is set to TIMEOUT ERROR.
- ERROR is set to the sequence number of the timed-out probe. For example, for the second consecutive timed-out probe, set this keyword to 2. For the third consecutive timed-out probe, set this keyword to 3.
- ACTION is set to NONE.

Tip – To facilitate debugging, specify a message that indicates the sequence number of the timed-out probe.

The following example shows the entries in a custom action file for increasing the maximum number of consecutive timed-out probes to five.

```
EXAMPLE 1-4 Changing the Maximum Number of Consecutive Timed-Out Probes { ERROR_TYPE=TIMEOUT;
```

EXAMPLE 1–4 Changing the Maximum Number of Consecutive Timed-Out Probes (*Continued*)

```
ERROR=2;
ACTION=NONE;
CONNECTION_STATE=*;
NEW STATE=*;
MESSAGE="Timeout #2 has occurred.";
ERROR TYPE=TIMEOUT;
ERROR=3;
ACTION=NONE;
CONNECTION STATE=*;
NEW STATE=*;
MESSAGE="Timeout #3 has occurred.";
ERROR TYPE=TIMEOUT;
ERROR=4:
ACTION=NONE;
CONNECTION STATE=*;
NEW STATE=*;
MESSAGE="Timeout #4 has occurred.";
ERROR TYPE=TIMEOUT;
ERROR=5;
ACTION=RESTART;
CONNECTION STATE=*;
NEW STATE=*;
MESSAGE="Timeout #5 has occurred. Restarting.";
}
```

This example shows the entries in a custom action file for increasing the maximum number of consecutive timed-out probes to five. These entries specify the following behavior:

- The server fault monitor ignores the second consecutive timed-out probe through the fourth consecutive timed-out probe.
- In response to the fifth consecutive timed-out probe, the action that the server fault monitor performs is restart.
- The entries apply regardless of the state of the connection between the database and the server fault monitor when the timeout occurs.
- The state of the connection between the database and the server fault monitor must remain unchanged after the timeout occurs.
- When the second consecutive timed-out probe through the fourth consecutive timed-out probe occurs, a message of the following form is printed to the resource's log file:

EXAMPLE 1–4 Changing the Maximum Number of Consecutive Timed-Out Probes (*Continued*)

Timeout #number has occurred.

■ When the fifth consecutive timed-out probe occurs, the following message is printed to the resource's log file:

Timeout #5 has occurred. Restarting.

Propagating a Custom Action File to All Nodes in a Cluster

A server fault monitor must behave consistently on all cluster nodes. Therefore, the custom action file that the server fault monitor uses must be identical on all cluster nodes. After creating or modifying a custom action file, ensure that this file is identical on all cluster nodes by propagating the file to all cluster nodes. To propagate the file to all cluster nodes, use the method that is most appropriate for your cluster configuration:

- Locating the file on a file system that all nodes share
- Locating the file on a highly available local file system
- Copying the file to the local file system of each cluster node by using operating system commands such as the rcp(1) command or the rdist(1) command

Specifying the Custom Action File That a Server Fault Monitor Should Use

To apply customized actions to a server fault monitor, you must specify the custom action file that the fault monitor should use. Customized actions are applied to a server fault monitor when the server fault monitor reads a custom action file. A server fault monitor reads a custom action file when the you specify the file.

Specifying a custom action file also validates the file. If the file contains syntax errors, an error message is displayed. Therefore, after modifying a custom action file, specify the file again to validate the file.



Caution – If syntax errors in a modified custom action file are detected, correct the errors before the fault monitor is restarted. If the syntax errors remain uncorrected when the fault monitor is restarted, the fault monitor reads the erroneous file, ignoring entries that occur after the first syntax error.

How to Specify the Custom Action File That a Server Fault Monitor Should Use

- 1. On a cluster node, become superuser.
- Set the Custom_action_file extension property of the SUNW.oracle server resource.

Set this property to the absolute path of the custom action file.

```
# scrgadm -c -j server-resource\
-x custom_action_file=filepath
```

- -j server-resource
 Specifies the SUNW.oracle server resource
- -x custom_action_file=filepath
 Specifies the absolute path of the custom action file

Upgrading the SUNW.oracle_server Resource Type

Upgrade the SUNW.oracle server resource type if the following conditions apply:

- You are upgrading from an earlier version of the Sun Cluster HA for Oracle data service.
- You require to use the new features of this data service.

For general instructions that explain how to upgrade a resource type, see "Upgrading a Resource Type" in *Sun Cluster 3.1 Data Service Planning and Administration Guide*. The information that you require to complete the upgrade of the SUNW.oracle_server resource type is provided in the subsections that follow.

Information for Registering the New Resource Type Version

The relationship between a resource type version and the release of Sun Cluster data services is shown in the following table. The release of Sun Cluster data services indicates the release in which the version of the resource type was introduced.

Resource Type Version	Sun Cluster Data Services Release
1	1.0
3.1	3.1 5/03
4	3.1 10/03

To determine the version of the resource type that is registered, use one command from the following list:

- scrgadm -p
- scrgadm -pv

The resource type registration (RTR) file for this resource type is /opt/SUNWscor/oracle_server/etc/SUNW.oracle_server.

Information for Migrating Existing Instances of the Resource Type

The information that you require to edit each instance of the SUNW.oracle_server resource type is as follows:

- You can perform the migration at any time.
- If you require to use the new features of the Sun Cluster HA for Oracle data service, the required value of the Type version property is 4.
- If you customized the behavior of the server fault monitor, set the Custom_action_file extension property. For more information, see "Customizing the Sun Cluster HA for Oracle Server Fault Monitor" on page 37.

The following example shows a command for modifying an instance of the SUNW.oracle_server resource type.

EXAMPLE 1-5 Migrating Instances of the SUNW.oracle_server Resource Type

```
# scrgadm -cj oracle-rs -y Type_version=4 \
-x custom_action_file=/opt/SUNWscor/oracle_server/etc/srv_mon_cust_actions
```

This command modifies a SUNW.oracle server resource as follows:

- The SUNW.oracle server resource is named oracle-rs.
- The Type version property of this resource is set to 4.
- Custom behavior for the fault monitor of this resource is specified in the file /opt/SUNWscor/oracle_server/etc/srv_mon_cust_actions.

APPENDIX \mathbf{A}

Preset Actions for Database Management System (DBMS) Errors and Logged Alerts

Preset actions for DBMS errors and logged alerts are listed as follows:

- DBMS errors for which an action is preset are listed in Table A–1.
- Logged alerts for which an action is preset are listed in Table A–2.

TABLE A-1 Preset Actions for DBMS Errors

Error Number	Action	Connection State	New State	Message
18	NONE	СО	di	Max. number of DBMS sessions exceeded
20	NONE	CO	di	Max. number of DBMS processes exceeded
28	NONE	on	di	Session killed by DBA, will reconnect
50	SWITCH	*	di	$\ensuremath{\text{O/S}}$ error occurred while obtaining an enqueue. See $\ensuremath{\text{o/s}}$ error.
51	NONE	*	di	timeout occurred while waiting for resource
55	NONE	*	*	maximum number of DML locks in DBMS exceeded
62	STOP	*	di	Need to set DML_LOCKS in init.ora file to value other than $\boldsymbol{0}$
107	RESTART	*	di	failed to connect to ORACLE listener process
257	NONE	*	di	archiver error. Connect internal only, until freed.
290	SWITCH	*	di	Operating system archival error occurred. Check alert log.
447	SWITCH	*	di	fatal error in background process
448	RESTART	*	di	normal completion of background process
449	RESTART	*	di	background process `%s' unexpectedly terminated with error %s

 TABLE A-1 Preset Actions for DBMS Errors
 (Continued)

Error Number	Action	Connection State	New State	Message
470	SWITCH	*	di	Oracle background process died
471	SWITCH	*	di	Oracle background process died
472	SWITCH	*	di	Oracle background process died
473	SWITCH	*	di	Oracle background process died
474	RESTART	*	di	SMON died, warm start required
475	SWITCH	*	di	Oracle background process died
476	SWITCH	*	di	Oracle background process died
477	SWITCH	*	di	Oracle background process died
480	RESTART	*	di	LCK* process terminated with error
481	RESTART	*	di	LMON process terminated with error
482	RESTART	*	di	LMD* process terminated with error
602	SWITCH	*	di	internal programming exception
604	NONE	on	di	Recursive error
705	RESTART	*	di	inconsistent state during start up
942	NONE	on	*	Warning - VSYSSTAT$ not accessible - check grant on $V_$SYSSTAT$
1001	NONE	on	di	Lost connection to database
1002	NONE	on	*	Internal error in HA-DBMS Oracle
1003	NONE	on	di	Resetting database connection
1012	NONE	on	di	Not logged on
1012	RESTART	di	CO	Not logged on
1014	NONE	*	*	ORACLE shutdown in progress
1017	STOP	*	*	Please correct login information in HA-DBMS Oracle database configuration
1031	NONE	on	*	Insufficient privileges to perform DBMS operations - check Oracle user privileges
1033	NONE	CO	CO	Oracle is in the shutdown or initialization process
1033	NONE	*	di	Oracle is in the shutdown or initialization process
1034	RESTART	CO	CO	Oracle is not available

TABLE A-1 Preset Actions for DBMS Errors (Continued)

Error Number	Action	Connection State	New State	Message
1034	RESTART	di	CO	Oracle is not available
1034	NONE	on	di	Oracle is not available
1035	RESTART	CO	CO	Access restricted - restarting database to reset
1041	NONE	on	di	
1041	NONE	di	CO	
1045	NONE	СО	*	Fault monitor user lacks CREATE SESSION privilege logon denied.
1046	RESTART	*	di	cannot acquire space to extend context area
1050	RESTART	*	di	cannot acquire space to open context area
1053	SWITCH	*	*	user storage address cannot be read or written
1054	SWITCH	*	*	user storage address cannot be read or written
1075	NONE	co	on	Already logged on
1089	NONE	on	di	immediate shutdown in progresss
1089	NONE	*	*	Investigate! Could be hanging!
1090	NONE	*	di	shutdown in progress - connection is not permitted
1092	NONE	*	di	ORACLE instance terminated. Disconnection forced
1513	SWITCH	*	*	invalid current time returned by operating system
1542	NONE	on	*	table space is off-line - please correct!
1552	NONE	on	*	rollback segment is off-line - please correct!
1950	NONE	on	*	Insufficient privileges to perform DBMS operations - check Oracle user privileges
2701	STOP	*	*	HA-DBMS Oracle error - ORACLE_HOME did not get set!
2703	RESTART	*	di	
2704	RESTART	*	di	
2709	RESTART	*	di	
2710	RESTART	*	di	
2719	RESTART	*	di	
2721	RESTART	*	*	

 TABLE A-1 Preset Actions for DBMS Errors
 (Continued)

Error Number	Action	Connection State	New State	Message
2726	STOP	*	*	Could not locate ORACLE executables - check ORACLE_HOME setting
2735	RESTART	*	*	osnfpm: cannot create shared memory segment
2811	SWITCH	*	*	Unable to attach shared memory segment
2839	SWITCH	*	*	Sync of blocks to disk failed.
2840	SWITCH	*	*	
2846	SWITCH	*	*	
2847	SWITCH	*	*	
2849	SWITCH	*	*	
2842	RESTART	*	*	Client unable to fork a server - Out of memory
3113	RESTART	CO	di	lost connection
3113	NONE	on	di	lost connection
3113	NONE	di	di	lost connection
3114	NONE	*	CO	Not connected?
4030	RESTART	*	*	
4032	RESTART	*	*	
4100	RESTART	*	*	communication area cannot be allocated insufficient memory
6108	STOP	CO	*	Can't connect to remote database - make sure SQL*Net server is up
6114	STOP	СО	*	Can't connect to remote database - check SQL*Net configuration
7205	SWITCH	*	di	
7206	SWITCH	*	di	
7208	SWITCH	*	di	
7210	SWITCH	*	di	
7211	SWITCH	*	di	
7212	SWITCH	*	di	
7213	SWITCH	*	di	
7214	SWITCH	*	di	

TABLE A-1 Preset Actions for DBMS Errors (Continued)

Error Number	Action	Connection State	New State	Message
7215	SWITCH	*	di	
7216	SWITCH	*	di	
7218	SWITCH	*	di	
7219	RESTART	*	*	slspool: unable to allocate spooler argument buffer.
7223	RESTART	*	*	slspool: fork error, unable to spawn spool process Resource limit reached
7224	SWITCH	*	*	
7229	SWITCH	*	*	
7232	SWITCH	*	*	
7234	SWITCH	*	*	
7238	SWITCH	*	*	slemcl: close error.
7250	RESTART	*	*	
7251	RESTART	*	*	
7252	RESTART	*	*	
7253	RESTART	*	*	
7258	RESTART	*	*	
7259	RESTART	*	*	
7263	SWITCH	*	*	
7269	SWITCH	*	*	
7279	SWITCH	*	*	
7280	RESTART	*	*	
7296	SWITCH	*	*	
7297	SWITCH	*	*	
7306	RESTART	*	*	
7310	SWITCH	*	*	
7315	SWITCH	*	*	
7321	SWITCH	*	*	
7322	SWITCH	*	*	

 TABLE A-1 Preset Actions for DBMS Errors
 (Continued)

Error Number	Action	Connection State	New State	Message
7324	RESTART	*	*	
7325	RESTART	*	*	
7351	SWITCH	*	*	
7361	RESTART	*	*	
7404	SWITCH	*	*	
7414	RESTART	*	*	
7415	RESTART	*	*	
7417	SWITCH	*	*	
7418	SWITCH	*	*	
7419	SWITCH	*	*	
7430	SWITCH	*	*	
7455	SWITCH	*	*	
7456	SWITCH	*	*	
7466	SWITCH	*	*	
7470	SWITCH	*	*	
7475	SWITCH	*	*	
7476	SWITCH	*	*	
7477	SWITCH	*	*	
7478	SWITCH	*	*	
7479	SWITCH	*	*	
7481	SWITCH	*	*	
9706	SWITCH	*	*	
9716	SWITCH	*	*	
9718	RESTART	*	*	
9740	SWITCH	*	*	
9748	SWITCH	*	*	
9747	RESTART	*	*	
9749	RESTART	*	*	

TABLE A-1 Preset Actions for DBMS Errors (Continued)

Error Number	Action	Connection State	New State	Message
9751	RESTART	*	*	
9755	RESTART	*	*	
9757	RESTART	*	*	
9756	SWITCH	*	*	
9758	SWITCH	*	*	
9761	RESTART	*	*	
9765	RESTART	*	*	
9779	RESTART	*	*	
9829	RESTART	*	*	
9831	SWITCH	*	*	
9834	SWITCH	*	*	
9836	SWITCH	*	*	
9838	SWITCH	*	*	
9837	RESTART	*	*	
9844	RESTART	*	*	
9845	RESTART	*	*	
9846	RESTART	*	*	
9847	RESTART	*	*	
9853	SWITCH	*	*	
9854	SWITCH	*	*	
9856	RESTART	*	*	
9874	SWITCH	*	*	
9876	SWITCH	*	*	
9877	RESTART	*	*	
9878	RESTART	*	*	
9879	RESTART	*	*	
9885	RESTART	*	*	
9888	RESTART	*	*	

TABLE A-1 Preset Actions for DBMS Errors (Continued)

Error Number	Action	Connection State	New State	Message
9894	RESTART	*	*	
9909	RESTART	*	*	
9912	RESTART	*	*	
9913	RESTART	*	*	
9919	SWITCH	*	*	
9943	RESTART	*	*	
9947	RESTART	*	*	
9948	SWITCH	*	*	
9949	SWITCH	*	*	
9950	SWITCH	*	*	
12505	STOP	*	*	TNS:listener could not resolve SID given in connect descriptor. Check listener configuration file.
12541	STOP	*	*	TNS:no listener. Please verify connect_string property, listener and TNSconfiguration.
12545	STOP	*	*	Please check HA-Oracle parameters. Connect failed because target host or object does not exist
27100	STOP	*	*	Shared memory realm already exists

 TABLE A-2 Preset Actions for Logged Alerts

Alert String	Action	Connection State	New State	Message
ORA-07265	SWITCH	*	di	Semaphore access problem
found dead multi- threaded server	NONE	*	*	Warning: Multi-threaded Oracle server process died (restarted automatically)
found dead dispatcher	NONE	*	*	Warning: Oracle dispatcher process died (restarted automatically)

Index

A	configuring (Continued)		
action file, See custom action file	Sun Cluster HA for Oracle		
ACTION keyword, 39	performing, 23		
actions	planning, 11		
listener fault monitor, 36	Connect_cycle extension property, 25		
preset for fault monitor, 49	Connect_string extension property, 25		
server fault monitor	CONNECTION_STATE keyword, 40		
changing, 39	custom action file		
definition, 35	format, 38		
adding, messages to log files, 40	maximum number of entries in, 38		
Alert log file extension property, 25	order of entries in, 43		
alert logs	propagating to cluster nodes, 46		
changing response to errors, 42	specifying, 46		
preset actions, 56	validating, 46		
use of by fault monitor, 36	Custom action file extension property, 26		
Auto End Bkp extension property, 25	customizing, server fault monitor, 37		
C C locale, 22 caution notice, server fault monitor	D database management system (DBMS) errors		
C locale, 22 caution notice, server fault monitor customizations, 37	database management system (DBMS) errors changing response to, 40		
C locale, 22 caution notice, server fault monitor	database management system (DBMS) errors		

E	fragmentation, of memory, 41
editing, resource type instances, 48	•
ERROR keyword, 39	
ERROR_TYPE keyword, 39	
errors	Н
in custom action file, 46	heap memory, 42
DBMS	hot backup mode, 25
changing response to, 40	•
preset actions for, 49	
ignoring, 42	
responding to, 41	I
SGA, 41	ignoring, minor errors, 42
timeouts, 43	installing
types detected by fault monitor, 38	Oracle software, 15
extension properties	Sun Cluster HA for Oracle
listener, 24	by using scinstall utility, 23
server, 25	by using Web Start program, 21
,	log files created, 22
	insufficient memory errors, 41, 42
	<i>,</i> , , ,
F	
fault monitor	
overview, 34	K
actions	keywords, custom action file, 38
changing, 39	, ,
definition, 35, 36	
alert logs, 36	
caution notice, 37	L
customizing, 37	listener, extension properties, 24
error types detected by, 38	listener fault monitor, 36
preset actions, 49	LISTENER_NAME extension property, 24
files	locales, 22
alert log	log files
changing response to errors in, 42	installation, 22
use of by fault monitor, 36	Sun Cluster HA for Oracle
custom action	additional messages in, 40
format, 38	location, 34
order of entries in, 43	logged alerts
propagating to cluster nodes, 46	changing response to, 42
specifying, 46	preset actions, 56
validating, 46	use of by fault monitor, 36
database, 11	·
installation logs, 22	
Oracle application, 11	
RTR, 48	M
Sun Cluster HA for Oracle logs	maximum values
additional messages in, 40	entries in custom action file, 38
location, 34	number of allowed timeouts, 43

memory shortage of, 41, 42 MESSAGE keyword, 40 migrating, resource type instances, 48	prtdiag -v command, 8 psrinfo -v command, 8
N NEW_STATE keyword, 40	R registering Sun Cluster HA for Oracle generally, 23 during upgrade, 47 resource type registration (RTR) file, 48
Oracle See also Sun Cluster HA for Oracle application files, 11 clients, 33 database configuring with Solstice DiskSuite, 13 configuring with VERITAS Volume Manager, 14	resource types, migrating instances of, 48 responding, to major errors, 41 Restart_type extension property, 27 restarts preventing for DBMS errors, 42 for timeouts, 43 RTR (resource type registration) file, 48
creating, 16 setting permissions, 18 error numbers, 49 installing, 15 preparing nodes for installation of, 12 verifying installation, 16 ORACLE_HOME extension property, 24, 26 ORACLE_SID extension property, 26 order, entries in custom action file, 43 overriding, server fault monitor presets, 37	scinstall -pv command, 8 server, extension properties, 25 server fault monitor actions changing, 39 definition, 35 alert logs, 36 caution notice, 37 customizing, 37 error types detected by, 38
Parameter_file extension property, 26 planning, Sun Cluster HA for Oracle configuration, 11 preset actions, fault monitor, 49 preventing unnecessary restarts for DBMS errors, 42 for timeouts, 43 Probe_timeout extension property, 26 properties See also extension properties Type_version, 48 prtconf -v command, 8	overview, 34 preset actions, 49 sessions effect of errors on, 41, 42 SGA (shared global area), errors, 41 shared global area (SGA), errors, 41 showrev -p command, 8 Sun Cluster HA for Oracle See also Oracle configuration performing, 23 planning, 11 installing by using scinstall utility, 23 by using Web Start program, 21

```
Sun Cluster HA for Oracle, installing
(Continued)
     overview of process, 10
     planning, 11
  listener extension properties, 24
  log files
     additional messages in, 40
     location, 34
  registering, 23
  resource type versions, 47
  server extension properties, 25
  SUNW. HAStoragePlus resource type, 29
  upgrading, 47
  verifying installation, 33
SUNW.HAStoragePlus resource type, 29
syntax errors, custom action file, 46
Т
timeouts, 43
Type version property, 48
U
upgrading, Sun Cluster HA for Oracle, 47
User_env extension property
  listener, 24
  server, 27
validating, custom action file, 46
/var/sadm/install/logs directory, 22
verifying
  Oracle installation, 16
  Sun Cluster HA for Oracle installation, 33
versions, resource types, 47
W
Wait for online extension property, 27
Web Start program, 21
```