libco源码阅读记录

A、主要数据结构

stCoRoutineEnv t:

```
//协程环境, 会被定义为线程私有变量
struct stCoRoutineEnv_t
{
    //协程数组
    stCoRoutine_t *pCallStack[ 128 ];
    //协程数量
    int iCallStackSize;
    //协程epoll对象
    stCoEpoll_t *pEpoll;

    //for copy stack log lastco and nextco
    //即将执行的协程以及当前协程
    stCoRoutine_t* pending_co;
    stCoRoutine_t* occupy_co;
};
```

• stCoEpoll_t:

```
struct stCoEpoll_t
{
    //epoll fd
    int iEpollFd;
    static const int _EPOLL_SIZE = 1024 * 10;
    //定时列表
    struct stTimeout_t *pTimeout;
    //超时列表
    struct stTimeoutItemLink_t *pstTimeoutList;
    //触发列表
    struct stTimeoutItemLink_t *pstActiveList;
    //epoll_event
    co_epoll_res *result;
};
```

stTimeout_t :

```
struct stTimeout_t
{

    //stTimeoutItemLink_t数组
    stTimeoutItemLink_t *pItems;
    //数组大小
    int iItemSize;

    //起始时间(室秒级)
    unsigned long long ullStart;
    //起始时间所对应的数组下标
    long long llStartIdx;
};
```

stCoRoutine_t :

```
struct stCoRoutine t
   stCoRoutineEnv t *env;
   //函数指针
   pfn_co_routine_t pfn;
   //函数参数
   void *arg;
   //协程栈信息
   coctx_t ctx;
   //是否已开始
   char cStart;
   char cEnd;
   //是否是主协程
   char cIsMain;
   //本协程是否使用hook的系统函数
   char cEnableSysHook;
   //是否使用共享栈
   char cIsShareStack;
   void *pvEnv;
   //char sRunStack[ 1024 * 128 ];
   //自定义栈内存信息指针
   stStackMem_t* stack_mem;
   //save satck buffer while confilct on same stack buffer;
   //共享栈时所需要的成员变量
   //栈顶
   char* stack sp;
   //本协程使用的栈大小
   unsigned int save_size;
   //每次切换协程时,需要重新申请内存来保存本协程栈数据
   char* save_buffer;
   stCoSpec_t aSpec[1024];
};
```

coctx t:

```
//协程栈信息
struct coctx_t
{
    //寄存器指针数组
    #if defined(__i386__)
        void *regs[ 8 ];
#else
        void *regs[ 14 ];
#endif
    //栈大小
        size_t ss_size;
    //栈顶指针
        char *ss_sp;
};
```

x86架构下32位有8个通用寄存器·64位有16个通用寄存器·rax、rbx、rcx、rdx、rsi、rdi、rbp、rsp、r8-r15。这16个寄存器除了rbp(保存栈底)、rsp(保存栈顶)·其余的除了特定的作用外还可以用来保存临时数据、中间结果或用于计算。这16个寄存器又分为callee-saved(被调用者保存)和caller-saved(调用者保存)。如下图所示:

Summary Table of Caller-Saved vs Callee-Saved Registers (System V ABI for Linux)

Register	Caller-Saved	Callee-Saved
rax	✓ (caller-saved)	
rcx	✓ (caller-saved)	
rdx	✓ (caller-saved)	
rsi	✓ (caller-saved)	
rdi	✓ (caller-saved)	
r8	✓ (caller-saved)	
r9	✓ (caller-saved)	
r10	✓ (caller-saved)	
r11	✓ (caller-saved)	
rbx		✓ (callee-saved)
rbp		✓ (callee-saved)
r12		✓ (callee-saved)
r13		✓ (callee-saved)
r14		✓ (callee-saved)
r15		✓ (callee-saved)

在属于caller-saved的寄存器中,只有r10、r11没有特定的作用,这应该就是libco不保存这两个寄存器的

原因。r8、r9可能会用于参数传递。如下图所示(参数再多则通过入栈来传递):

```
000000000000013fe <<mark>rain</mark>>:
     13fe:
           f3 0f 1e fa
                                   endbr64
     1402:
            55
                                   push %rbp
            48 89 e5
     1403:
                                          %rsp,%rbp
     1406:
           6a 08
                                   pushq $0x8
     1408:
           6a 07
                                   pushq $0x7
            41 b9 06 00 00 00
                                          $0x6,%r9d
                                   mov
           41 b8 05 00 00 00
     1410:
                                   mov
                                          $0x5,%r8d
     1416: b9 04 00 00 00
                                          $0x4,%ecx
                                   mov
    141b: ba 03 00 00 00
                                   mov
                                          $0x3,%edx
            be 02 00 00 00
                                   mov
                                          $0x2,%esi
    1425: bf 01 00 00 00
                                          $0x1,%edi
                                   mov
     142a: e8 08 ff ff ff
                                   callq 1337 <_Z4fun811111111>
                                          $0x10,%rsp
                                   add
     142f:
           48 83 c4 10
     1433:
           b8 00 00 00 00
                                   mov
                                          $0x0,%eax
     1438: c9
                                   leaveg
     1439: c3
                                   retq
```

B、部分API,其他感觉没啥可写的,正常逻辑没啥特殊点

· co create:

```
int co_create( stCoRoutine_t **ppco,const stCoRoutineAttr_t *attr,pfn_co_routine_t pfn,void *arg )
{
    if( !co_get_curr_thread_env() )
    {
        co_init_curr_thread_env();
    }
    stCoRoutine_t *co = co_create_env( co_get_curr_thread_env(), attr, pfn,arg );
    *ppco = co;
    return 0;
}
```

• co init curr thread env:

```
static __thread stCoRoutineEnv_t* gCoEnvPerThread = NULL;

void co_init_curr_thread_env()
{
    gCoEnvPerThread = (stCoRoutineEnv_t*)calloc( 1, sizeof(stCoRoutineEnv_t) );
    stCoRoutineEnv_t *env = gCoEnvPerThread;

    env->iCallStackSize = 0;
    //创建主协程
    struct stCoRoutine_t *self = co_create_env( env, NULL, NULL, NULL );
    self->cIsMain = 1;
    env->pending_co = NULL;
    env->occupy_co = NULL;
    coctx_init( &self->ctx );
    env->pCallStack[ env->iCallStackSize++ ] = self;

    stCoEpoll_t *ev = AllocEpoll();
    SetEpoll( env,ev );
}
```

co_create_env :

```
struct stCoRoutine t *co create env( stCoRoutineEnv t * env, const
stCoRoutineAttr t* attr,
    pfn_co_routine_t pfn,void *arg )
{
 stCoRoutineAttr_t at;
 if( attr )
   memcpy( &at,attr,sizeof(at) );
 if( at.stack_size <= 0 )</pre>
   //默认栈大小128KB
   at.stack_size = 128 * 1024;
 else if( at.stack_size > 1024 * 1024 * 8 )
    //最大栈8M
   at.stack_size = 1024 * 1024 * 8;
 //4K对齐,glibc默认的页大小,避免页缺失,优化内存访问
 if( at.stack_size & 0xFFF )
 {
   at.stack_size &= ~0xFFF;
   at.stack_size += 0x1000;
 stCoRoutine_t *lp = (stCoRoutine_t*)malloc( sizeof(stCoRoutine_t) );
 memset( lp,0,(long)(sizeof(stCoRoutine_t)));
 lp->env = env;
 lp->pfn = pfn;
 lp->arg = arg;
 stStackMem t* stack mem = NULL;
 if( at.share stack )
 {
    //共享栈
   stack_mem = co_get_stackmem( at.share_stack);
   at.stack_size = at.share_stack->stack_size;
 }
 else
   stack_mem = co_alloc_stackmem(at.stack_size);
  }
 lp->stack_mem = stack_mem;
 lp->ctx.ss_sp = stack_mem->stack_buffer;
 lp->ctx.ss_size = at.stack_size;
 lp->cStart = 0;
```

```
lp->cEnd = 0;
lp->cIsMain = 0;
lp->cEnableSysHook = 0;
lp->cIsShareStack = at.share_stack != NULL;

lp->save_size = 0;
lp->save_buffer = NULL;

return lp;
}
```

默认栈大小为128K,大抵是因为glibc初始的brk\mmap阈值是128K(可能会被动态调整,调用mallopt设置阈值或者其他的一些东西的时候会把动态调整关闭,32位的最大阈值是512K,64位最大是32M,ptmalloc里再做记录),这能避免内存碎片。但如果是共享栈的时候,每次做协程切换的时候,原来协程的栈的内容每次都会申请内存来保存,这个大小又没按这个阈值来,有点奇怪。save_stack_buffer代码截图如下所示:

```
void save_stack_buffer(stCoRoutine_t* occupy_co)
{
    ///copy out
    stStackMem_t* stack_mem = occupy_co->stack_mem;
    int len = stack_mem->stack_bp - occupy_co->stack_sp;

    if (occupy_co->save_buffer)
    {
        free(occupy_co->save_buffer), occupy_co->save_buffer = NULL;
    }

    occupy_co->save_buffer = (char*)malloc(len); //malloc buf;
    occupy_co->save_size = len;

    memcpy(occupy_co->save_buffer, occupy_co->stack_sp, len);
}
```

• co resume:

```
void co_resume( stCoRoutine_t *co )
{
    stCoRoutineEnv_t *env = co->env;
    stCoRoutine_t *lpCurrRoutine = env->pCallStack[ env->iCallStackSize - 1 ];
    if( !co->cStart )
    {
        //设置协程的
        coctx_make( &co->ctx,(coctx_pfn_t)CoRoutineFunc,co,0 );
        co->cStart = 1;
    }
    env->pCallStack[ env->iCallStackSize++ ] = co;
    co_swap( lpCurrRoutine, co );
}
```

coctx make:

```
int coctx_make(coctx_t* ctx, coctx_pfn_t pfn, const void* s, const void* s1) {
    char* sp = ctx->ss_sp + ctx->ss_size - sizeof(void*);
    //16个字节对齐,gcc现在默认堆栈对齐到16个字节,这是因为一些SSE指令如果没有做16个字节对齐会发生段错误。
    sp = (char*)((unsigned long)sp & -16LL);

    memset(ctx->regs, 0, sizeof(ctx->regs));
    void** ret_addr = (void**)(sp);
    *ret_addr = (void*)pfn;

    ctx->regs[kRSP] = sp;

    ctx->regs[kRSP] = sp;

    //第一个参数寄存器rdi
    ctx->regs[kRDI] = (char*)s;
    //第二个参数寄存器rsi
    ctx->regs[kRSI] = (char*)s1;
    return 0;
}
```

之所以要做16个字节对齐,是因为gcc现在默认堆栈对齐到16个字节,一些SSE指令如果没有做16个字节

对齐会发生段错误。资料地址:https://sourceforge.net/p/fbc/bugs/659/·测试结果如下图所示:

```
#include <stdio.h>
2
3
        void fun()
4
5
                char arr[8];
6
7
8
        void fun2()
9
10
                char arr[24];
(gdb)
11
12
13
        int main()
14
15
                return 0;
16
(gdb) disassemble fun
Dump of assembler code for function fun:
   0x0000000000001149 <+0>:
                               endbr64
   0x000000000000114d <+4>:
                               push %rbp
   0x0000000000000114e <+5>:
                                      %rsp,%rbp
                               mov
                                      $0x10,%rsp 栈顶向下移16个字节
   0x00000000000001151 <+8>:
                               sub
   0x0000000000001155 <+12>:
                                      %fs:0x28,%rax
                               mov
   0x0000000000000115e <+21>:
                                      %rax,-0x8(%rbp)
                               mov
   0x00000000000001162 <+25>:
                                      %eax,%eax
                               xor
   0x00000000000001164 <+27>:
                               nop
   0x0000000000001165 <+28>:
                                      -0x8(%rbp),%rax
                               mov
   0x0000000000001169 <+32>:
                                      %fs:0x28,%rax
                               xor
   0x00000000000001172 <+41>:
                                      0x1179 <fun+48>
                               je
   0x0000000000001174 <+43>:
                               callq 0x1050 <__stack_chk_fail@plt>
   0x00000000000001179 <+48>:
                               leaveq
   0x0000000000000117a <+49>:
                               retq
End of assembler dump.
(gdb) disassemble fun2
Dump of assembler code for function fun2:
   0x000000000000117b <+0>:
   0x000000000000117f <+4>:
                               push %rbp
   0x0000000000001180 <+5>:
                                      %rsp,%rbp
                                                     栈顶向下移32个
   0x0000000000001183 <+8>:
                                      $0x20,%rsp
   0x0000000000001187 <+12>:
                                      %fs:0x28,%rax
   0x0000000000001190 <+21>:
                               mov
                                      %rax,-0x8(%rbp)
   0x0000000000001194 <+25>:
                                      %eax,%eax
   0x0000000000001196 <+27>:
                               nop
   0x0000000000001197 <+28>:
                               mov
                                      -0x8(%rbp),%rax
                                      %fs:0x28,%rax
   0x0000000000000119b <+32>:
                               xor
                                      0x11ab <fun2+48>
   0x000000000000011a4 <+41>:
                               je
   0x000000000000011a6 <+43>:
                               callq 0x1050 <__stack_chk_fail@plt>
   0x00000000000011ab <+48>:
                               leaveq
   0x000000000000011ac <+49>:
                               retq
End of assembler dump.
```

coctx_swap:

```
//将rsp寄存器指向的地址赋值到rax
leaq (%rsp),%rax
//将寄存器的值赋值到相对于第一个参数偏移对应字节的地方
movq %rax, 104(%rdi)
movq %rbx, 96(%rdi)
movq %rcx, 88(%rdi)
movq %rdx, 80(%rdi)
```

```
//将rax(也就是rsp)指向地址的值赋值到rax,这个地址的此时值是coctx_swap调用者的
//下一条指令地址,这是因为调用者在调用coctx_swap函数时会将下一条指令压栈
movq 0(%rax), %rax
//保存rax
movq %rax, 72(%rdi)
//将寄存器的值赋值到相对于第一个参数偏移对应字节的地方
movq %rsi, 64(%rdi)
movq %rdi, 56(%rdi)
movq %rbp, 48(%rdi)
movq %r8, 40(%rdi)
movq %r9, 32(%rdi)
movq %r12, 24(%rdi)
movq %r13, 16(%rdi)
movq %r14, 8(%rdi)
movq %r15, (%rdi)
//将rax寄存器的值清空,对自己异或
xorq %rax, %rax
//将保存在第二个参数的内容赋值到寄存器
movq 48(%rsi), %rbp
movq 104(%rsi), %rsp
movq (%rsi), %r15
movq 8(%rsi), %r14
movq 16(%rsi), %r13
movq 24(%rsi), %r12
movq 32(%rsi), %r9
movq 40(%rsi), %r8
movq 56(%rsi), %rdi
movq 80(%rsi), %rdx
movq 88(%rsi), %rcx
mova 96(%rsi), %rbx
//将栈顶往上挪8个字节,为了下面将返回地址压栈
leaq 8(%rsp), %rsp
//将返回地址压栈
pushq 72(%rsi)
movq 64(%rsi), %rsi
//弹出栈顶的值,也就是返回地址并跳转
ret
```

对上面的注释的自测结果如下图所示:

调用coctx_swap函数前的寄存器信息:

76 c	coctx_swap(mainInfo,	funInfo);
(gdb) i r		
rax	0x555555555179	93824992235897
rbx	0x555555555350	93824992236368
rcx	0x7ffff7cfdb06	140737350982406
rdx	0x1	1 %
rsi	0x21000	135168
rdi	0x0	0
rbp	0x7ffffffffe190	0x7fffffffe190
rsp	0x7fffffffe190	0x7fffffffe190
r8	0x7ffff7a56010	140737348198416
r9	0x0	0
r10	0x22	34
r11	0x246	582
r12	0x55555555590	93824992235664
r13	0x7fffffffe280	140737488347776
r14	0x0	0
r15	0x0	0
rip	0x55555555238	0x5555555555238 <main()+25></main()+25>
eflags	0x206	[PFIF]
cs	0x33	51
SS	0x2b	43
ds	0x0	0
es	0x0	0
fs	0x0	0
gs	0x0	0

调用coctx_swap函数后的寄存器信息:

```
coctx_swap () at coctx_swap.S:30
                leaq (%rsp),%rax
(gdb) i r
              0x55555555179
                                   93824992235897
rax
              0x55555555350
rbx
                                   93824992236368
               0x7fffff7cfdb06
                                   140737350982406
rcx
rdx
               0x1
               0x555555580c0
                                   93824992248000
rsi
rdi
               0x55555558040
                                   93824992247872
               0x7ffffffffe190
                                   0x7fffffffe190
rbp
                                   0x7fffffffe188
              0x7fffffffe188
rsp
               0x7ffff7a56010
                                   140737348198416
r8
r9
               0x0
               0x22
                                   34
r10
r11
               0x246
                                   582
r12
              0x5555555590
                                   93824992235664
              0x7fffffffe280
                                   140737488347776
r13
r14
               0x0
r15
               0x0
rip
               0x555555552c4
                                   0x55555555552c4 <coctx swap>
eflags
               0x206
                                   [ PF IF ]
               0x33
CS
                                   51
               0x2b
                                   43
SS
ds
               0x0
                                   0
               0x0
                                   0
es
fs
               0x0
                                   0
               0x0
gs
(gdb) x /2xg 0x7fffffffe188
                               rsp寄存器的值,此时是指向调用coctx_swap后的下一条指令地址
0x7fffffffe188: 0x000055555555524b
                                       0x0000000000000000
(gdb) disassemble 0x000055555555524b
Dump of assembler code for function main():
   0x000055555555521f <+0>:
                                endbr64
   0x0000555555555223 <+4>:
                               push
                                      %rbp
   0x0000555555555224 <+5>:
                               mov
                                       %rsp,%rbp
   0x0000555555555227 <+8>:
                                lea
                                       0xde2(%rip),%rdi
                                                               # 0x55555556010
   0x000055555555522e <+15>:
                                callq 0x555555555070 <puts@plt>
   0x0000555555555233 <+20>:
                                callq 0x5555555551a3 <init()>
   0x0000555555555238 <+25>:
                                                                # 0x55555555580c0 <funInfo>
                                lea
                                       0x2e81(%rip),%rsi
   0x000055555555553f <+32>:
                                       0x2dfa(%rip),%rdi
                                                                # 0x555555558040 <mainInfo>
                                1ea
           555555555246 <+39>:
                                callq
           555595524b <+44>:
                                       0xdc8(%rip),%rdi
       005555555555252 <+51>:
                                callq
   0x0000555555555557 <+56>:
                                mov
                                       $0x0,%eax
   0x000055555555555 <+61>:
                                       %rbp
                                pop
   0x0000555555555525d <+62>:
                                retq
End of assembler dump.
```