
High-Availability & Dynamic Routing

420-634-AB Network Infrastructure and Automation

Sharma, Varun
JOHN ABOTT COLLEGE

HIGH AVAILABILITY & DYNAMIC ROUTING

In this project, a network with the following topology will be created in GNS3, with HSRP configured on R1 and R3 (192.168.1.0/24 network) and OSPF on all the three routers. R2 will act as an edge router, performing NAT and it will be configured as a DHCP client, obtaining its IP address from ISP.




IP Addressing Scheme:


Device	Interface	IP Address	Default Gateway
R1	f0/0	10.1.1.1/24	
	f1/0	10.1.1.1/30	
	f1/1	10.1.1.9/30	
R2	f0/0	DHCP	
	f1/0	10.1.1.2/30	
	f1/1	10.1.1.5/30	
R3	f0/0	192.168.1.3/24	
	f1/0	10.1.1.10/30	
	f1/1	10.1.1.6/30	
Sw1	SVI	192.168.1.11/24	192.168.1.254/24
Sw2	SVI	192.168.1.13/24	192.168.1.254/24
PC1	Eth0	192.168.1.101/24	192.168.1.254/24
PC2	Eth0	192.168.1.103/24	192.168.1.254/24

Bridging the network

1. Open GNS3 VM in VMware Workstation and click on VM > Settings.




2. Click on 'Network Adapter 2' and select 'Bridged'. Click 'OK'.



- Creating the topology
 - 1. In GNS3, add a cloud to the project and right click on it. Then click 'Configure'.



2. Select 'eth 0' adapter and click 'Delete' to remove it. Then click 'OK'.



3. Add the network devices and configure IP addresses on all the devices as per given addressing scheme.

Enabling OSPF

1. Enter the following commands on R1:

R1(config)# router ospf 10

R1(config-router)# network 10.1.1.0 0.0.0.3 area 0

R1(config-router)# network 10.1.1.8 0.0.0.3 area 0

R1(config-router)# network 192.168.1.0 0.0.0.255 area 0

R1(config-router)# exit

```
R1(config-router)#network 10.1.1.0 0.0.0.3 area 0
R1(config-router)#network 10.1.8.0 0.0.0.3 area 0
R1(config-router)#network 192.168.1.0 0.0.0.255 area 0
R1(config-router)#exit
R1(config)#router ospf 10
R1(config-router)#no network 10.1.8.0 0.0.0.3 area 0
R1(config-router)#network 10.1.1.8 0.0.0.3 area 0
R1(config-router)#network 10.1.1.8 0.0.0.3 area 0
```

2. Enter the following commands on R3:

R3(config)# router ospf 10

R3(config-router)# network 10.1.1.4 0.0.0.3 area 0

R3(config-router)# network 10.1.1.8 0.0.0.3 area 0

R3(config-router)# network 192.168.1.0 0.0.0.255 area 0

R3(config-router)# exit

```
R3(config)#router ospf 10
R3(config-router)#netw
R3(config-router)#network 10.1.1.4 0.0.0.3 area 0
R3(config-router)#network 10.1.1.8 0.0.0.3 area 0
R3(config-router)#network 10.1.1.8 0.0.0.3 area 0
*Feb 10 22:55:34.026: %OSPF-5-ADJCHG: Process 10, Nbr 192.168.1.1 on FastEth ernet1/0 from LOADING to FULL, Loading Done
R3(config-router)#network 192.168.1.0 0.0.0.255 area 0
R3(config-router)#
*Feb 10 22:56:06.046: %OSPF-5-ADJCHG: Process 10, Nbr 192.168.1.1 on FastEth ernet0/0 from LOADING to FULL, Loading Done
R3(config-router)#
```

3. Enter the following commands on R2:

R2(config)# router ospf 10

R2(config-router)# network 10.1.1.0 0.0.0.3 area 0

R2(config-router)# network 10.1.1.4 0.0.0.3 area 0

R2(config-router)# exit

```
R2(config)#router ospf 10
R2(config-router)#network 10.1.1.0 0.0.0.3 area 0
R2(config-router)#network 10.1.1.0 0.0.0.3 area 0
R2(config-router)#network 10.1.1.0 0.0.0.3 area 0
*Feb 10 22:57:41.834: %OSPF-5-ADJCHG: Process 10, Nbr 192.168.1.1 on FastEthere
t1/0 from LOADING to FULL, Loading Done
R2(config-router)#network 10.1.1.4 0.0.0.3 area 0
R2(config-router)#
*Feb 10 22:57:55.802: %OSPF-5-ADJCHG: Process 10, Nbr 192.168.1.3 on FastEthere
t1/1 from LOADING to FULL, Loading Done
R2(config-router)#exit
```

Configuring Default Static Route

1. Enter the following commands on R2:

R3(config)# ip route 0.0.0.0 0.0.0.0 10.164.0.1

R3(config)# router ospf 10

R3(config)# default-information originate

```
R2(config)#ip route 0.0.0.0 0.0.0.0 10.164.0.1
R2(config)#router ospf 10
R2(config-router)#def
R2(config-router)#default-i
R2(config-router)#default-information orig
R2(config-router)#default-information originate ?
  always Always advertise default route
  metric OSPF default metric
  metric-type OSPF metric type for default routes
  route-map Route-map reference
  <cr>
R2(config-router)#default-information originate
```

Enabling NAT

1. Enter the following commands on R2:

R2(config)# int f0/0

R2(config-if)# ip nat outside

R2(config-if)# int f1/0

R2(config-if)# ip nat inside

R2(config-if)# int f1/1

R2(config-if)# ip nat inside

R2(config-if)# exit

R2(config)# access-list 1 permit 192.168.0.0 0.0.255.255

R2(config)# access-list 1 permit 10.1.1.0 0.0.0.255

R2(config)# ip nat inside source list 1 interface f0/0 overload

```
R2(config)#int f0/0
R2(config-if)#ip nat outside
R2(config-if)#int f1/0
R2(config-if)#ip nat inside
R2(config-if)#ip nat inside
R2(config-if)#ip nat inside
R2(config-if)#ip nat inside
R2(config-if)#exit
R2(config)#access-list 1 permit 192.168.0.0 0.0.255.255
R2(config)#access-list 1 permit 10.1.1.0 0.0.0.255
R2(config)#ip nat inside source list 1 interface f0/0 ov
R2(config)#ip nat inside source list 1 interface f0/0 overload
```

Configuring HSRP

1. Enter the following commands on R1:

R1(config)# int f0/0

R1(config-if)# standby version 2

R1(config-if)# standby 1 ip 192.168.1.254

R1(config-if)# standby 1 priority 150

R1(config-if)# standby 1 preempt

R1(config-if)# end

```
R1(config)#int f0/0
R1(config-if)#standby version 2
R1(config-if)#standby 1 ip 192.168.1.254
R1(config-if)#
*Feb 10 23:30:24.770: %HSRP-5-STATECHANGE: FastEthernet0/0 Grp 1 state Standby -
> Active
R1(config-if)#standby 1 priority 150
R1(config-if)#standby 1 preempt
R1(config-if)#standby 1 preempt
R1(config-if)#end
```

2. Enter the same commands on R3:

```
R3(config)#int f0/0
R3(config-if)#standby version 2
R3(config-if)#standby 1 ip 192.168.1.254
R3(config-if)#standby 1 priority 100
R3(config-if)#standby 1 preempt
R3(config-if)#end
R3(config-if)#end
R3#
*Feb 10 23:34:48.314: %HSRP-5-STATECHANGE: FastEthernet0/0 Grp 1 state Speak
-> Standby
R3#
```

Verify the functioning of HSRP

1. Run show standby command on R1 and R3 to verify their status.

```
R1#sh standby
FastEthernet0/0 - Group 1 (version 2)
State is Active
2 state changes, last state change 00:05:22
Virtual IP address is 192.168.1.254
Active virtual MAC address is 0000.0c9f.f001 (MAC In Use)
Local virtual MAC address is 0000.0c9f.f001 (v2 default)
Hello time 3 sec, hold time 10 sec
Next hello sent in 1.632 secs
Preemption enabled
Active router is local
Standby router is 192.168.1.3, priority 100 (expires in 7.920 sec)
Priority 150 (configured 150)
Group name is "hsrp-Fa0/0-1" (default)

R3#show standby
FastEthernet0/0 - Group 1 (version 2)
```

```
R3#show standby
FastEthernet0/0 - Group 1 (version 2)
State is Standby
1 state change, last state change 00:00:49
Virtual IP address is 192.168.1.254
Active virtual MAC address is 0000.0c9f.f001 (MAC Not In Use)
Local virtual MAC address is 0000.0c9f.f001 (v2 default)
Hello time 3 sec, hold time 10 sec
Next hello sent in 1.728 secs
Preemption enabled
Active router is 192.168.1.1, priority 150 (expires in 9.584 sec)
MAC address is ca02.e495.0000
Standby router is local
Priority 100 (default 100)
Group name is "hsrp-Fa0/0-1" (default)
R3#
```

The output confirms that R1 is currently the active router and R3 is standby router.

2. Set the IP address of Virtual Router as the default gateway in PC1 and PC2.

```
PC1> ip 192.168.1.101 255.255.255.0 192.168.1.254
Checking for duplicate address...
PC1 : 192.168.1.101 255.255.255.0 gateway 192.168.1.254
PC1> show
NAME IP/MASK
                                                                 LPORT RHOST:
                                            00:50:79:66:68:00 20048 127.0.0
PC1
      192.168.1.101/24
                           192.168.1.254
1:20049
       fe80::250:79ff:fe66:6800/64
PC2> ip 192.168.1.103 255.255.255.0 192.168.1.254
Checking for duplicate address...
PC2 : 192.168.1.103 255.255.255.0 gateway 192.168.1.254
PC2> show
NAME
      IP/MASK
                           GATEWAY
                                                                LPORT RHOST: PO
RT
PC2
      192.168.1.103/24
                           192,168,1,254
                                            00:50:79:66:68:01 20050 127.0.0.
1:20051
      fe80::250:79ff:fe66:6801/64
```

3. Verify the internet connectivity of PC2 using ping. Then use the trace command to check the next hop address.

```
PC2> ping 8.8.8.8

84 bytes from 8.8.8.8 icmp_seq=1 ttl=116 time=51.984 ms
84 bytes from 8.8.8.8 icmp_seq=2 ttl=116 time=40.586 ms
84 bytes from 8.8.8.8 icmp_seq=3 ttl=116 time=54.048 ms
84 bytes from 8.8.8.8 icmp_seq=4 ttl=116 time=36.309 ms
84 bytes from 8.8.8.8 icmp_seq=5 ttl=116 time=36.009 ms

PC2> trace 8.8.8.8

trace to 8.8.8.8, 8 hops max, press Ctrl+C to stop
1 192.168.1.1, 21.653 ms 8.134 ms 8.806 ms
2 10.1.1.2 30.207 ms 31.544 ms 30.664 ms
3 10.164.0.1 48.739 ms 132.764 ms 35.179 ms
4 207.162.58.2 52.228 ms 51.662 ms 77.618 ms
5 132.202.51.245 30.253 ms 57.720 ms 62.729 ms
6 132.202.100.33 50.319 ms 42.261 ms 40.696 ms
7 * * *
8 192.77.55.209 43.851 ms 40.950 ms 41.758 ms
```

The output confirms that R1 is acting as the default router for PC2.

4. Shut interface f0/0 on R1.

```
R1(config)#int f0/0
R1(config-if)#shut
R1(config-if)#
*Feb 10 23:45:33.082: %HSRP-5-STATECHANGE: FastEthernet0/
Init
```

5. Run the trace command again to check the next-hop address.

```
PC2> trace 8.8.8.8
trace to 8.8.8.8, 8 hops max, press Ctrl+C to stop
1 192.168.1.3, 14.091 ms 9.281 ms 10.091 ms
2 10.1.1.5 29.234 ms 21.039 ms 20.766 ms
3 10.164.0.1 30.450 ms 41.306 ms 30.357 ms
4 207.162.58.2 62.995 ms 62.700 ms 68.597 ms
5 132.202.51.245 43.098 ms 40.112 ms 50.675 ms
6 132.202.100.33 41.385 ms 41.992 ms 41.595 ms
7 * * *
8 192.77.55.209 37.051 ms 51.366 ms 64.326 ms
```

The output confirms that R3 is now the active router and acting as the default router for PC2.

6. Similarly, check the next-hop on PC1.

```
PC1> ping 8.8.8.8

84 bytes from 8.8.8.8 icmp_seq=1 ttl=116 time=45.482 ms

84 bytes from 8.8.8.8 icmp_seq=2 ttl=116 time=35.731 ms

84 bytes from 8.8.8.8 icmp_seq=3 ttl=116 time=45.763 ms

84 bytes from 8.8.8.8 icmp_seq=4 ttl=116 time=35.754 ms

84 bytes from 8.8.8.8 icmp_seq=5 ttl=116 time=38.193 ms

PC1> trace 8.8.8.8

trace to 8.8.8.8, 8 hops max, press Ctrl+C to stop

1 192.168.1.3 14.321 ms 9.633 ms 10.467 ms

2 10.1.1.5 29.925 ms 30.221 ms 32.630 ms

3 10.164.0.1 41.835 ms 44.784 ms 40.146 ms

4 207.162.58.2 55.552 ms 82.331 ms 38.742 ms

5 132.202.51.245 29.327 ms 33.961 ms 30.204 ms

6 132.202.100.33 30.993 ms 51.131 ms 51.743 ms

7 * * *

8 192.77.55.209 43.744 ms 39.516 ms 41.250 ms
```

The output confirms that R3 is the active router.

7. On R1, enter the no shut command to enable interface f0/0.

```
R1(config-if)#no shut
R1(config-if)#
*Feb 10 23:58:59.486: %HSRP-5-STATECHANGE: FastEthernet0/0 Grp 1 stat
Active
R1(config-if)#
*Feb 10 23:59:00.162: %LINK-3-UPDOWN: Interface FastEthernet0/0, chan
o up
*Feb 10 23:59:01.162: %LINEPROTO-5-UPDOWN: Line protocol on Interface
et0/0, changed state to up
R1(config-if)#
```

8. Run the trace command again on PC1.

```
PC1> trace 8.8.8.8
trace to 8.8.8.8, 8 hops max, press Ctrl+C to stop

1 *192.168.1.1 23.065 ms 9.088 ms

2 10.1.1.2 29.544 ms 30.409 ms 29.367 ms

3 10.164.0.1 45.671 ms 40.961 ms 42.920 ms

4 207.162.58.2 61.895 ms 63.951 ms 53.215 ms

5 132.202.51.245 41.265 ms 41.843 ms 42.889 ms

6 132.202.100.33 41.120 ms 41.864 ms 53.711 ms

7 * * *

8 192.77.55.209 46.527 ms 41.083 ms 46.393 ms
```

The output confirms that R1 has again become the active router.