## **TASCA Go4 Analysis**

OpenOffice document tascaGo4intro.odt (H.Essel, 26. June 2009) SVN rev. 243

## Setups

#### Set up account

The tasca account should be customized for more convenience. One should define a variable for the repository path: export SVN=https://subversion:443/goofy/go4/applications/tasca

To create a new working copy of the repository, create a directory and

mkdir myws svn checkout \$SVN myws cd myws svn info

Then one can use svn commands like

svn list \$SVN

to get a listing of the subversion repository. Some useful alias:

svndiff='svn diff --diff-cmd /usr/bin/diff -x "-EwbB" 'svndiffl='svn diff --diff-cmd /usr/bin/diff -x "-qEwbB" '

On a workspace directory these give a list of files different from repository (second line file list only).

Above has been added to .bashrc file (HE). Other useful alias can be defined here.

## Set up working directory

Once the directory is made an svn working directory (by checking out a repository to it) there are few commands to deal with the repository:

svn info

show the repository the workspace belongs to

svn list \$SVN

list of repository

svn update

update workspace from repository

svn commit -m "enter here comment" [file]


copies all changed files to repository. If a file is specified, only this file is copied (if modified).

### After login

Setup everything for Go4 (now already done in .bashrc)

- . go4login 402-00
- . lealogin

(Note the space behind the dot.)



Go4 analysis steps

## The Go4 analysis

To build the **Tasca** analysis, simply:

make

The executable made is

MainUserAnalysis

It can be called from shell or is started from GUI. In principle it does the same in both cases.

### Batch mode

The analysis is steered by a ROOT macro file **setup.C**. You can edit this file before running the analysis. There are the following lines:

```
TString unpackProcess("yes");
TString unpackStore("no");
TString unpackOverWrite("yes");

TString caliProcess("yes");
TString caliStore("no");
TString caliOverWrite("yes");

TString checkProcess("yes");
TString checkStore("no");
TString checkOverWrite("yes");

TString analysisProcess("yes");
TString analysisProcess("yes");
TString analysisOverWrite("yes");

TString analysisOverWrite("yes");

TString autosave("yes");
Int_t autosaveinterval=0; // after n seconds, 0 = at termination of event loop
```

## **Examples:**

MainUserAnalysis -f file.lmd MainUserAnalysis -f @file.lml

processes file or list of files. respectively.

MainUserAnalysis -t r4-4 10000

connects to MBS transport node R4-4 and processes 10000 events.

Usually in batch mode one either writes an auto-save file (containing all histograms, parameters, etc.), and/or any event file. The auto-save file name and the event file names are prefixed by the input file or node name

```
b r4-4 AS.root, b r4-4 Unpacked.root, b r4-4 Calibrated.root, b r4-4 Checked.root, b r4-4 Analysis.root
```

The b\_ is added in batch mode only. Any of these can be opened by ROOT or in the GUI. To process these in batch:

MainUserAnalysis -f r4-4

The pre and postfixes are added automatically.

To process files from a data directory, the variable

```
export TASCASTORE=/data.local3/x/x/x
```

must be set. Then all files are read and stored from/to it. Currently no files can be stored on a directory different from the source directory.

#### Interactive mode

In interactive mode the analysis is started by the GUI. In this case, the file name prefix is the analysis name specified in the Start Client panel. This name is saved by Save Settings. In addition the prefix  $b_{\underline{}}$  is changed to  $i_{\underline{}}$ . Further setup is

specified in the configuration panel coming up after starting the analysis. Default settings are the ones from **setup.C**. This setup can be modified interactively and can be stored (NOTE: after **Submit!**) in

### Go4AnalysisPrefs.root

from where it is retrieved next time the analysis is started. If this file is present, the settings from setup.C are overwritten.

# The analysis steps

The analysis is divided into four steps as shown in the figure.

### Unpacker step

**Input:** LMD file or MBS (transport, stream server, event server)

Output: ROOT tree with values of all detector channels and detector hit lists. Details in TascaUnpackEvent.h

Autosave: Controls, Parameters, Pedestals and Codec

Histograms in directory Unpack: Adc\_nn GammaE\_n GammaT\_n Pedestals Contents AdcAllRaw AdcAllCal TraceRaw nn TraceE nn Hist nn Pileup nn

**Processing:** TascaUnpackProc constructor creates the parameters, histograms and pictures. Method *TascaUnpack* uses parameter class TascaCodec to decode Adc values, gamma values, and fills the data fields of TascaUnpackEvent. TascaCodec also contains the mapping tables for the multiplexed channels.

### Calibrator step

Input: TascaUnpackEvent (from Unpack step or from file)

Output: ROOT tree with calibrated values of all detector channels and gammas. Hit indices of all detectors and their values.

Details in TascaCaliEvent.h

Autosave: Controls, Parameters, Calibration, CaliFitter

Histograms in directory Cali: All detector channels, gamma channels, Sum of detector channels.

**Processing:** Filling histograms and TascaCaliEvent data fields.

#### Checker step

**Input:** TascaCaliEvent (from Unpack step or from file)

Output: ROOT tree with calibrated hits. Hit indices of all detectors and their values.

Condition filters: EvrH, AlphaL, Alpha1L, Alpha2L, Fission1H, Fission2H, BackH

Limits set in setparam.C
Details in TascaCheckEvent.h

Histograms in directory Check: 2d histograms of stop detector (Energy-Xstripe) for each Ystripe.

Autosave: Controls, Parameter

**Processing:** Filling histograms and TascaCheckEvent data fields.

### Analysis step

**Input:** TascaCheckEvent (from Checker step or from file)

Output: ROOT tree with data from TascaAnlEvent.h (currently none) or TascaEvent.h

Autosave: Creates parameters Controls, Parameters

Processing: Looking for chains, Create plain ROOT tree from TascaEvent

# Control files

There are some ROOT macro files to setup several parameter values.

**setcontrol.C**: Lines to change:

```
fControl->UnpackHisto =kFALSE; // used by Unpacker
  fControl->CaliHisto
                          =kFALSE; // used by Calibrator
  fControl->CheckHisto
                          =kFALSE; // used by Checker
                          =kFALSE; // used by Analysis
=kFALSE; // used by unpacker
  fControl->AnlHisto
  fControl->checkTof
  fControl->checkChopper =kFALSE; // used by unpacker
                          =kFALSE; // used by unpacker
  fControl->checkMacro
  fControl->checkMicro
                          =kFALSE; // used by unpacker
                          =kTRUE; // used by unpacker
  fControl->TofMustbe
  fControl->ChopperMustbe=kTRUE; // used by unpacker
  fControl->MacroMustbe =kFALSE; // used by unpacker
  fControl->MicroMustbe =kFALSE; // used by unpacker
setparam.C: Lines to change:
// Used by Checker
// Energy windows MeV
                             = 4.000,
       Float_t EvrHmin
                                       EvrHmax
                                                     = 15.000;
       Float_t Alpha0Lmin = 9.800,
Float_t Alpha1Lmin = 9.700,
                                       Alpha0Lmax = 10.200:
                                       Alpha1Lmax = 10.100;
       Float t Alpha2Lmin = 8.970,
                                       Alpha2Lmax = 9.3700;
       Float_t Fission1Hmin=60.000,
                                       Fission1Hmax=220.0000;
       Float_t Fission2Hmin=60.000,
Float_t BackHmin =10.000,
                                       Fission2Hmax=220.0000;
                                       BackHmax
                                                     = 80.000;
// Time windows sec
       Float_t fAlphaTmin
                                                      =900.;
                              =0.,
                                        fAlphaTmax
       Float_t fAlpha1Tmin =0.,
                                        fAlpha1Tmax = 20.;
       Float_t fAlpha2Tmin =0.,
Float_t fFission1Tmin=0.,
                                        fAlpha2Tmax = 180.;
                                        fFission1Tmax=900.;
                                        fFission2Tmax= 70.;
       Float_t fFission2Tmin=0.,
       fp->shift=5;
                                     // Unpacker gamma decoder for energies
       fp->Adc80TofMin=300;
                                    // signals Tof (instead of TOF register)
       fp->AdcThreshold=100;
                                    // Unpacker uses this is minimum raw value
       fp->EventStackSize=100000; // used in Analysis
        fp->AlphaMaxL=16000.;
                                    // Calibrator take low value up to this limit. Above
                                    // take high value up to this limit as low
       fp->AlphaMaxH=30000.;
        fp->AlphaMinL=1000.;
                                    // Unpacker <u>raw</u> minimum value for alpha
       fp->AlphaMinH=1000.;
                                    // Unpacker <u>raw</u> minimum value for alpha
setcali.C steers the calibration:
  fCalibration->EnableCalibration(kTRUE);
                                               // use calibration or not
  fCalibration->SetPrefix("cali2");
                                               // prefix for coefficient files
```

# Processing LMD files

To process several LMD files at once and store the results in one root file, one must create a text file with extension .lml and specify this file preceded by an @ instead of the LMD filename.

### Example t018f0790.lml

```
/data.local1/tasca/t018f0790381.lmd/data.local1/tasca/t018f0790382.lmd/data.local1/tasca/t018f0790383.lmd/data.local1/tasca/t018f0790384.lmd/data.local1/tasca/t018f0790385.lmd/data.local1/tasca/t018f0790386.lmd/data.local1/tasca/t018f0790387.lmd/data.local1/tasca/t018f0790388.lmd/data.local1/tasca/t018f0790388.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tasca/t018f0790389.lmd/data.local1/tas
```

I recommend to process in batch mode Unpacker and Calibration steps from one file set into one root file. Then run Checker from this root file. Append output of all inputs (output files from one file set of 4 GB are few 10 MB). Resulting ROOT file can be fast scanned by Analysis step.

It might be necessary to find events by event number in LMD files. For this purpose in each event the run and file number is stored (Run is high two bytes, file number low two bytes). In the ROOT files these events can be found easily via macros like filter...C or print...C macros. If one wants to create an LMD subset,

Create the LML files by changing into LMD file directory, then:

Imlrmake t018f 3 146

This creates files t018fxxx.lml with xxx=003 to 146 containing lists of files t018fxxx\*.lmd including full path. Create the LMD directory files by command:

Imdirmake <directory of LMD files>

Imdirmake -f file

The second command processes only one file. Search for events by command:

Imdirshow <directory> [event number]

Imdirshow -f file [event number]

Again the second command checks only one file.

LMD files have been moved to directories

/d/ship01/tasca/t018/badfiles

/d/ship01/tasca/t018/backup

/d/ship01/tasca/t018/calibration

/d/ship01/tasca/t018/targettest

Because working directly from /d was incredible slow, we first copy the data to local disk, then process, and remove the LMD files (from local disk). The place for the processed ROOT files and LMDIR files is on lxg0708:

/data.local3/offlinedata

/u/tasca/GO4\_offline\_t018/data

second being a soft link to the first for convenience.

GO4 analysis is in directories of

/u/tasca/GO4 offline t018

The code for the actual batch run is in checked01, data on data/stepdata/Imdir,calibrated0x,checked0x. There is also a shell script to execute:

runbatch.sh first last

First and last are numbers xxx mentioned above.

collectchecked.C(dirfile,rootfile,events)

root -b -l "collectchecked.C(\"p01.list\",\"b p01 Checked.root\",0)"

copies all checked ROOT files from a container text file into one. Additional filters could be applied.

filterchecked.C

copies all checked ROOT files with fast filter. Similar to collectchecked.C but uses partial read. One event cane be printed by

printcheckevent.C

root -b -l "printcheckevent.C(\"b p01 Checked.root\",event)"

# Analysis chain

 Produce ROOT files with calibrated and checked events. All LMD files of a run go into one ROOT file.
 File names are t018fRRRFFFF.lmd, where RRR is the run number, FFFF the file number. Adjust runbatch.sh script to the correct directories. In setup.C activate the Unpacker, Calibrator, and Checker. Activate output for Calibrator and Checker.

time runbatch.sh 196 206 >> runbatch196-206.log

- 2. Collect ROOT files with checked events into phase ROOT files like phase p04: time root -b -l "collectchecked.C(\"t018p04-196-206.list\",\"../data/stepdata/checked03/b\_p04\_Checked.root\",0)"
- 3. Run GO4 Analysis to search for chains. In setcontrol.C parameter writeChainTree steers the production of ROOT tree file with the chains named xxx\_Chains.root, where xxx is the first name part of the input tree file. In setup.C Deactivate all steps and activate Analysis.

  ./MainUserAnalysis -f p04 >> chainsSFoffp04.log
- 4. To get a complete printout of the data of a chain, use printevent.C(rootfile,chain number) root -b -l "printevent.C(\"b\_p04\_Chains.root\",23)"

#### Calibration

An automated generation of calibration coefficient files is done by macro

makecali.C(prefix, rootfile)

root -b -l "makecali(\"test\",\"test\_AS\")"

where prefix is a string used as prefix for all file names generated, rootfile is the name of the ROOT file containing the histograms (given without trailing .root). The macro should be adjusted. Several parameters can be set inside.

Histograms/Cali/StopXL: prefix StopXL[144] Histograms/Cali/StopYL: prefix StopYL[96] Histograms/Cali/StopXH: prefix StopXH[144] prefix StopYH[96] Histograms/Cali/StopYH: Histograms/Cali/BackH: prefix BackH[64] Histograms/Cali/BackL: prefix BackL[64] Histograms/Cali/VetoH: prefix VetoH[16] prefix VetoL[16] Histograms/Cali/VetoL: Histograms/Unpack/GammaE: prefix GammaE[8] Histograms/Unpack/GammaT: prefix GammaT[8]

The format of the calibration files is:

name value

The format of the generated files is: name index a0 a1 a2 : NOF ChiSquare

Class TascaCalibration is the parameter class holding the coefficients. This parameter is used in the TascaCaliProc processor of the second step.


To enable/disable the calibration the macro

setcali.C

must be edited. If enabled, it reads the files produced by makecali. For these the prefix string must be set.

Class TascaCaliFitter is a parameter class with the purpose of doing the calibration interactively. This might be necessary if the automatic calculations do not work for a histogram. This parameter is used in the TascaCaliProc processor of the second step. Calculating calibration parameters is done in two steps. First we need a histogram with the measured lines and a text file with the energies of these lines. These are present in arrays inside the parameter. First fitter LineFitter is used to find out true channel numbers for corresponding lines in calibration spectrum. This fit should be done interactively on the GUI side:

- Get parameter CaliFitter from analysis (Doubleclick)
- Display calibration spectrum.
- Double click on the LineFitter fitter in the parameter editor. Fit panel will open showing the current settings of the
  fitter. Press Use pad of the fit panel to assign this fitter to the view panel containing the calibration spectrum and
  Rebuild button.
- Use peak finder 3 to find the peaks. Enlarging the noise factor removes peaks as well as minimum noise.
- Do Fit. If the positions of the lines are fitted correctly, copy the fitter back to the calibration parameter: right mouse button click on LineFitter, select Get from FitPanel.
- Check if the name of the calibration file is correct.
- Set DoFit variable to 1 (will be set back to 0 after the fit).
- Now press left arrow button. This will perform fit of the calibration curve (polynomial of order 2) in the UpdateFrom() method of TascaCaliFitter on the analysis side.
- Pressing right arrow button will get the results of the calibration, present in the polynomial coefficients fdA[0]...fdA[2] and in the Calibrator fitter.
- The corresponding TGraph is UserObjects/CaliGraph and is displayed by double click. Then double click on the
  Calibrator fitter in the parameter editor to open in a fit panel, press Use Pad, Rebuild and Draw. This will draw the
  calibration polynomial over the points which indicate the energy/channel of the calibration lines.



The detector layouts