RDT小结

目标: 在不可靠的信道上实现可靠数据传输

- ■情况1——考虑数据可能出现bit错误。
 - ■要求: 1,接收端具有检查错误、ACK的能力, 从而发现错误并告知发送端: 2, 发送端具有 重传的能力。
 - ■但是,发送端一旦具有重传的能力,就会带来 新的问题——发送端重传的数据被接收端当做 新的数据。因此,要引入序列号。
 - ■最终的解决方案要整合三项机制:错误检查(Checksum)、ACK、序列号。

RDT小结

目标: 在不可靠的信道上实现可靠数据传输

- ■情况2——在情况1的基础上,考虑丢包。
 - ■要求: 1, 发送端要有检查丢包的能力: 设置 定时器, 一旦定时器超时, 就认为数据包丢失, 并重传。
 - ■但是,定时器超时并不一定意味着数据包丢失 ,有可能是因为数据包在网络中延迟太大。这 样会造成接收端接收到重复的数据,好在序列 号已经解决了这一问题。
 - ■最终的解决方案要整合四项机制:错误检查(Checksum)、ACK、序列号、定时器_{Pansport Layer}

RDT小结

目标: 在不可靠的信道上实现可靠数据传输

- ■是否还有第三种情况? 类比一下网购快递的过程
- ■是否考虑完全?四种情况的组合:发送端发现数据损坏、接收端发现数据损坏、发送端丢包、接收端丢包。
- ■定时器应如何设定?

Performance of rdt3.0

- □ rdt3.0 works, but performance stinks
- □ ex: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:


$$d_{trans} = \frac{L}{R} = \frac{8000 \text{bits}}{10^9 \text{bps}} = 8 \text{ microseconds}$$

O U sender: utilization - fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- 1KB pkt every 30 msec -> 33kB/sec thruput over 1 Gbps link
- o network protocol limits use of physical resources!

rdt3.0: stop-and-wait operation




$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

Pipelined protocols

Pipelining: sender allows multiple, "in-flight", yet-tobe-acknowledged pkts

- o range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

Two generic forms of pipelined protocols: go-Back-N, selective repeat

Pipelining: increased utilization



Pipelining Protocols

Go-back-N: big picture:

- Sender can have up to N unacked packets in pipeline
- Rcvr only sends cumulative acks
 - Doesn't ack packet if there's a gap
- Sender has timer for oldest unacked packet
 - If timer expires, retransmit all unacked packets


Selective Repeat: big pic

- Sender can have up to N unacked packets in pipeline
- Rcvr acks individual packets
- Sender maintains timer for each unacked packet
 - When timer expires, retransmit only unack packet

Go-Back-N

Sender:

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack'ed pkts allowed




- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
 - may receive duplicate ACKs (see receiver)
- timer for the oldest pkt
- timeout(n): retransmit pkt n and all higher seq # pkts in window

GBN: sender extended FSM

```
rdt send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt send(sndpkt[nextsegnum])
                          if (base == nextseqnum)
                            start timer
                          nextseqnum++
                       else
   Λ
                         refuse_data(data)
  base=1
  nextseqnum=1
                                           timeout
                                           start timer
                             Wait
                                           udt_send(sndpkt[base])
                                           udt send(sndpkt[base+1])
rdt_rcv(rcvpkt)
 && corrupt(rcvpkt)
                                           udt_send(sndpkt[nextsegnum-1])
                         rdt_rcv(rcvpkt) &&
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                           stop_timer
                          else
                           start_timer
```

GBN: receiver extended FSM




ACK-only: always send ACK for correctly-received pkt with highest in-order seq

- may generate duplicate ACKs
- o need only remember expectedseqnum

out-of-order pkt:

- discard (don't buffer) -> no receiver buffering!
- Re-ACK pkt with highest in-order seq #


GBN in action



Selective Repeat

- receiver individually acknowledges all correctly received pkts
 - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
 - sender timer for each unACKed pkt
- sender window
 - N consecutive seq #'s
 - again limits seq #s of sent, unACKed pkts

Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

Selective repeat

-sender

data from above:

□ if next available seq # in window, send pkt

timeout(n):

- resend pkt n, restart timer
- ACK(n) in [sendbase, sendbase+N]:
- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

receiver

pkt n in [rcvbase, rcvbase+N-1]

- ☐ send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt


pkt n in [rcvbase-N,rcvbase-1]

 \Box ACK(n)

otherwise:

ignore


Selective repeat in action



Selective repeat: dilemma

Example:

- seq #'s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- incorrectly passes duplicate data as new in (a)
- Q: what relationship between seq # size and window size?



GBN、SR小结

BASIS FOR COMPARISON	GO-BACK-N	SELECTIVE REPEAT
Basic	Retransmits all the frames that sent after the frame which suspects to be damaged or lost.	Retransmits only those frames that are suspected to lost or damaged.
Bandwidth Utilization	If error rate is high, it wastes a lot of bandwidth.	Comparatively less bandwidth is wasted in retransmitting.
Complexity	Less complicated.	More complex as it require to apply extra logic and sorting and storage, at sender and receiver.
Window size	N-1	<= (N+1)/2

注 意 : 表 格 中 术 语与教材不尽 致

yer 3-19

GBN、SR小结

Sorting	Sorting is neither required at sender side nor at receiver side.	Receiver must be able to sort as it has to maintain the sequence of the frames.
Storing	Receiver do not store the frames received after the damaged frame until the damaged frame is retransmitted.	Receiver stores the frames received after the damaged frame in the buffer until the damaged frame is replaced.
Searching	No searching of frame is required neither on sender side nor on receiver	The sender must be able to search and select only the requested frame.
ACK Numbers	NAK number refer to the next expected frame number.	NAK number refer to the frame lost.
Use	It more often used.	It is less in practice because of its complexity.

注 意 中 教 致

GBN、SR小结

目标:提高效率,都属于滑动窗口方法

- 与之相对, RDT可以认为是一种Stop-And-Wait方法, 窗口大小为1。
- GBN与SR的通信效率一致,GBN适用于网络条件较好的情况,SR适用于网络条件较差的情况。
- GBN与SR的动画演示: http://www.ccs-
 labs.org/teaching/rn/animations/gbn sr/

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer


- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP: Overview

RFCs: 793, 1122, 1323, 2018, 2581

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - o no "message boundaries"
- pipelined:
 - TCP congestion and flow control set window size
- send & receive buffers

- □ full duplex data:
 - bi-directional data flow in same connection
 - MSS: maximum segment size
- connection-oriented:
 - handshaking (exchange of control msgs) init's sender, receiver state before data exchange
- ☐ flow controlled:
 - sender will not overwhelm receiver



TCP segment structure


URG: urgent data (generally not used)

ACK: ACK # valid

PSH: push data now (generally not used)-

RST, SYN, FIN: connection estab (setup, teardown commands)

> Internet checksum' (as in UDP)



counting by bytes of data (not segments!)

> # bytes rcvr willing to accept


TCP seq. #'s and ACKs

<u>Seq. #'s:</u>

byte stream "number" of first byte in segment's data

ACKs:

- seq # of next byte expected from other side
- cumulative ACK
- Q: how receiver handles out-of-order segments
 - A: TCP spec doesn't say, - up to implementor



simple telnet scenario

TCP Round Trip Time and Timeout

- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short: premature timeout
 - unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- □ SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT


TCP Round Trip Time and Timeout

```
EstimatedRTT = (1-\alpha)*EstimatedRTT + \alpha*SampleRTT
```

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- \Box typical value: $\alpha = 0.125$

Example RTT estimation:

RTT: gaia.cs.umass.edu to fantasia.eurecom.fr



TCP Round Trip Time and Timeout

Setting the timeout

- EstimtedRTT plus "safety margin"
 - large variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

Then set timeout interval:

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP reliable data transfer

- □ TCP creates rdt service on top of IP's unreliable service
- Pipelined segments
- Cumulative acks
- ☐ TCP uses single retransmission timer

- Retransmissions are triggered by:
 - o timeout events
 - duplicate acks
- Initially consider simplified TCP sender:
 - ignore duplicate acks
 - ignore flow control, congestion control

TCP sender events:

data rcvd from app:

- Create segment with seq#
- □ seq # is byte-stream number of first data byte in segment
- start timer if not already running (think of timer as for oldest unacked segment)
- expiration interval: TimeOutInterval

timeout:

- retransmit segment that caused timeout
- restart timer

Ack rcvd:

- □ If acknowledges previously unacked segments
 - update what is known to be acked
 - o start timer if there are outstanding segments


```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
loop (forever) {
  switch(event)
  event: data received from application above
      create TCP segment with sequence number NextSeqNum
      if (timer currently not running)
         start timer
      pass segment to IP
      NextSeqNum = NextSeqNum + length(data)
   event: timer timeout
      retransmit not-yet-acknowledged segment with
           smallest sequence number
      start timer
   event: ACK received, with ACK field value of y
      if (y > SendBase) {
         SendBase = y
         if (there are currently not-yet-acknowledged segments)
              start timer
 } /* end of loop forever */
```

TCP sender (simplified)


Comment:

- SendBase-1: last cumulatively ack'ed byte Example:
- SendBase-1 = 71;
 y= 73, so the rcvr
 wants 73+;
 y > SendBase, so
 that new data is
 acked

TCP: retransmission scenarios



TCP retransmission scenarios (more)



Cumulative ACK scenario

TCP ACK generation [RFC 1122, RFC 2581]

Event at Receiver	TCP Receiver action
Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
Arrival of in-order segment with expected seq #. One other segment has ACK pending	Immediately send single cumulative ACK, ACKing both in-order segments
Arrival of out-of-order segment higher-than-expect seq. # . Gap detected	Immediately send <i>duplicate ACK</i> , indicating seq. # of next expected byte
Arrival of segment that partially or completely fills gap	Immediate send ACK, provided that segment starts at lower end of gap

Fast Retransmit

- □ Time-out period often relatively long:
 - long delay before resending lost packet
- Detect lost segments via duplicate ACKs.
 - Sender often sends many segments back-toback
 - If segment is lost, there will likely be many duplicate ACKs.

- ☐ If sender receives 3 ACKs for the same data, it supposes that segment after ACKed data was lost:
 - o fast retransmit: resend segment before timer expires




Figure 3.37 Resending a segment after triple duplicate ACK Layer 3-38

Fast retransmit algorithm:

```
event: ACK received, with ACK field value of y
          if (y > SendBase) {
             SendBase = y
             if (there are currently not-yet-acknowledged segments)
                 start timer
          else {
               increment count of dup ACKs received for y
               if (count of dup ACKs received for y = 3) {
                   resend segment with sequence number y
```

a duplicate ACK for already ACKed segment

fast retransmit


Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP Flow Control

receive side of TCP connection has a receive buffer:




 app process may be slow at reading from buffer

flow control.

sender won't overflow receiver's buffer by transmitting too much, too fast

■ speed-matching service: matching the send rate to the receiving app's drain rate

TCP Flow control: how it works



- (Suppose TCP receiver discards out-of-order segments)
- □ spare room in buffer
- = RcvWindow

- Rcvr advertises spare room by including value of RcvWindow in segments
- Sender limits unACKed data to RcvWindow
 - guarantees receive buffer doesn't overflow

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP Connection Management

- Recall: TCP sender, receiver establish "connection" before exchanging data segments
- initialize TCP variables:
 - o seq. #s
 - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator Socket clientSocket = new Socket ("hostname", "port number");
- server: contacted by client Socket connectionSocket = welcomeSocket.accept();

Three way handshake:

- Step 1: client host sends TCP SYN segment to server
 - specifies initial seq #
 - o no data
- **Step 2:** server host receives SYN, replies with SYNACK segment
 - server allocates buffers
 - specifies server initial seq.#
- <u>Step 3:</u> client receives SYNACK, replies with ACK segment, which may contain data


TCP Connection Management (cont.)

Closing a connection:

client closes socket:
 clientSocket.close();

Step 1: client end system sends TCP FIN control segment to server

Step 2: server receives FIN, replies with ACK. Closes connection, sends FIN.




TCP Connection Management (cont.)

<u>Step 3:</u> client receives FIN, replies with ACK.


 Enters "timed wait" will respond with ACK to received FINs

Step 4: server, receives ACK. Connection closed.

Note: with small modification, can handle simultaneous FINs.



TCP Connection Management (cont)



Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer


- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control


Principles of Congestion Control


Congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- □ a top-10 problem!

- two senders, two receivers
- one router, infinite buffers
- no retransmission









- large delayswhen congested
- maximum achievable throughput

- one router, finite buffers
- sender retransmission of lost packet



- \square always: $\lambda_{in} = \lambda_{out}$ (goodput)
- "perfect" retransmission only when loss: $\chi' > \chi_{\rm in}$ out,
- retransmission of delayed (not lost) packet makes λ_{in} (than perfect case) for same λ





"costs" of congestion:

- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt

- four senders
- multihop paths
- timeout/retransmit

Q: what happens as λ_{in} and λ'_{in} increase ?





Another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Approaches towards congestion control

Two broad approaches towards congestion control:

End-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

Network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate sender should send at

Case study: ATM ABR congestion control


ABR: available bit rate:

- "elastic service"
- if sender's path "underloaded":
 - sender should use available bandwidth
- if sender's path congested:
 - sender throttled to minimum guaranteed rate

RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
 - NI bit: no increase in rate (mild congestion)
 - O CI bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

Case study: ATM ABR congestion control



- two-byte ER (explicit rate) field in RM cell
 - o congested switch may lower ER value in cell
 - sender' send rate thus maximum supportable rate on path
- □ EFCI bit in data cells: set to 1 in congested switch
 - o if data cell preceding RM cell has EFCI set, sender sets CI bit in returned RM cell

Chapter 3 outline


- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- □ 3.7 TCP congestion control

TCP congestion control: additive increase, multiplicative decrease

- Approach: increase transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase CongWin by 1 MSS every RTT until loss detected
 - multiplicative decrease: cut CongWin in half after loss

Saw tooth behavior: probing for bandwidth



TCP Congestion Control: details

- sender limits transmission:

 LastByteSent-LastByteAcked

 ≤ CongWin
- Roughly,

rate =
$$\frac{CongWin}{RTT}$$
 Bytes/sec

CongWin is dynamic, function of perceived network congestion

How does sender perceive congestion?

- loss event = timeout or3 duplicate acks
- □ TCP sender reduces rate (CongWin) after loss event

three mechanisms:

- AIMD
- slow start
- conservative after timeout events


TCP Slow Start

- When connection begins, CongWin = 1 MSS
 - Example: MSS = 500 bytes & RTT = 200 msec
 - initial rate = 20 kbps
- available bandwidth may be >> MSS/RTT
 - desirable to quickly ramp up to respectable rate

When connection begins, increase rate exponentially fast until first loss event

TCP Slow Start (more)

- When connection begins, increase rate exponentially until first loss event:
 - double CongWin every RTT
 - done by incrementing CongWin for every ACK received
- Summary: initial rate is slow but ramps up exponentially fast



Refinement: inferring loss

- ☐ After 3 dup ACKs:
 - O Congwin is cut in half
 - window then grows linearly
- But after timeout event:
 - CongWin instead set to 1 MSS;
 - window then grows exponentially
 - o to a threshold, then grows linearly


Philosophy:

□ 3 dup ACKs indicates network capable of delivering some segments timeout indicates a "more alarming" congestion scenario

Refinement

Q: When should the exponential increase switch to linear?

A: When CongWin gets to 1/2 of its value before timeout.



Implementation:

- Variable Threshold
- ☐ At loss event, Threshold is set to 1/2 of CongWin just before loss event

Summary: TCP Congestion Control

- When CongWin is below Threshold, sender in slow-start phase, window grows exponentially.
- When CongWin is above Threshold, sender is in congestion-avoidance phase, window grows linearly.
- □ When a triple duplicate ACK occurs, Threshold set to CongWin/2 and CongWin set to Threshold.
- □ When timeout occurs, Threshold set to CongWin/2 and CongWin is set to 1 MSS.

TCP sender congestion control

State	Event	TCP Sender Action	Commentary
Slow Start (SS)	ACK receipt for previously unacked data	CongWin = CongWin + MSS, If (CongWin > Threshold) set state to "Congestion Avoidance"	Resulting in a doubling of CongWin every RTT
Congestion Avoidance (CA)	ACK receipt for previously unacked data	CongWin = CongWin+MSS * (MSS/CongWin)	Additive increase, resulting in increase of CongWin by 1 MSS every RTT
SS or CA	Loss event detected by triple duplicate ACK	Threshold = CongWin/2, CongWin = Threshold, Set state to "Congestion Avoidance"	Fast recovery, implementing multiplicative decrease. CongWin will not drop below 1 MSS.
SS or CA	Timeout	Threshold = CongWin/2, CongWin = 1 MSS, Set state to "Slow Start"	Enter slow start
SS or CA	Duplicate ACK	Increment duplicate ACK count for segment being acked	CongWin and Threshold not changed

TCP throughput

- What's the average throughout of TCP as a function of window size and RTT?
 - Ignore slow start
- □ Let W be the window size when loss occurs.
- When window is W, throughput is W/RTT
- □ Just after loss, window drops to W/2, throughput to W/2RTT.
- □ Average throughout: .75 W/RTT

TCP Futures: TCP over "long, fat pipes"


- □ Example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- □ Requires window size W = 83,333 in-flight segments
- Throughput in terms of loss rate:

$$\frac{1.22 \cdot MSS}{RTT\sqrt{L}}$$

- $\Box \rightarrow L = 2.10^{-10} Wow$
- New versions of TCP for high-speed

TCP Fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Why is TCP fair?

Two competing sessions:

- Additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- Multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- Instead use UDP:
 - pump audio/video at constant rate, tolerate packet loss
- Research area: TCP friendly

Fairness and parallel TCP connections

- nothing prevents app from opening parallel connections between 2 hosts.
- Web browsers do this
- Example: link of rate R supporting 9 connections;
 - o new app asks for 1 TCP, gets rate R/10
 - o new app asks for 11 TCPs, gets R/2!

Chapter 3: Summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - o reliable data transfer
 - o flow control
 - congestion control
- instantiation and implementation in the Internet
 - o UDP
 - o TCP

Next:

- leaving the network "edge" (application, transport layers)
- □ into the network "core"

思考题



- □为什么TCP是三次握手?
 - ○不是两次?
 - ○不是四次?

思考题



- □为什么TCP是四次挥手?
 - ○不是两次?
 - ○为什么还有等待时间?