Flexbox Properties

```
Parent (Flex Container) display: flex | inline-flex; flex-direction:
row | row-reverse | column | column-reverse; flex-wrap: wrap |
nowrap | wrap-reverse; flex-flow (shorthand for flex-direction and
flex-wrap)
justify-content (main axis): flex-start | flex-end | center | space-between | space-around |
space-evenly;
      align-items (cross axis - adjust to individual sizes): flex-start | flex-end | center | baseline
| stretch;
      align-content (cross axis - adjust to largest item): flex-start | flex-end | center | stretch |
space-between | space-around;
Children (Flex Items) order:
<integer>; flex-grow: <number>;
flex-shrink: <number>;
                            flex-
basis: <length> | auto;
      flex: shorthand for grow, shrink, and basis (default: 0 1 auto)
      align-self: overrides alignment set on parent
Grid Properties
Parent (Grid Container)
display: grid | inline-grid;
      grid-template-columns
      grid-template-rows: [optional: line name, in square brackets] <track-size> | <repeat>;
                                             line name: an arbitrary name for this item. If no
      track-size: length, %, fr, auto
name assigned, a number is used
             EXAMPLES:
       .myClass {
               grid-template-columns: [col1] 40px [col2] 3fr;
```

```
grid-template-rows: 50% 25vh auto;
}
.anotherClass {
  grid-template-rows: repeat(2, 350px [name]) 10%;
}
translates to
.anotherClass {
  grid-template-rows: 350px [name] 350px [name] 10%;
}
```

grid-template-areas:

List of names of areas. First, name areas via selector. Then specify layout via this property. Area name must be specified for each column/row. A . indicates no content in this row/column.

Note: in this example, the lines are named automatically: header-start, header-end, article-start, article-end, etc.

EXAMPLES:

```
.class1 {
    grid-area: header;
} .class2
{
    grid-area: article;
} .class3
{
    grid-area: aside;
}
    .wrapper {
        grid-template-columns: 1fr 3fr;
        grid-template-rows: auto; grid-template-areas:
        "header header header"
        "aside . article article";
}
```

grid-template:

Shorthand for grid-template-rows, grid-template-columns, and grid-template-areas in 1 declaration. Not covered in class.

grid-gap:

Shorthand for grid-column-gap and grid-row-gap.

1 number = same in all directions

2 numbers = row column

```
justify-items: start | end | center |
stretch; align grid items on row axis
    stretch is default

align-items: start | end | center | stretch;
    align grid items on column axis
stretch is default
```

justify-content: start | end | center | stretch | space-around | space-between |
spaceevenly;

If size of grid container is bigger than total of grid items, you can align grid items within the container (like flexbox). This works on row axis.

align-content: start | end | center | stretch | space-around | space-between |
spaceevenly;

If size of grid container is bigger than total of grid items, you can align grid items within the container (like flexbox). This works on column axis.

```
grid-auto-columns
grid-auto-rows: <track-size>;
```

If you create grid cells beyond those specified in grid-template-columns and gridtemplate-rows, this specifies how big these extra rows/columns should be.

grid: shorthand for all of the above properties. Not covered in class.

```
Children (Grid Items) grid-
```

column-start grid-column-end grid-row-start

grid-row-end: <number> | <name> | span <number> | span <name> | auto;
This is the longhand for declaring individual values for start and end points for rows and columns.

EXAMPLES:

```
class1 {
    grid-column-start: 1; grid-
    column-end: span 4; grid-row-
    start: 3;
    grid-row-end: span footer-end;
}
```

grid-column

grid-row: <start-line> / <end-line> | <start-line> / span <value>;
Combines start and end values, as used extensively in class.

EXAMPLES:

```
.class1 {
    grid-column: 1 / span 4;
```

By - syedash01

```
grid-row: 3 / span footer-end;
}
```

grid-area: <name> | <row-start> / <column-start> / <row-end> / <column-end>;
OR
<name>;

If you're confused, no wonder. grid-area can be used in 2 different ways:

- a. Assign a name for the grid-template-areas property (see above example under grid container/grid-template-areas)
- b. Assign a name AND the dimensions for a grid-template-areas property. If you use this methodology, you would not necessarily need a grid-template-rows and grid-templatecolumns declaration, depending on other factors.

EXAMPLES:

```
.class1 {
    grid-area: 1 / name3 / namedline / 4;
}
```

justify-self: start | end | center | stretch;

Aligns content in a grid item on the row axis. Overrides justify-items.

align-self: start | end | center | stretch;

Aligns content in a grid item on the column axis. Overrides align-items.