

OBJECTIVE: SCORE
Manage basic networking: 100%
Understand and use essential tools: 10%
Operate running systems: 0%
Configure local storage: 25%
Create and configure file systems: 25%
Deploy, configure and maintain systems: 29%
Manage users and groups: 0%
Manage security: 0%
Manage containers: 0%
Create simple shell scripts: 0%

RHCSA

Kernel Description **Package** kernel Contains no files, but ensures other kernel packages are accurately installed kernel-core Includes a minimal number of modules to provide core functionality kernel-devel Includes support for building kernel modules kernel-modules Contains modules for common hardware devices kernel-modules-Contains modules for not-so-common hardware extra devices kernel-headers Includes files to support the interface between the kernel and userspace libraries and programs kernel-tools Includes tools to manipulate the kernel kernel-tools-libs | Includes the libraries to support the kernel tools

groupadd -o -g 5000 dba groupadd -o -g linuxadm useradd user1000 usermod -aG dba user1000 /etc/group /etc/passwd groupmod -n sysadm linuxadm groupmod -g 6000 sysadm groupdel sysadm /etc/group visudo

groupadd -g 6000 Inxgroup useradd -u 5000 -g 6000 user5000 passwd user5000 chage -m 4 -M 30 user5000 groupmod -g 4000 Inxgroup sudo groupmod -g 7000 1nxgrp

cat

cat

cat

When two groups have an identical GID, members of both groups get identical rights on each other's files.

Job scheduling and execution is taken care of by two service daemons: atd and crond.

While atd manages the jobs scheduled to run one time in the future, crond is responsible for running jobs repetitively at pre-specified times.

/var/spool/cron and /etc/cron.d directories

/etc directory for either service. These files are named at.allow and at.deny for the at service, and cron.allow and

cron.deny for the cron service.

Variable	Description
DISPLAY	Stores the hostname or IP address for graphical terminal sessions
HISTFILE	Defines the file for storing the history of executed commands
HISTSIZE	Defines the maximum size for the HISTFILE
HOME	Sets the home directory path
LOGNAME	Retains the login name
MAIL	Contains the path to the user mail directory
PATH	Defines a colon-separated list of directories to be searched when executing a command. A correct setting of this variable eliminates the need to specify the absolute path of a command to run it.
PPID	Holds the identifier number for the parent program
PS1	Defines the primary command prompt
PS2	Defines the secondary command prompt
PWD	Stores the current directory location
SHELL	Holds the absolute path to the primary shell file
TERM	Holds the terminal type value
UID	Holds the logged-in user's UID
USER	Retains the name of the logged-in user

dnf list installed kernel*

export and unset command. env/printenv will print env variables. command subs: \u@\h

- 1. Where does GRUB2 read its configuration from on a BIOS system?/boot/grub2/grub.cfg
- 2. How can the redhat-support-tool be used to search and display the same Knowledgebase content as on the Red Hat Customer Portal? Using the search command followed by keywords or error codes
- 3. How does file system metadata alignment impact the performance of striped arrays (RAID 0, RAID 4, RAID
- 5, RAID 6)? If the write request is wider than the strip size, I/O requests could require two writes per disk instead of one or having all metadata ends up on one disk, causing that disk to become a hot spot.
- 4. How does the spare area of SSDs impact their performance on random writes? improvement
- 5. How does data striping in RAID increase throughput?
- By dividing data into stripes and distributing them among several disks in the RAID array
- 6. What are the steps in a typical change management procedure for performance tuning changes? Set a baseline by running the test workload and gathering metrics. 2. Perform changes one at a time, measuring the effect after each change. 3. Verify the effectiveness of the change by rerunning the test workload. 4. Reverse the change and compare with the baseline. 5. Apply and document the definitive change.
- 7. What are the main ideas behind the USE Method in performance tuning?

Checking Utilization, Saturation, and Errors for user interactions

What is a drop-in file in systemd and how is it used to configure unit settings?

file in systemd that overrides or adds specific options for a unit, created by making a directory under /etc/systemd/system/ named after the unit with .d appended, and then creating .conf files in this directory. For example, enabling memory accounting for sshd.service can be done by creating a 20-accounting.conf file in the directory /etc/systemd/system/sshd.service.d/.

While the sticky bit is most commonly used with directories, it can also be set on files. On files, the sticky bit has an outdated and limited use. It was historically used to keep a file in memory after execution.

How can you enable CPU, memory, and block I/O accounting for a service or a slice in systemd?

Create a drop-in file under /etc/systemd/system/ with the desired unit or slice name and .d appended and include the CPUAccounting, MemoryAccounting, and BlockIOAccounting settings.

What are the advantages of using custom slices in systemd?

System resource granularity and distribution equality

```
chmod +t (add sticky bit) drwxrwxrwxt (t) at the end refers to sticky
chmod g-s /usr/bin/write -v (gid)
ncdu
sudo find / -type f -exec du -h {} + 2>/dev/null | sort -rh | head -20
sudo du -ah / 2>/dev/null | sort -rh | head -20
find /var/log -min -100 -exec file {} \;
find /usr -maxdepth -type d -name src
find /tmp -perm -u=r
find /tmp -type f -exec Is -Id {} \;
find /tmp -name *.txt -ok cp {} \;
locate .sh -n2
locate -S
setfacl -m u:user1:r a.txt
setfacl -dm u:user100:7,user200:rwx /tmp/prj
find /dev -type c -perm 660
useradd user1000
usermod -aG sgroup user1000
ps -efl
pidof rsyslogd
pgrep rsyslogd
ps -U user1
ps -G root
nice -n -10
renice 5 5572
can also renice from top command(type r and give pID)
cat /var/log/cron
```

*/1 * 1-10 3 * : Any day, in March, from 1 to 10th, every hour, every one minute.

Column	Description
UID	User ID or name of the process owner
PID	Process ID of the process
PPID	Process ID of the parent process
С	CPU utilization for the process
STIME	Process start date or time
TTY	The controlling terminal the process was started on. "Console" represents the system console and "?" represents a daemon process.
TIME	Aggregated execution time for a process
CMD	The command or program name

useradd user100 useradd user200 usermod -aG sgroup user100 usermod -aG sgroup user200 mkdir /sdir chmod g+s /sdir chmod o-t /tmp

tree -hapf uname -snovpr wc -l , -w, -c rpm -qa (list all packages) rpm -q perl (list perl packages)

rpm -qf /etc/passwd (see which package owns the file)

rpm -qf /etc/group

dnf install policycoreutils

dnf info policycoreutils

dnf deflist policycoreutils

rpm -qi setup

rpm sushi -ve (remove package)

rpm -qf /etc/chrony.conf (see where the package is coming from)

cd /tmp

 $rmp2cpio \ / mnt/baseos/package/chrony-3.3.e18.x86_64.rpm \ | \ cpio \ -imd$

rpm2cpio

find . -name chrony.conf 9

rpm -K /tmp/chrony.. –no-signature (Use the MD5 checksum for verifying its integrity and the GNU Privacy Guard (GnuPG or GPG) public key signature for ensuring the credibility of its developer or publisher. cp -r /tmp/chrony.. /etc/chrony

rpmkeys –import /etc/pki/rpm-gpg/rpm/gpg-key-redhat-release

rpmkeys -K /mnt/BaseOS/packages/zsh-3.3 (answer should be digests signatures ok)

rpm -q qpq-pubkey

rpm -qi <key> (view specific details)

rpm -Vf /etc/sysconfig

rpm -qi zlib

rpm -qa | sort

environment groups and package groups:

The <u>environment groups</u> available in RHEL 8 are server, server with GUI, minimal install, workstation, virtualization host, and custom operating system. These are listed on the software selection window during RHEL 8 installation. The <u>package groups</u> include container management, smart card support, security tools, system tools, network servers, etc. LOGS: /var/log/dnf.log

main configuration file for dnf is <u>/etc/dnf/dnf.conf</u> preferred configuration location <u>/etc/yum.repos.d</u> . **dnf runs rpm in the background.**

RHEL 8 is shipped with two core repositories called BaseOS and Application Stream (AppStream).

BOOTLOADING:

The firmware phase, the bootloader phase, the kernel phase, the initialisation phase.

[BaseOS_RHEL_8.0]
name= RHEL 8.0 base operating system components
baseurl=file:///mnt/BaseOS
enabled=1
gpgcheck=0

EXAM TIP: Knowing how to configure a dnf/yum repository using a URL plays an important role in completing some of the RHCSA exam tasks successfully. Use two forward slash characters (//) with the baseurl directive for an FTP, HTTP, or HTTPS source.

dnf module list (node.js, mariadb etc.)
dnf group list (security, monitoring vs)
dnf group info "system tools" (show content of group)
dnf group install "system tools"
dnf list installed
dnf repoquery cifs-utils
dnf list installed | grep cifs-utils
dnf check-update


creating a directory inside /dev is not advisable, because /dev is dynamically managed by the system and device nodes are created automatically. dnf repolist

Use the MD5 checksum for verifying its integrity and the GNU Privacy Guard (GnuPG or GPG) public key signature for

```
ensuring the credibility of its developer or publisher.
rpm -K /mnt/package/baseOS/zsh.3.3 —no-signature (checksum)
rpm -q gpg-pubkey (viewing keys)
rpm -qi <key> (view specific details)
rpm -Vf /etc/sysconfig (show package modification details)
chmod -v 644 /etc/sysconfig/atd (back to original state)
Is-IR
ls -lai | grep dir1
set -o noclobber
!! (repeat the last command)
!?grep? (repeat last command contains ls)
alias
Is -Id /etc/??? (prints all three letters folders)
Is /usr/bin/[g]* (all folders starting with g)
ls /usr/bin[a-c]* (folders between a and c]
Is /etc | less
grep operator /etc/passwd
grep -v nologin /etc/passwd (print lines that don't have nologin)
grep -n pattern /etc/passwd (print findings with number)
grep -w acce.. /etc/lvm/lvm.conf (prints lines including word acce.. (i.e accept, access)
VIM <x> will delete current cursor, :<4,6d> ill delete lines
:%s/word/word1 -> replace word with word1
sed -i "s/old/new/g" replace old with new inplace
touch will change timestamp of the file
grep -i path ~/.bashrc (in-case-sensitive search)
file system check
df -h (see mounted disks)
(disk should be not mounted)
umount /dev/sdb
vi test & (run in the background)
jobs (check jobs)
fg %1 (bring job to fg)
kill <pid> (kill job)
Is /cdr /usr > output 2>&1
top then r (renice)
at 12:13pm 3/7/25
> date &> date.out
>ctrl+d
```

at -I (list jobs)

crontables:



The system runs the /etc/profile first, followed by .bash profile, .bashrc, and finally the /etc/bashrc file.

mandb

man -k xfs

In addition to the manual pages, apropos, whatis, info, and pinfo commands as well as documentation located in the /usr/share/doc directory are also available on the system.

COMMANDS:

mkdir -p A/B/C

touch (will change mod time)

stat (will print brith, mod, access time)

find / -name passwd

find / -maxdepth 3

find . -user root

Is -I | head -20 >> files

chmod ugo+rwx file / cmod ugo-rwx file

echo "umask 027" >> ~/.bashrc (newly created files: 640, directories: 750)

cat > b (write your input)

tar cvf b.tar b a (compress)

tar tf (view)

tar xf (extract)

tar cvfz /root/com.gz /etc

grep -nr "pass" /etc/passwd > /mnt/pass

Is /etc/yum.repos.d

vi /etc/yum.repos.d/local.repo

ROOT PASSWORD

1. "e" on boot screen

- 2. after UUID section, "rd.break", before initrd. and type ctrl+x. on vm: rw init=/bin/bash
- 3. chroot /sysroot
- 4. pwd (should be /)
- 4. mount -o remount,rw /
- 5. passwd (will be given in exam)
- 6. touch /.autorelabel
- 7. exit
- 8. reboot

kernel and support files are stored at different locations in the directory hierarchy, f which three locations /boot, /proc and /usr/lib/modules. kernel files are vmlinuz, initramfs, config and system.map. kernel version appended to their names. efi and grub2 subdirectories under /boot hold bootloader information. grub.cfg and grubevn contain critical data such as bootable kernel information and environment information that the kernel uses.

/**proc** is a virtual memory-based file system. about processor, memory, storage, file systems, swap, processes, network interfaces, connections, routing. /proc/**cpuinfo && /proc/meminfo.** data from /proc is referenced from many system utilities: top, ps, uname, free, uptime.

Updating kernel:

by default dnf command adds new kernel to the system.

rpm -qa | grep kernel

go to rhel official page, look for kernel, download, move files to /tmp/, dnf install /tmp/kernel*, dnf list installed kernel*, reboot, choose the latest downloaded from grub menu

/proc/cmdline -> booting arguments.

location of efi: /boot/efi/efi

chroot: change root directory of a process. only process can access files

RAID(redundant array of independent disks)

stripe, mirror

/etc/default/grub

sudo grub2-mkconfig -o /boot/grub2/grub.cfg (after editing /etc/default/grub issue command and restart after) /etc/grub/ (script location)

/boot/grub/grub.cfg && /boot/grub/grubenv

chroot creates isolated environment for testing, changes root directory of a process.

making new kernel default boot kernel: grub2-mkconfig -o /boot/grub2/grub.cfg.

system initialisation and service management scheme: systemd

grub.cfg file stores the location information of th partition. chroot command changes the specified directory path to /.

uname -r , rpm -q kernel

You need to know how to boot a RHEL 8 system into a specific target from the GRUB2 menu

to modify the fstab file or reset an unknown root user password.

rd.break, chroot /, mount -o remount, rw /, passwd, touch .autorelabel, exit uname -snovmpr (m: architecture, r: kernel version)
IPTABLES

rule based firewall scans until it finds matches allow block specific IP addresses or ports powerful firewall built in linux

-

5. Initialisation, logging, system tuning

systemd remounts files once autofs finishes checks. d-bus is another communication method that allows multiple services running in parallel on a system to talk to one another. units are systemd objects used for organising boot and maintenance tasks.

sshd.service, syslog.socket, umount.target, tmp.mount

units in /run/systemd/system are created at boot and destroyed when no longer needed.

initialisation scripts: /etc/rc.d/init.d

/usr/lib/systemd/system/sshd.service (see unit, service, install)

Unit Type	Description
Automount	Offers automount capabilities for on-demand mounting of file systems
Device	Exposes kernel devices in systemd and may be used to implement device-based activation
Mount	Controls when and how to mount or unmount file systems.
Path	Activates a service when monitored files or directories are accessed
Scope	Manages foreign processes instead of starting them
Service	Starts, stops, restarts, or reloads service daemons and the processes they are made up of
Slice	May be used to group units, which manage system processes in a tree-like structure for resource management
Socket	Encapsulates local inter-process communication or network sockets for use by matching service units
Swap	Encapsulates swap partitions
Target	Defines logical grouping of units
Timer	Useful for triggering activation of other units based on timers

Table 12-1 systemd Unit Types

Target	Description
halt	Shuts down and halts the system
poweroff	Shuts down and powers off the system
shutdown	Shuts down the system
rescue	Single-user target for running administrative and recovery functions. All local file systems are mounted. Some essential services are started, but networking remains disabled.
emergency	Runs an emergency shell. The root file system is mounted in read-only mode; other file systems are not mounted. Networking and other services remain disabled.
multi-user	Multi-user target with full network support, but without GUI
graphical	Multi-user target with full network support and GUI
reboot	Shuts down and reboots the system
default	A special soft link that points to the default system boot target (multi-user.target or graphical.target)
hibernate	Puts the system into hibernation by saving the running state of the system on the hard disk and powering it off. When powered up, the system restores from its saved state rather than booting up.

Table 12-2 systemd Targets

Targets

Targets are simply logical collections of units. They are a special systemd unit type with the .target file extension. They are also stored in the same directory locations as the other unit configuration files. Targets are used to execute a series of units. This is typically true for booting the system to a desired operational run level with all the required services up and running. Some targets inherit services from other targets and add their own to them. systemd includes several predefined targets that are described in Table 12-2.

VIRTUALISATION

yum install qemu-kvm libvirt virt-install virt-manager

REPOSITORY CONFIGURATION

- 0. dnf install <copy given epel release url>
- 1. dnf repolist
- 2.

CONTAINER

- 0. container file will be given
- 1. dnf install podman
- 2. podman build -t demo .
- 3. podman images
- 4. podman -d run -p 8080:80 <image>
- 5.

tar cvf, tar xvf

touch command can be used with -d and -t to add sepcific date and time, a and m will enable you to change access and modification time. touch -d 2020-09-20 sec.txt .

touch -m command will reverse it to original time.

soft link can link directories hard linnk can not link directories .

Boot: BIOS-> Master Boot Record(MBR)->partition Table(PT)->Boot loader(Grub)->Kernel-> Mounting / /usr->/etc/inittab(default run level)->/etc/fstab

run levels:

run level 0 power off

run level 1: singleuser mode text mode

run level 2 multiusr text mode except NFS, NIS

run level 3: support all services including NFS and NIS(network information service) (default)

run level 4: unused

run level 5: multiuser graphical mode

User account information for local users is stored in four files that are located in the /etc directory. These files—passwd, shadow, group, and gshadow.

UIDs between 1 and 200 are used by Red Hat to statically assign them to core service accounts. UIDs between 201 and 999 are reserved for non-core service accounts, and UIDs 1000 and beyond are employed for normal user accounts.

cat /etc/login.defs head -3 /etc/passwd tail -3 /etc/passwd

usermod -l user2new -u 2000 -d /home/user2new -m -s /sbin/nologin user2000 useradd user4 -s /sbin/nologin echo redhat | passwd --stdin user4 vi /et

(nologin is when user does not need login access) userdel user3new grep user2new /etc/passwd

tuned-adm list tuned-adm active (check which profile is active) tuned-adm recommend tuned-adm profile virtual-quest

docker run --cap-add=SYS_TIME -it bb4496e662fb /bin/bash

dnf install chrony (NTP) dnf install -y procps

docker run --privileged -d --name systemd_container -v /sys/fs/cgroup:/sys/fs/cgroup:ro 5c79fba2bcae What is the default number of days files in /tmp are kept before they are automatically deleted if not accessed or modified?

uname -v or cat /proc/version10 days (apropos -a list directory apropos " list directory" / man -k ext4

The udev service (part of systemd-udevd) is responsible for creating device nodes dynamically at system startup.

Wayland has replaced the X Window System as the default display protocol in RHEL 8.

RHEL supports seven types of files: regular, directory, block special device, character special device, symbolic link, named pipe, and socket.

In original.txt hardlink.txt # Create a hard link
Is -li original.txt hardlink.txt # Check inode numbers(same in hardlinnk)

local.repo name=baseOS baseurl=https://xyz.server.com/baseOS gpgcheck=0 enabled=1

name=appStream baseurl=https://xyz.server.com/appStream gpgcheck=0 enabled=1

subscription-manager attach —auto
subscription-manager repos —list
subscription-manager repos —enable=rhel-9-for-x86_64-baseos-rpms
subscription-manager repos —enable=rhel-9-for-x86_64-appstream-rpms
dnf repolist
dnf clean all
dnf update
ping subscription.rhsm.redhat.com
sudo subscription-manager list —consumed
subscription-manager unregister
subscription-manager clean
subscription-manager register —username=<> —password=<>

These permission bits are set user identifier bit (commonly referred to as setuid or suid), set group identifier bit (a.k.a. setgid or sgid), and sticky bit.

The setuid and setgid bits may be defined on binary executable files to provide non-owners and non-group members the ability to run them with the privileges of the owner or the owning group, respectively. The setgid bit may also be set on shared directories for group collaboration. The sticky bit may be set on public directories for inhibiting file erasures by non-owners.

A common example is the su command that is owned by the root user. T

timedatectl set-ntp true

groupadd newgroup (should be listed in /etc/group) useradd harsh -G newgroup useradd nolog -s /sbin/nologin passwd nolog (set password to redhat) setfacl -m u:natasha:rw /var/fstab (m for modify) getfacl /var/fstab setfacl -m g:Mac:--- /var/fstab 4: read , 2: write 1 : execute chmod u-x testfile -v (verbose) chmod go+w testfile -v

chown :Mac /linux
groupadd blue
chgrp blue
chmod g+s . (now all the files will belong to group blue)
chmod +t (Sticky Bit: ensure only linux group can delete files)
chmod g-w, u+r testfile -v (from group remove writing, to user add read)
chmod -v u+s /usr/bin/su (adding user id to /usr/bin/su)

systematl not default on container env. should enable agroups while running:

(i. e. : docker run --privileged -d --name systemd_container -v /sys/fs/cgroup:/sys/fs/cgroup:ro centos:8 /usr/sbin/init)

DISK PARTITION:

Isblk (check devices)

fdisk /dev/sda2 (+1G for 1 GB partition, then n, p, w for write)

partprobe /dev/sda2

Isblk(check the newly created partition)

mkdir newdisk

mkfs.xfs /dev/sda2p1

mount /dev/sda2p1 /newdisk (not persistent yet)

vi /etc/fstab (write in the file: /dev/sdap1 /newdisk defaults 0 0)

mount -a

SWAP MANAGEMENT:

free -m

fdisk nvmep2 (from the input menu type:

0.(type letters, m for help)

- 1. n(new), p(primary), w(write)
- 2. partition number default
- 3. first sector: default
- 4. last sector: +750M

- 5. type: t 6. partitio 7. L (get 8. partpro
- 6. partition number: 3
- 7. L (get hex codes, 82 for linux swap) (change partition type to linux swap)
- 8. partprobe nvmep2 (will make changes permanent)
- 9. mkswap /dev/nvmep2
- 10. vi /etc/fstab (/dev/nvmep2 swap swap defaults 0 0)
- 11. swapon -a (if no error, check with free -m, see swap has has increased by 750Mb)

LVM: (create logical volume, give size, extend existing logical volumem)

- 1. Create Physical Volume (pv)
- 2. Create Volume Group (vg)
- 3. Create Logical Volume (Iv)

pvcreate nvme0v3

pvcreate nvme0v4

pvcreate nvme0v5

pvs (show)

vgcreate vgtest /dev/nvme0v3 nvme0v4 nvme0v5 (create volume groups)

vgs (show)

(linear, striped, mirrored volumes)

Ivcreate -L 8Gb -n Ivtest vgtest

lvs

vi /etc/fstab (/dev/vgtest/lg1/ /lv xfs defaults 0 0)

mkdir /lv

mkfs.xfs /dev/vgtest/lvtest

mount -a

LVM Extension:

vgs

lvextend -r -L +2Gb /dev/vg1/lv1

vgextend vg1 /dev/nvme0v5

vgs

lvremove /dev/vg1/lv1 (you'll get warning filesystem is in use)

vim /etc/fstab (comment vg1/lv1)

unmount /lv

lvchange -an /dev/vg1/lv1

lvremove /dev/vg1/lv1

lvs

vgremove vg1

vgs

vgcreate -s 8M vg1 /dev/nvme0v3

lvcreate -l 10 -n lv2 /dev/vg1 (creating 80M logic volume 10 times)

STRATIS:

blockdev:minsize 1 gb

pool (combined block devices to create pool)

filesytem(no fixed size for filesystem, automatically grows)

dnf install stratisd stratis-cli

systemctl start stratisd

systemctl enable stratisd

stratis pool create pool1 /dev/nvme0n5 (create pool)

stratis pool list

stratis pool add-data pool1 /dev/nvme0n4 (extend pool)

stratis filesystem create pool1 fs1 (create filesystem)

stratis filesystem list

stratis filesystem create pool1 fs2

stratis filesystem list

mkdir /fs1

vi /etc/fstab (copy UUID from filesystem list output /fs1 xfs defaults,x-system.requires=stratisd.service 0 0)

mount -a

VIRTUAL DATA OPTIMISER (VDO)-deprecated.

New one: lvmvdo:

compression, thin provisioning, deduplication

dnf install lvm2 kmod-kvdo vdo

vdo create --name vdo1 --device /dev/nvme0n2 --vdoLogicalSize=50G

vdo list

mkfs.xfs /dev/mapper/vdo1

mkdir /vdo1

vi /etc/fstab (/dev/mapper/vdo1 /vdo1 auto defaults,x-systemd.requires=vdo.service 0 0)

mount -a

man vdo

dnf module info postresgl:10

dnf module install -y postgresql:10

you can only have one module installed at a time.

CRON:

execute command /usr/local/bin/backup at 10:00 am on Feb 4th every year. crontab -e (0 10 4 2 * /usr/local/bin/backup)

configure cron job for a user jiu at 12:08 every Thursday execute /bash/echo hello crontab -u jiu -e (08 12 * * THU /bash/echo hello)

GREP:

grep -i "root" /etc/group

grep -i "sbin" /etc/passwd > /tmp/pass

CH ROOT PASSWD:
press "e" boot screen
put "rd.break" after word quiet -mount -o remount,rw /sysroot -chroot /sysroot -passwd
touch /.autorelabel -exit
reboot

NETWORKING/HOSTNAME

ip addr show ens160

nmcli con add con-name "Default" type ethernet ifname ens160

nmcli con show

nmcli con add con-name "Default1" type ethernet ifname ens160 ipv4 192.168.1.1/24 gw4 192.168.1.2

nmcli con up "Default1"

nmcli con show Default1

nmcli con mod "Default1" connection.autoconnect yes

nmcli con show Default1

nmcli con mod Default1 ipv4.addresses 192.168.2.2/16

nmcli con mod Default1 ipv4.dns 172.2.2.2

nmcli con mod Default1 ipv4.addresses 192.168.3.3/24 (multiple ip addresses can be added)

nmcli con add "Net" type ethernet ifname eth0 ipv4.addresses 200.0.0.12/16 gw4 20.0.0.1

nmcli con mod Net ipv4.dns 8.8.8.8

nmcli con show Net

nmcli con up Net

nmcli con add "net2" type ethernet ifname ens160 ipv4.addresses 172.24.5.10/24 gw4 172.24.5.48

nmtui (alternative to nmcli)

/etc/hostname

hostnamectl status

hostnamectl set-hostname server

SELINUX

touch /var/www/html

Is -ld /var

mkdir /new

touch /new/index.html

Is -Is /new/index

vi /etc/httpd/conf/httpd.conf (check DocumentRoot="/var/www/html"

vi /new/index "DocumentBoot "/var/www/html"

Is -IZ /var/www/html/index.html (httpd_sys_content_t) is the content

Is -IZ /new/index (default) is the content

<Directory "/new">
AllowOverride All

```
#Allow open access
  Require all granted
</Directory>
--> add above to /etc/httpd/conf/httpd.conf
SEMANAGE:
semanage fcontext -a -t httpd sys content t "/new(/.*)?"
restorecon -Rv /new
SElinux modes: disabled permissive(0) enforced(1)
aetenforce
setenforce 0 | 1
/etc/sysconfig/selinux (modify file to disable, reboot is required)
getsebool -a | grep httpd_enable (policy bool)
setsebool -P httpd enable homedirs on (-p flag permananent change)
selinux modes, booleans, context, port
httpd is able to access home dir: (getsebool | grep httpd_enable_homedirs)
system is not able to access httpd on port 82
semanage port -a -t http_port_t -p tcp 82 (systemctl restart httpd is required)
ensure httpd is able to access files at test directory.
PODMAN:
podman login registry.redhat.io (optional)
podman search httpd
podman pull docker.io/registry/httpd
podman rmi <image>
podman run -d --name httpd -p 8080:80 <imageID>
podman ps
curl localhost:8080 (outside the httpd container, see It works!)
podman stop <container>
podman rm <container>
podman run --d it <imageID> /bin/bash
podman exec -it <containerID> /bin/bash (inside the container check find . -name index.html see:
/usr/local/apache2/htdocs)
mkdir /web && touch /web/mypage.html && vi mypage.html (add some context)
podman run -d --name web1 -p 8080:80 -v /web:/usr/local/apache2/htdocs/:Z <imageid>
after mapping
semanage fcontext -a -t httpd_sys_content "/web(/.*)?"
restore con -Rv /web
curl localhost:8080/mypage.html
QUADLET
podman info --debug | grep "rootless"
systemctl --user enable podman-auto-update-timer
```

systemctl --user daemon-reload

/etc/containers/systemd/sleep.container [Unit] Description=A minimal container

[Container] Image=centos Exec=sleep 60

[Service] Restart=always

systemctl daemon-reload systemctl start sleep.service systemctl start sleep.service (auto restart once system rebooted) systemctl status sleep.service

Quadlet files to be stored in either: user: /usr/share/containers/systemd/ system wide: /etc/containers/systemd/

https://dokumen.pub/qdownload/rhcsa-red-hat-enterprise-linux-8-training-and-exam-preparation-guide-ex200.

FILESYSTEM: fsck.ext4 /dev/sda1 xfs-repair -L /dev/sda1

GROUP QUOTA:

mount -o remount, usrquota, grpquota /dev/sdb2/ /quota

/dev/sdb2 /quota ext4 ->/etc/fstab

SCHEDULING AND PROCESS ADMIN at 10:03am today > command ctrl+D atq

CPIO: occupies less space compared to tar. cpio -icvf -I /root/backup

FTP.

```
AUTOFS:
SERVER
dnf install -y nfs* nfs-utils autofs
mkdir /share
touch /share/f1 /share/f2
chmod 777 /share
/share <clientIP>(ro,sync) >> /etc/exports
exportfs -avr
firewall-cmd --add-service={nfs,mountd,rpc-bind} --permanent
firewall-cmd --reload
```

CLIENT -in exam responsibility only client partdnf install nfs-utils autofs
showmount -r <clientIP>
/auto_mount /etc/auto_misc --timeout=60 >> /etc/auto.master
access --rw,soft,intr <serverIP>:/share >> /etc/auto.misc
systemctl enable autofs --now (after this command /auto_mount or /afs directory should be created)
cd auto_mount && cd access && Is (should see files f1 and f2)

SHELL

if [\$? -eq 0]; then echo "succesfull exit"

\$0 -> script's name

\$1 -> firstarg

\$# -> number of args

SSH

systemctl status sshd

firewall-cmd --zone=public --permanent --add-service=ssh

A list of the users who have successfully signed on to the system with valid credentials can be printed using one of the two basic Linux tools: who and w.

last

last user1000

last root

lastb

lastlog

id

id user1000

groups user1000

Service accounts take care of their respective services, which include apache, ftp, mail, and chrony.

3 main: networking | storage | manage groups

find -mmin -300 -exec file {} \;

find / -type p -o -type s 2>/dev/null find /usr -atime -100 -size -5M -user root setfacl -x u:user2000 /tmp/testfile

in vi %s/tes/fes/ sed -i 's/globe/earth/g'

/etc/nologin.txt (custom no login test if -s /sbin/nologin is defined when creating useradd user5 -s /sbin/nologin)

useradd -D default login settings

useradd -D -s /bin/sh -b /custom/home: this would set the default shell to /bin/sh and home directory to /custom/home for all future users.

Name the four local user authentication files. /etc/passwd, /etc/group, /etc/shadow, /etc/gshadow The who command in Linux consults the /var/run/utmp file to display information about currently logged-in users.

/var/log/wtmp: Keeps a history of all logins and logouts.

/var/log/btmp: Logs failed login attempts.

/etc/shadow- is the backup for /etc/shadow

/etc/nologin is a special file in Linux. When it exists, it prevents all non-root users from logging into the system.

who, w, id, groups

The lastlog command in Linux displays the most recent login information of all system users.

password aging is a secure mechanism to control user passwords in Linux

PACKAGES

rpm -q vsftpd

rpm -q createrepo

rpm -qf /bin/bash : Queries which installed RPM package provides the file /bin/bash.

NFS Server:

yum install nfs*

(remote server)

vi /etc/exports -> /remote 192.168.11.8(rw, sync)

exportfs

(on the client)

ifconfig -a (check IP can reach to remote server

show mount -2 192.168.11.7

mount -t nfs 192.168.11.7:/remote /nfs (change IP of client to 11.7 if it does not mount)

service network restart

df -h (check mount)

vi /etc/fstab -> 192.168.11.7:/remote /nfs defaults 0 0

vum list autofs

vi /etc/auto.master

vi /etc/auto.misc -> ram -fstype:nfs 192.168.11.7 (config for mount point)

SAMBA Server(device and file share across heterogenous OSes.

Ports: 137(name), 138(datagram), 139(session)

vi /etc/samba/smb.conf

cd /etc/samba && grep "log" *

service smb restart

(on the client)

smbclient -L //182.168.11.7/ -N

(exercise: secure shared shares in samba server)(disable printer sharing)

DHCP server:

PORTS: 67-bootp, 68-dhcp

yum install dhcp -y

cd /usr/share/doc/dhcp_server

cp dhcpd.conf.example /etc/dhcpd/dhcpd.conf

vi /etc/dhcpd.conf (edit subnet and range according to IP)

service dhcpd start

NETWORK INFORMATION SERVICE a.k.a YellowPages (NIS)

DNS RECORDS

CNAME. <u>files.example.org</u> alias hostname

A RECORD IP address of the domain. maps hostname to IPv4 address to be saved in icann.net

MX RECORD maps domain name to mailexchange server. host can have multiple MX

PTR RECORD maps ipv4 to the canonical name for the host. adds 192.168.1.10.in-addr.arpa (reverse address)

NS record maps domain name to list of DNS servers authoritative for that domain.

named-checkconf /etc/named.conf

named-checkconf /etc/rfc1912.zones

named-checkzone example.com example.for

named-checkzone 192.168.1.11.in-addr.arpa

APACHE:

port: 80

yum install http*

Additionally, certain configuration options have been deprecated or removed in recent BIND 9 releases. For instance, the auto-dnssec configuration statement was removed, and users are advised to use dnssec-policy or manual signing instead.

BIND 9 Documentation

It's advisable to consult the release notes of the specific BIND version you're using to stay informed about any changes to configuration options.

yum install system-config-kickstarter system-config-kickstart(will bring gui)

add

root password

installation method: ftp: server 192.168.10.7, ftp: directory: pub partition info: add 10GB mount boot filetype ext4,add swap 2048

network config: eth0: dhcp.

authentication: keep default settings

firewall: SElinux disabled

installation:

vmlinuz initrd.initrd.img repo=ftp://192.168.10.7/

Basic sendmail (deprecated)
yum install sendmail*
vi /etc/mail/sendmail.mc (nothing to be added)
make -C /etc/mail
vi /etc/mail/sendmail.mc
service sendmail start
service sendmail status
sendmail -v -s "Test Email" user@server.example.org

POSTFIX:

dnf remove sendmail dnf install postfix dnf install chkconfig chkconfig postfix off systemctl status postfix vi postfix.sh ... vi /etc/rc.local -> /root/postfix.sh LVM

redirection umask 022 chmod ugo tar xvf gz chmod g-s /usr/bin/write -v (gid)

TARGETS:

Subcommand	Description
daemon-reload	Re-reads and reloads all unit configuration files and recreates the entire user dependency tree.
enable (disable)	Activates (deactivates) a unit for autostart at system boot
get-default (set-default)	Shows (sets) the default boot target
get-property (set-property)	Returns (sets) the value of a property
is-active	Checks whether a unit is running
is-enabled	Displays whether a unit is set to autostart at system boot
is-failed	Checks whether a unit is in the failed state
isolate	Changes the running state of a system
kill	Terminates all processes for a unit
list- dependencies	Lists dependency tree for a unit
list-sockets	Lists units of type socket
list-unit-files	Lists installed unit files
list-units	Lists known units. This is the default behavior when systemctl is executed without any arguments.
mask (unmask)	Prohibits (permits) auto and manual activation of a unit to avoid potential conflict
reload	Forces a running unit to re-read its configuration file. This action does not change the PID of the running unit.
restart	Stops a running unit and restarts it
show	Shows unit properties
start (stop)	Starts (stops) a unit
status	Presents the unit status information

Table 12-3 systemctl Subcommands

systemctl list-unit-files systemctl –failed systemctl status atd systemctl -t target (list all targets)

systematl list-dependencies multi-user.target (list dependencies for multi-user target)

systemctl isolate multi-user (systemctl isolate command is used to change the current system's state by **isolating a specific target**)

SYSLOG: rsyslogd modern systems: journalctl

/var/log are the default location where the log files are stored. rsyslog service is modular, allowing modules listed in its configuration file to be dynamically loaded in the kernel as and when needed. each module brings new functionality to the system upon loading. **systemctl start/stop/status rsyslog**

/etc/rsyslog.conf : configuration file. Rules section has selectors(left) and action(right), facility(left) and priority(right).

rsyslogd logs messages based on priorities: emerg, alert, crit, error, warning, notice, info, debug. it will keep for target level and higher levels.

/var/log/messages | /var/log/boot | Is -I /var/log

files under /var/log can be filled very quickly. To prevent this a script called logrotate under /etc/cron.daily invokes the *logrotate* command. /etc/logrotate.conf

– each time a log file is rotated, an empty replacement file is created with the date as a suffix to its name, and logging restarted. services have each different logrotate configuration. /etc/logrotate.d/***script has option for postrotate (such as gzip) the log files. latest system messages: /var/log/messages (tail -f). It is helpful to tail the messages file when starting or restarting the service.

```
Mar 13 13:16:01 vbox systemd[1]: session-233.scope: Deactivated successfully.

Mar 13 13:17:01 vbox systemd[1]: Started Session 234 of User root.

Mar 13 13:17:18 vbox systemd[1]: session-234.scope: Deactivated successfully.

Mar 13 13:17:18 vbox systemd[1]: Starting Hostname Service...

Mar 13 13:17:18 vbox systemd[1]: Started Hostname Service:

Mar 13 13:17:48 vbox systemd[1]: systemd-hostnamed.service: Deactivated successfully.

Mar 13 13:17:55 vbox systemd[1]: Starting Hostname Service...

Mar 13 13:17:55 vbox systemd[1]: Started Hostname Service.

Mar 13 13:18:01 vbox systemd[1]: Started Session 235 of User root.

Mar 13 13:18:01 vbox systemd[1]: session-235.scope: Deactivated successfully.

Mar 13 13:18:25 vbox systemd[1]: systemd-hostnamed.service: Deactivated successfully.

[root@vbox "]# cat /var/log/messages

[0] 0:bash- 1:user2 2:user1 3:root*
```

iournalctl:

addition to rsyslog, systemd implements logging service for the collection of logs. this is implemented via **systemd-journald** daemon. *journalctl* command will print messages. **journalctl -o verbose**, **journalctl -b** (from last systemboot). -0: since the last system boot, -1: since previous system boot, -2: since two previous system boot.

```
journalctl -kb0 (only kernel generated alerts since last reboot)
journalctl -n5 (list only last 5 lines)
journalctl /usr/sbin/crond (see logs generated by crond)
journalctl _SYSTEMD_UNIT=sshd.service
journalctl _PID=$(pgrep chronyd) / journalctl _PID=$(pgrep sshd)
```

journalctl –since 2019-10-10 –until 2019-10-16 -p err journalctl –since today -p warning -r

journalctl -f (real time viewing, same as tail -f, logger to send messages to journal, "write root/user" to print msg on other logged in users)

logs are stored in /run/log/journal and its transient. options: volatile(stores in memory only), persistent(permanent under /var/log/journal), auto(similar to persistent but does not create /var/log/journal), none(disables both volatile and persistent storage, not recommended). file is rotated once a month. settings at /etc/systemd/journald.conf.

/etc/machine-id : where the system's machine ID is kept.

SYSTEM TUNING:

tuned: monitor storage, networking, audio, video and a variety of other connected devices. adjust parameters for better performance. there are several predefined tuning profiles, that may be activated statically or dynamically. for example during large file transfer network connection use increases. 9 profiles default, can create custom and save it under **/etc/tuned.** predefined profiles at **/usr/lib/tuned.** profile management: tuned-adm **(tuned-adm list)**

systemctl –now enable tuned (will stick tuned service to auto-start)
tuned-adm profile virtual-guest | tuned-adm active | tuned-adm recommend | tuned-adm off

Profile	Description		
Profiles (Optimized for Better Performance		
Desktop	Based on the balanced profile for desktop systems. Offers improved throughput for interactive applications.		
Latency- performance	For low-latency requirements		
Network-latency	Based on the latency-performance for faster network throughput		
Network- throughput	Based on the throughput-performance profile for maximum network throughput		
Virtual-guest	Optimized for virtual machines		
Virtual-host	Optimized for virtualized hosts		
Profile	Profiles Optimized for Power Saving		
Powersave	Saves maximum power at the cost of performance		
Balanced/Max Profiles			
Balanced	Preferred choice for systems that require a balance between performance and power saving		
Throughput- performance	Provides maximum performance and consumes maximum power		

Table 12-5 Tuning Profiles

systemctl set-default graphical-target systemctl get-default

Master Boot Record vs. GUID Partition | VDO | MBR Disk | GPT Disk data is stored on disks that are logically divided into partitions.

VDO: newer storage management solutions capitalize on thin provisioning, deduplication and compression to conserve storage space and improve data throughput.

a disk is stored on the disk in a small region, which is read by the operating system at boot time. region is referred to <u>as MBR on the BIOS</u>, and <u>GUID Partition Table(GPT)</u> on <u>UEFI</u>. store disk partition information and <u>the boot code</u>.

- MSDOS (MBR) and GPT are the two most common partition schemes in use today.
- Apple Partition Map (APM) was used in older Macs.
- · BSD Disklabel is used primarily by BSD-based operating systems.
- · LVM provides flexible disk management and works on top of MBR or GPT.
- Solaris Partition Table was used by older versions of Solaris before GPT.
- RAID is a technology for combining multiple disks but isn't a partitioning scheme in itself.
- · BIOS Boot Partition is part of GPT and needed for BIOS-based booting.
- Logical Partitions are a feature within MBR, allowing more than four partitions on a disk.

storage management tools: parted, gdisk, vdo, lvm, stratis.

parted is a simple tool that understands both MBR and GPT formats. **gdisk** is designed to support the GPT format only, it may be used as replacement of parted. **VDO** is a disk optimizer software that takes advantage of certain technologies to minimize the overall data footprint on storage devices. **LVM** is a feature rich logical volume management solution that gives flexibility in storage management. **Stratis** capitalizes on thin provisioning to create volumes much larger in size than the underlying storage options.

thin provisioning(lvm): economical allocation and utilisation of storage space by moving arbitrary data blocks to contiguous locations. i.e LVM, VDO, Stratis can create *thin pool* space and assign volumes much larger than the physical capacity of the pool. When a preset custom threshold(i.e 80%) on the actual consumption of the storage is reached, expand the pool dynamically by adding more storage. after creating the partition, /proc/partitions is also updated. repair: journalctl -xb, xfs_repair, smartctl -a /dev/sda

add 100mb.vdi: /dev/sdb

Subcommand	Description
print	Displays the partition table that includes disk geometry and partition number, start and end, size, type, file system type, and relevant flags.
mklabel	Applies a label to the disk. Common labels are gpt and msdos.
mkpart	Makes a new partition
name	Assigns a name to a partition
rm	Removes the specified partition

Table 13-1 Common parted Subcommands

parted provides commands for viewing, labeling, adding, naming and deleting partitions.

sudo parted /dev/sdb print (see unrecognised label, disk must be labelled before usage) sudo parted /dev/sdb mklabel msdos sudo parted /dev/sdc mklabel gpt sudo parted /dev/sdb print (see label) sudo parted /dev/sdb mkpart primary 1 50m sudo parted /dev/sdc mkpart primary 1 50m sudo parted /dev/sdd mkpart pri 1 200m sudo parted /dev/sdd rm 1 (will delete partition)

gdisk utility partitions disks using the gpt format. gdisk can create up to 128 partitions on a single disk on systems with UEFI firmware.

sudo **gdisk** /dev/sdd o: delete all partitions p: print partitions(1, n: new partition(+20M) w: write changes to disk d1: delete partition

write root (will start message sharing)

VDO

- 1. making use of the thin provisioning technology to identify and eliminate empty(zero-byte) data blocks, referred as *zero-block elimination*. removing randomization of data blocks by moving in-use data blocks to contiguous locations on the storage device -
- 2. keeping an eye on the data being written on the disk. If data is redundant vdo skips writing.(kernel module: universal deduplication service).
- 3. kvdo compresses the residual data blocks and distributes them on a lower number of blocks.

vdo runs in the background and processes inbound data through the three stages on vdo-enabled volumes. vdo is not cpu/memory intensive process, consuming a low amount of resources.

vdo can be initialised just like disk partitions or they can be used as lvm physical modules.

Subcommand	Description
create	Adds a new VDO volume on the specified block device
status	Returns the status and attributes of VDO volumes
list	Lists the names of all started VDO volumes
start	Starts a VDO volume
stop	Stops a VDO volume

Table 13-2 vdo Subcommands

dnf install vdo kmod-kvdo -y systemctl –now enable vdo systemctl status vdo systemctl list-units –type=service | grep vdo modprobe vdo (if vdo is not loaded on kernel)

vdi is not treated as raw storage. vdi adds an extra layer. but, vdo should contact directly with the storage. Linux-based VMs, you can create a **logical volume** (LV) with LVM and then use VDO on top of it. This allows VDO to manage storage optimization directly on the block device. raw block devices(VirtIO, SCSI)

vdo create –name vdo-vol1 –device /dev/sdc –vdoLogicalSize16G –vdoSlabSize 120 vdo list | vdostats –hu | vdostats –verbose | vdo status –name vdo-vol1 vdo remove –name vdo-vol1

exam vm will have no outside connection. refer to the manual pages and the documentation under /usr/share/doc directory.

hostnamectl set-hostname rhcsa2.example nmcli con mod enp0s3 *ipv4.addresses* 192.168.0.242/24 nmcli con mod enp0s3 *ipv4.gateway* 192.168.0.1 nmcli con mod enp0s3 *ipv4.dns* 192.168.0.1 nmcli con *down* enp0s3 && nmcli con *up* enp0s3 && nmcli con *show* enp0s3

useradd -u 9000 -c "this is user90" -e \$(date -d "+4 days" + %Y-%m-%d) user90 useradd -m -s /sbin/nologin user50 (create user with no login) passwd -l user90 (lock user90 fro logging)

setfacl -m u:user10:rw /tmp/file setfacl -d -m u:user10 /tmp

mkdir -p /dev/dvdrom mount /dev/cdrom /dev/dvdrom vi /etc/fstab (/dev/cdrom /dev/dvdrom iso9660 defaults 0 0)


vi /etc/yum.repos.d/rhel9-local.repo

[rhel9-local]
name=RHEL 9 Local Repo
baseurl=file:///mnt/dvdrom/AppStream/
enabled=1
gpgcheck=1
gpgkey=file:///mnt/dvdrom/RPM-GPG-KEY-redhat-release

PHYSICAL VOLUMES, VOLUME GROUPS AND LOGICAL VOLUMES

Volume Groups (VGs) are part of the Logical Volume Manager (LVM), which provides a flexible and dynamic

way to manage disk storage. Here are the primary use cases for Volume Groups:



Space taken from one or more physical volumes is combined to form a volume group

Figure 14-1 LVM Structure

sudo **pvs** sudo **vgs** sudo **vgdisplay** (see PE: physical extent, LE: logical extent)

logical extent can be smaller or larger than the physical extent.

sudo Ivdisplay

sudo gdisk /dev/sdc (n, +10m, w)

sudo parted /dev/sdb set 1 lvm on

sudo parted /dev/sdd set 1 lvm on

sudo parted /dev/sdd set 2 lvm on

sudo parted /dev/sdc set 2 lvm on

sudo vgcreate -vs 1 vgnew /dev/sdd2

sudo vgcreate -vs 1 vgnew2 /dev/sdc2 (add sdc2 to vgnew2)

sudo pvcreate /dev/sdc1

sudo vgcreate vg100 –physicalextentsize 16M /dev/sdc1 (by default PE is 4MB)

sudo lvcreate -n lv100 -L 10M vg100

sudo lvremove /dev/vg100/lv100

sudo vgremove /dev/vg100

sudo pvcreate /dev/sdd1 (initialize pv)

sudo pvcreate /dev/sdb1

sudo pvs -v

sudo pvdisplay /dev/sdc1

sudo vgextend vgnew /dev/sdb1 (will add sdb1 to vg(rhel))

sudo vgextend vgnew2 /dev/sdc1

sudo vgs (show actual virtual group)

sudo vgdisplay -v vgnew

sudo lvcreate -l 1 -n lvnew vgnew

sudo lvcreate -l 1 -n lvnew2 vgnew2

sudo lvs

sudo lvdisplay /dev/vgnew/lvnew

sudo lvextend -L +10m /dev/vgnew/lvnew

sudo Ivrename vgnew Ivnew Ivneww

sudo lvreduce -L 5m /dev/vgnew/lvneww

sudo lvresize -L 2m /dev/vgnew/lvneww

sudo pvmove /dev/sdc2 /dev/sdc3 (to another allocation in same vg)

sudo vgreduce vgnew2 /dev/sdc2 (before removal /dev/sdc2 data should be moved)

sudo pvremove /dev/sdc2

Command	Description	
Cre	ate and Remove Operations	
pvcreate/pvremove	Initializes/uninitializes a disk or partition for LVM use	
vgcreate/vgremove	Creates/removes a volume group	
lvcreate/lvremove	Creates/removes a logical volume	
Ext	end and Reduce Operations	
vgextend/vgreduce	Adds/removes a physical volume to/from a volume group	
lvextend/lvreduce	Extends/reduces the size of a logical volume	
lvresize	Resizes a logical volume. With the -r option, this command calls the resize2fs command and resizes the underlying file system as well. Applies to Ext2/Ext3/Ext4 file system types only.	
Rename Operations		
vgrename	Renames a volume group	
lvrename	Renames a logical volume	
List and Display Operations		
pvs/pvdisplay	Lists/displays physical volume information	
vgs/vgdisplay	Lists/displays volume group information	
lvs/lvdisplay	Lists/displays logical volume information	


Table 14-1 Common LVM Operations and Commands

sudo parted /dev/sdc set 1 lvm on (should update the flags part, see with print) sudo pvcreate /dev/sdd1 /dev/sda -v (initialisation) sudo vgcreate -vs -16 vgbook /dev/sdd1 /dev/sda sudo vgdisplay -v vgbook sudo pvdisplay /dev/sdd1

lv(pvcreate, vgcreate, lvcreate) and then apply vdo.

STRATIS(storage pool):

stratis capitalizes three matured storage comp: **device mapper(dm)**, kernel driver, the lvm solution and the xfs file system.



Space taken from one or more disks or partitions is combined to form a pool

Figure 14-2 Stratis Structure

actual size grows with data stored. startis handles everything automatically so nothing should be manually configured.

Command	Description
pool	Administers storage pools. Subcommands are available to list, create, rename, expand, and destroy a pool.
blockdev	Lists block devices
filesystem	Administers file systems within storage pools. Subcommands are available to list, create, rename, and destroy a file system.

For each pool created, stratis creates a subdirectory under the /stratis directory. then creates symbolik link for each file system under the directory and keep actual files in /dev directory. **min disk size: 2gb for Stratis2.0**

stratis pool create poolnew /dev/sdb

stratis pool list

stratis blockdev list poolnew

stratis pool add-data poolnew /dev/sde

stratis filesystem create poolnew fsnew

stratis filesystem list

stratis filesystem destroy poolnew fsnew (remove fs from pool)

stratis pool rename poolnew poolneww

stratis pool destroy poolneww (remove pool)

stratis filesystem list (confirm removal)

mkdir /newfs mount /stratis/newpool/newfs /newfs umount /newfs lsblk

LVM and Stratis can exist on the same system as long as they manage different partitions.

Stratis typically manages pools of storage, while LVM works with volume groups and logical volumes.

FILESYSTEMS

logical container that stored files and directories. Each file system is created with a discrete partition, vdo volume, logical volume or stratis pool. production RHEL has / and /boot during installation, additionally other file systems created during boot are: /home, /opt, /tmp, /usr, /var.

RHEL supports three basic groups: disk-based, network-based, memory-based.

disk-based: SATA, USB, Fibre and other, network: shared, memory: virtual.

EXT is divided into two: first is the metadata(inode, permission, ownership, access/creation times), second is the actual data.

XFS high performing 64bit extent based journaling file system type. it does not run file system checks at system boot, relies on the user to use *xfs_repair*. Only caveat to use is that XFS's inability to shrink. XFS uses *sophisticated techniques in its architecture for speedy input/output performance*. *It can be snapshot in a mounted active state, and then be used for backup or other(migration) purposes.*

VFAT: FAT16, introduced early versions of ms-dos.

ISO9660: optical disc media(cd/dvd), originally high-sierra file system(hsfs)

Command	Description
	Extended File System
e2label	Modifies the label of a file system
mke2fs	Creates a file system. Can also be invoked as mkfs.ext3, mkfs.ext4, mkfs -t ext3, and mkfs -t ext4.
resize2fs	Resizes a file system. This command is automatically invoked when the lvresize command is run with the -r switch.
tune2fs	Tunes or displays file system attributes
	XFS
mkfs.xfs	Creates a file system. Can also be invoked as mkfs - t xfs.
xfs_admin	Tunes file system attributes
xfs_growfs	Extends the size of a file system
xfs_info	Exhibits information about a file system
	VFAT
mkfs.vfat	Creates a file system. It is equivalent to using mkfs -t vfat.
	General File System Commands
blkid	Displays block device attributes including their UUIDs and labels
df	Reports file system utilization
du	Calculates disk usage of directories and file systems
Isblk	Lists block devices and file systems and their attributes including their UUIDs and labels
mount	Mounts a file system for user access. Displays currently mounted file systems.
umount	Unmounts a file system

Table 15-2 File System Management Commands

mount -t xfs (getting information on the xfs file system)

mount command requires sudo and absolute path. mount point should be empty. after mount, the kernel places an entry on the /proc/self/mounts. (file structure is similar to /etc/fstab). remount is used to enable/disable an option.-

Option	Description
acl (noacl)	Enables (disables) the support for ACLs
auto (noauto)	Mounts (does not mount) the file system when the - a option is specified
defaults	Mounts a file system with all the default values (async, auto, rw, etc.)
_netdev	Used for a file system that requires network connectivity in place before it can be mounted. VDO and NFS are examples.
remount	Remounts an already mounted file system to enable or disable an option
ro (rw)	Mounts a file system read-only (read/write)

UUID: xfs-admin -u /dev/sda1 / tune2fs (ext4) blkid (all)

- UUID which is assigned to the file system remains persistent across system reboots.
- RHEL attempts to mount all file systems that are listed in /etc/fstab over its UUID or label.
- with the unmount kernel removes the corresponding file system entry from /proc/self/mounts. monitoring disk: df -h (usage information) du -sh (amount of space a file or directory occupies)

-T to add the file system type to the output (example: **df** -

hT)

-x to exclude the specified file system type from the

output (example: df -hx tmpfs)

-t to limit the output to a specific file system type

(example: df -t xfs)

-i to show inode information (example: df -hi)

Labelling:

xfs-admin -l /dev/sda1 , lsblk -f /dev/sda1 (to view label)

to create a label target must be unmounted.

umount /boot

xfs admin -L bootfs /dev/sda1

mount /boot

e2label for ext filesystem, label is not recommended for VDO and LVM volumes. It is self-managed.

/etc/fstab file needs only one of four: block device, uuid, label, mount point. any missing or invalid entry may make the system unbootable, and should be booted in emergency mode to fix the file. find the line start with linux and add: systemd.unit=emergency.target

1: path or UUID 2: mount-point(/, /boot, none, swap) 3: filesystem: Ext4, XFS, VFAT, ISO9660, swap 4: comma-seperated options(defaults) 5: dump-check(0: disables) 6: sequence number runs e2fsck(repair utility) 0 for memory-based, remote and removable filesystems, 1 for /, and 2 for /boot and other physical systems. only valid for Ext.

UUID /boot xfs defaults 0 0

EX15.1

parted /dev/sdb mklabel msdos parted /dev/sdb mkpart primary 1 20m parted /dev/sdb mkpart primary 21 40m mkfs -t ext4 /dev/sdb1 mkfs -t vfat /dev/sdb2 parted /dev/sdb print mkfs.xfs /dev/sdd -f (parititon > 300mb, -f fore removal of old partition) lsblk -f /dev/sdb /dev/sdb >> /etc/fstab (determine UUID) organise fstab after mkdir /ext4fs1 /vfatfs1 /xfsfs1 mount -a systemctl daemon-reload df -hT 15.2 EXT with VDO 15.3 XFS with LVM parted /dev/sde mklabel gpt parted /dev/sde mkpart primary 1 160m pvcreate /dev/sde1 vgcreate -s 16 vgfs /dev/sde1

Ivcreate -n ext4vol -L 20 vgfs

Ivcreate -n xfsvol -L 20 vgfs

mkfs.ext4 /dev/vgfs/ext4vol

mkfs.xfs /dev/vgfs/xfsvol -f

Isblk -f /dev/sde >> /etc/fstab

mkdir /ext4fs2 /xfsfs2

mount -a

df -hT | grep fs2

15.4 Resize Ext4 and XFS

pvcreate /dev/sde2

vgextend vgfs /dev/sde2

vgdisplay vgfs (check pv count:2)

lvextend -L +10m /dev/vgfs/ext4vol (adds 10m to ext4vol)

lvdisplay /dev/vgfs/ext4vol

Ivextend -L +10m /dev/vgfs/xfsvol (adds 10m/one extent(16m) to xfsvol)

Ivdisplay /dev/vgfs/xfsvol

lvresize -r -L +10m /dev/vgfs/xfsvol

lvresize -r -L +10m /dev/vgfs/ext4vol

15.5 Create, Mount, Expand with Stratis

stratis pool create /dev/sdf

stratis pool list

stratis blockdev list strpool

stratis filesystem create strpool strfs2

stratis filesystem list (UUID can be found)

lsblk /dev/stratis/strpool/strfs2 -o UUID (or such)

>/etc/fstab

/strfs2 xfs "UUID" x-systemd.requires=stratisd.service 0 0

mkdir /strfs2

mount -a

stratis pool add-data strpool /dev/sdg (add new pv to stratis pool)

SWAP

an independent region on the physical disk used for holding idle data until it is needed. Physical memory is split into small chunks: pages and maps their physical location to virtual locations on swap. Mapping

information is stored in the *page table*, maintained by the kernel. Paging data out and in is known as demand paging. Excessive amount of paging causes system degradation called *thrashing*. When trashing begins, the system deactivates new processes to launch until the system reaches the threshold value back. Swap may be twice or larger than the physical memory or smaller. *free -ht*

mkswap: create swapon: activate swapoff: deactivate swapon -s: list

15.6 Create and Activate Swap

parted /dev/sdb mkpart primary 1 80
parted /dev/sdb mkpart primary 80 160
parted /dev/sdb mkpart primary 160 240
vgcreate vgfs /dev/sdb1
lvcreate -n swapvol -L 80
mkswap /dev/vgfs/swapvol
mkswap /dev/sdb2
swapon -a
swapon
free -ht

[tm@vbox ~]]\$ free -ht		,	, ,	, <u> </u>	,,, , <u>-</u>
	total	used	free	shared	buff/cache	available
Mem:	1.7Gi	1.2Gi	76Mi	20Mi	637Mi	543Mi
Swap:	2.1Gi	0B	2.1Gi			
Total:	3.8Gi	1.2Gi	2.2Gi			

Isblk -f >> /etc/fstab

UUID="<>" swap swap pri=1 0 0
/dev/vgfs/swapvol swap swap pri=2 0 0
cat /proc/swaps

[tm@vbox ~]\$ cat /proc/swaps Filename Size Used Priority /dev/dm-1 partition 2097148 Θ -2 /dev/sdb3 partition 59388 Θ /dev/dm-2 40956 0 partition

cat /proc/mounts

rhel99_1.vdi	399,66 MB	2,00 MB
rhel99_2.vhd	399,66 MB	3,00 KB
rhel99_3.vmdk	399,66 MB	64,00 KB
rhel99_4.vdi	399,66 MB	2,00 MB

VMDK (VMware Virtual Machine Disk):

VMware uses a specific format for its virtual disks, and one key component of a VMDK file is the
way it stores metadata for the virtual disk. The 64KB file size you're referring to is often related
to the block size or the minimum allocation for a virtual disk in VMware. VMware may reserve
small blocks of space in the virtual disk for things like metadata, snapshots, and disk
management. Thus, a VMDK file might show up as 64KB, even if the actual disk content is
smaller.

VHD (Virtual Hard Disk - used by Hyper-V):

 VHD files are also formatted in a way that has space reserved for disk management structures and metadata. The 3KB "real" size you mentioned may be the actual size of the metadata block or the overhead associated with tracking the virtual disk's state.

VDI (VirtualBox Disk Image):

Similarly, VirtualBox's VDI format has a slightly larger size (2MB real size) because of the way it
organizes blocks and metadata. VirtualBox manages virtual disks in a way that can result in
some overhead storage for file system structures, although it's typically more efficient in terms
of block size compared to VMware or Hyper-V.

15.1 Create VFAT, Ext4, XFS File Systems in partitions and mount persistently

```
FSVER LABEL UUID
                                                                                       FSAVAIL FSUSE% MOUNTPOINTS
da
-sda1
                  xfs
                                              0cdd878c-ed88-4631-9ed7-1df8a52c91c6
                                                                                        610.4M
                                                                                                   36% /boot
 sda2
                  LVM2_member LVM2 001
                                              3KsWDq-77cJ-CIpv-SsST-FcJ6-x1If-h1ubyJ
  -rhel_vbox-root xfs
                                              e1fd8d5c-58a0-49ce-bad7-2fee1450483a
                                                                                         12.2G
                                                                                                   28% /
   rhel_vbox-swap swap
                                              a22b1e7b-52d6-42fb-bc94-c65c20f00f83
db
-sdb1
                  vfat
                               FAT16
                                               782A-1688
                                                                                         74.8M
                                                                                                    0% /vfatfs5
sdb2
                                                                                         60.4M
                  ext4
                               1.0
                                              db7ee7fa-d24e-4d6d-8622-59c0322a0d1a
                                                                                                   0% /ext4fs5
 -sdb3
                  xfs
                                              c090dd64-208d-49af-b62d-60adae8fef51
                                                                                         65.2M
                                                                                                    6% /xfsfs5
```

```
[root@vbox tm]# df -h
Filesystem
                              Size
                                    Used Avail Use% Mounted on
devtmpfs
                              4.0M
                                        Θ
                                           4.0M
                                                  0% /dev
tmpfs
                              888M
                                        Θ
                                           888M
                                                  0% /dev/shm
                                           350M
tmpfs
                              355M
                                    5.7M
                                                   2% /run
/dev/mapper/rhel_vbox-root
                               17G
                                    4.8G
                                            13G
                                                 28% /
/dev/sda1
                                                  37% /boot
                              960M
                                    350M
                                           611M
tmpfs
                              178M
                                     96K
                                           178M
                                                  1% /run/user/1000
/dev/sdb1
                               75M
                                        0
                                            75M
                                                  0% /vfatfs5
/dev/sdb2
                                     14K
                                            61M
                                                   1% /ext4fs5
                               66M
dev/sdb3
                               70M
                                    4.5M
                                            66M
                                                   7% /xfsfs5
```

15.2 Create XFS in VDO volume and mount persistently

sudo subscription-manager repos --enable=rhel-9-for-x86 64-baseos-rpms

--enable=rhel-9-for-x86_64-appstream-rpms

vdo create —name=vdo5 —device=/dev/sdc —size=1G —slab_size=1M vdostatus vdostats mkfs.xfs /dev/mapper/vdo5 mkdir /vdofs5 nlkid /dev/mappers/vdo5 UUID="<>" /vdofs5 xfs defaults,_netdev 0 0 umount /vdofs5 mount -a df -h

15.3 Create ext4 and xfs in lvm pvcreate /dev/sdc vgcreate vg20 /dev/sdc lvcreate -L 120M -n lv200 vg20 lvcreate -L 100M -n lv100 vg20 mkfs.ext4 /dev/vg20/lv200 mkfs.ext4 /dev/vg20/lv300 mkdir /lvmfs5 /lvmfs6 mount /dev/vg20/lv200 /lvmfs5 mount /dev/vg20/lv300 /lvmfs6 blkid /dev/vg20/lv300 >> /etc/fstab blkid /dev/vg20/lv300 >> /etc/fstab umount /lvmfs5 /lvmfs6 mount -a df -h

[rooc@vbox cm]# di −n					
Filesystem	Size	Used	Avail	Use%	Mounted on
devtmpfs	4.0M	0	4.0M	0%	/dev
tmpfs	888M	0	888M	0%	/dev/shm
tmpfs	355M	5.7M	350M	2%	/run
/dev/mapper/rhel_vbox-root	17G	4.8G	13G	28%	/
/dev/sdal	960M	350M	611M	37%	/boot
tmpfs	178M	96K	178M	1%	/run/user/1000
/dev/sdb1	75M	0	75M	0%	/vfatfs5
/dev/sdb2	66M	14K	61M	1%	/ext4fs5
/dev/sdb3	70M	4.5M	66M	7%	/xfsfs5
/dev/mapper/vg20-lv200	107M	14K	99M	1%	/lvmfs5
/dev/mapper/vg20-lv300	95M	6.0M	89M	7%	/lvmfs6

15.4 Extend ext4 and xfs in lvm

pvcreate /dev/sdd

vgextend vg20 /dev/sdd lvextend -L +80m /dev/vg20/lv200 (additional) lvextend -L 300m /dev/vg20/lv300 (final) /etc/fstab modification is not necessary

```
[root@vbox tm]# lsblk
NAME
                  MAJ:MIN RM
                               SIZE RO TYPE MOUNTPOINTS
sda
                                20G 0 disk
 -sda1
                                1G 0 part /boot
                               19G 0 part
  sda2
                    8:2
  rhel_vbox-root 253:0
rhel_vbox-swap 253:1
                              17G 0 lvm
                               2G 0 lvm
sdb
                          0 312.2M 0 disk
                    8:16
 -sdb1
                          0 75M 0 part /vfatfs5
 -sdb2
                    8:18
                               76M 0 part /ext4fs5
 -sdb3
                                    0 part /xfsfs5
                          0 399.7M 0 disk
sdc
                    8:32
 -vg20-lv200
                  253:2
                          0 320M 0 lvm /lvmfs5
  vg20-lv300
                              300M
                                    0 l∨m
                                           /lvmfs6
sdd
                    8:48 0 399.7M 0 disk
 -vg20-lv200
                           0 320M 0 lvm /lvmfs5
                  253:2
  vg20-lv300
                  253:3
                          0 300M 0 lvm /lvmfs6
                    8:64
                          0 399.7M
                                    0 disk
sdf
                    8:80
                          0 399.7M 0 disk
sr0
                   11:0
                           1 1024M 0 rom
```

15.5 create xfs in stratis volume stratis pool create strpool5 /dev/sdg stratis filesystem create strfs5 stratis pool list stratis filesystem list mkdir /strfs5 mkfs.xfs /dev/stratis/strpool5/strfs5 mount /dev/stratis/strpool5/strfs5 /strfs5 blkid /dev/stratis/strpool5/strfs5 >> /etc/fstab

15.6 create swap in partition and lvm volume and activate persistently

parted /dev/sde mklabel msdos parted /dev/sde mkpart primary 1 100 parted /dev/sde mkpart primary 101 200 mkswap /dev/sde1 -L swapp1 lsblk -f /dev/sde >> /fstab

swapon -a && swapon -s

pvcreate /dev/sde2 vgextend vg20 /dev/sde2 lvcreate -L 80m -n swapvol vg20 mkswap /dev/vg20/swapvol mkswap /dev/sde2 lsblk -f /dev/sde2 >> fstab (none swap defaults 0 0) swapon -a && swapon -s



Remote File System

- network file system service(mount/unmount)
- autofs

multiple nfs clients can access single share simultaneously

supports linux, unix, windows.

enables sharing of common application binaries, read-only information, reducing administration overhead and storage cost.

consolidation of scattered user home directories.

nfsv4 uses usernames and group names instead of UID and GIDs.

4.0, 4.1-> TCP, 4.2-> UDP

ex16.1 export share on nfs

(on server2) dnf install -y nfs-utils mkdir /common chmod 755 /common firewall-cmd –permane

firewall-cmd -permanent -add-service nfs

firewall-cmd -reload

systemctl status nfs-server && systemctl start nfs-server

/common 192.168.0.110(rw) >> /etc/exports

exportfs -av

exportfs -u 192.168.0.110:/common (unexport)

16.2 mount share on nfs

(on server1)
dnf install -y nfs-utils
mkdir /local
mount 192.168.0.120:/common /local
192.168.0.120:/common /local nfs _netdev 0 0 >> /etc/fstab
mount | grep local
df -h
umount /local
mount -a

touch /local/nfsfile (on srv1) ls -l /common (on srv2)

AutoFS

autofs is a client side service.autofs mounts share automatically, it's not accessed over time. mounts need no entry in /etc/fstab while using autofs. /etc/autofs.conf.

autofs requires nfs shares be defined in config files called maps, located in /etc or /etc/auto.master.d. autofs does not need root privileges .

autofs map types: master, direct, indirect.

/etc/auto.master.d/auto.direct is automatically parsed at startup. /etc/auto.misc: indirect direct mounted shares are always visible to users. /etc/mtab maintains a list of all mounted file systems.

ex16.3 access NFS using direct map

dnf install -y autofs
mkdir /autodir
/- /etc/auto.master.d/auto.dir >> /etc/auto.master
/autodir 192.168.0.120:/common >> /etc/auto.master/auto.dir
systemctl enable –now autofs
systemctl status –autofs -l –no-pager
ls /autodir

Indirect Map: is preferred over direct map if all of the shares are mounted under one common parent directory. local and indirect shares cannot coexist under the same parent directory.

ex16.4 access NFS using indirect map

autoindir 192.168.0.120:/common >> /etc/auto.misc systemctl enable –now autofs systemctl status autofs -l –no-pager ls /misc/autoindir

*:references to specific mount points

&: references to specific mount points

* -rw &:/home/& >> /etc/auto.master.d/auto.home

with this no need to update autoFS config files. user30 can find its home directory in both servers.

ex16.5 automount user home using indirect map

(server2)
useradd -u 3000 user30
echo pass30 | passwd –stdin user30
/home 192.168.0.110(rw) >> /etc/exports
exportfs -avr

(server1)

dnf install -y autofs

useradd -u 3000 -Mb /nfshome user30 echo pass30 | passwd –stdin user30 mkdir /nfshome

/nfshome /etc/auto.master.d/auto.home >> /etc/auto.master

* -rw 192.168.0.120:/home/user30 (for multiple user setup, replace user30 with &, ensure all users exist in both systems with same name and id)

systemctl enable autofs –now

systemctl status autofs -l -no-pager

su - user30 & pwd/ls

user is successfully logged in with their home directory automounted from the NFS server. (mount | grep user30)

17. Networking

nmcli device status
ip route show
journalctl -xe | grep network
hostnamectl set-hostname server1
nmcli con mod enp0s3 ipv4.addresses 10.0.4.2/24
nmcli con mod enp0s3 ipv4.dns 10.0.4.1

public: A(16m nodes(0-127), B 64k nodes(128-191), C 254 nodes(192-223))

private: D(multicast), E(experimental)

all nodes in a given subnet have same mask, each subnet acts as isolated network and requires router to talk

other subnets.

protocols: /etc/protocols

well known ports: /etc/service

ipv6 packet size: 1280 bytes, ipv4 packet size: 576 bytes

network (NIC) can have multiple connection profiles, but only one profile is active at a time.

/etc/sysconfig/network-scripts/enp0s3

Directive	Description
BOOTPROTO	Defines the boot protocol to be used. Common values include dhcp to obtain IP assignments from a DHCP server and none or static to use a static IP as set with the IPADDR directive.
BROWSER_ONLY	Works if PROXY_METHOD is set to auto. Default is no.
DEFROUTE	Whether to use this connection as the default route
DEVICE	Specifies the device name for the network interface
DNS1	Defines the IP address or the hostname of the first DNS server. This address/hostname is placed in the /etc/resolv.conf file if the PEERDNS directive is set to no in this file.
GATEWAY	Specifies the gateway address for the connection if the BOOTPROTO directive is set to none or static
HWADDR	Describes the hardware address for the device
IPADDR	Specifies the static IP for the connection if the BOOTPROTO directive is set to none or static
IPV4_FAILURE_FATAL	Whether to disable the device if IPv4 configuration fails. Default is no.
IPV6INIT	Whether to enable IPv6 support for this connection
NAME	Any description given to this connection. The default matches the device name.
NETMASK	Sets the netmask address for the connection if the BOOTPROTO directive is set to none or static
NM_CONTROLLED	Whether the NetworkManager service is to be allowed to modify the configuration for this connection. It should be turned off on computers that use static IP addresses. Default is yes.
ONBOOT	Whether to auto-activate this connection at system boot
PEERDNS	Whether to modify the DNS client resolver

man nm-settings

	file /etc/resolv.conf.Default is yes if BOOTPROTO is set to dhcp.
PREFIX	Defines the number of subnet bits. This directive may be used in lieu of NETMASK.
PROXY_METHOD	Method to be used for proxy setting. Default is no.
UUID	The UUID associated with this connection
TYPE	Specifies the type of this connection

Table 17-2 Network Connection Configuration Directives

17.3 manual interface configuration

settings: enable network adapter-> internal network. (establishes new enp0s8) *vi /etc/sysconfig/network-script/enp0s8*

```
"/etc/sysconfig/network-scripts/ifcfg-enp0s8" [New] 11L, 166B written
[root@server1 ~]# cat /etc/sysconfig/network-scripts/ifcfg-enp0s8
TYPE=Ethernet
BOOTPROTO=static
DEFROUTE=yes
IPV4_FAILURE_FATAL=no
IPV6INIT=no
NAME=enp0s8
DEVICE=enp0s8
ONBOOT=yes
IPADDR=172.10.10.110
PREFIX=24
GATEWAY=172.10.10.1
```

ifup enp0s8 / nmcli con up enp0s8

Object	Description		
Connection: activates, deactivates, and administers network connections			
show	Lists connections		
up / down	Activates/deactivates a connection		
add	Adds a connection		
edit	Edits an existing connection or adds a new one		
modify	Modifies one or more properties of a connection		
delete	Deletes a connection		
reload	Instructs NetworkManager to re-read all connection profiles		
load	Instructs NetworkManager to re-read a connection profile		
Device: displays and administers network interfaces			
status	Exhibits device status		
show	Displays detailed information about all or the specified interface		

17.4 nmcli interface configuration

nmcli con show nmcli dev show nmcli con add type Ethernet ifname enp0s8 con-name enp0s8 ipv4 172.10.10.120/24 gw4 172.10.10.1 cat /etc/sysconfig/network-scripts/ifcfg-enp0s8 (old-fashion)

cat /etc/NetworkManager/system-connections

ip a nmcli c down enp0s8 nmcli c up enp0s8 nmcli c s

/etc/hosts

192.168.0.110 server1.example.com server1 192.168.0.120 server2.example.com server2 172.10.10.119 server1p0s8.example.com server1s8 172.10.10.120 server2p0s8.example.com server2s8 ping 192.168.0.120 -c 2 ping -c2 server2 ping -c1 server2s8

nmcli con add type Ethernet ifname enp0s8 con-name enp0s8 ipv4 172.10.10.100/24 gw4 172.10.10.1 nmcli con add type Ethernet ifname enp0s8 con-name enp0s8 ipv4 172.10.10.200/24 gw4 172.10.10.1 /etc/hosts

172.10.10.100 server1.example.com server1 172.10.10.200 server2.example.com server2

Chrony

new implementation of network time protocol. port 123. response time efficiency carries the highest importance. /etc/chrony.conf
dnf install -y chrony
cat /etc/chrony.conf | grep ntp (check for the pool info)
systemctl enable chronyd –now
hwclock –systhoc
hwclock –show
chronyc sources
dig <srv>

server <NTP-server> >> /etc/chrony.conf timedatectl set-timezone CET timedatectl set-ntp true

Geolookup: curl https://ipinfo.io/<srv>




Figure 18-2 Sample DNS Hierarchy

dns roles: primary, secondary or client.

Keyword	Meaning	Default Action
success	Information found in source and provided to the requester	return (do not try the next source)
notfound	Information not found in source	continue (try the next source)
unavail	Source down or not responding; service disabled or not configured	continue (try the next source)
tryagain	Source busy, retry later	continue (try the next source)

dig -X <ip> (reverse lookup) host redhat.com host -v <ip> getent hosts redhat.com

OPENSSH

symmetric / asymmetric : secret / public key encryption

GSSAPI based auth - with Kerberos

Host-bases auth- ~/.shosts

priv/pub key based

challenge resp

pass based - checks /etc/passwd

RSA: Rivest-Shamir Adleman, DSA: Digital Signature Algorithm, ECDAS: Elliptic Curve Digital Signature.

client: /etc/ssh/ssh_config server: /etc/ssh/sshd_config

ssh-copy-id: copy public key to remote servers /var/log/secure : logs related to authentication

Directive	Description
Port	Specifies the port number to listen on. Default is 22.
Protocol	Specifies the default protocol version to use.
ListenAddress	Sets the local addresses the sshd service should listen on. Default is to listen on all local addresses.
SyslogFacility	Defines the facility code to be used when logging messages to the /var/log/secure file. This is based on the configuration in the /etc/rsyslog.conf file. Default is AUTHPRIV.
LogLevel	Identifies the level of criticality for the messages to be logged. Default is INFO.
PermitRootLogin	Allows or disallows the root user to log in directly to the system. Default is yes.
PubKeyAuthentication	Enables or disables public key- based authentication. Default is yes.
AuthorizedKeysFile	Sets the name and location of the file containing a user's authorized keys. Default is ~/.ssh/authorized_keys.
PasswordAuthentication	Enables or disables local password authentication. Default is yes.
PermitEmptyPasswords	Allows or disallows the use of null passwords. Default is no.
ChallengeResponseAuthentication	Enables or disables challenge- response authentication mechanism. Default is yes.
UsePAM	Enables or disables user authentication via PAM. If enabled, only root will be able to run the sshd daemon. Default is yes.

ssh-keygen -N "" -q ssh-copy-id server2 ssh-copy-id i ~/.ssh/id_rsa.pub user2@server2 (more specific) scp server2:/tmp/test .

rsync -avz (copies only updated files, -a option to preserve all file attributes, -v to use verbosity, z: compression, -P: show progression)

firewall: secure inbound and outbound traffic flow. /usr/lib/firewalld directory. /etc/firewalld /etc/services: common ports

packet classification: *nftables*.

network connection can be part of one zone at a time. a zone can have multiple network connections assigned to it. zone configuration may include ports, protocols that may be open or closed. firewalld makes inspection for each package, applies package to that zone, if nothing applies then to default zone.

Zone	Description
trusted	Allow all incoming
internal	Reject all incoming traffic except for what is allowed. Intended for use on internal networks.
home	Reject all incoming traffic except for what is allowed. Intended for use in homes.
work	Reject all incoming traffic except for what is allowed. Intended for use at workplaces.
dmz	Reject all incoming traffic except for what is allowed. Intended for use in publicly-accessible demilitarized zones.
external	Reject all incoming traffic except for what is allowed. Outgoing IPv4 traffic forwarded through this zone is masqueraded to look like it originated from the IPv4 address of an outgoing network interface. Intended for use on external networks with masquerading enabled.
public	Reject all incoming traffic except for what is allowed. It is the default zone for any newly added network interfaces. Intended for us in public places.
block	Reject all incoming traffic with icmp-host-prohibited message returned. Intended for use in secure places.
drop	Drop all incoming traffic without responding with ICMP errors. Intended for use in highly secure places.

Table 20-1 firewalld Default Zones

/usr/lib/firewalld/zones -> /etc/firewalld/zones

20.1 Add Services, Port and Manage Zones

firewall-cmd -get-default-zone

firewall-cmd -permanent -add-service http

firewall-cmd -reload

firewall-cmd -list-services

cat /etc/firewalld/zones/public.xml | grep http

firewall-cmd -add-port 443/tcp

firewall-cmd –list-ports

firewall-cmd –add-port 5901-5910/tcp –permanent –zone internal

cat /etc/firewalld/zones/internal.xml

firewall-cmd -set-default-zone internal

firewall-cmd -reload

firewall-cmd –list-ports

firewall-cmd –remove-port 5901-5910/tcp –permanent

firewall-cmd -remove-service ssh

firewall-cmd -add-service ssh

nft list ruleset

SELINUX

subject: system u for Selinux system user, unconfined u: subjects that are not bound by Selinux.

object: resource(file, dir, hardware, device, network interface/connection, port, pipe socket.

access: action performed by subject on an object.

policy: defined ruleset (targeted(confined domain) / mls(tight security / minimum(light security)

user cannot run su or sudo for programs that are located in their home dir if they are mapped to the selinux user $user_u$

seinfo -u semanage port -l

domain transitioning: allowing a process to enter another domain to execute an application taht is restricted to run in that domain only. entrypoint: control processes that can transition into another domain.

Is -IZ /usr/bin/passwd (see passed has passwd_exec_t type) but passwd has to access /etc/shadow file with type shadow t. this happens via selinux.

booleans; /sys/fs/selinux/booleans (setsebool, getseebool) restorecon

/etc/selinux/config. use permissive while debugging. see status with sestatus, /etc/sestatus.conf

Command	Description		
Mode Management			
getenforce	Displays the current mode of operation		
sestatus	Shows SELinux runtime status and Boolean values		
setenforce	Switches the operating mode between enforcing and permissive temporarily		
	Context Management		
chcon	Changes context on files (changes do not survive file system relabeling)		
restorecon	Restores default contexts on files by referencing the files in the /etc/selinux/targeted/contexts/files directory		
semanage	Changes context on files with the fcontext subcommand (changes survive file system relabeling)		
	Policy Management		
seinfo	Provides information on policy components		
semanage	Manages policy database		
sesearch	Searches rules in the policy database		
Boolean Management			
getsebool	Displays Booleans and their current settings		
setsebool	Modifies Boolean values temporarily, or in the policy database		
semanage	Modifies Boolean values in the policy database with the boolean subcommand		
Troubleshooting			
sealert	The graphical troubleshooting tool		

Table 21-1 SELinux Management Commands

21.1
mkdir sedir && touch sedir/sefile
chcon -vu user_u -t public_content_t sedir -R
21.2

```
will add entry into: /etc/selinux/targeted/contexts/files/file context.local
 validate : semanage fcontext -Cl
 chcon -vu staff u -t etc t sedir -R
 restorecon -Rv sedir
 21.3 Adding non-standard network port(8010) to http
 semanage port -at http port t -p tcp 8010
 semanage port -l | grep http
 any non-standard port should be added to selinux policy database with correct type.
 21.4 context preservation
 preserving context: cp /tmp/sefile /etc/default -preserve-context (see user tmp t is preserved)
 21.5 toggle selinux values
 getsebool -a | grep nfs export all rw
 sestatus -b | grep nfs export all rw
 semanage boolean -l | grep nfs_export_all_rw (will see "on")
 setsebool -P nfs_export_all_rw off (-P for persistent)
 semanage boolean -l | grep nfs_export_all_rw (will see "off")
 selinux alert> /var/log/audit/audit.log (when mode is enforcing and permissive)
 sealert -a /var/log/audit/audit.log (will log any failed attempts such as changing passwd)
 21.2 resursive labelling
 semanage fcontext -CI /tmp/dir1
 semanage fcontext -a -t etc t "/tmp/dir1(/.*)?"
 restorecon -Rv /tmp/dir1
 21.3
 semanage port -a -t http_port_t -p tcp 9001
 semanage port -l | grep 9001
 21.5
 sestatus ssh_use_tcpd
 getsebool -a | grep ssh use tcpd
 setsebool -P ssh_use_tcpd off
Glossary:
```

semanage fcontext -a -s user u -t public content t '/tmp/sedir(/.*)?'

block: collection of bytes of data transmitted as a single unit.

block device file: file associated with devices that transfer data randomly in blocks(disk).

chrony: implementation of Network Time Protocol for time synchronization on network devices.

CIDR: classless inter domain routing

DAC(SELinux): Discretionary Access Control(set of traditional access controls)

De-deplication: removal of redundant data blocks De-encapsulation: Reverse of encapsulation

Defunct process: zombie process firewalld: a dynamic firewall manager

firewalld zone: a method of segregating incoming network traffic

globbing: regex

GPG: Gnu privacy guard. open source implementation of PGP(pretty good privacy).

host table: maintains UP and hostname mappings.

index node: hold's file properties: permissions, size, creation/modification time pointer to the data blocks that is stored.

IPC: inter-process comm(data sharing, synchronization, resource sharing). Types: Pipes, message queue, shared memory, semaphores, sockets, signals, remote procedure calls.

job: process started in the background

journaled file system: file system that uses the journaling mechanism for a swift recovery after crash.

kerberos: authentication over unsecure networks.

logical extent: a unit of space allocation for logical volumes in lvm logical volume: logical container in lvm that holds a file system or swap

masquerading: SNAT

mbr(master boot record): small region that stores disk partition information.

named group: specific group that receives ACLs.

named pipe: two unrelated process (on a same/separate system) exchange data.

named user: specific user that receives ACLs.

NDP: neighbor discovery protocol

nftables: packet classification framework to monitor network traffic.

octal mode: method for setting permissions on a file or directory using octal numbering system.

on-demand activation: systemd way of activation of a service when needed.

orphan process: alive child process of a terminated parent process.

package integrity: complete and error-free package

paging: process of transferring data between memory and swap space.

pam: :pluggable authentication module

pattern matching: regex. metachars: chars that have special meaning for machines.

public key encryption: asymmetric encryption.

forward proxy: content filtering, anonymity, internet access behind firewalld (shodowsocks, squid, privoxy, tor, proxychains)

reverse proxy: load balancing, ssl termination, security caching

sticky bit: disable non-owners to delete files.

symmetric encryption technique: technique that employs secret key for private communication between two network entities.

target: logical collection of systemd units. all units within a target are treated as a single entity.

unit: systemd object to organize service startups, socket creation etc.

thin pool: pool of storage allows to create volumes larger than actual size.

thin provisioning: economical technique of storage allocation and utilization.

trashing: excessive amount of paging.

udevd: dynamic device management service

vfat: virtual file allocation table

wayland: superior networking protocol that has replaced the x window system.

workload: any application that runs on the system.

zero-block elimination: technique removing empty data blocks from storage.

hardware-assisted virtı	ualization will have eithe	er the vmx (Intel) or s v	vm (AMD) flags in the /	proc/cpuinfo.