Module Interface Specification for ANN (Artificial Neural Network)

Tanya Djavehrpour

March 19, 2024

1 Revision History

Date	Version	Notes
March 19	1.0	Initial Draft

2 Symbols, Abbreviations and Acronyms

See SRS Documentation Djavaherpour (2024b) at HERE.

Contents

1	Revision History	i					
2	Symbols, Abbreviations and Acronyms ii						
3	Introduction 1 Notation 1						
4							
5	Module Decomposition	2					
6	MIS of ANN Control Module	4					
	6.1 Module	4 4 4 4 4 4					
	6.4.2 Environment Variables	4 4 5 5					
7	MIS of Saved ANN Model Module	6					
	7.1 Module	6 6 6 6 6 6 6					
	7.4.3 Assumptions	6 6 7					
8	MIS of Output Module	8					
	8.1 Module	8 8 8 8					
	8.3.2 Exported Access Programs	8					

	8.4	Seman	${ m tics}$														8
		8.4.1	State Variables														8
		8.4.2	Environment Variables														8
		8.4.3	Assumptions														8
		8.4.4	Access Routine Semantics					 									8
		8.4.5	Local Functions	•												•	9
9	MIS	of In	put Classifier Module														10
	9.1	-	le														10
	9.2																10
	9.3	Syntax	x														10
		9.3.1	Exported Constants														10
		9.3.2	Exported Access Programs														10
	9.4	Seman	-														10
		9.4.1	State Variables														10
		9.4.2	Environment Variables														10
		9.4.3	Assumptions														10
		9.4.4	Access Routine Semantics														11
10	N 410	СТ															10
10			put Image Module														12
			le														12
																	12
	10.3		K														12
			Exported Constants														12
	10.4		Exported Access Programs														12
	10.4		ntics														12
			State Variables														12
			Environment Variables														12
			Assumptions														12
			Access Routine Semantics														13
		10.4.5	Local Functions	٠	•	 ٠	 •	 •	 •	•	•	•	 •	٠	٠	•	13
11	MIS	of Tr	aining Model Module														14
	11.1	Modul	le														14
	11.2	Uses															14
	11.3	Syntax	x														14
		11.3.1	Exported Constants														14
		11.3.2	Exported Access Programs	3.													14
	11.4	Seman	${ m atics}$														14
		11.4.1	State Variables														14
			Environment Variables														14
		11.4.3	Assumptions														14
			Access Routine Semantics														14

		11.4.5 Local Functions	15
12	Inpu	at Preparing and Preprocessing Module	16
	12.1	Module	16
			16
	12.3	Syntax	16
		·	16
		12.3.2 Exported Access Programs	16
	12.4		16
			16
		12.4.2 Environment Variables	16
			16
		•	16
			17
13	Data	a Preparing and Preprocessing Module	18
	13.1	$Module \dots \dots$	18
	13.2	Uses	18
	13.3	Syntax	18
		13.3.1 Exported Constants	18
		13.3.2 Exported Access Programs	18
	13.4	Semantics	18
		13.4.1 State Variables	18
		13.4.2 Environment Variables	18
		13.4.3 Assumptions	19
		13.4.4 Access Routine Semantics	19
		13.4.5 Local Functions	19
		8 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4	21
			21
			21
	14.3	· ·	21
		1	21
			21
	14.4		21
			21
			21
		±	21
		14.4.4 Access Routine Semantics	22
		14.4.5 Local Functions	22

3 Introduction

The following document details the Module Interface Specifications for ANN (Artificial Neural Network). This document specifies how every module is interfacing with every other parts.

Complementary documents include the System Requirement Specifications (SRS) Djavaherpour (2024b) and Module Guide (MG) Djavaherpour (2024a). The full documentation and implementation can be found at Github repository for ANN.

Notation 4

The structure of the MIS for modules comes from Hoffman and Strooper (1995), with the addition that template modules have been adapted from Ghezzi et al. (2003). The mathematical notation comes from Chapter 3 of Hoffman and Strooper (1995). For instance, the symbol := is used for a multiple assignment statement and conditional rules follow the form $\Rightarrow r_1|c_2 \Rightarrow r_2|...|c_n \Rightarrow r_n).$ The following table summarizes the primitive data types used by NN. $(c_1 \Rightarrow r_1 | c_2 \Rightarrow r_2 | \dots | c_n \Rightarrow r_n).$

	Data Type	Notation	Description
	1D array	\mathbf{A}_i	A linear sequence of elements
<i>.</i>	2D matrix	${f M}_{ij}$	A collection of elements arranged in rows and columns
This is to show the subscript M is the material of the subscript M is the material of the subscript M is the subscript M i	3D matrix	\mathbf{M}_{ijk}	A structure composed of elements arranged in a grid with three dimensions
chow the.	boolean	bool	True or False
2 / m / - 10 mg	string	str	A sequence of characters
Mazille	character	char	a single symbol or digit
the subscript	integer	\mathbb{Z}	a number without a fractional component in $(-\infty, \infty)$
M os the	positive Integer	\mathbf{Z}_{+}	a number without a fractional component in $(0, \infty)$
watux	natural number	N	a number without a fractional component in $[1, \infty)$
W :	real	\mathbb{R}	any number in $(-\infty, \infty)$

The specification of ANN uses some derived data types: sequences, strings, and tuples. Sequences are lists filled with elements of the same data type. Strings are sequences of characters. Tuples contain a list of values, potentially of different types. In addition, ANN uses functions, which are defined by the data types of their inputs and outputs. Local functions are described by giving their type signature followed by their specification.

1

5 Module Decomposition

The following table is taken directly from the Module Guide $\frac{Djavaherpour}{2024a}$ document for this project.

Level 1	Level 2
Hardware-Hiding	
Behaviour-Hiding	ANN Control Module Saved ANN Model Module Output Module Input Classifier Module Input Image Module Training Model Module
Software Decision	Input Preparing and Preprocessing Module Data Preparing and Preprocessing Module Training and Testing Module

Table 1: Module Hierarchy

6 MIS of ANN Control Module

6.1 Module

main

6.2 Uses

- Hardware-Hiding Module
- Saved ANN Model Module (7)
- Output Module (8)

6.3 Syntax

6.3.1 Exported Constants

None.

6.3.2 Exported Access Programs

Name	In	Out	Exceptions
main	-	-	-

6.4 Semantics

6.4.1 State Variables

None.

6.4.2 Environment Variables

None.

6.4.3 Assumptions

- The ANN Control Module assumes that the Hardware-Hiding Module, Saved ANN Model Module, and Output Module are implemented according to their specifications. However, it does include error handling to manage unexpected behaviors or failures in these modules.
- The system environment (operating system, hardware) is assumed to be stable. Also, essential libraries and dependencies are presumed to be correctly installed and configured.

6.4.4 Access Routine Semantics

main():

• transition: Initializes the program.

Somer else line what some sa a coordinator between different te or producing output :

Note: As the ANN Control Module mainly serves as a coordinator between different modules without maintaining its own state or producing output, its primary function is to ensure the correct sequence of operations and interactions between these modules. It relies on the robustness of the called modules' error handling.

6.4.5 Local Functions

MIS of Saved ANN Model Module

Module 7.1

model

	0	T T
1.	. Z	Uses

- Hardware-Hiding Module
- Training and Testing Module (14)

7.3

7.3.1

None.

7.3.2

401			
2 Uses			that.
• Hardware-Hiding Module		. 10.0	fthis men
• Training and Testing Module (14)	0	or provide a win	
3 Syntax	he programme	provide a new of the new of the new of the new colly me to you really me to you than the new of the	n to
3.1 Exported Constants	Horan	1 st. Celly 11	to who
one.	ι,	My My	pws . 7
3.2 Exported Access Programs		Bangra a au	This method on worked on them
Name In	Out	Exceptions	
save_model -	bool	PermissionError	- how your on
load_model -	$\left[\mathbf{M}_{ijk},\mathbf{M}_{ij} ight]$	FileNotFoundErr	or you have taken
4 Semantics			or vor bored on

7.4

State Variables 7.4.1

• modelData: Data structure holding the current ANN model's data. This is an array could you be more specifix about . The type to so model later? including weights and biases

Environment Variables

modelFile: A file on the file system where the ANN model data is saved and from where it This has been remarked beyond on implementation. is loaded.

7.4.3Assumptions

None.

Access Routine Semantics

save_model():

• transition: Writes the current state of the ANN model (weights and biases) to the modelFile.

out := Two

• output: Returns True if model is saved successfully.

• exception: Raises PermissionError if the module lacks the necessary permissions to write to modelFile. It may also raise an IOError if there are issues with the file system, such as insufficient storage space.

load_model():

• transition: Reads the model data from modelFile.

• output: Returns the trained model based on weights and biases from modelData. The return value is a list. The first argument is a list of weights (each weight matrix is \mathbf{M}_{ij}), so that this argument is a \mathbf{M}_{ijk} . The second argument is a list of biases (each bias vector is \mathbf{A}_i). This argument is a \mathbf{M}_{ij} .

• exception: Raises FileNotFoundError if modelFile does not exist or cannot be accessed. Additionally, an exception may be raised for data corruption or format mismatch, indicating issues with the integrity or compatibility of the stored model data.

7.4.5 Local Functions

MIS of Output Module 8

Module 8.1

output

8.2 Uses

- Hardware-Hiding Module
- Input Classifier Module (9)

8.3 Syntax

8.3.1 **Exported Constants**

None.

8.3.2 **Exported Access Programs**

Name	In	Out	Exceptions
set_class	-	-	-
$\mathtt{set_feedback}$	str	bool	PermissionError

8.4 Semantics

8.4.1 State Variables

None.

8.4.2 **Environment Variables**

None.

8.4.3 Assumptions

None.

Access Boutine Semantics

get_class():

Ast in
Section 8.3.2

mantics
seceive Sounds We an input, not an output
dauged

• transition: Receives the classification result from the Input Classifier Module (9).

• output: None.

• exception: None.

Lpo state fransition should

You don't hour any state
cariables to get?
I changed it to save feedback

be given for a getter

set_feedback(): You can't how a formatter without state

• transition: Sets user feedback on classification result.

- output: Returns a confirmation message or status after recording the feedback.
- exception: Raises PermissionError if the module lacks the necessary permissions to record feedback.

8.4.5 Local Functions

9 MIS of Input Classifier Module

9.1 Module

classifier

9.2 Uses

- Hardware-Hiding Module
- Saved ANN Module (7)
- Input Preparing and Preprocessing Module (12)

9.3 Syntax

9.3.1 **Exported Constants**

None.

9.3.2**Exported Access Programs**

Name	In	Out	Exceptions
load_model	-	-	-
get_image_pi	xels-	-	-
$\mathtt{get}_\mathtt{class}$	-	str	-

9.4

• modelData: Data structure holding the current ANN model's data. This is a including weights and bigger eprocessing.

Inis is an array

eprocessing.

From the load-modul? including weights and biases.

• imagePixels: An array of input image's pixels after preprocessing.

9.4.2 **Environment Variables**

None.

Assumptions 9.4.3

get_class():

• transition: Classifies the input image.

• output: The class of the input image.

• exception: None.

10 MIS of Input Image Module

10.1 Module

input

10.2 Uses

• Hardware-Hiding Module

10.3 Syntax

10.3.1 Exported Constants

- HEIGHT: A value (\mathbf{Z}_{+}) describing acceptable height of input image (currently 32).
- WIDTH: A value (\mathbf{Z}_{+}) describing acceptable width of input image (currently 32).
- IMAGE_FORMAT: A list of strings (str) of acceptable types of input image (currently PNG and JPEG).

10.3.2 Exported Access Programs

Name	In	Out	Exceptions
set_input	File path	-	FileNotFoundError,
			InvalidSize,
			InvalidFormat
get_image_pixels	-	\mathbf{M}_{ijk}	

10.4 Semantics

10.4.1 State Variables

• inputImage: A \mathbf{M}_{ijk} of the RGB input image.

10.4.2 Environment Variables

None.

10.4.3 Assumptions

10.4.4 Access Routine Semantics

set_input(inputImagePath):

- transition: Receives the input image from end user and saves its matrix as inputImage.
- output: None.
- exception: Raises FileNotFoundError if inputImagePath does not exist or cannot be accessed. Also, InvalidSize is raised when the size of input image in not compatible with HEIGHT or WIDTH. Additionally, InvalidFormat is thrown if the input image's format is not compatible with IMAGE_FORMAT.

get_image_pixels():

- transition: Getter of the input image's matrix.
- \bullet output: \mathbf{M}_{ijk} of inputImage.
- exception: None.

10.4.5 Local Functions

11 MIS of Training Model Module

11.1 Module

training_model

11.2 Uses

• Data Preparing and Preprocessing Module (13)

11.3 Syntax

11.3.1 Exported Constants

- LAYERS_NUMBER: A value (\mathbf{Z}_{+}) describing the number of neural network's layers.
- LAYERS_NEURONS: An array including each layer's number of neurons.

11.3.2 Exported Access Programs

Name	In	Out	Exceptions
create_gradients	-	${f A}_i$	-

11.4 Semantics

11.4.1 State Variables

None.

11.4.2 Environment Variables

None.

11.4.3 Assumptions

None.

11.4.4 Access Routine Semantics

create_gradients():

- transition: Creates zero arrays for all needed gradients based on the LAYERS_NUMBER and LAYERS_NEURONS.
- output: All gradients' zero vector (\mathbf{A}_i)
- exception: None.

11.4.5 Local Functions

12 Input Preparing and Preprocessing Module

12.1 Module

input_prep

12.2 Uses

None.

12.3 Syntax

12.3.1 Exported Constants

None.

12.3.2 Exported Access Programs

Name	In	Out	Exceptions
input_prep	-	${f A}_i$	-

12.4 Semantics

12.4.1 State Variables

• input: A M_{ijk} incling input image pixels.

12.4.2 Environment Variables

None.

12.4.3 Assumptions

None.

12.4.4 Access Routine Semantics

input_prep():

- transition: Prepares and preprocess the input image to change it the way model can use it to predicts the class.
- ullet output: an ${f A}_i$ including prepared and preprocessed input image.
- exception: None.

12.4.5 Local Functions

- set_image_pixels():
 - transition: Receives the input image pixels and saves in input.
 - output: None.
 - exception: None.
- rgb2gray():
 - transition: Converts RGB data (input) into grayscale in order to reduce complexity.
 - output: Grayscaled input (\mathbf{M}_{ijk}) .
 - exception: None.
- prep_pixels(grayInput):
 - transition: Normalizes grayscaled input to change the range of data between 0 and 1.
 - output: Normalized input.
 - exception: None.
- flat_data(normalInput):
 - transition: Data is flatten since input image should be vectorized with the size of 1024. After grayscaling input image is a \mathbf{M}_{ij} . this should be an \mathbf{A}_i to be used by implemented model.
 - output: flatten input.
 - exception: None.

13 Data Preparing and Preprocessing Module

13.1 Module

data

13.2 Uses

None.

13.3 Syntax

13.3.1 Exported Constants

None.

13.3.2 Exported Access Programs

Name	${f In}$	Out	Exceptions
get_train_datase	et -	$[\mathbf{M}_{ij},\mathbf{A}_i]$	UnableToLoad
get_test_dataset	; -	$[\mathbf{M}_{ij},\mathbf{A}_i]$	UnableToLoad

13.4 Semantics

13.4.1 State Variables

- train_data: Data structure holding train data images and their labels. Since train images after processing are vectors (\mathbf{A}_i) , a list of these images is a matix (\mathbf{M}_{ij}) . Alos, labels are saving in a vector (\mathbf{A}_i) . Consequently, this data structure is a list in $[\mathbf{M}_{ij}, \mathbf{A}_i]$ format.
- test_data: Data structure holding test data images and their labels. Since test images after processing are vectors (\mathbf{A}_i) , a list of these images is a matix (\mathbf{M}_{ij}) . Alos, labels are saving in a vector (\mathbf{A}_i) . Consequently, this data structure is a list in $[\mathbf{M}_{ij}, \mathbf{A}_i]$ format.
- train_label: An **A**_i incling traing data labels.
- test_label: An A_i incling test data labels.

13.4.2 Environment Variables

13.4.3 Assumptions

None.

13.4.4 Access Routine Semantics

get_train_dataset():

- transition: Returns the prepared and processed train data.
- output: train_data.
- exception: None.

get_test_dataset():

- transition: Returns the prepared and processed test data.
- output: test_data.
- exception: None.

13.4.5 Local Functions

- load_data():
 - transition: Downloads and extracts dataset. After extracting data, this function saves train_label and test_label.
 - output: Unprocessed train and test data, and their labels. These images are in RGB.
 - exception: This function raises UnableToDownload, when there is a problem with downloading or extracting data.
- rgb2gray(unprocessedTrainData, unprocessedTestData):
 - transition: Converts RGB data into grayscale in order to reduce complexity.
 - output: Grayscaled train and test data (\mathbf{M}_{ijk}) .
 - exception: None.
- prep_pixels(grayTrainData, grayTestData):
 - transition: Normalizes grayscaled images to change the range of data between 0 and 1.
 - output: Normalized train and test data.
 - exception: None.

- flat_data(normalTrainData, normalTestData):
 - transition: Data is flatten since images should be vectorized with the size of 1024. After grayscaling each image is a \mathbf{M}_{ij} . These images should be an \mathbf{A}_i to be used in training and testing process by implemented model.
 - output: flatten train and test data.
 - exception: None.
- shuffle_data(flatTrainData, flatTestData):
 - transition: Attaches traind data and test data to their labels (train_label and test_label). Also, shuffle the attached data to improve the performance.
 - output: train_data and test_data.
 - exception: None.

14 MIS of Training and Testing Module

The details of functions using here are described in SRS document Djavaherpour (2024b).

14.1 Module

train_and_test

14.2 Uses

- Training Model Module (11)
- Data Preparing and Preprocessing Module (13)

14.3 Syntax

14.3.1 Exported Constants

- BATCH_SIZE: The partition size of the dataset for each step of learning, typically a power of two.
- LEARNING_RATE: Speed at which the model learns; controls adjustments to the weights.
- EPOCHS: Total number of training cycles through the entire dataset.

14.3.2 Exported Access Programs

Name	In	Out	Exceptions
train_and_test	$\mathbf{A}_i, [\mathbf{M}_{ij}, \mathbf{A}_i], [\mathbf{M}_{ij}, \mathbf{A}_i]$	$[\mathbf{M}_{ijk},\mathbf{M}_{ij}]$	-
$\mathtt{set}_{ extsf{-}}\mathtt{layers}$	-	-	-

14.4 Semantics

14.4.1 State Variables

• layers: Layers dimensions are defined based on the model architecture and are saved in an A_i named layers.

14.4.2 Environment Variables

None.

14.4.3 Assumptions

14.4.4 Access Routine Semantics

train_and_test(gradientsArrays, train_data, test_data):

- transition: Train the model based on constant variables defined in 11. Gradient arrays and train data are needed for training. Input parameters are achieved from 11 and 13. At the same time, apply changes on test_data to make sure it is working and being trained correctly.
- output: Returns a data structure ([$\mathbf{M}_{ijk}, \mathbf{M}_{ij}$]) including weights and biases of trained model.
- exception: None.

set_layers():

- transition: layers is set based on Train Model Module (11).
- output: None.
- exception: None.

14.4.5 Local Functions

- sigmoid(x):
 - transition: Claculates sigmoid function for x, as the activation function.
 - output: Sigmoid value of x.
 - exception: None.
- initialize_parameters(layers):
 - transition: Allocates random normal weights (\mathbf{M}_{ij}) and zero biases (\mathbf{A}_i) for each layer.
 - output: Returns a dictionary (named parameters) that the keys define weights or biases, and the values are allocated random numbers to each of them.
 - exception: None.
- compute_cost(predicted, actual):
 - transition: Claculates the sum of the squared errors based on the predicted and actual values.
 - output: Returns the sum of the squared errors
 - exception: None.
- feed_forward(predicted, parameters, layersNumb):

- transition: Claculates feedforwarding process as described in SRS Djavaherpour (2024b). This is done by using the predicted value of previous step, parameters and the number of layers, parameters dictionary and the number of layers.
- output: Returns the new predicted value and a cache including new and old parameters.
- exception: None.

• extract_parameters(cache):

- transition: Extracts parameters saved during forwardfeeding from the cache, based on layers, parameters dictionary and the number of layers.
- output: Returns extracted parameters.
- exception: None.
- backpropagation(cache, predicted, actual, layers):
 - transition: Claculates backpropagation process as described in SRS Djavaherpour (2024b) to calculate gradients of wights and biases.
 - output: A dictionary as gradients that keys are labels of gradients to define weights or biases, and values are gradients.

There is a lot of thought that has gone into this design, but the inconsistence in the presentation make it difficult to understand. Someon else would have defficulty inplanently this design from the spec. Compare your should design to you implementation and you should See the inconsistencies better. Thoule you someth for your time and verien, Dr. Smith I changed this document

23

a lot (based on feed backs during my presentation, returns feedbacks and yours). I believe these problems are finel no-

References

- Tanya Djavaherpour. Module guide. https://github.com/tanya-jp/ANN-CAS741/blob/main/docs/Design/SoftArchitecture/MG.pdf, 2024a.
- Tanya Djavaherpour. System requirements specification. https://github.com/tanya-jp/ANN-CAS741/blob/main/docs/SRS/SRS.pdf, 2024b.
- Carlo Ghezzi, Mehdi Jazayeri, and Dino Mandrioli. Fundamentals of Software Engineering. Prentice Hall, Upper Saddle River, NJ, USA, 2nd edition, 2003.
- Daniel M. Hoffman and Paul A. Strooper. Software Design, Automated Testing, and Maintenance: A Practical Approach. International Thomson Computer Press, New York, NY, USA, 1995. URL http://citeseer.ist.psu.edu/428727.html.