# **Project Name:**

**Secure Network Infrastructure with Cisco ASA and VPN Integration.** 

# **Description:**

Designed and implemented a secure network architecture with Cisco ASA, configuring IPS to detect and block malicious traffic. Deployed secure IPsec VPNs for encrypted remote communication, implemented AAA protocols for access control, and applied Layer 2 security measures to protect against threats like VLAN hopping and MAC spoofing and IEEE 802.1x.

# Supervised by Dr Sahar El-Shazly at NTI.

• Chief Engineer at National Telecommunications institute.

Tel: +0201093632281


• Email: sahar.alsaid@nti.sci.eg

# This project is designed by Dr Sahar El-Shazly. Project is configured and implemented by Eng. Tarek Fayez Mohamed.

• Network Engineer | Network Security Engineer

• Tel: +0201113543384

Email: <u>tarekfayez99@gmail.com</u>



## First, we have network 192.168.70.0/24 and I will make subnetting for this network.

## 1. Creating 11 Networks from 192.168.70.0/24.

To create 11 subnets from the 192.168.70.0/24 network, we need to determine the subnet mask that provides at least 11 subnets.

- The original network is 192.168.70.0/24 (256 total IPs).
- To create 11 subnets, we need at least 4 additional bits (since 24=16≥1124=16≥11).
- The new subnet mask will be  $\sqrt{28}$  (24 + 4 = 28).

Each subnet will have 232–28=16232–28=16 IPs, with 14 usable hosts per subnet (excluding network and broadcast addresses).

#### **Subnet Ranges:**

No.	Networks	First	Last	Broadcast	Subnet mask
1.	192.168.70.0/28	192.168.70.1	192.168.70.14	192.168.70.15	
2.	192.168.70.16/28	192.168.70.17	192.168.70.30	192.168.70.31	
3.	192.168.70.32/28	192.168.70.33	192.168.70.46	192.168.70.47	
4.	192.168.70.48/28	192.168.70.49	192.168.70.62	192.168.70.63	
5.	192.168.70.64/28	192.168.70.65	192.168.70.78	192.168.70.79	255.255.255.240
6.	192.168.70.80/28	192.168.70.81	192.168.70.94	192.168.70.95	255.255.255.240
7.	192.168.70.96/28	192.168.70.97	192.168.70.110	192.168.70.111	
8.	192.168.70.112/28	192.168.70.113	192.168.70.126	192.168.70.127	
9.	192.168.70.128/28	192.168.70.129	192.168.70.142	192.168.70.143	
10.	192.168.70.144/28	192.168.70.145	192.168.70.158	192.168.70.159	

#### 2. Creating 6 Networks (Between Routers)

From the last subnet (192.168.70.160/28), we need to create 6 subnets, each with 2 usable hosts.

- To accommodate 2 hosts, we need 22=422=4 IPs per subnet (2 usable hosts + network + broadcast).
- The subnet mask for each subnet will be  $\sqrt{30}$  (32 2 = 30).

#### **Subnet Ranges:**

No.	Networks	First	Last	Broadcast	Subnet mask
11.	192.168.70.160/30	192.168.70.161	192.168.70.162	192.168.70.163	
12.	192.168.70.164/30	192.168.70.165	192.168.70.166	192.168.70.167	
13.	192.168.70.168/30	192.168.70.169	192.168.70.170	192.168.70.171	255.255.255.252
14.	192.168.70.172/30	192.168.70.173	192.168.70.174	192.168.70.175	233.233.233.232
15.	192.168.70.176/30	192.168.70.177	192. 168.70.178	192.168.70.179	
16.	192.168.70.180/30	192.168.70.181	192.168.70.182	192.168.70.183	


## **Basic Configuration**

```
enable
configure terminal
hostname SW8
enable secret 12345
no ip domain-lookup
ip domain-name cisco.com
security passwords min-length 5
login block-for 10 attempts 5 within 30
crypto key generate rsa general-keys modulus 1024
ip ssh version 2
ip ssh time-out 60
ip ssh authentication-retries 2
username adminSW8 secret 12345
service password-encryption
service timestamps log datetime msec
banner motd #
******* AUTHORIZED ACCESS ONLY **********
UNAUTHORIZED ACCESS TO THIS DEVICE IS PROHIBITED *
****************
                Tarek Fayez
***************
line console 0
login local
exec-timeout 2 5
logging synchronous
exit
line vty 0 15
login local
transport input ssh
exec-timeout 2 5
logging synchronous
exit
do write memory
```

# **R7 Configuration**

- Basic Configuration
- R7 will only handle routing configurations

Make Static Routing



## !!!! Configure Basic Configuration

enable

configure terminal

hostname R7

enable secret 12345

no ip domain-lookup

ip domain-name cisco.com

security passwords min-length 5

login block-for 10 attempts 5 within 30

crypto key generate rsa general-keys modulus 1024

ip ssh version 2

ip ssh time-out 60

ip ssh authentication-retries 2

username adminR7 secret 12345

service password-encryption

service timestamps log datetime msec

## !!!! Configure IP to each interface

interface Serial0/1/0

ip address 192.168.70.181 255.255.255.252

no sh

interface Serial0/1/1

ip address 192.168.70.161 255.255.255.252

no sh

interface Serial0/2/0

ip address 192.168.70.165 255.255.255.252

no sh

interface Serial0/2/1

ip address 192.168.70.169 255.255.255.252

no sh

interface Serial0/3/0

ip address 192.168.70.173 255.255.255.252

no sh

interface Serial0/3/1

ip address 192.168.70.177 255.255.255.252

no sh

## !!!! Static Routing

ip route 192.168.70.0 255.255.255.240 192.168.70.178 ip route 192.168.70.16 255.255.255.240 192.168.70.178 ip route 192.168.70.32 255.255.255.240 192.168.70.182 ip route 192.168.70.48 255.255.255.240 192.168.70.182 ip route 192.168.70.64 255.255.255.240 192.168.70.182 ip route 192.168.70.80 255.255.255.240 192.168.70.182 ip route 192.168.70.96 255.255.255.240 192.168.70.162 ip route 192.168.70.112 255.255.255.240 192.168.70.166 ip route 192.168.70.128 255.255.255.240 192.168.70.174 ip route 200.1.1.0 255.255.255.224 192.168.70.170

## !!!! Syslog Server

logging trap debugging logging 192.168.70.100

#### !!!! NTP Server

ntp server 192.168.70.100 ntp authentication-key 1 md5 cisco123 ntp authenticate ntp trusted-key 1 ntp update-calendar

#### !!!! tacacs+ Server

tacacs-server host 192.168.70.101 tacacs-server key cisco123

## !!!! radius Server


aaa new-model radius server RADIUS\_SERVER address ipv4 192.168.70.102 key cisco123

#### !!!! Enable authentication and ssh

aaa authentication login default group tacacs+ group radius local line console 0 login authentication default exec-timeout 2 5 exit line vty 0 4 login authentication default transport input ssh exec-timeout 2 5 exit

# **R1 Configuration**

- Basic configuration
- Configure VLANs:
  - o VLAN 10, 20, 30 for data
  - VLAN 40 for management
  - VLAN 50 Native Vlan
  - A dedicated VLAN for the native VLAN
- Apply VLAN security and STP security mechanisms.
- Implement port security:
  - First detected device: Protect mode
     Second device: Shutdown mode
  - Third device: Restrict mode
- R1 will function as a DHCP server and maintain three separate DHCP pools for the three VLANs.
- SVI requires a static IP.
- On router Configure three user views: Admin, Senior, and Junior.
- Implement all Layer 2 security measures will Configured on switches.
  - Port Security.
  - Enable DHCP Snooping for network security.
  - Enable DAI



## !!!! Configure Basic Configuration

enable
configure terminal
hostname R1
no ip domain-lookup
ip domain-name cisco.com
security passwords min-length 5
crypto key generate rsa general-keys modulus 1024
enable secret 12345
username adminR1 privilege 15 secret 12345
service password-encryption
service timestamps log datetime msec
ip ssh version 2
ip ssh time-out 60
ip ssh authentication-retries 2

## !!!! Configure IP to each interface

interface Serial 0/1/0 ip address 192.168.70.182 255.255.255.252 interface GigabitEthernet0/0/0 sn sh exit interface GigabitEthernet0/0/0.10 encapsulation dot1Q 10 ip address 192.168.70.33 255.255.255.240 exit interface GigabitEthernet0/0/0.20 encapsulation dot1Q 20 ip address 192.168.70.49 255.255.255.240 exit interface GigabitEthernet0/0/0.30 encapsulation dot1Q 30 ip address 192.168.70.65 255.255.255.240 exit interface GigabitEthernet0/0/0.40 encapsulation dot1Q 40 ip address 192.168.70.81 255.255.255.240 exit interface GigabitEthernet0/0/0.50 encapsulation dot1Q 50 exit

ip route 0.0.0.0 0.0.0.0 192.168.70.181

#### !!!! DHCP For Vlans

ip dhcp excluded-address 192.168.70.33 192.168.70.34 ip dhcp excluded-address 192.168.70.49 192.168.70.50 ip dhcp excluded-address 192.168.70.65 192.168.70.66 ip dhcp pool VLAN10 network 192.168.70.32 255.255.255.240 default-router 192.168.70.33 dns-server 8.8.8.8 exit ip dhcp pool VLAN20 network 192.168.70.48 255.255.255.240 default-router 192.168.70.49 dns-server 8.8.8.8 exit ip dhcp pool VLAN30 network 192.168.70.64 255.255.255.240 default-router 192.168.70.65 dns-server 8.8.8.8 exit

## !!!! Create 3 Views (ADMIN, JUNIOR, SENIOR)

aaa new-model
parser view ADMIN
secret 12345
commands exec include setup
commands exec include all show
commands exec include telnet
commands exec include terminal
commands exec include traceroute

parser view JUNIOR secret 12345 commands exec include ping commands exec include reload commands exec include ssh

parser view SENIOR
secret 12345
commands exec include dir
commands exec include show
commands exec include show arp
commands exec include show ip
commands exec include show ip interface
commands exec include show version

## !!!! Syslog Server

logging trap debugging logging 192.168.70.100

#### !!!! NTP Server

ntp server 192.168.70.100 ntp authentication-key 1 md5 cisco123 ntp authenticate ntp trusted-key 1 ntp update-calendar

#### !!!! tacacs+ Server

tacacs-server host 192.168.70.101 tacacs-server key cisco123

#### !!!! radius Server

aaa new-model radius server RADIUS\_SERVER address ipv4 192.168.70.102 key cisco123

#### !!!! Enable authentication and ssh

aaa authentication login default group tacacs+ group radius local line console 0 login authentication default exec-timeout 2 5 exit line vty 0 4 login authentication default transport input ssh exec-timeout 2 5 exit

## !!!! VPN IPsec on R1

access-list 100 permit ip 192.168.70.32 0.0.0.15 192.168.70.96 0.0.0.15 access-list 100 permit ip 192.168.70.48 0.0.0.15 192.168.70.96 0.0.0.15 access-list 100 permit ip 192.168.70.64 0.0.0.15 192.168.70.96 0.0.0.15 access-list 100 permit ip 192.168.70.80 0.0.0.15 192.168.70.96 0.0.0.15

crypto isakmp enable crypto isakmp policy 10 hash sha authentication pre-share group 5 encryption aes 256 lifetime 3600 exit

crypto isakmp key cisco123 address 192.168.70.162 crypto ipsec transform-set R1\_R2 esp-aes esp-sha-hmac

crypto map VPN\_IPSEC 10 ipsec-isakmp set peer 192.168.70.162 set pfs group5 set security-association lifetime seconds 900 set transform-set R1\_R2 match address 100 exit

interface Serial0/1/0 crypto map VPN\_IPSEC

## SW2

## !!! DHCP Snooping and Dynamic arp inspection

no ip dhcp snooping information option ip dhcp snooping ip dhcp snooping vlan 10,20,30,40 ip arp inspection vlan 10,20,30,40

interface range FastEthernet0/1-2 switchport trunk native vlan 50 ip dhcp snooping limit rate 10 switchport mode trunk

## switchport nonegotiate

interface GigabitEthernet0/1 switchport trunk native vlan 50 switchport trunk allowed vlan 10,20,30,40 ip arp inspection trust ip dhcp snooping trust switchport mode trunk

## **!!!!STP Security**

spanning-tree portfast default spanning-tree portfast bpduguard default

## !!!! SVI (Management Vlan)

interface Vlan40 ip address 192.168.70.83 255.255.255.240 exit ip default-gateway 192.168.70.81

## !!!! implement Vlan Security (in all Switches)

interface range FastEthernet0/3-24 switchport access vlan 999 switchport mode access shutdown

## SW1 and SW3

## !!! DHCP Snooping and Dynamic arp inspection

ip arp inspection vlan 10,20,30,40 ip dhcp snooping vlan 10,20,30,40 no ip dhcp snooping information option ip dhcp snooping

## !!!!STP Security

spanning-tree portfast default spanning-tree portfast bpduguard default

### interface FastEthernet0/1

switchport trunk native vlan 50 ip arp inspection trust ip dhcp snooping trust switchport mode trunk

### interface FastEthernet0/2

switchport access vlan 10 ip dhcp snooping limit rate 10 switchport mode access switchport port-security switchport port-security violation protect

## interface FastEthernet0/3

switchport access vlan 20 ip dhcp snooping limit rate 10 switchport mode access switchport port-security switchport port-security violation shutdown

#### interface FastEthernet0/4


switchport access vlan 30 ip dhcp snooping limit rate 10 switchport mode access switchport port-security switchport port-security violation restrict

## interface FastEthernet0/4

switchport access vlan 30 ip dhcp snooping limit rate 10 switchport mode access interface Vlan40 ip address 192.168.70.82 255.255.255.240 exit ip default-gateway 192.168.70.81

## **R2 Configuration (Wired & Wireless LANs)**

- Enhance wireless LAN security by changing SSID name and modifying encryption protocols.
- Implement a authentication approach for login:
  - Primary method: TACACS+
     Secondary method: RADIUS
  - 3. **Tertiary method:** Local database
- All routers (except R5) must use AAA authentication with TACACS+ as the primary method and RADIUS as the secondary method.
- All routers must **send logs to a Syslog server** located on R2's network.
- Implement **802.1x authentication** for PC 8
- Establish a site-to-site IPsec VPN between R1 and R2.



enable
configure terminal
hostname R2
enable secret 12345
no ip domain-lookup
ip domain-name cisco.com
crypto key generate rsa general-keys modulus 1024
ip ssh version 2
ip ssh time-out 60
ip ssh authentication-retries 2
username adminR2 privilege 15 secret 12345
service password-encryption
service timestamps log datetime msec

interface GigabitEthernet0/0/0 ip address 192.168.70.97 255.255.255.240 no sh interface Serial0/1/1 ip address 192.168.70.162 255.255.252 no sh ip route 0.0.0.0 0.0.0.0 192.168.70.161

logging trap debugging logging 192.168.70.100

ntp server 192.168.70.100 ntp authentication-key 1 md5 cisco123 ntp authenticate ntp trusted-key 1 ntp update-calendar

tacacs-server host 192.168.70.101 tacacs-server key cisco123 aaa new-model radius server RADIUS\_SERVER address ipv4 192.168.70.102 key cisco123 ex

aaa authentication login default group tacacs+ group radius local

line console 0
login authentication default
exec-timeout 2 5
exit
line vty 0 4
login authentication default
transport input ssh
exec-timeout 2 5
exit

#### !!!! DHCP for wireless

ip dhcp excluded-address 192.168.70.97 192.168.70.105 ip dhcp pool pool\_Wireless network 192.168.70.96 255.255.255.240 default-router 192.168.70.97 dns-server 8.8.8.8 exit

#### !!!! VPN IPsec on R2

access-list 100 permit ip 192.168.70.96 0.0.0.15 192.168.70.32 0.0.0.15 access-list 100 permit ip 192.168.70.96 0.0.0.15 192.168.70.48 0.0.0.15 access-list 100 permit ip 192.168.70.96 0.0.0.15 192.168.70.64 0.0.0.15 access-list 100 permit ip 192.168.70.96 0.0.0.15 192.168.70.80 0.0.0.15

crypto isakmp enable crypto isakmp policy 10 hash sha authentication pre-share group 5 encryption aes 256 lifetime 3600 exit

crypto isakmp key cisco123 address 192.168.70.182 crypto ipsec transform-set R1\_R2 esp-aes esp-sha-hmac

crypto map VPN\_IPSEC 10 ipsec-isakmp set peer 192.168.70.182 set pfs group5 set security-association lifetime seconds 900 set transform-set R1\_R2 match address 100 exit

interface Serial0/1/1 crypto map VPN\_IPSEC

enable
configure terminal
hostname SW4
enable secret 12345
no ip domain-lookup
ip domain-name cisco.com
crypto key generate rsa general-keys modulus 1024
ip ssh version 2
ip ssh time-out 60
ip ssh authentication-retries 2
username adminSW4 secret 12345
service password-encryption
service timestamps log datetime msec

aaa new-model

## !!!! Configure RADIUS Server

radius-server host 192.168.70.102 auth-port 1645 radius-server key cisco123

## !!!! Configure AAA for 802.1X

aaa authentication dot1x default group radius aaa authentication login default group radius local

## !!!! Enable 802.1X Globally

dot1x system-auth-control


## !!!! Configure Interface for 802.1X

interface fas0/5 switchport mode access authentication port-control auto dot1x pae authenticator exit

line console 0 login authentication default exec-timeout 2 5 exit


line vty 0 4 login authentication default transport input ssh exec-timeout 2 5 exit

## To enable 802.1x you should enable Allow EAP-MD5



## **R3 Configuration (Zone-Based Firewall)**

- Internal users can access all external traffic types.
- DMZ servers located externally should only be accessible via ICMP, HTTP, and HTTPS.



enable
configure terminal
hostname R3
no ip domain-lookup
ip domain-name cisco.com
crypto key generate rsa general-keys modulus 1024
ip ssh version 2
ip ssh time-out 60
ip ssh authentication-retries 2
security passwords min-length 5
enable secret 12345
username adminR3 secret 12345
service password-encryption
service timestamps log datetime msec

logging trap debugging logging 192.168.70.100 ntp server 192.168.70.100 ntp authentication-key 1 md5 cisco123 ntp authenticate ntp trusted-key 1 ntp update-calendar tacacs-server host 192.168.70.101 tacacs-server key cisco123 aaa new-model radius server RADIUS SERVER address ipv4 192.168.70.102 key cisco123 ex aaa authentication login default group tacacs+ group radius local line console 0

tarekfayez99@gmail.com

exec-timeout 25

exit

login authentication default

line vty 0 4 login authentication default transport input ssh exec-timeout 2 5 exit

interface GigabitEthernet0/0/0
ip address 192.168.70.1 255.255.255.240
no sh
exit
interface GigabitEthernet0/0/1
ip address 192.168.70.17 255.255.255.240
no sh
exit
interface Serial0/2/1
ip address 192.168.70.178 255.255.252
no sh
exit

ip route 0.0.0.0 0.0.0.0 192.168.70.177 zone security INSIDE

exit

zone security DMZ

exit

zone security **PUBLIC** 


exit

class-map type inspect match-any DMZ_PROTOCOLS	class-map type inspect match-any INSIDE_PROTOCOLS		
match protocol http	match protocol icmp		
match protocol https	match protocol tcp		
match protocol icmp	match protocol udp		
exit	exit		
policy-map type inspect DMZ_TO_PUBLIC	policy-map type inspect INSIDE_TO_PUBLIC		
class type inspect DMZ_PROTOCOLS	class type inspect INSIDE_PROTOCOLS		
inspect	inspect		
exit	exit		
exit	exit		
zone-pair security PUBLIC_TO_DMZ source PUBLIC destination	zone-pair security INSIDE_TO_PUBLIC source INSIDE destination		
DMZ	PUBLIC		
service-policy type inspect DMZ_TO_PUBLIC	service-policy type inspect INSIDE_TO_PUBLIC		
exit	exit		

interface g0/0/1
zone-member security DMZ
interface g0/0/0
zone-member security INSIDE
interface s0/2/0
zone-member security PUBLIC

## **R4 Configuration (IPS - Intrusion Prevention System)**

 Internal devices can ping external networks, but external networks cannot initiate pings to internal devices.



enable configure terminal hostname R4 enable secret 12345 no ip domain-lookup ip domain-name cisco.com

crypto key generate rsa general-keys modulus 1024 ip ssh version 2 ip ssh time-out 60 ip ssh authentication-retries 2

username adminR4 secret 12345 service password-encryption service timestamps log datetime msec

interface GigabitEthernet0/0/0 ip address 192.168.70.129 255.255.255.240 no sh

interface Serial0/2/0 ip address 192.168.70.174 255.255.255.252 no sh

ip route 0.0.0.0 0.0.0.0 192.168.70.173

logging trap debugging logging 192.168.70.100

ntp server 192.168.70.100 ntp authentication-key 1 md5 cisco123 ntp authenticate ntp trusted-key 1 ntp update-calendar


tacacs-server host 192.168.70.101 tacacs-server key cisco123 aaa new-model radius server RADIUS\_SERVER address ipv4 192.168.70.102 key cisco123 aaa authentication login default group tacacs+ group radius local line console 0 login authentication default exec-timeout 2 5 exit line vtv 0 4 login authentication default transport input ssh exec-timeout 2 5 exit **!!!!** Configure IPs IOS show version Save the running-config and reload show version R1# mkdir ipsdir R1(config)# ip ips config location flash:ipsdir R1(config)# ip ips name iosips R1(config)# ip ips notify log R1(config)# ip ips signature-category R1(config-ips-category)# category all R1(config-ips-category-action)# retired true (config-ips-category-action)# exit R1(config-ips-category)# category ios ips basic R1(config-ips-category-action)# retired false R1(config-ips-category-action)# exit R1(config-ips-cateogry)# exit Do you want to accept these changes? [confirm] **Enter>** R1(config)# interface g0/0/0 R1(config-if)# ip ips iosips out R1(config)# ip ips signature-definition R1(config-sigdef)# signature 2004 0 R1(config-sigdef-sig)# status R1(config-sigdef-sig-status)# retired false R1(config-sigdef-sig-status)# enabled true R1(config-sigdef-sig-status)# exit R1(config-sigdef-sig)# engine R1(config-sigdef-sig-engine)# event-action produce-alert R1(config-sigdef-sig-engine)# event-action deny-packet-inline R1(config-sigdef-sig-engine)# exit

tarekfayez99@gmail.com

R1(config-sigdef-sig)# exit R1(config-sigdef)# exit

## **R5 Configuration (Firewall - Edge Router)**

- R5 acts as the network's edge router.
- Define three zones:
  - o DMZ (Blue)
  - Inside Network (Yellow)
  - Outside Network (Purple)
- Implement complete firewall configuration from hostname setup to AAA, Syslog, and NTP server integration.



## !!!!R5

```
enable
configure terminal
hostname R5
no ip domain-lookup
ip domain-name cisco.com
crypto key generate rsa general-keys modulus 1024
ip ssh version 2
ip ssh time-out 60
ip ssh authentication-retries 2
security passwords min-length 5
enable secret 12345
username adminR5 secret 12345
service password-encryption
service timestamps log datetime msec
line console 0
login local
exec-timeout 2 5
logging synchronous
```

```
exit
line vty 0 15
login local
transport input ssh
exec-timeout 2 5
logging synchronous
exit
do write memory
interface GigabitEthernet0/0/0
ip address 200.1.1.1 255.255.255.224
no sh
interface Serial0/2/1
ip address 192.168.70.170 255.255.252
no sh
ip classless
ip route 0.0.0.0 0.0.0.0 192.168.70.169
```

## !!!! Syslog Server !!!!!!!

logging trap debugging logging 172.16.10.2

#### !!!! NTP Server !!!!!!!!

ntp server 172.16.10.2 ntp authentication-key 1 md5 cisco123 ntp authenticate ntp trusted-key 1 ntp update-calendar

#### !!!! tacacs+ Server !!!!!!!!

tacacs-server host 172.16.10.2 tacacs-server key cisco123

#### !!!! radius Server !!!!!!!!

aaa new-model radius server RADIUS\_SERVER address ipv4 192.168.70.102 key cisco123

## !!!! Enable authentication and ssh !!!!!!!!

aaa authentication login default group tacacs+ group radius local line console 0 login authentication default exec-timeout 2 5 exit line vty 0 4 login authentication default transport input ssh exec-timeout 2 5

## !!! Firewall hostname ASA domain-name cisco.com enable password 12345 username admin password 12345 aaa authentication ssh console LOCAL crypto key generate rsa modulus 1024 yes interface GigabitEthernet1/1 nameif OUTSIDE security-level 0 ip address 200.1.1.2 255.255.255.224 exit interface GigabitEthernet1/2 nameif INSIDE security-level 100 ip address 172.16.10.1 255.255.255.0 exit interface GigabitEthernet1/3 nameif DMZ security-level 70 ip address 172.16.20.1 255.255.255.0 exit object network INSIDE-NET subnet 172.16.10.0 255.255.255.0 nat (INSIDE,OUTSIDE) dynamic interface object network DMZ-SERVER host 172.16.20.2 nat (DMZ,OUTSIDE) static 200.1.1.10 route OUTSIDE 0.0.0.0 0.0.0.0 200.1.1.1 1 access-list dmz extended permit udp any host 172.16.20.2 eq ftp

ssh timeout 10


ssh 172.16.10.0 255.255.255.0 INSIDE ssh 200.1.1.1 255.255.255.255 OUTSIDE

ļ

dhcpd address 172.16.10.5-172.16.10.20 INSIDE dhcpd dns 8.8.8.8 interface INSIDE dhcpd lease 20000 dhcpd enable INSIDE

access-list OUTSIDE\_DMZ permit icmp any host 172.16.20.2 eq 80 access-list OUTSIDE\_DMZ permit tcp any host 172.16.20.2 eq 80 access-list OUTSIDE\_DMZ permit tcp any host 172.16.20.2 eq 443 access-list OUTSIDE\_DMZ permit udp any host 172.16.20.2 eq 20 access-list OUTSIDE\_DMZ permit tcp any host 172.16.20.2 eq 21 access-list OUTSIDE\_DMZ permit udp any host 172.16.20.2 eq 53 access-list OUTSIDE\_DMZ permit tcp any host 172.16.20.2 eq 53 access-group OUTSIDE\_DMZ in interface OUTSIDE

# **R6 Using IPv6 ACL and routing OSPF**



enable
configure terminal
hostname R6
enable secret 12345
no ip domain-lookup
ip domain-name cisco.com
crypto key generate rsa general-keys modulus 1024
ip ssh version 2
ip ssh time-out 60
ip ssh authentication-retries 2
username adminR6 privilege 15 secret 12345
service password-encryption
service timestamps log datetime msec

interface GigabitEthernet0/0/1 ip address 192.168.70.113 255.255.255.240 no sh

logging trap debugging logging 192.168.70.100 ntp server 192.168.70.100 ntp authentication-key 1 md5 cisco123

ntp authenticate ntp trusted-key 1 ntp update-calendar

tacacs-server host 192.168.70.101
tacacs-server key cisco123
aaa new-model
radius server RADIUS\_SERVER
address ipv4 192.168.70.102
key cisco123
ex
aaa authentication login default group tacacs+ group radius local

line console 0
login authentication default
exec-timeout 2 5

exit line vty 0 4 login authentication default transport input ssh exec-timeout 2 5 exit