Chapter 5: Optimizing Program Performance

CSCI3240: Lecture 12 and 13

Dr. Arpan Man Sainju

Middle Tennessee State University





Today

Overview

Generally Useful Optimizations

- Code motion/precomputation
- Strength reduction
- Sharing of common subexpressions
- Removing unnecessary procedure calls

Optimization Blockers

- Procedure calls
- Memory aliasing





Performance Realities

■ There's more to performance than asymptotic complexity

Constant factors matter too!

- Easily see 10:1 performance range depending on how code is written
- Must optimize at multiple levels:
 - algorithm, data representations, procedures, and loops

• Must understand system to optimize performance

- How programs are compiled and executed
- How modern processors + memory systems operate
- How to measure program performance and identify bottlenecks
- How to improve performance without destroying code modularity and generality





Optimizing Compilers

Provide efficient mapping of program to machine

- register allocation
- code selection and ordering (scheduling)
- dead code elimination
- eliminating minor inefficiencies

Don't (usually) improve asymptotic efficiency

- up to programmer to select best overall algorithm
- big-O savings are (often) more important than constant factors
 - but constant factors also matter

Have difficulty overcoming "optimization blockers"

- potential memory aliasing
- potential procedure side-effects





Limitations of Optimizing Compilers

Operate under fundamental constraint

- Must not cause any change in program behavior
- Often prevents it from making optimizations that would only affect behavior under pathological conditions.
- Behavior that may be obvious to the programmer can be obfuscated by languages and coding styles
 - e.g., Data ranges may be more limited than variable types suggest
- Most analysis is performed only within procedures
 - Whole-program analysis is too expensive in most cases
 - Newer versions of GCC do inter-procedural analysis within individual files
 - But, not between code in different files
- Most analysis is based only on static information
 - Compiler has difficulty anticipating run-time inputs
- When in doubt, the compiler must be conservative





Generally Useful Optimizations

- Optimizations that you or the compiler should do regardless of processor / compiler
- A. Code Motion
- B. Reduction in Strength
- C. Share Common Subexpression





A. Code Motion

A. Code Motion

- Avoid repeated computation
 - If it will always produce same result
 - Especially moving code out of loop

```
void set_row(double *a, double *b,
    long i, long n)
{
    long j;
    for (j = 0; j < n; j++)
        a[n*i+j] = b[j];
}
</pre>

    long j;
    int ni = n*i;
    for (j = 0; j < n; j++)
        a[ni+j] = b[j];
}
</pre>
```





Compiler-Generated Code Motion (-01)

```
void set_row(double *a, double *b,
    long i, long n)
{
    long j;
    for (j = 0; j < n; j++)
        a[n*i+j] = b[j];
}</pre>
```

```
long j;
long ni = n*i;
double *rowp = a+ni;
for (j = 0; j < n; j++)
*rowp++ = b[j];</pre>
```

```
set_row:
    testq %rcx, %rcx  # Test n
    jle .L1  # If 0, goto done
    imulq %rcx, %rdx  # ni = n*i
    leaq(%rdi,%rdx,8), %rdx # rowp = A + ni*8
    movl $0, %eax  # j = 0

.L3:  # loop:
    movsd (%rsi,%rax,8), %xmm0  # t = b[j]
    movsd %xmm0, (%rdx,%rax,8)  # M[A+ni*8 + j*8] = t
    addq$1, %rax  # j++
    cmpq%rcx, %rax  # j:n
    jne .L3  # if !=, goto loop
.L1:  # done:
    rep; ret
```





B. Reduction in Strength

- Replace costly operation with simpler one
- Shift, add instead of multiply or divide

```
16*x --> x << 4
```

- Utility machine dependent
- Depends on cost of multiply or divide instruction
 - On Intel Nehalem, integer multiply requires 3 CPU cycles
- Recognize the sequence of products

```
for (i = 0; i < n; i++) {
  int ni = n*i;
  for (j = 0; j < n; j++)
    a[ni + j] = b[j];
}</pre>
```

```
int ni = 0;
for (i = 0; i < n; i++) {
  for (j = 0; j < n; j++)
    a[ni + j] = b[j];
  ni += n;
}</pre>
```





C. Share Common Subexpressions

- Reuse portions of expressions
- GCC will do this with –O1

```
/* Sum neighbors of i,j */
up = val[(i-1)*n + j ];
down = val[(i+1)*n + j ];
left = val[i*n + j-1];
right = val[i*n + j+1];
sum = up + down + left + right;
```

3 multiplications: i*n, (i-1)*n, (i+1)*n

```
leaq 1(%rsi), %rax # i+1
leaq -1(%rsi), %r8 # i-1
imulq %rcx, %rsi # i*n
imulq %rcx, %rax # (i+1)*n
imulq %rcx, %r8 # (i-1)*n
addq %rdx, %rsi # i*n+j
addq %rdx, %rax #
(i+1)*n+j
addq %rdx, %r8 # (i-
1)*n+j
```

```
long inj = i*n + j;
up =    val[inj - n];
down = val[inj + n];
left = val[inj - 1];
right = val[inj + 1];
sum = up + down + left + right;
```

1 multiplication: i*n

```
imulq %rcx, %rsi # i*n
addq %rdx, %rsi # i*n+j
movq %rsi, %rax # i*n+j
subq %rcx, %rax # i*n+j-n
leaq (%rsi,%rcx), %rcx # i*n+j+n
```

Here, n refers to number of columns, i and j indicates row index and column index respectively.

tems: A Programmer's Perspective, Third Edition

Optimization Blocker #1: Procedure Calls

Procedure to Convert String to Lower Case


```
void lower(char *s)
{
    size_t i;
    for (i = 0; i < strlen(s); i++)
        if (s[i] >= 'A' && s[i] <= 'Z')
            s[i] -= ('A' - 'a');
}</pre>
```





Lower Case Conversion Performance

- Time quadruples when double string length
- Quadratic performance







Convert Loop To Goto Form

```
void lower(char *s)
   size t i = 0;
   if (i >= strlen(s))
     goto done;
 loop:
   if (s[i] >= 'A' \&\& s[i] <= 'Z')
        s[i] -= ('A' - 'a');
   i++;
   if (i < strlen(s))</pre>
     goto loop;
 done:
```

• strlen executed every iteration





Calling Strlen

```
/* My version of strlen */
size_t strlen(const char *s)
{
    size_t length = 0;
    while (*s != '\0') {
    s++;
    length++;
    }
    return length;
}
```

Strlen performance

• Only way to determine length of string is to scan its entire length, looking for null character.

Overall performance, string of length N

- N calls to strlen
- Require times N, N-1, N-2, ..., 1
- Overall O(N²) performance





Improving Performance

```
void lower(char *s)
{
    size_t i;
    size_t len = strlen(s);
    for (i = 0; i < len; i++)
        if (s[i] >= 'A' && s[i] <= 'Z')
        s[i] -= ('A' - 'a');
}</pre>
```


- Move call to strlen outside of loop
- Since result does not change from one iteration to another
- Form of code motion (but compiler does not do it for you)





Lower Case Conversion Performance

- Time doubles when double string length
- Linear performance of lower2







Optimization Blocker: Procedure Calls

Why couldn't compiler move strlen out of inner loop?

- Procedure may have side effects
 - Alters global state each time called
- Function may not return same value for given arguments
 - Depends on other parts of global state
 - Procedure lower could interact with strlen

Warning:

- Compiler treats procedure call as a black box
- Weak optimizations near them

Remedies:

- Use of inline functions
 - GCC does this with –O1
 - Within single file
- Do your own code motion

```
size_t lencnt = 0;
size_t strlen(const char *s)
{
    size_t length = 0;
    while (*s != '\0') {
    s++; length++;
    }
    lencnt += length;
    return length;
}
```



Memory Matters

```
/* Sum rows is of n X n matrix a
    and store in vector b */
void sum_rows1(double *a, double *b, long n) {
    long i, j;
    for (i = 0; i < n; i++) {
    b[i] = 0;
    for (j = 0; j < n; j++)
        b[i] += a[i*n + j];
    }
}</pre>
```

```
# sum_rows1 inner loop
.L4:

    movsd (%rsi,%rax,8), %xmm0 # FP load
    addsd (%rdi), %xmm0 # FP add
    movsd %xmm0, (%rsi,%rax,8) # FP store
    addq $8, %rdi
    cmpq %rcx, %rdi
    jne .L4
```

- Code updates b [i] on every iteration
- Why couldn't compiler optimize this away?





Memory Aliasing

```
/* Sum rows is of n X n matrix a
    and store in vector b */
void sum_rows1(double *a, double *b, long n) {
    long i, j;
    for (i = 0; i < n; i++) {
        b[i] = 0;
        for (j = 0; j < n; j++)
            b[i] += a[i*n + j];
    }
}</pre>
```

```
double A[9] =
    { 0,     1,     2,
        4,     8,     16,
        32,     64,     128};

double B[3] = A+3;     //B[3] is alias to A+3

sum_rows1(A, B, 3);
```

Value of B:

```
init: [4, 8, 16]

i = 0: [3, 8, 16]

i = 1: [3, 28, 16]

i = 2: [3, 28, 224]
```

- Code updates b [i] on every iteration
- Must consider possibility that these updates will affect program behavior





Removing Aliasing

```
/* Sum rows is of n X n matrix a
   and store in vector b */
void sum_rows2(double *a, double *b, long n) {
   long i, j;
   for (i = 0; i < n; i++) {
      double val = 0;
      for (j = 0; j < n; j++)
        val += a[i*n + j];
      b[i] = val;
}</pre>
```

```
# sum_rows2 inner loop
.L10:
    addsd (%rdi), %xmm0 # FP load + add
    addq $8, %rdi
    cmpq %rax, %rdi
    jne .L10
```

No need to store intermediate results





Optimization Blocker: Memory Aliasing

Aliasing

- Two different memory references specify single location
- Easy to have happen in C
 - Since allowed to do address arithmetic
 - Direct access to storage structures
- Get in habit of introducing local variables
 - Accumulating within loops
 - Your way of telling compiler not to check for aliasing





Exploiting Instruction-Level Parallelism


- Need general understanding of modern processor design
 - Hardware can execute multiple instructions in parallel
- Performance limited by data dependencies
- Simple transformations can yield dramatic performance improvement
 - Compilers often cannot make these transformations
 - Lack of associativity and distributivity in floating-point arithmetic





Benchmark Example: Data Type for Vectors

```
/* data structure for vectors */
typedef struct{
    size_t len;
    data_t *data;
} vec;
```



Data Types

- Use different declarations for data t
- int
- long
- float
- double

```
/* retrieve vector element
   and store at val */
int get_vec_element
   (*vec v, size_t idx, data_t *val)
{
   if (idx >= v->len)
      return 0;
   *val = v->data[idx];
   return 1;
}
```





Benchmark Computation

```
void combine1(vec_ptr v, data_t *dest)
{
    long int i;
    *dest = IDENT;
    for (i = 0; i < vec_length(v); i++) {
        data_t val;
        get_vec_element(v, i, &val);
        *dest = *dest OP val;
    }
}</pre>
```

Compute sum or product of vector elements

Data Types

- Use different declarations for data t
- int
- long
- float
- double

Operations


- Use different definitions of OP and IDENT
- + / 0
- * / 1





Cycles Per Element (CPE)

- Convenient way to express the performance of a program that operates on vectors or lists
- Length = n
- In our case: CPE = cycles per OP
- T = CPE*n + Overhead
 - CPE is slope of line







Benchmark Performance

```
void combine1(vec_ptr v, data_t *dest)
{
    long int i;
    *dest = IDENT;
    for (i = 0; i < vec_length(v); i++) {
        data_t val;
        get_vec_element(v, i, &val);
        *dest = *dest OP val;
    }
}</pre>
```

Compute sum or product of vector elements

Method	Integer		Double FP	
Operation	Add	Mult	Add	Mult
Combine1 unoptimized	22.68	20.02	19.98	20.18
Combine1 -O1	10.12	10.12	10.17	11.14





Basic Optimizations

```
void combine4(vec_ptr v, data_t *dest)
{
  long i;
  long length = vec_length(v);
  data_t *d = get_vec_start(v);
  data_t t = IDENT;
  for (i = 0; i < length; i++)
    t = t OP d[i];
  *dest = t;
}</pre>
```

```
/* Return length of vector */
size_t vec_length(vec *v)
{
    return v->len;
}

data_t *get_vec_start(vec *v)
{
    return v->data;
}
```

- Move vec_length out of loop
- Avoid bounds check on each cycle
- Accumulate in temporary

```
/* retrieve vector element
   and store at val */
int get_vec_element
   (*vec v, size_t idx, data_t *val)
{
   if (idx >= v->len)
      return 0;
   *val = v->data[idx];
   return 1;
}
```





Effect of Basic Optimizations

```
void combine4(vec_ptr v, data_t *dest)
{
  long i;
  long length = vec_length(v);
  data_t *d = get_vec_start(v);
  data_t t = IDENT;
  for (i = 0; i < length; i++)
    t = t OP d[i];
  *dest = t;
}</pre>
```


Method	Integer		Double FP	
Operation	Add Mult		Add	Mult
Combine1 -O1	10.12	10.12	10.17	11.14
Combine4	1.27	3.01	3.01	5.01

Eliminates sources of overhead in loop





Modern CPU Design







Superscalar Processor


- Definition: A superscalar processor can issue and execute multiple instructions in one cycle. The instructions are retrieved from a sequential instruction stream and are usually scheduled dynamically.
- Benefit: without programming effort, superscalar processor can take advantage of the instruction level parallelism that most programs have
- Most modern CPUs are superscalar.
- Intel: since Pentium (1993)





Pipelined Functional Units

```
long mult_eg(long a, long b, long c) {
   long p1 = a*b;
   long p2 = a*c;
   long p3 = p1 * p2;
   return p3;
}
```



	Time						
	1	2	3	4	5	6	7
Stage 1	a*b	a*c			p1*p2		
Stage 2		a*b	a*c			p1*p2	
Stage 3			a*b	a*c			p1*p2

- Divide computation into stages
- Pass partial computations from stage to stage
- Stage i can start on new computation once values passed to i+1
- E.g., complete 3 multiplications in 7 cycles, even though each requires 3 cycles





Haswell CPU

8 Total Functional Units

Multiple instructions can execute in parallel

2 load, with address computation

1 store, with address computation

4 integer

2 FP multiply

1 FP add

1 FP divide

Latency refers to total number of clock cycles required to perform the operation.

Issue time indicates the minimum number of cycles between two independent operation of same type.

Some instructions take > 1 cycle, but can be pipelined

Instruction	Latency	Cycles/Issue
Load / Store	4	1
Integer Addition	1	1
Integer Multiply	3	1
Integer/Long Divide	3-30	3-30
Single/Double FP Multiply	5	1
Single/Double FP Add	3	1
Single/Double FP Divide	3-15	3-15





x86-64 Compilation of Combine4

Inner Loop (Case: Integer Multiply)

Method	Integer		Double FP		
Operation	Add Mult		Add	Mult	
Combine4	1.27	3.01	3.01	5.01	
Latency Bound	1.00	3.00	3.00	5.00	

- Here, we have series of multiplication of integers. But we must wait for the imull operation (3 clock cycle bound) to complete before performing the next imull instruction.
- The measurement here corresponds to the latency bound of the machine.






Combine4 = Serial Computation (OP = *)



- Sequential dependence
 - Performance: determined by latency of OP





 $1 d_0$



Loop Unrolling (2x1)

```
void unroll2a combine(vec ptr v, data t *dest)
    long length = vec length(v);
    long limit = length-1;
    data t *d = get vec start(v);
    data t x = IDENT;
    long i;
    /* Combine 2 elements at a time */
    for (i = 0; i < limit; i+=2) {
       x = (x OP d[i]) OP d[i+1];
    /* Finish any remaining elements */
    for (; i < length; i++) {
       x = x OP d[i];
    *dest = x;
```

Perform 2x more useful work per iteration





Effect of Loop Unrolling

Method	Integer		Double FP		
Operation	Add	Mult	Add	Mult	
Combine4	1.27	3.01	3.01	5.01	
Unroll 2x1	1.01	3.01	3.01	5.01	
Latency Bound	1.00	3.00	3.00	5.00	

Helps integer add

Achieves latency bound

$$x = (x OP d[i]) OP d[i+1];$$

- Others don't improve. Why?
 - Still sequential dependency





Loop Unrolling with Reassociation (2x1a)

```
void unroll2aa combine(vec ptr v, data_t *dest)
    long length = vec length(v);
    long limit = length-1;
    data t *d = qet vec start(v);
    data t x = IDENT;
    long i;
    /* Combine 2 elements at a time */
    for (i = 0; i < limit; i+=2) {
       x = x OP (d[i] OP d[i+1]);
    /* Finish any remaining elements */
    for (; i < length; i++) {
       x = x OP d[i];
                              Compare to before
    *dest = x;
                              x = (x OP d[i]) OP d[i+1];
```

- Can this change the result of the computation?
- Yes, for FP. Why?





Effect of Reassociation

Method	Integer		Double FP		
Operation	Add	Mult	Add	Mult	
Combine4	1.27	3.01	3.01	5.01	
Unroll 2x1	1.01	3.01	3.01	5.01	
Unroll 2x1a	1.01	1.51	1.51	2.51	
Latency Bound	1.00	3.00	3.00	5.00	
Throughput Bound	0.50	1.00	1.00	0.50	

■ Nearly 2x speedup for Int *, FP +, FP *

Reason: Breaks sequential dependency

$$x = x OP (d[i] OP d[i+1]);$$

Why is that? (next slide)

2 func. units for FP * 2 func. units for load

4 func. units for int +


2 func. units for load





Reassociated Computation

$$x = x OP (d[i] OP d[i+1]);$$



What changed:

 Ops in the next iteration can be started early (no dependency)

Overall Performance

- N elements, D cycles latency/op
- (N/2+1)*D cycles:
 CPE = D/2





Loop Unrolling with Separate Accumulators (2x2)

```
void unroll2a combine(vec ptr v, data t *dest)
    long length = vec length(v);
    long limit = length-1;
    data t *d = get vec start(v);
    data t x0 = IDENT;
    data t x1 = IDENT;
    long i;
    /* Combine 2 elements at a time */
    for (i = 0; i < limit; i+=2) {
       x0 = x0 \text{ OP d[i]};
       x1 = x1 OP d[i+1];
    /* Finish any remaining elements */
    for (; i < length; i++) {
        x0 = x0 \text{ OP d[i]};
    *dest = x0 OP x1;
```

Different form of reassociation





Effect of Separate Accumulators

Method	Integer		Double FP		
Operation	Add	Mult	Add	Mult	
Combine4	1.27	3.01	3.01	5.01	
Unroll 2x1	1.01	3.01	3.01	5.01	
Unroll 2x1a	1.01	1.51	1.51	2.51	
Unroll 2x2	0.81	1.51	1.51	2.51	
Latency Bound	1.00	3.00	3.00	5.00	
Throughput Bound	0.50	1.00	1.00	0.50	

Int + makes use of two load units

$$x0 = x0 \text{ OP d[i];}$$

 $x1 = x1 \text{ OP d[i+1];}$

2x speedup (over unroll2) for Int *, FP +, FP *






Separate Accumulators

$$x0 = x0 \text{ OP d[i];}$$

 $x1 = x1 \text{ OP d[i+1];}$



What changed:

Two independent "streams" of operations

Overall Performance

- N elements, D cycles latency/op
- Should be (N/2+1)*D cycles:
 CPE = D/2
- CPE matches prediction!

What Now?





Unrolling & Accumulating

Idea

- Can unroll to any degree L
- Can accumulate K results in parallel
- L must be multiple of K

Limitations

- Diminishing returns
 - Cannot go beyond throughput limitations of execution units
- Large overhead for short lengths
 - Finish off iterations sequentially





Case

- Intel Haswell
- Double FP Multiplication
- Latency bound: 5.00. Throughput bound: 0.50

FP *	Unrolling Factor L							
K	1	2	3	4	6	8	10	12
1	5.01	5.01	5.01	5.01	5.01	5.01	5.01	
2		2.51		2.51		2.51		
3			1.67					
4				1.25		1.26		
6					0.84			0.88
8						0.63		
10							0.51	
12								0.52







Unrolling & Accumulating: Int +

Case

- Intel Haswell
- Integer addition
- Latency bound: 1.00. Throughput bound: 1.00

Int +	Unrolling Factor L							
K	1	2	3	4	6	8	10	12
1	1.27	1.01	1.01	1.01	1.01	1.01	1.01	
2		0.81		0.69		0.54		
3			0.74					
4				0.69		1.24		
6					0.56			0.56
8						0.54		
10							0.54	
12								0.56



STATE UNIVERSITY.



Achievable Performance

Method	Integer		Double FP	
Operation	Add	Mult	Add	Mult
Best	0.54	1.01	1.01	0.52
Latency Bound	1.00	3.00	3.00	5.00
Throughput Bound	0.50	1.00	1.00	0.50

- Limited only by throughput of functional units
- Up to 42X improvement over original, unoptimized code






Floating Point Registers





SIMD

■ SMID refers to "Single Instruction Multiple Data"



Single Instruction Multiple Data

PU: processing unit





SMID Instruction Set Extensions

- MMX (1996)
- 3DNow! (1988)
- SSE(1998) [Streaming SMID Extension]
- SSE2(2001)
- SSE3(2004)
 - 16 32-bytes registers
- AVX(2008) [Advance Vector Extension]
- AVX2(2013)
- AVX-512(2015)
 - 16 64-bytes registers
- AMX(2022) [Advance Matrix Extension]
 - designed to work on matrices to accelerate artificial intelligence (AI) / machine learning (ML) -related workloads.






Programming with SSE3

XMM Registers


- 16 total, each 16 bytes
- 16 single-byte integers







Scalar & SIMD Operations




STATE UNIVERSITY.


Programming with AVX2

YMM Registers









■ 8 single-precision floats

■ 4 double-precision floats

■ 1 single-precision float

■ 1 double-precision float






SIMD Operations (Single Instruction Multiple Data)


■ SIMD Operations: Single Precision

vaddps %ymm0, %ymm1, %ymm1



■ SIMD Operations: Double Precision

vaddpd %ymm0, %ymm1, %ymm1







Using Vector Instructions

Method	Integer		Double FP	
Operation	Add	Mult	Add	Mult
Scalar Best	0.54	1.01	1.01	0.52
Vector Best	0.06	0.24	0.25	0.16
Latency Bound	0.50	3.00	3.00	5.00
Throughput Bound	0.50	1.00	1.00	0.50
Vec Throughput Bound	0.06	0.12	0.25	0.12

Make use of AVX Instructions

- Parallel operations on multiple data elements
- See OPT:SIMD





What About Branches?

Challenge

 Instruction Control Unit must work well ahead of Execution Unit to generate enough operations to keep EU busy


```
404663:
                  $0x0, %eax
          MOV
                                        Executing
404668:
                  (%rdi),%rsi
          cmp
40466b:
          jge
                  404685
                                            How to continue?
40466d:
                  0x8(%rdi),%rax
          mov
404685:
          repz reta
```

• When encounters conditional branch, cannot reliably determine where to continue fetching






Modern CPU Design





Branch Outcomes

- When encounter conditional branch, cannot determine where to continue fetching
 - Branch Taken: Transfer control to branch target
 - Branch Not-Taken: Continue with next instruction in sequence
- Cannot resolve until outcome determined by branch/integer unit








Branch Prediction

Idea

- Guess which way branch will go
- Begin executing instructions at predicted position
 - But don't actually modify register or memory data







Branch Prediction Through Loop

```
Assume
                  (%rdx),%xmm0,%xmm0
401029:
          vmulsd
40102d:
                  $0x8, %rdx
          add
                                             vector length = 100
401031:
                  %rax,%rdx
          cmp
                               i = 98
                  401029
401034:
          ine
                                             Predict Taken (OK)
401029:
          vmulsd
                  (%rdx), %xmm0, %xmm0
40102d:
                  $0x8, %rdx
          add
401031:
                  %rax,%rdx
          cmp
                               i = 99
401034:
                  401029
          jne
                                             Predict Taken
                                             (Oops)
401029:
          vmulsd
                  (%rdx), %xmm0, %xmm0
40102d:
                  $0x8,%rdx
          add
                                                             Executed
                                             Read
401031:
                  %rax,%rdx
          cmp
                               i = 100
                                             invalid
401034:
                  401029
          jne
                                             location
401029:
          vmulsd
                  (%rdx),%xmm0,%xmm0
                                                              Fetched
40102d:
                  $0x8,%rdx
          add
401031:
                  %rax,%rdx
          cmp
                               i = 101
401034:
          jne
                  401029
```





Branch Misprediction Invalidation

```
Assume
401029:
          vmulsd
                  (%rdx), %xmm0, %xmm0
40102d:
                  $0x8,%rdx
          add
                                             vector\ length = 100
401031:
                  %rax,%rdx
          cmp
                                i = 98
401034:
          jne
                  401029
                                             Predict Taken (OK)
401029:
          vmulsd (%rdx),%xmm0,%xmm0
40102d:
          add
                  $0x8, %rdx
                  %rax,%rdx
401031:
          cmp
                                i = 99
401034:
          jne
                  401029
                                             Predict Taken
                                             (Oops)
401029:
          vmulsd (%rdx),%xmm0,%xmm0
40102d:
          add
                  $0x8, %rdx
401031:
                  %rax,%rdx
          cmp
                                i = 100
401034:
          ine
                  401029
                                                 Invalidate
          vmulsd (%rdx), %xmm0, %xmm0
401029:
401024.
          add
                  Sny8 grdy
401031 •
                  gray grdy
          cmn
                                i = 101
101031.
                  101029
```





Branch Misprediction Recovery

```
401029:
          vmulsd
                  (%rdx),%xmm0,%xmm0
40102d:
                  $0x8, %rdx
          add
                                    i = 99
                                               Definitely not taken
401031:
          cmp
                  %rax,%rdx
401034:
          jne
                  401029
401036:
                  401040
          jmp
                                                  Reload
                                                  Pipeline
         vmovsd %xmm0, (%r12)
401040:
```

Performance Cost

- Multiple clock cycles on modern processor
- Can be a major performance limiter





Getting High Performance

- Good compiler and flags
- Don't do anything stupid
 - Watch out for hidden algorithmic inefficiencies
 - Write compiler-friendly code
 - Watch out for optimization blockers: procedure calls & memory references
 - Look carefully at innermost loops (where most work is done)

Tune code for machine

- Exploit instruction-level parallelism
- Avoid unpredictable branches
- Make code cache friendly (Covered later in course)



