# C++11 BLWS (Wednesday 1)

#### **Smart Pointers**

```
1. C++11: std::shared_ptr
2. C++11: std::weak_ptr
3. C++11: std::unique_ptr
4. Deprecated std::auto_ptr
5. Boost: Smart Pointer
6. Boost: Scoped Pointer
7. Boost: Scoped Array
8. Boost: Intrusive Pointer
9. Boost: Pointer Container
10. Garbage Collection
```

Short breaks will be inserted as convenient.

1/25

Styled with styling.css by Martin Weitze

## C++11: std::shared\_ptr

With std::shared ptr C++11 introduced a Smart Pointer type that does reference counting on its pointee:

- When created by its default constructor it points to no object and creates an owner (reference) count set to zero.
- When created and initialized with a bare pointer it assumes it is the first and only one and creates an owner count set to 1.
- When initialized from another of its kind it points to the same object as the other (if any) and increments the - then shared - owner count.
- When assigned from another of its kind it first decrements the owner count and if that drops to zero, destroys the pointee; then it continues as if it were initialized from the pointer assigned to it.
- When it goes out of scope it also decrements the owner count and if that drops to zero, destroys the pointee.

#### **Shared Pointee Construction**

Per default an std::shared ptr is initialized with no pointee.

Given

```
class MyClass { ... MyClass(bool, double, std::string); ... };
```

an std::shared\_ptr can be initialized to point to a heap allocated object of type MyClass as follows:\*

```
std::shared_ptr<MyClass> p1{new MyClass(true, 3.14, "hi!")};
```

Or:

```
auto p2 = std::make_shared<MyClass>(true, 3.14, "hi!");
```

The usual recommendation is to prefer the second way over the first as it can reserve space for MyClass together with the helper object (holding owner and observer count\*) in a single heap allocation.

<sup>\*:</sup> The observer count has not yet been introduced; its purpose will become clear when std::weak\_ptr gets explained.

#### Shared Pointee Access

Given an std::shared\_ptr<SomeType> p the most typical access to the pointee is via overloaded operator\* or operator->, possibly after a testing whether there is an object:\*

```
if (p) ... *p ...; // access whole object
           ... p->m ...; // access data member m ... p->f(); // call member function f
```

Furthermore p.get() returns the address of the pointee (or nullptr), so

- it can bridge between std::shared ptr and legacy code that expects a native pointer,
- at least as long as the recipient is short-lived (compared to p) and
- does not assume ownership.



### **Shared Pointee Sharing**

Sharing the pointee is the *raison d'être* of a an std::share ptr. Therefore it is clear that the following code

```
auto p1 = std::make_shared<T>( ... ); // create T with c'tor arguments
                                  `--- as supplied here in parentheses
auto p2 = p1;
                    // OK
```

will create pointee which is then shared between p1 and p2 but with

```
auto p3 = p1.get()
```

p3 assumes to be the sole owner of the object created as pointee for p1.



According to the standard this is *Undefined Behavior* which in practice will typically lead dangling pointers ...\*

<sup>...</sup> and depending on the whether and when the released memory is put into use again to unpredictable aftereffects.

#### Shared From this

The same problem arises slightly disguised if an object already managed by a shared pointer needs "to return itself":\*

```
class MyClass {
    // ...
    MyClass* myself() { return this; }
};
```

If the address returned by MyClass::myself is used to initialize an std::shared\_ptr<MySelf> the problem is **exactly** the one discussed on the previous page.

This is the recipe to follow:

```
class MyClass : public std::enable_shared_from_this {
    // ...
    std::shared_ptr<MyClass> myself() { return shared_from_this(); }
};
```

<sup>\*:</sup> A closeley related scenario is given when an object needs to register a member function bound to itself as call-back to be invoked later.

#### **Shared Pointee Destruction**

The default way to destruct the pointee (when the owner count drops to zero) is with delete.

If this is not appropriate a custom deleter can be specified at construction time:

```
std::shared_ptr<std::FILE> auto_close_fp{
    std::fopen("somefile", "r"),
    [](FILE *fp) { if (fp) std::fclose(fp); }
};
```

If the pointee is guaranteed to be valid or a custom deleter with a single pointer argument of pointee-type that is nullptr-safe\* it could be specified directly:

```
if (auto fp = fopen("myfile", "w")) {
    std::shared_ptr<std::FILE> auto_close_fp{fp, std::fclose};
    ...
}
```

<sup>\*:</sup> Implementations of fclose differ in C, some are more robust and check the pointer argument for (FILE\*)0, but according to the C-Standard an invalid pointer causes undefined behavior.

## C++11: std::weak ptr

With std::weak ptr C++ introduced a companion to std::shared ptr, mainly used to break cyclic references, which would otherwise defeat one of the main motivations for using smart pointers as a light-weight, highefficiency garbage collector.

- An std::weak ptr acts as **observer** of a pointee **owned** by an std::shared ptr.
- As such it shares and manages an observer count (similar to but different from the owner count).
- A non-zero observer count will not keep the pointee alive if the owner count drops to zero.
- Therefore an std::weak ptr has no way to access the pointee directly via overloaded operator\* or operator->.
- To gain access it **first has to obtain an std::shared ptr** which might fail but if successful will keep the pointee alive even if all other owners cease to exist.

#### Weak Pointee Usage

Per default an std::weak ptr is initialized with no pointee.

Given std::shared\_ptr<MyClass> p an std::weak\_ptr can be initialized to the pointee referred by p (if any) with:

```
std::weak_ptr<MyClass> wp{p};
```

To get access to the pointee an std::shared\_ptr must be obtained and tested:

```
if (auto sp = wp.lock()) {
     // sp != nullptr
     // now owns the object wp had observed
    " *sp ...; // access whole object
... sp.m ...; // access data member m
... sp->f(); // call member function f
} // sp goes out of scope, if all other owners
 // are gone pointee will get destroyed here
```

## C++11: std::unique\_ptr

An std::unique\_ptr is - as the name suggests - the sole owner of its pointee:

- Therefore there can always be only one for each pointee, i.e.
  - it is **not possible** to copy-construct or copy-assign an std::unique\_ptr from another one of its kind (yields a compile time error), but
  - it **is possible** to move-construct or move-assign an std::unique\_ptr from another one of its kind.
- When an std::unique\_ptr goes out of scope or is re-assigned it first destroys its pointee (if any).

The implementation of std::unique\_ptr is very close to native pointers, i.e. same memory footprint, and also for most operations same performance, except those that need to care for destruction of a (previous) pointee.

(CC) BY-SA: Dipl.-Ing. Martin W eitzel im Auftrag von MicroConsult Training & Consult ing GmbH MICROCONSULT

### **Unique Pointee Construction**

Per default an std::unique\_ptr is initialized with no pointee.

Given any type T (a built-in type, a class from the standard library, or a user defined class) an std::unique ptr can be initialized to point

to a single heap allocated object of this type\*

```
std::unique_ptr<T> ptr{new T};
```

• or to an array of N heap allocated objects:

```
std::unique ptr<T[]> arr{new T[N]};
```

The appropriate deleter is set depending on the template instantiation argument T or T[].

Constructor arguments may be supplied as usual but there is no std::make\_unique analogous to std::make\_shared until C++14.

### **Unique Pointee Access**

Given an std::unique ptr<SomeType> p the most typical access to the pointee is via overloaded operator\*, operator->, or operator[] if the pointee is an array, possibly after a testing whether there is an object:\*

```
if (p) ... *p ...; // access whole object
       ... p->m ...; // access data member m
       ... p->f(); // call member function f
       ... p[i] ...; // access i-th whole object (0-origin)
```

#### Furthermore

- p.get() returns the address of the pointee (or nullptr), so it can bridge between std::unique\_ptr and legacy code that expects a native pointer with shorter lifetime as p;
- p.release() is similar but relinquishes ownership of the pointee which the recipient has to assume then.



### Moving Unique Pointers

As unique pointers can not be copied, the (deliberate) use as initial values for copy constructor arguments is not possible:

```
extern std::unique_ptr<MyClass> make_MyClass();
std::unique ptr<MyClass> p1 = make MyClass(); // OK (move c'tor)
std::unique_ptr<MyClass> p2(p1); // ERROR (no copy c'tor exists)
```

Instead the exsting pointer needs to be moved:

```
std::unique_ptr<MyClass> p3(std::move(p1)) // OK (p1 nullptr now!)
```

Same for assignment - move works, copy does not:

```
p1 = p3;  // ERROR (no copy assignment exists)
p1 = make_MyClass(); // OK (move assignment)
p1 = std::move(p3); // OK (p3 nullptr now!)
```

### **Unique Pointee Destruction**

Per default the pointee is destructed with delete or delete[] depending on the way an std::unique\_ptr has been created. Wrong pairing will not be detected at compile time but cause undefined runtime behaviour.\*

```
{ std::unique_ptr<T[]> ptr{new T};
...
} // destructor does delete[] on pointee address
```

Or:

```
{ std::unique_ptr<T> arr{new[N] T};
...
} // destructor does delete on pointee address
```



Pairing plain allocation with array deallocation or array allocation with plain deallocation has undefined behavior.

<sup>\*:</sup> In the best case this will cause an immediate crash with a good error message. But a crash may also occur much later with a misleading error message (if any) and therefore may be hard to relate to its original cause, or there may be a memory leak, memory overwritten with bad values, whatever ...

## Deprecated std::auto ptr

The only Smart Pointer in C++98 was std::auto ptr, which is deprecated since C++11.

- It had nearly the same behavior (and implementation) as std::unique ptr has now, but C++98 had no means to forbid the copying versions of constructor and assignment while still allowing the move versions.
- Therefore std::auto\_ptr had "copy"-constructor and -assignment which set their right hand side to NULL, i.e. the auto-pointer used for initialisation or from which the pointee was assigned lost its pointee.
- That came as a surprise to some developers expecting a "more intelligent" behaviour from a "smart pointer".

Or as Bjarne Stroustrup once put it: With C++11 std::unique ptr became what std::auto ptr in C++98 always should have been but couldn't, due to lacking proper language support.

### **Boost: Smart Pointer**

The term *Smart Pointer* is also used to subsume pointer-like helper classes in Boost:

- boost::shared\_ptr: much like std::shared\_ptr (the latter mostly emerged from the former);
- boost::weak\_ptr: much like std::weak\_ptr (the latter mostly emerged from the former);
- boost::scoped\_ptr and boost::scoped\_array: close to std::unique\_ptr but in two variants to provide different destructors to do a plain delete or a delete[] on the pointee.
- boost::intrusive\_ptr: similar in purpose to boost::shared\_ptr or std::shared\_ptr but storing the rerefence count inside the pointee (which therefore must be accessible).

(CC) BY-SA: Dipl.-Ing. Martin W eitzel im Auftrag von MicroConsult Training & Consult ing GmbH MICROCONSULT

## **Boost: Scoped Pointer**

A Scoped Pointer considers itself to be the sole owner of a

single object allocated on the heap

and will finally destroy its pointee (if any) when going out of scope or a new pointee is assigned.

- There is no copy-constructor and -assignment, the only way to reassign a boost::scoped\_ptr is via swap (available globally and as member function);
- Final destruction will use delete, therefore expecting the pointee is a single object.

If a boost::scoped\_ptr is initialized with an address not returned from new or is pointing to an array of objects returned from array heap allocation, undefined behaviour will result at deletion time.

## **Boost: Scoped Array**

A Scoped Array considers itself to be the sole owner of

an array of objects allocated on the heap

and will finally destroy its pointee (if any) when it goes out of scope or a new pointee is assigned.

- There is no copy-constructor and -assignment, the only way to reassign a boost::scoped\_array is via swap (available globally and as member function);
- Final destruction will use delete[], therefore expecting the pointee is an array of objects.

If a boost::scoped\_array is initialized with an address not returned from new or pointing to a single object returned from plain heap allocation, undefined behaviour will result at deletion time.

### **Boost: Intrusive Pointer**

An Intrusive Pointer is much like a reference counted boost::shared\_ptr or std::shared\_ptr.

- Instead of allocating reference counts separately it expects two global functions overladed for pointers to the pointee's type:
  - intrusive\_ptr\_add\_ref called when a new referrer for the pointee is added.
  - intrusive\_ptr\_release called when an existing referrer of the pointee gets re-assigned or goes out of scope.
- Furthermore there is a class boost::intrusive\_ref\_counter from which the pointee's class may be derived.\*

Boost recommends in case of doubt to prefer ordinary shared pointers and to avoid using intrusive pointers without good reason.

(CC) BY-SA: Dipl.-Ing. Martin W eitzel im Auftrag von MicroConsult Training & Consult ing GmbH MICROCONSULT

<sup>\*:</sup> Of course given its source is written from scratch or at least available and can be modified.

### Intrusive Pointer Example

To make MyClass usable with intrusive pointers it can be written as:\*

Or if it should be usable in a multi-threaded environment:

Then there can be intrusive pointers of MyClass:

```
boost::intrusive_ptr<MyClass> p{new MyClass(...)};
```

<sup>\*:</sup> The second template argument may be omitted as it defaults to boost::thread\_unsafe\_counter.

### **Boost: Pointer Container**

A number of Pointer Containers has been made available by boost, paralleling the STL containers with a pointer version that

- omits the pointer syntax at instantiation,
- adds one level of dereferencing to each member access, and
- considers its elements as pointers owning the memory pointed to.

While the former two are more a matter of convenience (see example on next slide), the last one has a severe semantical implication:

• If the container goes out of scope it deletes all the pointees of its (still) contained elements.\*



Storing non-owning pointers or pointers that do not even point to heap-allocated memory in a pointer container will cause undefined behaviour when the container goes out of scope.

tribis effect can alternatively be achieved by storing std::unique ptr-s in an ordinary container.

### Pointer Container Example

Storing and later on processing a boost::ptr\_vector:\*

In case the processing loop is not reached or left before the content is fully processed, **the pointer container destructor** will call delete for the pointers still contained, avoiding a memory leak.

<sup>\*:</sup> If a pointer container actually gets filled and processed concurrently as suggested by the comment in the example, mutexes or other synchronization techniques must be added as modifying operations are not thread-safe by themselves.

#### Pointer Container Substitute

Storing and later on processing a container of custodial pointers:\*

```
std::vector<std::unique ptr<MyClass>> v;
// fill in some content (probably in a loop):
... v.emplace back(new MyClass(...));
// process later (or maybe in a different thread):
while (!v.empty()) {
   ... *(v.back()) ... // access MyClass as a whole
   ... v.back()->m ... // access MyClass data member
   ... v.back()->f() ... // call MyClass member function
   v.pop_back();
}
```

In case the processing loop is not reached or left before the content is fully processed, the std::unique\_ptr destructors will call delete for their pointees, avoiding a memory leak.

 $<sup>^{*}</sup>$ : If an STL container actually gets filled and processed concurrently as suggested by the comment in the example, mutexes or other synchronization techniques must be added as modifying operations are not thread-safe by themselves.

## **Garbage Collection**

There is no garbage collection in C++ because of a specific difficulty:

- An address once obtained from new may not be visible in any memory location capable of holding a heap address, instead it
  - 1. may have been modified by address arithmetic ... which will of course be reverted before the delete takes place;
  - 2. may be temporarily stored in an integral type\* ... and will of course be restored to a pointer of appropriate type before the delete takes place.

Both are not a sign of bad programming style but have some valid uses in the C and C++ code base written in the last 35 years, so they cannot be easily ruled out by a new language standard.

 $<sup>^*</sup>$ : C/C++ even guarantees that when an integral type of sufficient size is used as temporary to store a pointer, after assigning the content back to the original pointer type the memory location pointed to will not have changed ... which by no means says that the bit patterns stays the same all the time!

#### C++11: Garbage Collection API

C++11 has defined an Garbage Collection ABI to enable *Interested Third* Parties to supply garbage collection as add-on library.\*

Mainly the ABI allows to say (put colloquially):

- The object at this address I name to you may appear not to be any longer in use.
  - You may not find it in any memory location capable of holding a heap pointer. Nevertheless be assured: it is still in use, so do not garbage collect it, I'll take up responsibility and return the reserved space in due course when its *really* not in use any more.
- In this memory area I name to you, you may find storage cells looking like pointers to heap memory, but they aren't.
  - So, in case there is any memory pending to be freed and its only use appears to be from inside this area, feel free to go ahead and garbage collect that stuff.

<sup>\*:</sup> It will surely be interesting to watch such efforts and whether any third-party garbage collector for C++ gets into wide-spread use. If so, then probably rather for new software, not for large amounts of legacy code (including libraries), and maybe only with additional support by compiler warnings.