# C++11 BLWS (Wednesday 2)

#### The STL and Beyond

- 1. STL Containers (recap)
- 2. STL Container Adapters
- 3. C++11: New Containers
- 4. Boost: Unordered
- 5. Boost: BiMap
- 6. Boost: Property Tree
- 7. STL Iterators (recap)
- 8. STL algorithms (recap)
- 9. C++11: New Algorithms
- 10. Boost: Range
- 11. Boost: Algorithm

Short breaks will be inserted as convenient.

Styled with styling.css by Martin Weitzel

# STL Containers (recap)

The STL and its template-based containers are at the heart of reusable library components standardized with C++98 (besides character strings and I/O-streams).

While there originally where

- · three sequential containers, and
- four associative containers,

C++11 had extended this by

- two more to a total of five sequential containers, and
- four more to a total of eight associative containers.

### Sequential Containers

Sequential containers more or less reflect typical basic data structures:

- Contiguous memory ...
  - ... of fixed size: std::array (new in C++11)
  - ... with heap allocation: `std::vector
- Lists were elements point to each other ...
  - o ... singly linked: std::forward\_list (new in C++11)
  - ... doubly linked: std::list
- Finally a mix of both if form of ...
  - ... adjacent memory in chunks: std::deque\*

\*: Abbreviating *Double Ende Queue* but pronounced as "deck".

#### **Choosing from Sequential Containers**

The choice largely depends on the required operations and their performance.

- When size can be fixed at compile time, std::array is best.\*
- If insertions and extractions need to occur at both or at different ends, this leaves std::list and std::deque ...
- ... otherwise std::vector would be a good default choice.
- Furthermore std::array and std::vector are the only to choose from when **memory layout compatible to builtin arrays** is mandatory.
- If random access is required std::array, std::vector and std::deque are the candidates ...
- ... otherwise, if insertions and extractions need to be efficient everywhere std::list and std::forward\_list.

<sup>\*:</sup> The picture is slightly different if only the *maximum size* can be fixed at compile time: depending on what is to be stored an std::array outrule itself when there is no way to tell "valid" from "invalid" elements and no suitable (default) constructor for the latter ones.

#### **Associative Containers**

Associative containers can be grouped around three dimenions:

- Whether they contain a key value pair or just a key:
  - map-types versus set-types
- Whether duplicate keys are allowed:
  - multi-types versus the others.
- Whether the underlying data structures is hash-based or a binary tree:
  - unordered-types versus the others.

Viewn pragmatically the data structure rather impacts the following:

- Need lookups be as fast as possible (O(1) even for huge collections)?
- Will there be sequential processing with preferred order of traversal?

If the first is more important as the second, prefer hash-based variant, if vice versa the tree-based one.

# **STL Container Adapters**

There are a number of use patterns for which the standard STL containers are more powerful as desirable - or in other words:

- · where some operations should be completely taken away,
- or be made available in a limited or different form.

This is the problem that adapters are designed to solve.

#### **Stacks**

The stl::stack adapts a container so that insertions and deletions can take place only at the same end.

- The default underlying container is an std::deque but also std::vector or std::list can be chosen.\*
- Instead of "back" and "front" as conventionally used for a sequential container
  - the most recent element (inserted last) is named "top", and
  - at that end elements are simply "push"-ed and "pop"-ed.
- Also there is no iterator style (or other interface) to iterate over the whole content.

<sup>\*:</sup> Interestingly an stl::forward\_list cannot be adapted to a stack, though it implements perfect stack\_semantics. This is because a stack adapter expects to work at the "back"-side of its underlying container, not the "front"-side that the singly linked list exposes.

#### **Stack Code Examples**

The following shows a possible way to fill ...

```
std::stack<int> data;
...
int x;
while (std::cin >> x)
    data.push(x);
... and to extract from a stack;
while (!data.empty()) {
    std::cout << data.top() << ' ';
    data.pop();
}</pre>
```

#### Queues

The stl::queue adapts a container so that insertions and deletions can take place only at different ends.

- The default underlying container is an std::deque but also std::vector can be chosen.
- The "back" and "front" ends as conventionally used for a sequential container are kept,
  - the most recent element (inserted last) is "push"-ed to the "back",
     and
  - the least recent element (inserted longest ago) may be "pop"-ed from the "front".
- Also there is no iterator style (or other interface) to iterate over the whole content.

#### **Queue Code Examples**

The following shows a possible way to fill ...

```
std::queue<int> data;
...
int x;
while (std::cin >> x)
    data.push(x);

... and to extract from a queue;

while (!data.empty()) {
    std::cout << data.front() << ' ';
    data.pop();
}</pre>
```

### **Priority Queues**

Considering its core interface an std::priority\_queue is similar to an an std::queue.

- The default underlying container is an std::vector.
- Elements are "push"-ed and "pop"-ed ...
  - ... while any extraction takes place on the "top"
  - ... which is the largest element currently contained.
- For flexibility a sort criteria is to be specified at construction time.

Priority queues can be - and probably are - implemented based on the STL algorithms for managing heap data structures.\*

<sup>\*:</sup> Here the term heap is used differently from its usual meaning, which is to refer to the *free store area* of the (technical) execution modell.

#### **Priority Queue Code Examples**

A priority queue storing int-s in the default order (extract greatest first) ...

std::priority\_queue<int> pq1;

... which is the same as specifying all defaults explicit ...

std::priority\_queue<int, std::vector<int>, std::less<int>> pq1;

... and vice versa (extracts smallest first):\*

std::priority\_queue<int>, std::vector<int>, std::greater<int>> pq2;

Note that the comparison functor orders by what goes to the top last!

<sup>\*:</sup> As the sort functor is the third template argument the second (the container on which the priority queue is based) must be specified too, even if the default applies.

### C++11: New Containers

The following were introduced with C++11:

- std::array a wrapper around builtin arrays
- std::forward\_list a singly linked list
- std::unordered\_set the hash-based version of std::set
- std::unordered\_multiset the hash-based version of std::mulitset
- std::unordered\_map the hash-based version of std::map
- std::unordered\_multimap the hash-based version of std::mulitmap
- std::bitset is not a new container but has been slightly extended.
- The iterator interface of all existing containers has been extended with the member functions cbegin(), cend(), crbegin(), and crend() to obtain const\_iterators from non-const containers.

### std::array

This wrapper makes builtin arrays look more like standard conforming containers. It has to be instantiaed with a type and a size argument:\*

```
std::array<double, 50> data;
```

The wrapper adds:

- Standard embedded type definitions like size\_type, value\_type etc.
- Standard member functions like size(), empty() etc.
- Everything required for walking over the content using the iterator interface.

The latter not only makes iterating over builtin arrays no more different from the other containers, but also enables range based for loops.

On the other hand, builtin arrays are compatible with range-based for, so - if this were the only reason to use the wrapper - it actually isn't!

<sup>\*:</sup> The size argument cannot be omitted, even if the array definition is combined with an initialization!

### std::forward\_list

This container makes a minimum-overhead, singly-linked list available.

It has the following differences to the probably well-known std::list:

- An std::forward\_list does not know its size so testing for contained elements must be done empty(), not size() == 0.
- Insertion and extraction take place at the "front"-side, hence
  - member functions front, push\_front, and pop\_front are available
  - but not their counterparts working at the "back"-side.\*
- When walking over the content with an iterator, it does not allow to insert new elements at the iterator position but only after it.
  - This is technically easy to explain as a minimum-overhead iterator can not know the element prior to the one it refers to.
  - Therefore the member function implementing insertion is not called insert but insert\_after.

#### hash-based containers

Hash-based containers will improve lookup-performance at the price that the order when iterating over the container is not predictable:

- With a decent hash function most any key will be found in O(1) time or a decission made that a key does not exist.
- When the container is filled by incrementally adding more elements over time, it also will extend its reserved space incrementally and herefore its elements must more or less frequently be re-hashed.
- Differently from std::vector iterators keep valid even when elements are rehashed.
- Though no specific order can be epected when walking over a hashbased container, elements with the same key follow each other (as elements with te same hash-value will do).
- Elements of a set or keys of a map are not required to implement operator< but operator==.\*</li>

<sup>\*:</sup> Though probably not to expect in practice this could have subtle effects if an ordered container were exchanged with its unordered cousin or vice versa.

## **Boost: Unordered**

If a C++ implementation does not (yet) make hash-based containers available Boost.Unordered may be used as drop-in replacement.

The most important difference is that the standard containers are in namespace std while their Boost couterparts are in namespace boost.

### Boost: BiMap

Boost.Bimap allows bidirectional key-value lookup.

#### The interface to

- nameservice.left is like that of a map<IP, Host>;
- nameservice.right is like that of a map<Host, IP>.

# **Boost: Property Tree**

Boost.Property\_Tree is a recursive data structure.

A node (starting with the single root node)

- has some data value (typically an std::string)
- and a list of children (empty for leaf nodes),
  - each of which holds a key (typically an std::string)
  - o and a sub-tree starting with a node that
    - has some data value
    - and a list of children
      - each of which holds a key
      - and a sub-tree starting with ...

### Property Tree (cont.)

When represented in main memory a property tree can be navigated programmatically (e.g. searched for sub-notes).\*

Besides that in can be made persistent in an external representation, i.e. written to file and read back in a number of serialization formats:

- JSON (JavaScript Object Notation)
- Info-File format (similar to JSON with lesser punctuation)
- Ini-File format (as widely used by MS-Windows "in the old days")
- XML (with a fixed conversion schema, no generic DTD or document object model)

Therefore property trees are well suited for storing configuration data or state information between consecutive program exections, though that's not their sole possible use.

<sup>\*:</sup> Navigation is only within one level, there is no automatic recursion, i.e. any descending into a sub-tree must be explicit, it will never happen automatically.

#### C++11 Extensions to Bitsets

The std::bitset class from C++98 has been extended in C++11 with string conversions.

One effect that can be achieved with extended bitsets is that binary numbers can be converted from and two an representation as printable '0' and '1' characters in a string literal or on output.

### **Binary Literals**

With the macro BOOST\_BINARY (defined in <boost/utility.hpp>) it becomes possibiltiy to specify binary literals as series of 0 and 1:\*

- BOOST\_BINARY(1 1 1 1) yields 0xF or 15
- B00ST\_BINARY(1 0 1 0 1 0 ) yields 0x1A or 42
- BOOST\_BINARY\_UL(1 0 1 0 1 0 ) yields 0x1AL or 42uL
- B00ST\_BINARY(10 0000 0000) yields 0x400 or 1024

<sup>\*:</sup> In C++14 internal support for binary literals is expected so that examples like above could be written as 0b1111, 0x101010 etc. Some C++ compilers already support this as an exetension.

# STL Iterators (recap)

The STL was designed around the idea that the glue between *Containers* and *Algorithms* should be provided by *Iterators* which were further categorized by their capabilities:

- **Input- and Output-Iterators** same operations as Forward-Iterators but restricted order of application.
- **Forward-Iterators** comparable to each other, operator++ in preund postfix version, operator\* for derefenrencing.
- Bidirectional-Iterators in addition operator - in pre- and postfix version.
- **Random-Access-Iterators** in addition operator+= and operator-= to increment and decrement in steps of more than one and operator-to determine distance between two iterators.

Containers document the iterator category they offer and Algorithms the one they require.

#### STL Iterators Efficiency

To allow a maximally efficient implementation of iterators with respect to

- Memory Footprint and
- Runtime Performance

safety requirements were not cast into any of the C++ standards but left as a *Quality of Implementation* (QoI) issue.\*

For most containers an interator can be as efficient as a pointer.

Walking through all elements of a container with an iterator does

- not require any large support data structure, and
- may map to very few assembly level instructions.

<sup>\*:</sup> What is frequently misunderstood is that implementations actually **can** prefer safety over efficiency; e.g. the original STL as used internally be Hewlett-Packard had a special macro that could be defined at compile time to enable many additional tests. If some vendor (or free implementations) of standard C++ do not exploit the leeway given by the standard to add "safety" features then presumably because there is not *that* much from the respective clients to have such improvements ... or at least not at the price to pay for it, in terms of lost efficiency.

# STL algorithms (recap)

Algorithms originally supplied when the STL was standardized with C++98 are too numerous to give them full coverage here.

Instead refer to a good documentation source like named below or equivalent:

- http://en.cppreference.com/w/cpp/algorithm
- http://www.cplusplus.com/reference/algorithm/

The following only recapitulates some of the systematic approach and after this highlights a few C++11 extensions.

#### Iterator Interface to Containers

Algorithms usually deal with containers but abstract that fact away by taking two iterator arguments:

```
std::vector<int> data;
...
// add all values in container
const auto n = std::accumulate(data.begin(), data.end(), 0);
```

This may seem as a minor inconvenience but easily allows for subranges without the need for specialized algorithms:

```
assert(data.size() > 3);
// add values in container except the first two and the last
const auto n = std::accumulate(data.begin()+2, data.end()-1, 0);
```

Note that a typical requirement of algorithms is that of the two iterators specifying the range the second is *reachable* from the first.

This means, if the first is incremented often enough it must - while staying within the container bounds - compare equal to the second.

#### Generic Iterator Interface

Another reason that makes the iterator interface to algorithms powerfull is that iterators are not required to connect to containers.

It can make sense to define a class that exposes the same interface as an iterator while actually calculating values on the run.

```
class Iota
    : public std::iterator<std::input_iterator_tag, int> {
    int i, s;
public:
    Iota(int i_ = 0, int s_ = 1) : i(i_), s(s_) {}
    int operator*() { return i; }
    Iota operator++() { return Iota(i += s, s); }
    Iota operator++(int) { i += s; return Iota(i - s, s); }
};
```

Given the above class a container be filled with a number range:

```
std::copy_n(Iota(), 20, std::back_inserter(data));
std::copy_n(Iota(10, 3), 20, std::back_inserter(data));
```

### Algorithm Families

To the degree to which it makes sense STL algorithms come in families:

- A plain algorithm (say: std::remove) does its work modifying a container, basing its decission (which elements to remove) on a fixed value.
- The \_copy-version (i.e. std::remove\_copy) leaves the original container unmodified, storing the result to another container\*
- The \_if-versions (i.e. std::remove\_if) generalizes the predicate throung the use a *Callable* as last argument (function, functor, lambda).
- If both of the above versions exist they will also be found combined into a \_copy\_if version (i.e. std::remove\_copy\_if).

<sup>\*:</sup> The target for this operation again is specified with an *iterator* that gets used as *output iterator*; it will kind of an inserter.

### Using Algorithms on Builtin Array

With builtin pointers used as iterators, all of the STL algorithms can also be used to process builtin arrays.

There is price to pay: any algorithm that logically removes values cannot make the array smaller - so it returns the new end.

#### Return Values from Removals

Generally algorithms that logically remove elements from a container return the "new end".

This is also true if the physical size of the underlying container could be made smaller, like for the sequential STL containers:

Physically reducing the container size must happen explicitely:

```
x.erase(new_end, x.end());
```

### Return Values from Filling

Many algorithms that fill a container - in case of families especially the \_copy-version - return an iterator pointing after the last element copied to the result.

This is often useful, especially when the filling state of a builtin array needs to be tracked

```
const int N = 32767;
static_assert(ckdiv2(N+1), "N must be one less than a power of two");
int data[N], *data_end = data;
for (int n = 1, i = (N+1)/2; i > 0; ++n, i /= 2)
    data_end = std::fill_n(data_end, i, n);
```

# C++11: New Algorithms

Again the following does not intend to be exhaustive, instead it should just shortly highlight C++11 additions for those who know STL algorithms quite well from C++98.

- The largest group in which most start with is\_. These algorithms check for certain properties of a container content.
- A few algorithms have probably been added because a substantial number of people found them "missing".
  - In one subgroup the new algorithms will actually improve performance.
  - Others could have been well expressed with the available algorithms but an algorithm with an expressive name makes the intent clearer.

<sup>\*:</sup> Or rather sequences, as the interface is of course through iterators, no underlying needs to be exposed.

### New Ways to Search through Containers

The following algorithms take a predicate as argument to check for each container element, but all have the chance to shortcut the evaluation:

- std::all\_of can return false the first time the predicate is false
- std::any\_of can return true the first time the predicate is true
- std::none\_of can return false the first time the predicate is true

Though each of the above can be written in terms of any other, it is usually clearest to express the intent with the fewest negations.

#### Compare:

```
std::none_of(x.begin(), x.end(), [](int v) { return (v > 0); }
!std::any_of(x.begin(), x.end(), [](int v) { return (v > 0); }
std::all_of(x.begin(), x.end(), [](int v) { return !(v > 0); }
```

<sup>\*:</sup> For a good test if a condition is clearly expressed imagine you read it out load to someone at the telephone. Which one of these do you think will be understood then without any doubt or asking back?

#### New Ways to Fill Containers

A new algorithm to copy from one container to another one allows to specify the number of elements instead of an end iterator.

This allows sometime for easier calculations:

```
const std::size_t Ndata = 50, Nresult = 20;
int data[100], *data_filled = data;
int result[50], *result_filled = result;
... // data has been filled up to data_filled
... // result also has content up to result_filled;
// copy from data to result until
// - data is exhausted, or
// - result is completely full:
const auto available = data_filled - data;
const auto freespace = result + Nresult - result_filled;
std::copy_n(result_filled, std::max(availble, freespace), data);
```

Also it is now easily possible to fill a container with increasing values:\*

```
std::iota(data, data+Ndata, 1); // fills in: 1 2 3 4 ...
```

<sup>\*:</sup> Note that std::iota expects container elements to exist. E.g. if an std::vector had to be filled it must be resized first.

### Algorithms Adding Negation

Elements to be copied from one container to another one can now be selected with a predicate.

Given two sequential containers  ${\sf x}$  and result with element type T the following code would do this:

With a negated predicate std::remove\_copy\_if will have the same effect.

Similarly when searchin for the first container element that does not have a given property, checked with a predicate:

```
... std::find_if_not(x.begin(), x.end(), [](T elem) { return ...; });
```

Again, std::find\_if with a negated predicate will do the same search.

### Algorithms Improving Performance

It is now possible to search for the minimum and maximum value at the same time, passing over the sequence only once and doing lesser comparisons:\*

```
auto result_it = std::minmax_sequence(x.begin(), x.end());
... result_it.first ... // iterator denoting minimum element
... result_it.last ... // iterator denoting maximum
```



Of course, the iterators returned must not be derefeneced without a prior test if the sequence might have been empty!

There is also a simpler version returning a reference to two variables:

```
int a, b;
... // fill in values
auto result = std::min_max(a, b);
... result.first ... // reference to variable holding the smaller value
... result.last ... // reference to variable holding the greater value
// or store into two separate variables:
int min, max;
std::tie(min, max) = std::minmax(a, b);
```

(CC) BY-SA: Dipl.-Ing. Martin Weitzel im Auftrag von MicroConsult Training & Consulting GmbH

### **Boost: Range**

Boost.Range extends the basic idea to combine iterators to pairs - called ranges - with the goal eliminate the need to always have to supply two arguments when just a single container is involved.\*

- Additional algorithms accept these ranges instead of the separate arguments their STL counterparts require.
- The concept of ranges is then extended so that algorithm can be glued together with a high degree of flexibility.

<sup>\*:</sup> Of course the "two arguments" style adopted by the original STL has the advantage that subranges do not require additional algorithms that allow to specify parts of containers.

# **Boost: Algorithm**

Boost.Algorithm is a collection of algorithms to extending the STL.

Parts of this collection have been standardized with C++11, others are intended to become part of C++14, some will still stay "Boost only".