Memory Management: Address space and Segmentation

CS 571: Operating Systems (Spring 2020) Lecture 6a

Yue Cheng

Some material taken/derived from:

GEORGE

• Wisconsin CS-537 materials created by Remzi Arpaci-Dusseau. Licensed for use under a Creative Commons Attribution-NonCommercial-ShareAlike 3.0 Unported License.

Announcement

HW1 posted on BB

• Due next Monday, 03/09, 11:59pm

Today's outline

- 1. Address space
- 2. Virtual memory accesses
- 3. Relocation

4. Segmentation

Early Systems


- OS was a set of libraries
- OS sat in memory starting at physical address 0
- The rest was used by running program

0KB **Operating System** (code, data, etc.) 64KB **Current Program** (code, data, etc.)

max

Multiprogramming & Time Sharing

- OS makes sure each process is confined to its own address space in memory
- One naïve implementation:
 - <base register & limit register> pair



The Abstraction

 A process has a set of addresses that map to a collection of bytes

This set is called an address space

Review: what stuff is in an address space?


Match that Segment!

```
int x;
int main(int argc, char *argv[]) {
    int y;
    int *z = malloc(sizeof(int));
}
```

```
x code main data y heap z stack
```


Match that Segment!

```
int x;
int main(int argc, char *argv[]) {
    int y;
    int *z = malloc(sizeof(int));
}
```



Match that Segment!


```
int x;
int main(int argc, char *argv[]) {
    int y;
    int *z = malloc(sizeof(int));
}
```



In OSTEP

The Address Space

- Address space
 - An easy-to-use abstraction of physical memory
- The address space is the running program's view of memory in the system
 - Virtual address or logical address
 - Physical address refers to those seen by the memory unit hardware
- The user program generates logical addresses; it never sees the real physical addresses



the code segment: where instructions live

the heap segment: contains malloc'd data dynamic data structures (it grows downward)

(it grows upward) the stack segment: contains local variables arguments to routines, return values, etc.

High-level Goals

- Transparency
 - User program behaves as if it has its own private physical memory
- Efficiency
 - Space and time efficient memory virtualization
 - Performance relies on hardware support (e.g., TLBs)
- Protection
 - Isolation property
 - User process shouldn't access or affect anything outside its own address space

All Memory Addresses You See are Virtual

 Any address that a programmer can see is a virtual address

```
#include <stdio.h>
#include <stdlib.h>
int main(int argc, char *argv[]) {
   printf("location of code : %p\n", (void *) main);
   printf("location of heap : p\n", (void *) malloc(1));
    int x = 3;
   printf("location of stack : %p\n", (void *) &x);
   return x;
```

Result:

```
location of code : 0x1095afe50
location of heap : 0x1096008c0
location of stack: 0x7fff691aea64
```

```
#include <stdio.h>
#include <stdlib.h>

int main(int argc, char *argv[]) {
    int x;
    x = x + 2;
}

int main(int argc, char *argv[]) {
    int x;
    x = x + 2;
}
```

```
_main:
0000000100000fa0 pushq%rbp
0000000100000fa1 movq %rsp, %rbp
0000000100000fa4 xorl %eax, %eax
0000000100000fa6 movl %edi, -0x4(%rbp)
000000100000fa9 movq %rsi, -0x10(%rbp)
000000100000fad movl 0x8(%rbp), %edi
000000100000fb0 addl $0x2, %edi
000000100000fb3 movl %edi, 0x8(%rbp)
000000100000fb6 popq %rbp
0000000100000fb7 retq
```

% otool -tv demo (or objdump in Linux)

```
main:
                                               000000100000fa0 pushg %rbp
#include <stdio.h>
                                               000000100000fal movg %rsp, %rbp
#include <stdlib.h>
                                               000000100000fa4 xorl %eax, %eax
                                               0000000100000fa6 movl %edi, -0x4(%rbp)
                                               000000100000fa9 movq %rsi, -0x10(%rbp)
int main(int argc, char *argv[]) {
                                               000000100000fad movl 0x8(%rbp), %edi
    int x;
                                               000000100000fb0 addl $0x2, %edi
    x = x + 2;
                                               000000100000fb3 movl %edi, 0x8(%rbp)
                                               000000100000fb6 popq %rbp
                                               0000000100000fb7 retg
```

% otool -tv demo (or objdump in Linux)

```
% \text{rip} = 0 \times 100000 \text{ fad}
% \text{rbp} = 0 \times 200
```

Memory accesses:

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

```
%rip = 0x100000fad
%rbp = 0x200
```

Memory accesses:

Fetch instr. at addr 0x100000fad

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

```
% \text{rip} = 0 \times 100000 \text{fad}
% \text{rbp} = 0 \times 200
```

Memory accesses:

Fetch instr. at addr 0x100000fad Exec, load from addr 0x208

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

```
%rip = 0x100000fb0
%rbp = 0x200
```

Memory accesses:

Fetch instr. at addr 0x100000fad Exec, load from addr 0x208

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

```
%rip = 0x100000fb0
%rbp = 0x200
```

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

Memory accesses:

Fetch instr. at addr 0x100000fad Exec, load from addr 0x208

Fetch instr. at addr 0x100000fb0

```
%rip = 0x100000fb0
%rbp = 0x200
```

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

Memory accesses:

Fetch instr. at addr 0x100000fad Exec, load from addr 0x208

Fetch instr. at addr 0x100000fb0 Exec, no load

```
%rip = 0x100000fb3
%rbp = 0x200
```

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

Memory accesses:

Fetch instr. at addr 0x100000fad Exec, load from addr 0x208

Fetch instr. at addr 0x100000fb0 Exec, no load

```
%rip = 0x100000fb3
%rbp = 0x200
```

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

Memory accesses:

Fetch instr. at addr 0x100000fad Exec, load from addr 0x208

Fetch instr. at addr 0x100000fb0 Exec, no load

Fetch instr. at addr 0x100000fb3

```
%rip = 0x100000fb3
%rbp = 0x200
```

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

Memory accesses:

Fetch instr. at addr 0x100000fad Exec, load from addr 0x208

Fetch instr. at addr 0x100000fb0 Exec, no load

Fetch instr. at addr 0x100000fb3 Exec, store to addr 0x208

```
% \text{rip} = 0 \times 100000 \text{fb3}
% \text{rbp} = 0 \times 200
```

```
0x100000fad movl 0x8(%rbp), %edi
0x100000fb0 addl $0x2, %edi
0x100000fb3 movl %edi, 0x8(%rbp)
```

Memory accesses:

Fetch instr. at addr 0x100000fad Exec, load from addr 0x208

Fetch instr. at addr 0x100000fb0 Exec, no load

Fetch instr. at addr 0x100000fb3 Exec, store to addr 0x208

How to relocate the memory access in a way that is transparent to the process?

How to Run Multiple Programs?

- Approaches:
 - Static relocation
 - Dynamic relocation
 - Segmentation


Static Relocation


 Idea: rewrite each program before loading it into memory as a process


 Each rewrite uses different addresses and pointers


• Change jumps, loads, etc.


Q: Can any addresses be unchanged?











How to Run Multiple Programs?


- Approaches:
 - Static relocation
 - Dynamic relocation
 - Base
 - Base-and-Bounds
 - Segmentation

Base


 Idea: translate virtual address to physical by adding an offset each time

- Store base addr in a base register
- Each process has a different value in the base register when running


Base Relocation




Base Relocation




Base Relocation







Virtual	Physical
P1: load 100, R1	




Virtual	Physical
P1: load 100, R1	load 2148, R1




Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	




Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	load 10340, R1




Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	load 10340, R1
P2: load 2000, R1	



Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	load 10340, R1
P2: load 2000, R1	load 12240, R1





Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	load 10340, R1
P2: load 2000, R1	load 12240, R1
P1: load 2000, R1	



Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	load 10340, R1
P2: load 2000, R1	load 12240, R1
P1: load 2000, R1	load 4048, R1


Base Relocation Hardware





Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	load 10340, R1
P2: load 2000, R1	load 12240, R1
P1: load 2000, R1	load 4048, R1

Can P1 hurt P2? Can P2 hurt P1?



Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	load 10340, R1
P2: load 2000, R1	load 12240, R1
P1: load 2000, R1	load 4048, R1
P1: store 9241, R1	store 11289, R1

Can P1 hurt P2? Can P2 hurt P1?


How to Run Multiple Programs?


- Approaches:
 - Static relocation
 - Dynamic relocation
 - Base
 - Base-and-Bounds
 - Segmentation


- Idea: add bound register to avoid "overflow"
- Two CPU registers
 - Base register
 - Bounds register (or limit register)

```
physical addr = virtual addr + base
```

- The base-and-bounds hardware referred to as <u>Memory Management Unit</u> (MMU)
- Protection: The hardware provides special instructions to modify the base and bounds register
 - Allowing OS to change them when different processes run
 - Privileged (only in kernel mode)








Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	load 10340, R1
P2: load 2000, R1	load 12240, R1
P1: load 2000, R1	load 4048, R1
P1: store 9241, R1	

Can P1 hurt P2?



Virtual	Physical
P1: load 100, R1	load 2148, R1
P2: load 100, R1	load 10340, R1
P2: load 2000, R1	load 12240, R1
P1: load 2000, R1	load 4048, R1
P1: store 9241, R1	Interrupt!

Can P1 hurt P2?

Base-and-Bounds Pros/Cons

Pros?

- Fast + simple
- Little bookkeeping overhead (2 registers)

Cons?

- Not flexible
- Wastes memory for large memory addresses


Base-and-Bounds Pros/Cons

- Pros?
 - Fast + simple
 - Little bookkeeping overhead (2 registers)
- Cons?
 - Not flexible
 - Wastes memory for large memory addresses

Problems with Base-and-Bounds?

 Simple base-and-bounds approach wastes a chunk of "free" space between stack and heap

• Impossible to run a program when its entire address space is greater than the memory capacity



0KB

1KB

2KB

3KB

4KB

5KB

6KB

How to Run Multiple Programs?

- Approaches:
 - Static relocation
 - Dynamic relocation
 - Base
 - Base-and-Bounds
 - Segmentation

Segmentation

• Idea: generalize base-and-bounds


- Each base+bounds pair is a segment
- Use different segments for heap and memory
 - Requires more registers
- Resize segments as needed

Segmentation (cont.)


 A segment is a contiguous portion of the address space

- A program is a collection of segments
- A segment can be a logical unit:
 - E.g., main program, procedure, function, object, local variables, global variables, common block, stack, heap, symbol table, or arrays, etc.


Logical View of Segmentation




Virtual address space of a process



physical memory





Segfault!

Access to the address 7KB ...


Segmentation Architecture

Logical address consists of a pair:


<segment-number, offset>

- Segment table maps two-dimensional physical addresses. Each table entry has:
 - base contains the starting physical address where the segments reside in memory
 - limit specifies the length of the segment (or bound)
- Segment-table base register (STBR) points to the segment table's location in memory
- Segment-table length register (STLR) indicates number of segments used by a process
 - segment number s is legal if s < STLR

Segmentation Hardware



Example of Segmentation



Worksheet