What You Must Know about Memory, Caches, and Shared Memory

Kenjiro Taura

Contents

- Introduction
- Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Introduction

- so far, we have learned
 - parallelization across cores,
 - vectorization (SIMD) within a core, and
 - instruction level parallelism
- ullet another critical factor you must know to understand program performance is $data\ access$

Why data access is so important?

• no data, no computation

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
for (i = 0; i < M; i++)

for (j = 0; j < N; j++)

for (k = 0; k < K; k++)

C(i,j) += A(i,k) * B(k,j);
```

Why data access is so important?

• no data, no computation

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
for (i = 0; i < M; i++)

for (j = 0; j < N; j++)

for (k = 0; k < K; k++)

C(i,j) += A(i,k) * B(k,j);
```

• accessing data is sometimes far more costly than calculation

Why data access is so important?

• no data, no computation

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
for (i = 0; i < M; i++)

for (j = 0; j < N; j++)

for (k = 0; k < K; k++)

C(i,j) += A(i,k) * B(k,j);
```

- accessing data is sometimes far more costly than calculation
- moreover, the cost of the same data access instruction significantly differs depending on where dare are coming from
 - registers
 - caches
 - main memory
 - another processor's cache

Conceptual goals of the study

- understand how are processors, caches and memory are connected
- understand the behavior of caches, so as to reason about how much traffic the algorithm will generate between main memory ↔ caches (and among cache levels)
- ullet \Rightarrow be able to reason about a performance limit of your program, due to the memory

• latency: get a sense of how many cycles it takes to get data from main memory and caches

- latency: get a sense of how many cycles it takes to get data from main memory and caches
- bandwidth: get a sense of how much data CPU can bring from main memory and caches

- latency: get a sense of how many cycles it takes to get data from main memory and caches
- bandwidth: get a sense of how much data CPU can bring from main memory and caches
- what does "memory bandwidth" we see in a processor spec sheet really mean? e.g.,
 - the processor data sheet of E5-2698 (68 GB/s): http://ark.intel.com/products/81060/Intel-Xeon-Processor-E5-2698-v3-40M-Cache-2_30-GHz
 - in general,
 - 8 bytes × DDR frequency × memory channel, per CPU socket
 - our "big" CPU (Skylake-X Gold 6130)
 - 8 bytes \times 2666 MHz \times 6 channels = 128 GB/sec per socket

 128×4 sockets = 512 GB/sec in the entire node

- latency: get a sense of how many cycles it takes to get data from main memory and caches
- bandwidth: get a sense of how much data CPU can bring from main memory and caches
- what does "memory bandwidth" we see in a processor spec sheet really mean? e.g.,
 - the processor data sheet of E5-2698 (68 GB/s):
 http://ark.intel.com/products/81060/Intel-Xeon-Processor-E5-2698-v3-40M-Cache-2_30-GHz
 - in general,
 - 8 bytes × DDR frequency × memory channel, per CPU socket
 - our "big" CPU (Skylake-X Gold 6130)
 - 8 bytes \times 2666 MHz \times 6 channels = 128 GB/sec per socket
 - 128×4 sockets = 512 GB/sec in the entire node
- Can we achieve this easily? If not, when/how can we?

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

What does memory performance imply for FLOPS?

• many computationally *efficient* algorithms do not touch the same data too many times


What does memory performance imply for FLOPS?

- many computationally *efficient* algorithms do not touch the same data too many times
- e.g., O(n) algorithms \rightarrow uses a single element only a constant number of times (on average)

What does memory performance imply for FLOPS?

- many computationally *efficient* algorithms do not touch the same data too many times
- e.g., O(n) algorithms \rightarrow uses a single element only a constant number of times (on average)
- if data \gg cache for such an algorithm, the algorithm's performance is often limited by the memory bandwidth (or, worse, latency), not processor's compute throughput

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```



```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
y = M
```

- accesses 16 nnz bytes and performs 2 nnz flops
 - assuming elements of double (8 bytes) and indexes of ints (4 bytes × 2), not counting access to x and y
 - details aside, it performs only an FMA / element

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
y = M
A
A
```

- accesses 16 nnz bytes and performs 2 nnz flops
 - assuming elements of double (8 bytes) and indexes of ints (4 bytes × 2), not counting access to x and y
 - details aside, it performs only an FMA / element
- to achieve Skylake-X peak (32 DP FMAs per core per cycle), a core must access 32 matrix elements (= 512 bytes) / cycle

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
y = M
```

- accesses 16 nnz bytes and performs 2 nnz flops
 - assuming elements of double (8 bytes) and indexes of ints (4 bytes × 2), not counting access to x and y
 - details aside, it performs only an FMA / element
- to achieve Skylake-X peak (32 DP FMAs per core per cycle), a core must access 32 matrix elements (= 512 bytes) / cycle
- assuming 2.0GHz processor and the matrix \gg cache, it requires the *main memory bandwidth* of

```
\approx 512 \text{ bytes} \times 2.0 \text{ GHz} = 1 \text{ TB/sec per core (no way!)}
```

- ullet say an algorithm performs C flops (or computation in more general) on N bytes of data
 - ullet assume it needs to access every element of the N bytes at least once (likely the case)

- ullet say an algorithm performs C flops (or computation in more general) on N bytes of data
 - ullet assume it needs to access every element of the N bytes at least once (likely the case)
- there are two obvious lower bounds on the time to complete the algorithm

$$T \geq \frac{C}{\text{the peak FLOPS}} \quad \text{(compute)}$$

$$T \geq \frac{N}{\text{the peak memory bandwidth}} \quad \text{(memory)}$$

- ullet say an algorithm performs C flops (or computation in more general) on N bytes of data
 - ullet assume it needs to access every element of the N bytes at least once (likely the case)
- there are two obvious lower bounds on the time to complete the algorithm

$$T \ge \frac{C}{\text{the peak FLOPS}}$$
 (compute)

$$T \ge \frac{N}{\text{the peak memory bandwidth}}$$
 (memory)

- often, the latter is much larger and such algorithms are called "memory-bound"
- O(N), $O(N \log N)$ algorithms are almost always memory bound

• memory-bound \iff

$$\frac{C}{\text{the peak FLOPS}} \ll \frac{N}{\text{the peak memory bandwidth}}$$

$$\iff \frac{C}{N} \ll \frac{\text{the peak FLOPS}}{\text{the peak memory bandwidth}}$$

- the LHS: arithmetic intensity or compute intensity of the algorithm
- ullet the reciprocal of RHS: the byte per FLOPS of the machine
- note that being memory-bound suggests it is inefficient in the processor utilization view point, but it is efficient in time-complexity sense (it is not necessarily a bad thing)

Note: dense matrix-vector multiply

• the same argument applies even if the matrix is *dense*

```
for (i = 0; i < M; i++)
for (j = 0; j < N; j++)
y[i] += a[i][j] * x[j];</pre>
```

Note: dense matrix-vector multiply

• the same argument applies even if the matrix is *dense*

```
for (i = 0; i < M; i++)
for (j = 0; j < N; j++)
y[i] += a[i][j] * x[j];

A
```

• MN flops on (MN + M + N) elements

Note: dense matrix-vector multiply

• the same argument applies even if the matrix is *dense*


```
for (i = 0; i < M; i++)
for (j = 0; j < N; j++)
y[i] += a[i][j] * x[j];

A
```

- MN flops on (MN + M + N) elements
- ⇒ it performs only an FMA / matrix element


Dense matrix-matrix multiply

• the argument does *not* apply to matrix-matrix multiply (we've been trying to get close to CPU peak)



Dense matrix-matrix multiply

• the argument does *not* apply to matrix-matrix multiply (we've been trying to get close to CPU peak)



• for $N \times N$ square matrices, it performs N^3 FMAs on $3N^2$ elements

Why dense matrix-matrix multiply *can* be efficient?

• assume $M \sim N \sim K$

```
for (i = 0; i < M; i++)

for (j = 0; j < N; j++)

for (k = 0; k < K; k++)

C(i,j) += A(i,k) * B(k,j);
```

- a microscopic argument
 - the innermost statement

```
C(i,j) += A(i,k) * B(k,j)
```

still performs (only) 1 FMA for accessing 3 elements

- but the same element (say C(i,j)) is used many (K) times in the innermost loop
- similarly, the same A(i,k) is used N times
- \Rightarrow after you use an element, if you reuse it many times before it is evicted from a cache (even a register), then the memory traffic is hopefully not a bottleneck

A simple memcpy experiment ...

```
double t0 = cur_time();
memcpy(a, b, nb);
double t1 = cur_time();
```

A simple memcpy experiment ...

```
double t0 = cur_time();
memcpy(a, b, nb);
double t1 = cur_time();
```

```
1 $ gcc -03 memcpy.c

2 $ ./a.out $((1 << 26)) # 64M long elements = 512MB

536870912 bytes copied in 0.117333 sec 4.575611 GB/sec
```

A simple memcpy experiment ...

```
double t0 = cur_time();
memcpy(a, b, nb);
double t1 = cur_time();
```


• much lower than the advertised number ...

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?


Cache and memory in a single-core processor

you almost certainly know this (*caches* and main memory), don't you?




..., with multi level caches, ...

recent processors have *multiple levels* of caches (L1, L2, ...)




..., with multicores in a chip, ...

- a single chip has several cores
- each core has its *private* caches (typically, L1 and L2)
- cores in a chip share a cache (typical, L3) and main memory




..., with simultaneous multithreading (SMT) in a core, ...

• each core has two *hardware threads*, which share L1/L2 caches and some or all execution units




..., and with multiple sockets per node.

- each node has several chips (sockets), connected via an interconnect (e.g., Intel QuickPath, AMD HyperTransport, etc.)
- each socket serves a part of the entire main memory
- each core can still access any part of the entire main memory



Today's typical single compute node



Typical cache sizes

• L1 : 16KB - 64KB/core

• L2 : 256KB - 1MB/core

• L3 : $\sim 50 \text{MB/socket}$

• speed:

L1 > L2 > L3 > main memory

 \bullet speed:

• capacity:

L1 < L2 < L3 < main memory

• speed:

• capacity:

• each cache holds a subset of data in the main memory

 $L1, L2, L3 \subset main memory$

• speed:

• capacity:

• each cache holds a subset of data in the main memory

$$L1, L2, L3 \subset main memory$$

• typically but not necessarily,

$$L1 \subset L2 \subset L3 \subset main memory$$

• speed:

• capacity:

• each cache holds a subset of data in the main memory

$$L1, L2, L3 \subset main memory$$

• typically but not necessarily,

$$L1 \subset L2 \subset L3 \subset main memory$$

 which subset is in caches? → cache management (replacement) policy

ullet a cache generally holds data in $recently\ accessed$ addresses, up to its capacity

- a cache generally holds data in *recently accessed* addresses, up to its capacity
- this is accomplished by the LRU replacement policy (or its approximation):
 - every time a load/store instruction misses a cache, the least recently used data in the cache will be replaced

- a cache generally holds data in *recently accessed* addresses, up to its capacity
- this is accomplished by the LRU replacement policy (or its approximation):
 - every time a load/store instruction misses a cache, the least recently used data in the cache will be replaced
- \bullet \Rightarrow a (very crude) approximation; data in 32KB L1 cache

 $\approx most \ recently \ accessed \ 32K \ bytes$


- a cache generally holds data in *recently accessed* addresses, up to its capacity
- this is accomplished by the LRU replacement policy (or its approximation):
 - every time a load/store instruction misses a cache, the least recently used data in the cache will be replaced
- ullet \Rightarrow a (very crude) approximation; data in 32KB L1 cache

$\approx most \ recently \ accessed \ 32K \ bytes$

• due to implementation constraints, real caches are slightly more complex

Cache organization: cache line


- a cache = a set of fixed size *lines*
 - typical line size = 64 bytes or 128 bytes,



a 32KB cache with 64 bytes lines (holds most recently accessed 512 distinct blocks)

Cache organization: cache line


- a cache = a set of fixed size *lines*
 - typical line size = 64 bytes or 128 bytes,
- a single line is the minimum unit of data transfer between levels (and replacement)



a 32KB cache with 64 bytes lines (holds most recently accessed 512 distinct blocks)

Cache organization: cache line

- a cache = a set of fixed size *lines*
 - typical line size = 64 bytes or 128 bytes,
- a single line is the minimum unit of data transfer between levels (and replacement)



a 32KB cache with 64 bytes lines (holds most recently accessed 512 distinct blocks)

data in 32KB L1 cache (line size 64B)

 $\approx most\ recently\ accessed\ 512\ distinct\ lines$


Associativity of caches

full associative: a block can occupy any line in the cache, regardless of its address

direct map: a block has only *one* designated "seat" (*set*), determined by its address

K-way set associative: a block has K designated "seats", determined by its address

- direct map \equiv 1-way set associative
- full associative $\equiv \infty$ -way set associative



An example cache organization

• Skylake-X Gold 6130

level	line size	capacity	associativity
L1	64B	$32 \mathrm{KB/core}$	8
L2	64B	$1 \mathrm{MB/core}$	16
L3	64B	22MB/socket (16 cores)	11

• Ivy Bridge E5-2650L


level	line size	capacity	associativity
L1	64B	32KB/core	8
L2	64B	$256 \mathrm{KB/core}$	8
L3	64B	36MB/socket (8 cores)	20

What you need to remember in practice about associativity

- avoid having addresses used together "a-large-power-of-two" bytes apart
- corollaries:
 - avoid having a matrix with a-large-power-of-two number of columns (a common mistake)
 - avoid managing your memory by chunks of large-powers-of-two bytes (a common mistake)
 - avoid experiments only with $n = 2^p$ (a *very* common mistake)
- why? ⇒ they tend to go to the same set and "conflict misses" result

Conflict misses


- consider 8-way set associative L1 cache with 32KB (line size = 64B)
 - $32KB/64B = 512 (= 2^9)$ lines
 - $512/8 = 64 (= 2^6)$ sets
- \Rightarrow given an address a, a[6:11] (6 bits) designates the set it belongs to (indexing)



• if two addresses a and b are a multiple of 2^{12} (4096) bytes apart, they go to the same set

A convenient way to understand conflicts

• it's convenient to think of a cache as two dimensional array of lines. e.g. 32KB, 8-way set associative = 64 (sets) × 8 (ways) array of lines




A convenient way to understand conflicts

• formula 1:

if addresses are this much apart, they go to the same set

• e.g., 32KB 8-way set associative ⇒ the worst stride = 4096



A convenient way to understand conflicts


• lesser powers of two are significant too; continuing with the same setting (32KB, 8way-set assocative)

stride	the number of sets	utilization
	they are mapped to	
2048	2	1/32
1024	4	1/16
512	8	1/8
256	16	1/4
128	32	1/2
64	64	1

• formula 2: you stride by


$$P \times \text{line size} \quad (P \text{ divides } S)$$

- \Rightarrow you utilize only 1/P of the capacity
- N.B. formula 1 is a special case, with P = S



A remark about virtually-indexed vs. physically-indexed caches

- ullet caches typically use *physical* addresses to select the set an address maps to
- so "addresses" I have been talking about are physical addresses, not virtual addresses you can see as pointer values



• since virtual \rightarrow physical mapping is determined by the OS (based on the availability of physical memory),


"two virtual addresses 2^b butes apart"

does not necessarily imply "their physical addresses 2^b bytes apart"

• so what's the significance of the stories so far?

A remark about virtually-indexed vs. physically-indexed caches

- virtual \rightarrow physical translation happens with page granularity (typically, $2^{12} = 4096$ bytes)
- \bullet \to the last 12 bits are intact with the translation



A remark about virtually-indexed vs. physically-indexed caches


• therefore,

"two virtual addresses 2^b bytes apart" \rightarrow "their physical addresses 2^b bytes apart"

for up to page size $(2^b \le page \ size)$

 \bullet \to the formula 2 is valid for strides up to page size


•	, оне тоги
stride	utilization
4096	1/64
2048	1/32
1024	1/16
512	1/8
256	1/4
128	1/2
64	1



Remarks applied to different cache levels

- small caches that use only the last 12 bits to index the set make no difference between virtually- and physically-indexed caches
- for larger caches, the utilization will similarly drop up to stride = 4096, after which it will stay around 1/64
- L1 (32KB/8-way) vs. L2 (256KB/8-way)

stride	utilization
	$\sim 1/64$
16384	$\sim 1/64$
8192	$\sim 1/64$
4096	1/64
2048	1/32
1024	1/16
512	1/8
256	1/4
128	1/2
64	1



Avoiding conflict misses

• e.g., if you have a matrix:

```
float a[100][1024];
then a[i][j] and a[i+1][j] go to the same set in L1 cache;
```

- \Rightarrow scanning a column of such a matrix will experience almost 100% cache miss
- avoid it by:

```
float a[100][1024+16];
```

- consider a cache of
 - capacity = C bytes
 - line size = Z bytes
 - associativity = K

- consider a cache of
 - capacity = C bytes
 - line size = Z bytes
 - associativity = K
- approximation 0.0 (only consider C; $\equiv Z = 1, K = \infty$):

Cache \approx most recently accessed C distinct addresses

- consider a cache of
 - capacity = C bytes
 - line size = Z bytes
 - associativity = K
- approximation 0.0 (only consider C; $\equiv Z = 1, K = \infty$):

Cache \approx most recently accessed C distinct addresses

• approximation 1.0 (only consider C and Z; $K = \infty$):

Cache \approx most recently accessed C/Z distinct lines

- consider a cache of
 - capacity = C bytes
 - line size = Z bytes
 - associativity = K
- approximation 0.0 (only consider C; $\equiv Z = 1, K = \infty$):

Cache \approx most recently accessed C distinct addresses

• approximation 1.0 (only consider C and Z; $K = \infty$):

Cache \approx most recently accessed C/Z distinct lines

- approximation 2.0 (consider associativity too):
 - depending on the stride of the addresses you use, reason about the utilization (effective size) of the cache
 - in practice, avoid strides of "line size $\times 2^{b}$ "

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Assessing the cost of data access

- we like to obtain cost to access data in each level of the caches as well as main memory
- latency: time until the result of a load instruction becomes available
- bandwidth: the maximum amount of data per unit time that can be transferred between the layer in question to CPU (registers)

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

How to measure a latency?

ullet prepare an array of N records and access them repeatedly

How to measure a latency?

- \bullet prepare an array of N records and access them repeatedly
- to measure the *latency*, make sure N load instructions make a chain of dependencies (link list traversal)


```
for (N times) {
   p = p->next;
}
```

How to measure a latency?

- \bullet prepare an array of N records and access them repeatedly
- to measure the *latency*, make sure N load instructions make a chain of dependencies (link list traversal)

```
for (N times) {
   p = p->next;
}
```


• make sure p->next links all the elements in a random order (the reason becomes clear later)



Data size vs. latency

• main memory is local to the accessing thread


```
$ numactl --cpunodebind 0 --interleave 0 ./mem
$ numactl -N 0 -i 0 ./mem # abbreviation
```




How long are latencies

- heavily depends on in which level of the cache data fit
- environment: Skylake-X Xeon Gold 6130 (32KB/1MB/22MB)


size	level	latency	latency]
		(cycles)	(ns)	
12,736	L1	4.004	1.31] ;
103,616	L2	13.80	4.16	poolimonto
2,964,928	L3	77.40	24.24	l of col
301,307,584	main	377.60	115.45	




- if a cache stricly follows the LRU replacement policy, once data overflow the cache, repeated access to the data will quickly become *almost-always-miss*
- the "cliffs" in the experimental data look gentler than the theory would suggest




- if a cache stricly follows the LRU replacement policy, once data overflow the cache, repeated access to the data will quickly become *almost-always-miss*
- the "cliffs" in the experimental data look gentler than the theory would suggest



- if a cache strictly follows the LRU replacement policy, once data overflow the cache, repeated access to the data will quickly become *almost-always-miss*
- the "cliffs" in the experimental data look gentler than the theory would suggest




- ullet part of the gap is due to virtual \to physical address translation
- another factor, especially for L3 cache, will be a recent replacement policy for cyclic accesses (c.f. http://blog.stuffedcow.net/2013/01/ivb-cache-replacement/)



Latency to a remote main memory

• make main memory remote to the accessing thread

```
1 $ numactl -N 0 -i 1 ./mem
```




Contents


- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Bandwidth of a random link list traversal


$$bandwidth = \frac{total\ bytes\ read}{elapsed\ time}$$

• in this experiment, we set record size = 64






The "main memory" bandwidth



- \ll the memcpy bandwidth we have seen ($\approx 4.5 \text{ GB/s}$)
- not to mention the "memory bandwidth" in the spec

Why is the bandwidth so low?

• while traversing a single link list, only a single record access (64 bytes) is "in flight" at a time



• in this condition,


$$bandwidth = \frac{a \ record \ size}{latency}$$

• e.g., take 115.45 ns as a latency

$$\frac{64 \text{ bytes}}{115.45 \text{ ns}} \approx 0.55 \text{ GB/s}$$


How to get more bandwidth?

• just like flops/clock, the only way to get a better throughput (bandwidth) is to perform many load operations concurrently



How to get more bandwidth?

• just like flops/clock, the only way to get a better throughput (bandwidth) is to perform many load operations concurrently




• there are several ways to make it happen; let's look at conceptually the most straightforward: traverse multiple lists

```
for (N times) {
   p1 = p1->next;
   p2 = p2->next;
   ...
}
```

Contents


- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?



• let's zoom into "main memory" regime (size > 100MB)


Bandwidth to the local main memory (not cache)

• an almost proportional improvement up to ~ 10 lists




Bandwidth to a remote main memory (not cache)


- pattern is the same (improve up to ~ 10 lists)
- remember the remote latency is longer, so the bandwidth is accordingly lower



• observation: bandwidth increase fairly proportionally to the number of lists, matching our understanding, . . .




• observation: bandwidth increase fairly proportionally to the number of lists, matching our understanding, . . .



• question: ... but up to ~ 10 , why?

• observation: bandwidth increase fairly proportionally to the number of lists, matching our understanding, . . .



- question: ... but up to ~ 10 , why?
- answer: there is a limit in the number of load operations in flight at a time

- Line fill buffer (LFB) is the processor resource that keeps track of outstanding cache misses, and its size is 10 in Haswell
 - I could not find the definitive number for Skylake-X, but it will probably be the same

- Line fill buffer (LFB) is the processor resource that keeps track of outstanding cache misses, and its size is 10 in Haswell
 - I could not find the definitive number for Skylake-X, but it will probably be the same
- this gives the maximum attainable bandwidth per core

 $\frac{\text{cache line size} \times \text{LFB size}}{\text{latency}}$

- Line fill buffer (LFB) is the processor resource that keeps track of outstanding cache misses, and its size is 10 in Haswell
 - I could not find the definitive number for Skylake-X, but it will probably be the same
- this gives the maximum attainable bandwidth per core

$$\frac{\text{cache line size} \times \text{LFB size}}{\text{latency}}$$

• this is what we've seen (still much lower than what we see in the "memory bandwidth" in the spec sheet)

- Line fill buffer (LFB) is the processor resource that keeps track of outstanding cache misses, and its size is 10 in Haswell
 - I could not find the definitive number for Skylake-X, but it will probably be the same
- this gives the maximum attainable bandwidth per core

$$\frac{\text{cache line size} \times \text{LFB size}}{\text{latency}}$$

- this is what we've seen (still much lower than what we see in the "memory bandwidth" in the spec sheet)
- how can we go beyond this? ⇒ the only way is to use multiple cores (covered later)

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

- we've learned:
 - maximum bandwidth \approx as many memory accesses as possible always in flight
 - there is a limit due to LFB entries (10 in Haswell)

- we've learned:
 - maximum bandwidth \approx as many memory accesses as possible always in flight
 - there is a limit due to LFB entries (10 in Haswell)
- so far, we have achieved larger bandwidth by traversing multiple lists explicitly (sometimes difficult if not impossible to apply)

- we've learned:
 - maximum bandwidth \approx as many memory accesses as possible always in flight
 - there is a limit due to LFB entries (10 in Haswell)
- so far, we have achieved larger bandwidth by traversing multiple lists explicitly (sometimes difficult if not impossible to apply)
- fortunately, the life is not always that tough; there are other ways to issue many memory accesses concurrently
 - make addresses sequential
 - 2 make address generations independent
 - operation prefetch by software (make address generations go ahead)
 - use multiple threads/cores


- we've learned:
 - maximum bandwidth \approx as many memory accesses as possible always in flight
 - there is a limit due to LFB entries (10 in Haswell)
- so far, we have achieved larger bandwidth by traversing multiple lists explicitly (sometimes difficult if not impossible to apply)
- fortunately, the life is not always that tough; there are other ways to issue many memory accesses concurrently
 - make addresses sequential
 - 2 make address generations independent
 - operation prefetch by software (make address generations go ahead)
 - use multiple threads/cores
- remember, all boil down to keep as many memory accesses as possible (up to LFB entries) in flight

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Make addresses sequential


- again build a (single) linked list, but this time, p->next always points to the immediately following block
- note that *the instruction sequence is identical* to before; only addresses differ



Bandwidth of traversing address-ordered list


• a factor of 10 faster than random case, but this time with only a single list

bandwidth of random list traversal vs address-ordered list traversal [0,1073741824]



The reason this is faster

- hardware prefetcher
- CPU watches the sequence of addresses accessed
- sequential addresses (addresses of a small constant stride) trigger CPU's hardware prefetcher
- CPU issues load instruction ahead of actual data stream on your behalf, to keep the maximum number of loads in flight




Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Make address generations independent

• if addresses of memory accesses can be computed without values returned from previous loads, CPU can issue them concurrently


```
for (N times) {
    j = ... /* not use a[·] */
    a[j];
}
```



• note: it's *not* a prefetch (but a real fetch)

Bandwidth when not traversing a list


- ptrchase : chase pointers of a random list
- random : access random addresses, but w/o pointer chasing
- sequential : access sequential addresses, w/o pointer chasing



Main memory bandwidth

- pointer chase ≪ random < sequential
- random is $\approx 5x$ faster than traversing a single random list


list traversal vs random access vs sequential access [33554432,1073741824]



Main memory bandwidth (random vs. sequential)

- sequential gets $\approx 3x$ more bandwidth than random
- may not be as bad as you thought?
- but why is there *any* difference, if both have the same number of loads in flight?

list traversal vs random access vs sequential access [33554432,1073741824]



Random (index) vs. sequential

- if both can have up to 10 (LFB entries) outstanding L1 cache misses, why is there *any* difference?
- I don't have a definitive answer, but presumably,
 - the hardware prefetcher happens at multiple levels (\rightarrow L1 and \rightarrow L2)
 - prefetchers to L2 are not subject of the LFP entries limit (the limit will be slightly more)
 - prefething to L2 make effective latency to the processor smaller

When "random access" is really bad

 \bullet in practice, when random vs. sequential makes a large ($\gg 2)$ difference, it's because

a single element < a single cache line

- recall that touching a single byte in a cache line still brings the whole line (64 bytes)
- e.g., if you access an array of float (4 bytes) randomly, the bandwidth of *useful* data is amplified by a factor of 16 (= 64/4)

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

- hardware prefetch happens only for sequential (a small constant stride) accesses
- for other patterns, you the programmer may know addresses you are going to access soon

- hardware prefetch happens only for sequential (a small constant stride) accesses
- for other patterns, you the programmer may know addresses you are going to access soon
- *if* you can generate those addresses much ahead of actual load instructions, you can *prefetch* them

- hardware prefetch happens only for sequential (a small constant stride) accesses
- for other patterns, you the programmer may know addresses you are going to access soon
- if you can generate those addresses much ahead of actual load instructions, you can prefetch them
- instructions:
 - prefetcht $\{0,1,2\}$
 - prefetchnta

- hardware prefetch happens only for sequential (a small constant stride) accesses
- for other patterns, you the programmer may know addresses you are going to access soon
- *if* you can generate those addresses much ahead of actual load instructions, you can *prefetch* them
- instructions:
 - prefetcht $\{0,1,2\}$
 - prefetchnta
- intrinsics:

```
__builtin_prefetch(a [, rw, hint])
```

• truth is, there are actually not many cicumstances this is useful

- truth is, there are actually not many cicumstances this is useful
- \bullet why? by the time you can prefetch it, you can likewise load it!

- truth is, there are actually not many cicumstances this is useful
- why? by the time you can *prefetch* it, you can likewise *load* it!
- in our example,
 - no point in applying it to index-based accesses (CPU will issue many load instructions already)

- truth is, there are actually not many cicumstances this is useful
- \bullet why? by the time you can prefetch it, you can likewise load it!
- in our example,
 - no point in applying it to index-based accesses (CPU will issue many load instructions already)
 - on the other hand, it's difficult to apply it to list traversal (it takes equally long time to generate address to prefetch)


- truth is, there are actually not many cicumstances this is useful
- \bullet why? by the time you can prefetch it, you can likewise load it!
- in our example,
 - no point in applying it to index-based accesses (CPU will issue many load instructions already)
 - on the other hand, it's difficult to apply it to list traversal (it takes equally long time to generate address to prefetch)
- the only way to apply it is to change the data structure of the linked list

- truth is, there are actually not many cicumstances this is useful
- \bullet why? by the time you can prefetch it, you can likewise load it!
- in our example,
 - no point in applying it to index-based accesses (CPU will issue many load instructions already)
 - on the other hand, it's difficult to apply it to list traversal (it takes equally long time to generate address to prefetch)
- the only way to apply it is to change the data structure of the linked list
- but how?

have another pointer pointing many elements ahead


```
for (N times) {
   p = p->next;
   prefetch(p->prefetch);
}
```

• it should point to Q elements ahead to have Q concurrent accesses in flight




"prefetch pointers" pointing to several elements ahead

Result



Summary: bandwidth of various access patterns

• sequential (w/o pointer chase) > sorted list > random (w/o pointer chase) ≈ 5 random lists ≈ a random list + software prefetch > a random list



Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Memory bandwidth with multiple cores


• the bandwidth to a single core is limited by LFB entries and is much lower than the memory bandwidth itself

$$\frac{\text{transfer (line) size } \times \text{ LFB entries}}{\text{latency}}$$

• you can go beyond that by using multiple cores and this is the only way

Memory bandwidth with multiple cores

- run up to 16 threads,
- each running on a distinct physical core of a single socket
- allocate all the data on the same socket (numactl N 0 i 0)
- note: they are still random pointer chasing




With random indexing and sequential accesses

- similar experiments with random indexing/sequential accesses
- ~ 80 GB/sec with sequential accesses by ≥ 12 threads
- the theoretical peak is

8 bytes $\times 2.666$ GHz $\times 6$ channels = 128 GB/sec

bandwidth with various methods and number of threads [33554432,1073741824]




With multiple CPU sockets

• the total bandwidth depends on how to place threads and data

threads\data	CPU x	CPU y	all CPUs	local CPU
CPU x	1-local	1-remote	1-all	1-local
all CPUs	all-1	all-1	all-all	all-local

- control threads/data placement by numactl command
- combine it with OMP_PROC_BIND=true to get a desired effect



numact1 command (1)

- usage (see man numactl for details)
- 1 \$ numactl options command
 - for underlying system calls, see man -s 3 numa
- processors
 - -N x runs threads only on the CPU(s) x. e.g.,

```
\ numactl -N 0 command # threads on CPU 0
```

• --physcpubind x runs threads only on core(s) x. e.g.,

```
# threads on cores 0-11 and 16-27
$ numactl --physcpubind 0-11,16-27 command
```

numact1 command (2)

- memory (data)
 - -i y allocates data (physical pages) on CPU(s) y

```
$ numactl -i 0,1 command # data on CPU 0 or 1
$ numactl -i all command # data on all CPUs
```

• -1 allocates physical pages to the CPU that touches the page for the first time (*first touch policy*; the default policy of Linux)

```
1 $ numactl -1 command
```

About the -1 option

- -1 (equivalent: --localalloc) allocates the physical page for a logical page on the CPU that first touches it (first touch)
- allocated physical pages do not move thereafter (unless you do so by move_pages() system call)
- don't be fooled by its name; it is *not* a policy that automagically makes memory accesses local
- quite contrary, it often makes a *hotspot* in a single CPU, especially when only one thread initializes (first-touches) the data
- -iall is not optimal, but often much safer for parallel applications

OpenMP thread placement

• combine them with OMP_NUM_THREADS= and OMP_PROC_BIND=true to get a desired effect. e.g.,

```
$ OMP_NUM_THREADS=48 OMP_PROC_BIND=true numact1 --physcpubind 0-11,16-27,32-43,48-59 -1 command
```

to

- run 12 threads on each CPU (of a host in the big partition)
- and use the first touch policy

Achieved bandwidth

- Skylake X 6130 ×4 CPUs (a host of the "big" partition)
- use 12 (of 16) cores on each CPU
- in each measurement, each thread reads $\approx 640 \text{MB}$ sequentially 10 times

setting	threads	bandwidth (GB/sec)
1-local	12	85
1-remote	12	16
1-all	12	57
all-1	48	2
all-all	48	97
all-local	48	320

Remarks on remote access bandwidths


- numbers for remote accesses are ridiculously low
- the measurement is repeated 6 times and there were almost no variations in the result (within a few per cents)
- I am suspecting a wrong BIOS snoop setting (https://software.intel.com/en-us/forums/software-tuning-performance-optimization-platform-montopic/602160)

setting	threads	bandwidth (GB/sec)
1-local	12	85
1-remote	12	16
1-all	12	57
all-1	48	2
all-all	48	97
all-local	48	320


Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

• if thread P writes to an address a and then another thread B reads from a, Q observes the value written by P




• if thread P writes to an address a and then another thread B reads from a, Q observes the value written by P




- ordinary load/store instructions accomplish this (hardware shared memory)
- this should not be taken for granted; processors have *caches* and a single address may be cached by multiple cores/sockets

- ⇒ processors sharing memory are running a complex, *cache coherence protocol* to accomplish this
- roughly,




- ⇒ processors sharing memory are running a complex, *cache coherence protocol* to accomplish this
- roughly,
 - a write to an address by a processor "invalidates" all other cache lines holding the address, so that no caches hold "stale" values



Shared memory

- ⇒ processors sharing memory are running a complex, cache coherence protocol to accomplish this
- roughly,
 - a write to an address by a processor "invalidates" all other cache lines holding the address, so that no caches hold "stale" values
 - ② a read to an invalid line causes a miss and searches for a cache holding its "valid" value




• each line of a cache is inone of the following states


Modified (), Shared (), Invalid ()

- each line of a cache is inone of the following states


 Modified (), Shared (), Invalid ()
 - Modified () \iff you can read and write the line without invoking a transaction
 - Shared () \iff you can read but not write the line without invoking a transaction
 - Invalid (—) \iff you can neither read nor write the line without invoking a transaction




• a single address may be cached in multiple caches (lines)



- a single address may be cached in multiple caches (lines)
- \bullet \Rightarrow there are only two legitimate states for each line
 - \bullet one Modified (owner) + others Invalid (\bullet , \bullet , \bullet , \bullet , \bullet , ...)



- a single address may be cached in multiple caches (lines)
- \bullet \Rightarrow there are only two legitimate states for each line
 - one Modified (owner) + others Invalid (\blacksquare , \blacksquare , \blacksquare , \blacksquare , \blacksquare , ...)
 - ② no Modified (□, ■, □, □, ■, ...)



Cache states and transaction

- suppose a processor reads or writes an address and finds a line caching it
- what happens when the line is in each state:

	Modified	Shared	Invalid
read	hit	hit	read miss
write	hit	write miss	read miss; write miss

Cache states and transaction

- suppose a processor reads or writes an address and finds a line caching it
- what happens when the line is in each state:

	Modified	Shared	Invalid
read	hit	hit	read miss
write	hit	write miss	read miss; write miss

- read miss: \rightarrow
 - there may be a cache holding it in Modified state (owner)
 - searches for the owner and if found, downgrade it to Shared
 - —, <mark>—</mark>, —, [—], —, … ⇒ —, —, [—], —, …

Cache states and transaction

- suppose a processor reads or writes an address and finds a line caching it
- what happens when the line is in each state:

	Modified	Shared	Invalid
read	hit	hit	read miss
write	hit	write miss	read miss; write miss

- read miss: \rightarrow
 - there may be a cache holding it in Modified state (owner)
 - searches for the owner and if found, downgrade it to Shared
 - —, —, [—], —, … ⇒ —, —, [—], —, …
- write miss: \rightarrow
 - there may be caches holding it in Shared state (sharer)
 - searches for sharers and downgrade them to Invalid
 - ullet ullet , ullet ,

MESI and MESIF

• exntensions to MSI have been commonly used

MESI and MESIF

- exitensions to MSI have been commonly used
- MESI: MSI + Exclusive (owned but not modified)
 - when a read request finds no other caches that have the line, it owns it as Exclusive
 - Exclusive lines do not have to be written back to main memory when discarded

MESI and MESIF

- exntensions to MSI have been commonly used
- MESI: MSI + Exclusive (owned but not modified)
 - when a read request finds no other caches that have the line, it owns it as Exclusive
 - Exclusive lines do not have to be written back to main memory when discarded
- MESIF: MESI + Forwarding (a cache responsible for forwarding a line)
 - used in Intel QuickPath
 - when a line is shared by many readers, one is designated as the Forwarder
 - when another cache requests the line, only the forwarder sends it and the new requester becomes the forwarder
 - (in MSI or MESI, all sharers forward it)


How to measure communication latency?

• measure "ping-pong" latency between two threads

```
volatile long x = 0;
volatile long y = 0;
```

```
1  (ping thread)
2  for (i = 0; i < n; i++) {
3     x = i + 1;
4     while (y <= i);
5  }

(pong thread)
2  for (i = 0; i < n; i++) {
3     while (x <= i);
4     y = i + 1;
5  }</pre>
```



Environment

- Skylake X Gold 6130 ("big" partition of the IST cluster)
- 2 hardware threads \times 16 cores \times 4 sockets (= 128 processors seen by OS)
- ensure variables x and y are at least 64 bytes apart (not on the same cache line)
- bind both threads on specific processors by OpenMP environment variable OMP_BIND_PROC=true
- try all combinations of threads (i.e., with p threads, measure all the p(p-1) pairs) and show a matrix

Result

• (i, j) indicates the roundtrip latency (in reference clocks) between processor i and j

src	dest	latency
0	1-15	≈ 800
0	16-63	≈ 1100
0	64	≈ 110
0	65-79	≈ 450
0	80-127	≈ 1100

• a beautiful pattern emerges which is obviously telling

Result

- e.g., which processor is "close" to processor 0?
 - 64 is closest
 - 1-15 and 65-79 are close
 - 16-63 and 80-127 are farthest
- a natural interpretation
 - x and (x + 64) are two hardware threads on a core
 - 0-15 (and 65-79) are the 16 physical cores (32 hwts) on a socket
 - others are on different sockets

What they imply to parallel algorithms?

- you do not want to have many threads concurrently updating the same data
- remember SpMV COO?

```
// assume inside #pragma omp parallel
...
#pragma omp for
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
#pragma omp atomic
   y[i] += Aij * x[j];
}</pre>
```

• y[i] += may be costing 1000 cycles when its single-thread execution would take just dozens of cycles

Summary (1): latency and bandwidth

• latency of data access heavily depends on which level of caches you actually access:

$$L1 \ (a \ few \ cycles) \le main \ memory \ (> 200 \ cycles)$$

• a single core bandwidth is limited by:

$$\frac{\text{cache line size} \times \text{LFB size}}{\text{latency}}$$

- for main memory, it's much lower than what you see in the spec
- max bandwidth is attainable only with multiple cores

Summary (2): bandwidth differs by access patterns

bandwidth = $\frac{\text{line size} \times \text{number of accesses in flight}}{\text{latency}}$

- bandwidth heavily depends on the number of in-flight accesses, which depend on *access patterns*
 - random address pointer chasing
 - random but independent addresses
 - sequential

Common misunderstanding

- pointer chasing is always bad
 - not when data fit in L1 (perhaps L2) cache
 - not when accessed addresses are sequential
 - not when you manage to chase many pointer chains
- random access is always worse than sequential access
 - not so much when an element \approx cache size

Summary (3): inter processor communication

- cores communicate as a side effect of memory accesses (cache misses)
- it is natually as expensive as L2/L3 misses (or more), depending on whom you communicate with
- shared memory is nice, but you cannot forget the cost