


Alan Murray

Topic nr.1- Signals and Communications 3






Alan Murray – University of Edinburgh

Topic nr.2- Signals and Communications 3

Capacitance: Definition

- Take two chunks of conductor
 - Separated by insulator
- Apply a potential V between them
- Charge will appear on the conductors, with Q₊ = +CV on the higher-potential and Q₋ = -CV on the lower potential conductor
- C depends upon both the "geometry" and the nature of the material that is the insulator



Topic nr.3- Signals and Communications 3


Calculating Capacitance?

- C = f(geometry, dielectric)
 - e.g. C = εArea/separation = εA/d for a parallelplate capacitor
- With much symmetry, C can be calculated
 - And capacitors are often manufactured in simple geometries!
- Without such symmetry approximation and estimation is necessary
 - Can be made arbitrarily accurate
 - Remember Laplace and field plotting?
- Tackle calculation, then estimation

Topic nr.4- Signals and Communications 3


Example 1 : Parallel-Plate Capacitor

- calculate field
 strength **E** as a
 function of charge
 ±Q on the plates
- Integrate field to calculate potentialV between the plates
- 3. Q=CV, C=Q/V



Example 1 : Parallel-Plate Capacitor

- Gauss's Law <u>D</u>, <u>E</u> ≠ 0 only on bottom face
- Charge enclosed = $A_G \times Q/A$




Example 1 : Parallel-Plate Capacitor

$$\mathbf{E} = -\frac{Q\mathbf{a}_z}{c\Delta}$$
 from Gauss's Law

$$V = -\int_{z=0}^{z=d} \underline{\mathbf{E}}.\underline{\mathbf{dI}} = -\int_{z=0}^{z=d} -\left(\frac{Q\underline{\mathbf{a}}_{z}}{\varepsilon A}\right).\underline{\mathbf{dI}} = \left(\frac{Q}{\varepsilon A}\right)\int_{z=0}^{z=d} \underline{\mathbf{a}}_{z}.\underline{\mathbf{dI}}$$


$$V = \left(\frac{Qd}{\varepsilon A}\right), Q = \left(\frac{\varepsilon A}{d}\right)V$$


$$C = \frac{\varepsilon A}{d}$$



Example 2 : Cylindrical Capacitor

- Two concentric cylindrical conductors, overlap length L
 - e.g. co-axial TV lead cable
- Separated by a dielectric (insulator)





Example 2 : Cylindrical Capacitor


$$\mathbf{E} = \frac{\rho_l \mathbf{a}_r}{2\pi\varepsilon r} = \frac{\left(\frac{\mathbf{Q}}{L}\right)\mathbf{a}_r}{2\pi\varepsilon r}$$
 from Gauss's Law

$$V = -\int_{l=a}^{l=b} \mathbf{E} \cdot \mathbf{dl} = -\int_{l=a}^{l=b} \frac{\rho_l \mathbf{a}_r \cdot \mathbf{dl}}{2\pi\varepsilon r}$$

$$V = -\frac{\rho_l}{2\pi\varepsilon} \int_{r-a}^{r=b} \frac{dr}{r} = -\frac{\rho_l}{2\pi\varepsilon} \left[\ln(r) \right]_a^b$$

$$V = -\frac{\rho_l}{2\pi\varepsilon} \left[\ln(b) - \ln(a) \right] = -\frac{\rho_l}{2\pi\varepsilon} \ln\left(\frac{b}{a}\right)$$


$$V = -\frac{\ln\left(\frac{b}{a}\right)}{2\pi\varepsilon}\rho_{I} = -\frac{\ln\left(\frac{b}{a}\right)}{2\pi\varepsilon}\frac{Q}{L}, \text{ so } C_{L} = \frac{2\pi\varepsilon}{\ln\left(\frac{b}{a}\right)}$$



$$C_L = \frac{2\pi\varepsilon}{\ln\left(\frac{b}{a}\right)}$$
 is the Capacitance/unit length (F/M)


Estimating Capacitance ...


- When the electrodes are not as symmetrical as these examples
- Also our "ideal" parallel-plate capacitor should really look thus:-



Estimating Capacitance: Principle

- Sketch equipotentials and field lines using field plotting
- Can be arbitrarily accurate
- More accuracy means more $V_0 = \frac{1}{4} (V_1 + V_2 + V_3 + V_4)$
- Use a computer!





Capacitance?


Capacitance/unit depth (÷a)?

 $=\epsilon$

$$C=\varepsilon A = \varepsilon a \times 0.5a = \varepsilon a$$
d 0.5a

$$C=\varepsilon \underline{A} = \varepsilon \underline{a} \times \underline{a} = \varepsilon \underline{a}$$
 = $\varepsilon \underline{a}$


$$C=\varepsilon \underline{A} = \varepsilon \underline{a} \times 2\underline{a} = \varepsilon \underline{a}$$
 = $\varepsilon \underline{a} \times 2\underline{a} = \varepsilon \underline{a}$



a/2

Capacitance?

Capacitance/unit depth (÷a)?



$$C=\varepsilon \underline{A} = \varepsilon \underline{a} \times \underline{a} = \varepsilon \underline{a}$$
 $d = a$

$$=\epsilon$$

$$C \approx \underline{A} = \underline{\epsilon} \underline{a} \times \underline{a} = \underline{\epsilon} \underline{a}$$


Estimation: Example


Positive electrode

Equipotential

Equipotential


Equipotential





Estimation : Example

Each of these is $\varepsilon A/d = \varepsilon \times x \times x/x$ 4 in series, 30 in parallel Capacitance = $30x\varepsilon/4$ Or capacitance/unit depth = $10\varepsilon/4$



Alan Murray - University of Edinburgh

Estimating Capacitance: Recipe

- Draw equipotentials as accurately as you have time for
 - Using field mapping in reality
- Draw field lines to make square "cells" (cubes in 3D)
 - Field line and equipotentials cross at 90°
 - Make cells as square as possible
- Count series and parallel each is a capacitance of εx (ε per unit depth when using a 2D diagram)

Topic nr.5- Signals and Communications 3