Here's the steps to setup MAIL PHP :

1. Download the sendmail.zip through this link
   http://www.glob.com.au/sendmail/sendmail.zip

2. Now, extract the folder and put it to **C:/wamp64/SendMail**. Make sure that these four files are present: **sendmail.exe**, **libeay32.dll**, **ssleay32.ddl** and **sendmail.ini.**

3. Open **sendmail.ini** and set the configuration as follows:
   - `smtp_server=smtp.gmail.com`
   - `smtp_port=465`
   - `smtp_ssl=ssl`
   - `default_domain=localhost`
   - `error_logfile=error.log`
   - `debug_logfile=debug.log`
   - `auth_username=[your_gmail_account_username]@gmail.com`
   - `auth_password=[your_gmail_account_password]`
   - `pop3_server=`
   - `pop3_username=`
   - `pop3_password=`
   - `force_sender=`
   - `force_recipient=`
   - `hostname=localhost`

4. Access your email account. Click the **Gear Tool > Settings > Forwarding and POP/IMAP > IMAP access**. Click "**Enable IMAP**", then save your changes.

5. Run your WAMP Server.
   - Enable **ssl_module** under **Apache Module**.
   - Next, enable **openssl (php_ openssl)** and **sockets (php_sockets)** under **PHP/PHP Extensions.**

6. Open **php.ini** from "**C:\wamp64\bin\apache\Apache2.4.41\bin**" and configure it as the codes below. Basically, you just have to set the sendmail path.

```ini
[mail function]
; For Win32 only.
; http://php.net/smtp
;SMTP =
; http://php.net/smtp-port
;smtp_port = 25

; For Win32 only.
; http://php.net/sendmail-from
;sendmail_from = you@domain.com
; For Unix only.  You may supply arguments as well (default:
"sendmail -t -i").
; http://php.net/sendmail-path
sendmail_path = "C:\wamp64\sendmail\sendmail.exe -t -i"
```

7. Restart Wamp Server

8. Create a PHP file and write the following code in it:

```php
<?php
$to = 'thuyle2000@gmail.com';

$subject = 'Testing sendmail.exe';

$message = 'Hi, you just received an email using sendmail!';

$headers = 'From: YourEmail@gmail.com';


if(mail($to, $subject, $message, $headers))
    echo "Email sent";
else
    echo "Email sending failed";
?>
```