Lab5B - Saving and Loading Models

In the process of training the model, you may stop the training temporarily and resume it later. You may also want to save the best model which may not be the model generated in the last iteration. More importantly, after completion of training, you want to deploy your model to the field. All this requires you to save and load the model.

Objectives:

In this practical, students learn how to:

- 1. Save and loading models
- 2. Resume previous training

References:

import torch

import torch.nn as nn

import torchvision

1. Saving and loading models

```
In [1]:

from google.colab import drive drive.mount('/content/gdrive')

Drive already mounted at /content/gdrive; to attempt to forcibly remount, call drive.mount("/content/gdrive", force_remount=True).

In [2]:

cd "./gdrive/MyDrive/UCCD3074_Labs/UCCD3074_Lab5"

/content/gdrive/MyDrive/UCCD3074_Labs/UCCD3074_Lab5

Import the required library.

In [3]:

# imports
import numpy as np
```

import torch.nn.functional as F

```
import torchvision.transforms as transforms
from torch.utils.data import DataLoader
import torch.optim as optim
import os
from cifar10 import CIFAR10

In [4]:
    if not os.path.exists("./models"):
        os.mkdir("models")
```

1. Introduction

When it comes to saving and loading models, there are three core functions to be familiar with:

1. torch.save [manual]

Saves a serialized object to disk. This function uses Python's pickle utility for serialization. Models, tensors, and dictionaries of all kinds of objects can be saved using this function.

2. torch.load [manual]

Uses pickle's unpickling facilities to deserialize pickled object files to memory. This function also facilitates the device to load the data into (see Saving & Loading Model Across Devices).

3. torch.nn.Module.load_state_dict [manual] Loads a model's parameter dictionary using a deserialized state_dict.

What is a state dict()?

- Each <u>model</u> has a state_dict. The model state_dict is simply a Python dictionary object that maps each layer to its parameter tensors stored in model.parameters(). state_dict stores the following tensors:
 - learnable parameters (convolutional layers, linear layers, etc.)
 - registered buffers (batchnorm's running mean).
- The optimizer object (torch.optim) also have a state_dict, which contains information about

- the optimizer's state
- the hyperparameters used.

Because state_dict objects are Python dictionaries, they can be easily saved, updated, altered, and restored, adding a great deal of modularity to PyTorch models and optimizers.

First, let's build our model.

```
In [5]:
         class Net(nn.Module):
             def init (self):
                 super().__init__()
                 self.conv1 = nn.Conv2d(3, 8, kernel size=3, stride=1, padding=1)
                 self.bn1 = nn.BatchNorm2d(8)
                 self.conv2 = nn.Conv2d(8, 16, 3)
                 self.bn2 = nn.BatchNorm2d(16)
                 self.fc1 = nn.Linear(16*30*30, 256)
                 self.fc2 = nn.Linear(256, 10)
             def forward(self, x):
                 x = self.conv1(x)
                 x = self.bn1(x)
                 x = F.relu(x)
                 x = self.conv2(x)
                 x = self.bn2(x)
                 x = F.relu(x)
                 x = x.view(x.size(0), -1) # flat
                 x = self.fc1(x)
                 x = self.fc2(x)
                 return x
```

The following shows the state_dict of the model. Note that state_dict stores not only the *parameters* (weight and bias) of the trainable layers but also the *running mean* of the batch norm layer.

```
In [6]: model = Net()
```

```
In [7]:
         # Print model's `state dict`
         print("Model's state dict:")
         for param tensor in model.state dict():
             print(param tensor, "\t", model.state dict()[param tensor].size())
        Model's state dict:
        conv1.weight
                         torch.Size([8, 3, 3, 3])
        conv1.bias
                          torch.Size([8])
        bn1.weight
                         torch.Size([8])
        bn1.bias
                         torch.Size([8])
        bn1.running mean
                                 torch.Size([8])
        bn1.running var
                                 torch.Size([8])
        bn1.num batches tracked
                                         torch.Size([])
        conv2.weight
                         torch.Size([16, 8, 3, 3])
        conv2.bias
                          torch.Size([16])
        bn2.weight
                         torch.Size([16])
        bn2.bias
                          torch.Size([16])
        bn2.running mean
                                 torch.Size([16])
        bn2.running var
                                 torch.Size([16])
        bn2.num batches tracked
                                          torch.Size([])
                         torch.Size([256, 14400])
        fc1.weight
        fc1.bias
                          torch.Size([256])
        fc2.weight
                         torch.Size([10, 256])
        fc2.bias
                         torch.Size([10])
       The following code shows the state dict of the optimizer. It stores the hyperparameter settings (e.g., 1r, momentum, dampening,
        weight decay, nesterov) as well as the optimizer states (params)
In [8]:
         optimizer = optim.SGD(model.parameters(), lr=0.1, momentum=0.9)
In [9]:
         print("Optimizer's state dict:")
         for var name in optimizer.state dict():
             print(var name, "\t", optimizer.state dict()[var name])
        Optimizer's state dict:
        state {}
                        [{'lr': 0.1, 'momentum': 0.9, 'dampening': 0, 'weight decay': 0, 'nesterov': False, 'params': [0, 1, 2, 3, 4, 5,
        param groups
        6, 7, 8, 9, 10, 11]}]
```

1.1 Saving & Loading Model Parameters Only

```
torch.save(model.state_dict(), PATH)
```

When saving a model for inference, it is only necessary to save the trained model's learned parameters. We do not need to save the network structure itself. To do that, use the command torch.save(). A common PyTorch convention is to save models using either a .pt or .pth file extension.

```
In [10]: model = Net()
  torch.save(model.state_dict(), "./models/saved_params.pt")
```

model. load state dict(torch.load(PATH))

To load the model parameters, use the model's function load_state_dict() . load_state_dict() takes a dictionary object, NOT a path to a saved object. So, you must deserialize the saved state_dict first (torch.load(PATH)) before you pass it to the load_state_dict() function.

1.2 Saving the Entire Model

The previous method only saves the model *parameters* but not the *network* itself. As a result, the saved parameters must be accompanied by the *model class*, i.e., the class Net, so that we can create the *network* first before loading the parameters. Because of this, your code can break in various ways when used in other projects or after refactors.

```
torch.save(model, PATH)
```

You may save the whole model and use it for inference by providing model rather than model.state_dict() as the argument for torch.save. This eliminates the need to attach the model class together with your saved model file.

```
In [12]:    model = Net()
    torch.save(model, "saved_model.pt")
```

model = torch.load(PATH)

When we load, we load both the network and the model. There is no need for us to create the model first: new_model2 = Net().

```
new_model = torch.load("saved_model.pt")
print(new_model)

Net(
    (conv1): Conv2d(3, 8, kernel_size=(3, 3), stride=(1, 1), padding=(1, 1))
    (bn1): BatchNorm2d(8, eps=1e-05, momentum=0.1, affine=True, track_running_stats=True)
    (conv2): Conv2d(8, 16, kernel_size=(3, 3), stride=(1, 1))
    (bn2): BatchNorm2d(16, eps=1e-05, momentum=0.1, affine=True, track_running_stats=True)
    (fc1): Linear(in_features=14400, out_features=256, bias=True)
    (fc2): Linear(in_features=256, out_features=10, bias=True)
)
```

Caution:

- If you are doing inference, remember that you must call model.eval() to set *dropout* and *batch normalization* layers to evaluation mode before running inference. Failing to do this will yield inconsistent inference results.
- If you wish to resuming training, call model.train() to ensure these layers are in training mode.

1.3 Saving the Model Parameters and Optimizer State

It is common to train your model in multiple session where you stop the training temporarily and resume it only at a later day. To do this you need to save **checkpoints**.

When saving a checkpoint, to be used for either inference or resuming training, you must save more than just the model's state_dict. It is important to also save:

- 1. optimizer's state_dict
- 2. model's state_dict
- 3. current epoch number
- 4. training loss
- 5. others

Assume the following as the current state of training.

```
epoch = 0
model = Net()
optimizer = optim.SGD(model.parameters(), lr=0.1, momentum=0.9)
loss = np.inf
```

To save multiple components, you can organize them into a dictionary and use torch.save() to serialize the dictionary. A common PyTorch convention is to save these checkpoints using the .tar file extension.

First, load the *network's parameters* and *optimizer's state*. For the *optimizer*, the learning rate (1r) is a compulsory argument. It will be overwritten when we load the saved optimizer's state.

```
new_model = Net()
new_optimizer = optim.SGD(new_model.parameters(), lr=0.1)
```

Since you wish to resuming training, remember to call model.train() to ensure that that the dropout and batch normalization layers are in training mode.

(conv1): Conv2d(3, 8, kernel size=(3, 3), stride=(1, 1), padding=(1, 1))

```
(bn1): BatchNorm2d(8, eps=1e-05, momentum=0.1, affine=True, track_running_stats=True)
  (conv2): Conv2d(8, 16, kernel_size=(3, 3), stride=(1, 1))
  (bn2): BatchNorm2d(16, eps=1e-05, momentum=0.1, affine=True, track_running_stats=True)
  (fc1): Linear(in_features=14400, out_features=256, bias=True)
  (fc2): Linear(in_features=256, out_features=10, bias=True)
)
```

Now you are ready to resume your training.

2. Example

Load the dataset

We will use the CIFAR10 dataset for example

Define training function

First, we define our training model. To allow the model to resume training, we do the following:

- 1. Define the model and optimizer outside the train function
- 2. Save the model at the end of each epoch (line 56 to 62)

```
device = "cuda" if torch.cuda.is available() else "cpu"
In [20]:
In [21]:
          def train(model, optimizer, start epoch=0, max epochs=10):
              # compute loss 3 times in each epoch
              loss iterations = int(np.ceil(len(trainloader)/3))
              # transfer model to GPU
              model = model.to(device)
              # set the optimizer. Use SGD with momentum
              # set to training mode
              model.train()
              # train the network
              for e in range(start epoch, max epochs):
                  running loss = 0
                  running count = 0
                  for i, (inputs, labels) in enumerate(trainloader):
                      # Clear all the gradient to 0
                      optimizer.zero grad()
                      # transfer data to GPU
                      inputs = inputs.to(device)
                      labels = labels.to(device)
                      # forward propagation to get h
                      outs = model(inputs)
                      # compute loss
                      loss = F.cross entropy(outs, labels)
                      # backpropagation to get gradients of all parameters
                      loss.backward()
                      # update parameters
                      optimizer.step()
```

```
# get the loss
   running loss += loss.item()
   running count += 1
    # display the averaged loss value
   if i % loss iterations == loss iterations-1 or i == len(trainloader) - 1:
        # compute training loss
       train loss = running loss / running count
        running loss = 0.
        running count = 0.
        print(f'[Epoch {e+1:2d} Iter {i+1:5d}/{len(trainloader)}]: train loss = {train loss:.4f}')
# save the model
checkpoint file = './models/saved model.pt'
torch.save({
    'epoch': e,
    'loss': train loss,
    'model state dict': model.state dict(),
    'optimizer state dict': optimizer.state dict(),
   }, checkpoint file)
```

Train model

Train the model for 2 epochs

Resume training

Resume training and train for another 2 epochs. To do that, we get the load the *previous* model's and optimizer's state_dict, the last epoch and training loss value.

```
In [23]:
          # define a new model
          new model = Net()
          # define a new optimizer
          new optimizer = optim.SGD(new model.parameters(), lr=0.1)
          # load the checkpoint file
          checkpoint = torch.load('./models/saved model.pt')
          new_model.load_state_dict(checkpoint['model state dict'])
          new optimizer.load state dict(checkpoint['optimizer state dict'])
          previous epoch = checkpoint['epoch']
          previous loss = checkpoint['loss']
          # resume training
          print(f'Resuming previous epoch. Last run epoch: {previous epoch+1}, last run loss: {previous loss:.4f}')
          train(new model, new optimizer, start epoch=previous epoch+1, max epochs=4)
         Resuming previous epoch. Last run epoch: 2, last run loss: 1.3252
         [Epoch 3 Iter
                         105/313]: train loss = 1.1209
                         210/313]: train loss = 1.1996
         [Epoch 3 Iter
         [Epoch 3 Iter
                         313/313]: train loss = 1.1479
         [Epoch 4 Iter
                         105/313]: train loss = 0.8928
                          210/313]: train loss = 0.9637
         [Epoch 4 Iter
                         313/313]: train_loss = 0.9826
         [Epoch 4 Iter
                                                                 -- END OF LAB ---
```