# Package 'dynmdl'

May 6, 2020

```
Type Package
Title An R version of Dynare
Version 1.3.0
Author Rob van Harrevelt [aut, cre]
Maintainer Rob van Harrevelt < rvanharrevelt@gmail.com>
Description An R version of Dynare.
SystemRequirements GNU make
License GPL (>= 2)
LazyData TRUE
RoxygenNote 7.1.0
Roxygen list(markdown = TRUE, r6 = FALSE)
LinkingTo Rcpp, BH, Rcereal
Imports Rcpp,
     nleqslv,
     Matrix,
     compiler,
     R6,
     geigen,
     gsubfn,
     tools,
     stringi,
     umfpackr,
     numDeriv,
     openxlsx,
     tictoc
Depends R (>= 3.5.0),
     regts,
     methods
Suggests testthat,
     knitr,
     rmarkdown,
     caret
```

VignetteBuilder knitr

# $\mathsf{R}$ topics documented:

all.equal	3
change_data-methods	4
change_static_data-methods	5
check	7
clear_fit	8
сору	9
DynMdl	9
dyn_mdl	12
get_data-methods	15
get_eigval	16
get_equations	17
get_fit-methods	17
get_fit_steady	19
get_instrument_names/get_sigma_names	20
get_jacob	20
get_labels/get_tex_names	21
get_max_lag/get_max_lead	22
get_mdldef	23
get_name-methods	23
get_period-methods	24
	25
	26
	27
<del>-</del>	28
	29
·	30
	30
	31
·	33
_	34
	35
$\mathcal{E} = \mathcal{E}$	37
	39
<del>-</del>	40
<del>-</del>	42
	43
	44
	44
	45
	46
	47
— •	49
solve_steady_dynare	50
	51
	52
write inityal file	53

all.equal 3

Index 55

all.equal

Test if two DynMdl objects are (nearly) equal

# **Description**

all.equal(x,y) is a utility to compare R objects x and y testing near equality. If they are different, comparison is still made to some extent, and a report of the differences is returned. Do not use all.equal directly in if expressions - use isTRUE(all.equal(...)).

### Usage

```
## S3 method for class 'DynMdl'
all.equal(target, current, ...)
```

# **Arguments**

target and DynMdl object
current another DynMdl object, to be compared with target
... Arguments passed to the internal call of all.equal.

### **Details**

The implementation of all.equal for DynMdl objects first serialized the model using the DynMdl method serialize and then uses all.equal of the base package.

#### Value

Either TRUE or a character vector describing the differences between target and current.

### See Also

```
all.equal
```

# **Examples**

```
mdl <- islm_mdl("2017Q2/2018Q2")
mdl2 <- mdl$copy()
print(all.equal(mdl, mdl2))

# now modify mdl2
mdl2$set_endo_values(600, names = "c")
print(all.equal(mdl, mdl2))</pre>
```

change\_data-methods

 ${\tt change\_data-methods}$ 

DynMdl methods: changes the endogenous or exogenous model data by applying a function.

### **Description**

These methods of R6 class DynMdl changes endogenous and/or exogenous model data by applying a function. If the model has trends, then the change is applied to the trended model variables.

### Usage

```
mdl$change_endo_data(fun, names, pattern, period = mdl$get_data_period(), ...)
mdl$change_exo_data(fun names, pattern, period = mdl$get_data_period(), ...)
mdl$change_data(fun, names, pattern, period = mdl$get_data_period(), ...)
mdl is a DynMdl object
```

### **Arguments**

fun a function applied each model variable specified with argument names or pattern. See Details. names a character vector with variable names

pattern a regular expression for selecting the names of variables whose values must be changed
period an period\_range object or an object that can be coerced to a period\_range: the period
for which the function will be applied

```
... arguments passed to fun
```

If neither names nor pattern have been specified, then the function is applied to all endogenous or exogenous variables.

#### **Details**

The function specified with argument fun should be a function with at least one argument, for example fun = function(x)  $\{x + 0.1\}$ . The first argument (named x in the example) will be the model variable. The function is evaluated for each model variable separately. The values of the model variables for period range period are passed as a normal numeric vector (not a timeseries) to the first argument.

An example may help to clarify this. Consider the following statement

```
mdlschange_endo_data(fun = myfun, names = c("c", "y"),
period = "2017q1/2017q2"),
```

where mdl is a DynMdl object and myfun some function whose details are not relevant here. Method change\_endo\_data evaluates this as

```
data <- mdl$get_endo_data(names = c("c", "y"), period = "2017q1/2017q2")
data[, "c"] <- myfun(as.numeric(data[, "c"]))
data[, "y"] <- myfun(as.numeric(data[, "y"]))
mdl$set_data(data)</pre>
```

The function result must be a vector (or timeseries) of length one or with the same length as the number of periods in the period range period.

#### Methods

change\_endo\_data Changes endogenous model variables, including fit instruments and Lagrange multipliers used in the fit method (if present).

change\_exo\_data Changes exogenous model variables

change\_data Changes endogenous and/or exogenous model variables, including fit instruments and Lagrange multipliers used in the fit method (if present).

#### See Also

```
get_data-methods, set_data and set_values-methods
```

### **Examples**

```
change_static_data-methods
```

DynMdl methods: changes static values of the endogenous or exogenous model data by applying a function.

### **Description**

These methods of R6 class DynMd1 changes the static values of the endogenous and/or exogenous model data by applying a function.

### Usage

```
mdl$change_static_endos(fun, names, pattern, ...)
mdl$change_static_exos(fun names, pattern, ...)
mdl$change_static_data(fun, names, pattern, ...)
mdl is a DynMdl object
```

### **Arguments**

fun a function applied each model variable specified with argument names or pattern. See Details. names a character vector with variable names

pattern a regular expression for selecting the names of variables whose values must be changed ... arguments passed to fun

If neither names nor pattern have been specified, then the function is applied to all endogenous or exogenous variables.

#### **Details**

The function specified with argument fun should be a function with at least one argument, for example fun = function(x)  $\{x + 0.1\}$ . The first argument (named x in the example) will be the model variable. The function is evaluated for each model variable separately.

The function result must be a vector of length one.

### Methods

change\_static\_endos Changes the static values of endogenous model variables, including fit instruments and Lagrange multipliers used in the fit method (if present).

change\_static\_exos Changes the static values of exogenous model variables

change\_static\_data Changes the static values of endogenous and/or exogenous model variables, including fit instruments and Lagrange multipliers used in the fit method (if present).

### See Also

```
set-slash-get_static_endos, set_static_data and set_static_exo_values
```

# **Examples**

check 7

```
print(mdl$get_static_exos())
```

check

DynMdl method: Compute the eigenvalues of the linearized model around the steady state.

### **Description**

This method of R6 class DynMdl computes the steady state, constructs a linear model around the state steady and finally computes the eigenvalues of the linearized model around the steady state. It also checks if the Blachard and Kahn conditions are satisfied. The Blanchard and Kahn conditions state that the number of eigenvalues larger than 1 should be equal to the number of forward looking variables (variables with leads).

### Usage

```
mdl$check(tol = sqrt(.Machine$double.eps))
mdl is a DynMdl object
```

### **Arguments**

tol The tolerance parameter used to test if an eigenvalue is significantly larger than 1 when checking the Blanchard-Kahn conditions. The default is the square root of the machine precision (typically about 1.5e-8). See Details.

### **Details**

To test if the Blanchard-Kahn conditions are satisfied, we need to determine the number of eigenvalues larger than 1. If an eigenvalue is exactly equal to 1, the actually calculated eigenvalue may be slightly larger than 1 because of rounding errors. To check the Blanchard-Kahn conditions, we therefore count the number of eigenvalues larger than 1 + to1, where to1 is a small number (by default the square root of the machine precision). Use argument to1 to change this tolerance parameter.

Method check also prints the number of eigenvalues with absolute values between 1 -tol and 1 + tol. Thus the values of these eigenvalues are not significantly different from 1.

### Warning

Method check is only possible for models with a maximum lag and lead of 1. If the original model has lags or leads greater than 1, use argument max\_lag\_lead\_1 = TRUE of function dyn\_mdl to create a transformed model with maximum lag and lead 1.

#### See Also

```
solve_steady and get_eigval
```

8 clear\_fit

### **Examples**

```
mdl <- islm_mdl()
mdl$check()
print(mdl$get_eigval())</pre>
```

clear\_fit

DynMdl method: removes fit targets and turns off fit instruments.

# Description

This method of R6 class DynMd1 removes all fit targets, sets the sigma-parameters of the fit-instruments to -1 and sets all Lagrange multipliers to 0, for both the dynamic and static version of the model.

By removing the fit targets (which is equivalent to setting all fit targets to NA), all endogenous variables are calculated according to the equations of the model, while the fit instruments stay fixed at their current value, and are efficitively exogenous (even though they are still implemented as endogenous variables).

If the model had been solved before clear\_fit was called, then the model is still solved after clear\_fit has been called.

### Usage

```
mdl$clear_fit()
mdl is a DynMdl object implementing the fit method. '
```

### See Also

```
get_data-methods, set_fit, set_fit_steady, set_fit_values and clear_fit.
```

# **Examples**

```
mdl <- islm_mdl(period = "2016Q1/2017Q3", fit = TRUE)

# create a regts with fit targets
y <- regts(c(1250, 1255, 1260), start = "2016Q1")
t <- regts(c(250, 255), start = "2016Q1")
fit_targets <- cbind(y, t)

# register the fit targets in the DynMdl object
mdl$set_fit(fit_targets)

mdl$solve()
mdl$clear_fit()

# the next statements gives 0 iterations.
mdl$solve()</pre>
```

copy 9

сору

DynMdl method: Returns a copy of this DynMdl object

# Description

This method of R6 class DynMdl returns a deep copy of a DynMdl object

# Usage

```
mdl$copy()
mdl is a DynMdl object
```

# **Details**

```
mdl$copy() is equivalent to mdl$clone(deep = TRUE)
```

# **Examples**

```
mdl <- islm_mdl("2017Q1/2019Q2")
mdl2 <- mdl$copy()</pre>
```

DynMd1

An R6 class for a Dynare model

# Description

An R6 class for a Dynare model

### **Format**

```
R6Class object.
```

#### Value

Object of R6Class containing a macro-economic model,

### Methods

```
get_max_lag Returns the maximum lag
get_max_lead Returns the maximum lead
get_endo_names Returns the names of the endogenous variables.
get_exo_names Returns the names of the exogenous variables.
set_labels Set labels for the model variables
```

10 DynMdl

```
get_labels Returns the labels of the model variables and parameters
get_tex_names Returns the LaTeX names of the model variables and parameters
get_par_names Returns the names of the parameters.
set_param Sets the parameters of the model.
set_param_values Sets the values of one or more model parameters.
get_param Returns the parameters of the model.
get_all_param Returns the parameters of the model, including the sigma parameters used in the
     fit method.
set_static_exos Sets the static values of the exogenous variables used to compute the steady
    state.
set_static_exo_values Sets the values of one or more static exogenous variables
get_static_exos Returns the static values of the exogenous variables.
set_static_endos Sets the static values of the endogenous variables.
get_static_endos Returns the static values of the endogenous variables.
set_static_data Sets the static values of the model variables.
change_static_endos Changes the static values of endogenous model variables by applying a
    function
change_static_exos Changes the static values of exogenous model variables by applying a func-
change_data Changes the static values of endogenous and exogenous model variables by applying
    a function.
get_static_data Returns the static values of the model variables.
get_all_static_endos Returns the static values of the endogenous model variables, including fit
    instruments and lagrange multupliers.
    #
get_all_static_data Returns the static values of the exogenous and endogenous model vari-
     ables, including fit instruments and lagrange multupliers.
init_data Initializes the model data
set_period Sets the model period
get_period Returns the model period
get_data_period Returns the model data period.
get_lag_period Returns the lag period.
get_lead_period Returns the lead period
set_endo_values Sets the values of endogenous model variables
set_exo_values Sets the values of exogenous model variables
set_data Transfer timeseries to the model data
change_endo_data Changes the values of endogenous model variables by applying a function
change_exo_data Changes the values of exogenous model variables by applying a function
```

DynMdl 11

```
change_data Changes the values of endogenous and exogenous model variables by applying a
         function.
    get_data Returns the model data, including exogenous end exogenous variables, fit instruments
         and trend variables (but excluding Lagrange multipliers).
    get_all_endo_data Returns all endogenous model variables, including exogenous end exogenous
         variables, fit instruments and trend variables (but excluding Lagrange multipliers).
    get_all_data Returns all endogenous end exogenous model varieables, including fit instruments
         and Lagrange multipliers
    get_endo_data Returns the endogenous model data
    get_exo_data Returns the exogenous model data
    get_vars_pars Returns a list with model variables and parameters
    solve_steady Solves the steady state
    solve Solves the model
    solve_steady_dynare Solves the steady state and eigenvalues with Dynare (employing Matlab or
    solve_dynare Solves the model with Dynare (employing Octave or Matlab)
    check Compute the eigenvalues of the linear system and check if the Blachard and Kahn conditions
         are satisfied.
    residual_check Calculates the residuals of the equations and reports the differences larger than a
         tolerance parameters
    static_residual_check Calculates the residuals of the static model equations and reports the
         differences larger than a tolerance parameters
    solve_perturbation Solves the model using the perturbation theory used in the Dynare function
         stoch_simul. Only shocks in the first solution period are allowed.
    get_jacob Returns the Jacobian for the dynamic model
    get_static_jacob Returns the Jacobian for the static version of the model
    get_back_jacob Returns the Jacobian for a backward looking model at a specific period
    get_eigval Returns the eigenvalues computed with method check or solve_perturbation
    get_equations Returns a character vector with the parsed equations of the model.
    get_original_equations Returns a character vector with the equations of the original model.
    copy Returns a deep copy of the DynMdl object
    get_solve_status Returns the status of the last model solve attempt
    get_mdldef Returns a list with technical details of the model.
Methods for the fit method
    get_instrument_names Returns the names of the fit instruments.
    get_sigma_names Returns the names of the sigma parameters used in the fit procedure.
```

set\_fit\_values Sets the values of the fit targets
set\_fit Sets the targets for the fit procedure

12 dyn\_mdl

```
set_fit_steady Sets the targets for the fit procedure for the steady state.
get_fit Returns the fit targets used in the fit procedure
get_fit_steady Returns the fit targets used in the fit procedure for the steady state.
get_fit_instruments Returns all non-zero fit instruments used in the fit procedure
set_sigma Sets one or more sigma parameters used in the fit method
set_sigma_values Sets the values of sigma parameters used in the fit method
get_sigmas Returns all sigma parameters >= 0 used in the fit procedure. If a sigma parameter is negative, then the corresponding fit instrument is not included
get_lagrange Returns the Lagrange multipliers used in the fit procedure.
run_initval Run the initval equations to obtain new values for endogenous and exogenous static variables for the current values or parameters.
```

dyn\_mdl

Creates a DynMdl object from a mod file

# **Description**

Creates a DynMdl object from a mod file. If the mod file contains a fit block, then the DynMdl object implements the fit procedure (except if argument fit is FALSE).

```
dyn_mdl(
 mod_file,
 period,
  data.
 base_period = NULL,
  calc = c("internal", "R", "bytecode", "dll"),
  fit_mod_file,
  debug = FALSE,
  dll_dir,
 max_laglead_1 = FALSE,
  strict = TRUE,
 warn_uninit_param = TRUE,
  init_param_na = FALSE,
  fit = TRUE,
  fit_fixed_period = FALSE,
  latex = TRUE,
  latex_options,
 nostrict,
  silent = FALSE
)
```

dyn\_mdl 13

#### **Arguments**

mod\_file the name of the model file (including extension .mod)

period a period\_range object specifying the model period, i.e. the period range for

which the model will be solved. Thus this period range excludes the lag and

lead period.

data the model data as a regts object with column names

base\_period a period object specifying the base period for the trends. This is used if the

model has trend variables. All trend variables will be equal to 1 at the base

period.

calc Method used to evaluate the model equations. Possible values are "internal",

"R", "bytecode" and "dll". See Details.

fit\_mod\_file the name of the generated fit mod file. If not specified, then the fit mod file is

destroyed after the model has been parsed. This argument should not be specified if the model contains trends, since in that case the fit mod file cannot be used a input mod file for function dyn\_mdl or for Dynare. If wou want to check

the equations in the fit mod file, use argument DEBUG (see below).

debug If logical (default FALSE), only used when the model is a fit model. If TRUE, then

intermediate files created when preparing the fit model are written to the current directory. By default these files are written in a temporary directory and deleted

when the R session terminates.

dll\_dir the directory where the dynamically linked library is stored. Primarily used for

testing. Only used if argument use\_dll is TRUE.

max\_laglead\_1 a logical indicating whether the model should be transformed internally to a

model with a maximum lag and lead of 1. The default is FALSE. This option has no effect if the maximum lag and lead of the original model is 1. Set this argument to TRUE if you want to analyse the stability of the steady state with

method check for models with a maximum lag or lead larger than 1.

strict A logical. If TRUE (the default), then an error is given when endogenous or

exogenous variables are not used in the model block or when an undeclared symbol is assigned in the initval block. If FALSE, then only a warning is issued, unused endogenous variables are removed, and the assignments of undeclared

symbols in the initval block are ignored.

warn\_uninit\_param

A logical. If TRUE (the default) then a warning is given for each parameter that has not been initialized in the mod file. Uninitialized parameters are set to zero

or NA, depending on argument init\_param\_na.

init\_param\_na A logical (default FALSE). If TRUE, then the parameters that have not been ini-

tialized in the mod file are set to NA. Otherwise these parameters are initialised

with zero.

fit a logical (default TRUE) indicating if the DynMdl object returned by this function

should implement the fit procedure if the mod file contains a fit block. Specify FALSE if the mod file has a fit block while you do not want to use the fit

procedure.

14 dyn\_mdl

fit\_fixed\_period

a logical. If TRUE, then the fit conditions are derived for a fixed period, treating lags and leads as exogenous variables. If FALSE (the default), the fit conditions

are derived from the stacked-time equations.

latex A logical. If TRUE (the default), then LaTeX files are created if the model

block contains a write\_latex\_static\_model, write\_latex\_dynamic\_model

or write\_latex\_original\_model statement.

latex\_options a list with options for writing LaTeX files. See Details.

nostrict Obsolete: the logical negation of argument strict. This argument should not

be used in new code: use argument strict instead.

silent A logical (default FALSE). If TRUE, then output of the Dynare parser is suppressed

except for warnings.

#### **Details**

### **Evaluation of model equations:**

There are several methods available for evaluating the model equations and the Jacobian. These methods can be specified with argument calc. The possible methods are

R the model equations and Jacobian are evaluated using R functions . This is very slow for large models. This method should therefore only be used for small models.

bytcode the same as R, except that the R function is turned into byte code. This is usually only slightly faster than using the R method

dll The model equations and Jacobian are evaluated using a shared library created for this specific model. Function dyn\_mdl generates C code for evaluating the equations and the Jacobian, and subsequently compiles the C code to create a shared library. The evaluation of the equations and Jacobian is much faster than for the R and bytecode methods. However, the compilation of the C code can take a considerable amount time for large models.

internal This methods converts the equations to internal byte code using reverse Polish notation. The internal byte code is evaluated using compiled C++ code that is part of package dynmdl. For this method the evaluation of the equations and Jacobian is as fast as for the dll method, but the compilation time is much faster. However, the internal method does not yet support all features of Dynare models. For example, it cannot handle model-local variables and some built-in functions (the only supported built-in functions are currently exp, log, sqrt, abs and sign).

If possible, use the internal method, because this method is faster than the other methods for both compiling the model and for evaluating the equations and Jacobian. The internal method is therefore the default method. However, as explained above, the mod file may contain features not yet supported for the internal method, in which case another method must be selected.

**Latex options:** When the mod file contains a write\_latex\_static\_model, write\_latex\_dynamic\_model or write\_latex\_oiriginal\_model statement, then the Dynare parser of package dynmdl generates LaTeX files in directory latex. Argument latex\_options can be used to change the format of the LaTeX files. It should be a named list containing one or more of the following components:

par\_as\_num A logical. If TRUE, then the parameters are written as numerical constants to the LaTeX file, using the numerical values as specified in the mod file. The default is FALSE.

get\_data-methods 15

ndigits The number of significant digits used when parameters as written as numerical values (default 4). This argument is only used if par\_as\_num is TRUE. For example, if ndigits is 4, then the number  $\pi$  is printed as 3.142, the number 120.25 as 120.2, and the number 10.1234 as 1.012e+05

# Value

A DynMdl object.

get\_data-methods

DynMdl methods: Retrieve timeseries from the model data

### **Description**

These methods of R6 class DynMdl can be used to retrieve timeseries from the model data.

If the DynMdl object is also a DynMdl object, then get\_data also returns the fit instruments. In contrast, get\_endo\_data does not return these fit instruments. Both get\_data and get\_endo\_data do not return the Lagrange multipliers used in the fit method. Use method get\_lagrange to obtain these Lagrange multipliers. get\_all\_endo\_data returns all endogenous variables, fit instruments and Lagrange multipliers, for the complete data period. get\_all\_data also returns all exogenous variables. These functions can be useful to save the complete solution of a model that be used as initial values for the endogenous variables in another model.

# Usage

### **Arguments**

pattern a regular expression for selecting the names of variables. names a character vector with variable names. 16 get\_eigval

period an period\_range object or an object that can be coerced to a period\_range.

trend a logical. This argument is used for model with trend variables. If TRUE (the default), then the endogenous variables are multiplied with their trends (called deflators in the mod file).

If neither names nor pattern have been specified, then all variables with the specific type are returned.

#### Methods

- get\_data: All model variables: exogenous and endogenous model variables, trends variables, and fit instruments for DynMdl objects
- get\_endo\_data: Endogenous model variables, excluding fit instruments.
- get\_exo\_data: Exogenous model variables
- get\_trend\_data: Trend variables (variables declared with trend\_var in the mod file).
- get\_all\_endo\_data: All endogenous variables, including fit instruments and lagrange multipliers.
- get\_all\_data: All endogenous and exogenous variables, including fit instruments and lagrange multipliers.

#### See Also

```
get_fit-methods, get_fit, get_fit_instruments, get_lagrange and get_vars_pars.
```

### **Examples**

```
mdl <- islm_mdl(period = "2017Q1/2017Q3")
mdl$get_data(names = "c", pattern = "y.", period = "2017Q1/2017Q2")</pre>
```

get\_eigval

DynMdl method: Return the eigenvalues computed with method check

# Description

This method of R6 class DynMdl returns the eigenvalues computed with method check, ordered with increasing absolute value

### Usage

```
DynMdl method:
mdl$get_eigval()
mdl is a DynMdl object
```

#### See Also

check

get\_equations 17

get_equations
---------------

### **Description**

These method of R6 class DynMdl returns a character vector with the model equations (excluding local equations) of the dynamic version of the model. get\_equations returns the parsed equations, where trends (if present) have been removed. get\_original\_equations returns the equations as defined in the mod file.

### Usage

```
DynMdl method:

md$get_equations(i)
mdl$get_original_equations(i)

mdl is a DynMdl object
```

### **Arguments**

i A numeric vector with the indices of the non-local equations. If not specified, then the function returns all equations

#### **Examples**

```
mdl <- islm_mdl(period = "2018Q1/2023Q3")

# print the 4th equation nicely to the screen
cat(mdl$get_equations(4))

# print all equations
print(mdl$get_equations())</pre>
```

get\_fit-methods

DynMdl methods: get variables used in the fit method.

# Description

These methods of R6 class DynMdl can be used to retrieve the variables used in the fit method: the fit targets, fit instruments or Lagrange multipliers.

By default, function get\_fit only returns fit targets with any non-NA value for the period range with any non-NA value. Thus columns with only NA values and leading and trailing rows with only NA values are removed. If all values are NA, then the function returns NULL. If argument period

18 get\_fit-methods

has been specified, then the function always returns a timeseries with the specified period range. If names or pattern has been specified, it always returns a timeseries with the specified variables, except if all values are NA.

For method get\_fit there are corresponding set\_fit and set\_fit\_values methods. There are currently no special methods to set or change the fit instruments and Lagrange multipliers. However, since they are internally implemented as endogenous variables you can use methods set\_data, set\_endo\_values, and change\_endo\_data to change the fit instruments or Lagrange multipliers.

### Usage

```
mdl$get_fit(pattern, names, period) # fit targets
mdl$get_fit_instruments(pattern, names, period = mdl$get_period())
mdl$get_lagrange(names, period = mdl$get_period())
mdl is a DynMdl object implementing the fit method.
```

### **Arguments**

```
pattern a regular expression for selecting the names of the variables
names a character vector with variable names
period an period_range object or an object that can be coerced to a period_range
```

### See Also

```
get_data-methods, set_fit, set_fit_values and clear_fit.
```

# **Examples**

```
mdl <- islm_mdl(period = "2016Q1/2017Q3", fit = TRUE)

# create a regts with fit targets
y <- regts(c(1250, 1255, 1260), start = "2016Q1")
t <- regts(c(250, 255), start = "2016Q1")
fit_targets <- cbind(y, t)

# register the fit targets in the DynMdl object
mdl$set_fit(fit_targets)

mdl$solve()

print(mdl$get_fit())
print(mdl$get_fit_instruments())
print(mdl$get_lagrange())</pre>
```

get\_fit\_steady 19

get\_fit\_steady

DynMdl method: get fit targets used in the steady state calculation

### **Description**

This methods of R6 class DynMd1 returns the static fit targets, i.e. the fit targets used when the steady state is solved.

By default, function get\_fit only returns fit targets with any non-NA value. If all values are NA, then the function returns NULL. If names or pattern has been specified, it always returns a timeseries with the specified variables.

For method get\_fit\_syteady the is a corresponding set\_fit\_steady method. There are currently no special methods to set or change the fit instruments and Lagrange multipliers. However, since they are internally implemented as endogenous variables you can use methods set\_static\_data to change the static fit instruments or Lagrange multipliers.

# Usage

```
mdl$get_fit_steady(pattern, names) # fit targets
mdl is a DynMdl object implementing the fit method.
```

### **Arguments**

pattern a regular expression for selecting the names of the fit targets. names a character vector with variable names.

#### See Also

```
set/get_static_endos/exos, set_fit_steady, and clear_fit.
```

### **Examples**

```
mdl <- islm_mdl(fit = TRUE)
fit_targets <- c(y = 1250, t = 255)
# register the fit targets in the DynMdl object
mdl$set_fit_steady(fit_targets)
mdl$solve_steady()
print(mdl$get_fit_steady())</pre>
```

20 get\_jacob

```
get_instrument_names/get_sigma_names
```

DynMdl methods: Retrieve the names of the fit instruments or sigma parameters used in the fit method.

### **Description**

These methods of R6 class DynMd1 return the names of the fit instruments or sigma parameters used in the fit method.

### Usage

```
mdl$get_instrument_names(all = FALSE)
mdl$get_sigma_names()
mdl is a DynMdl object implementing the fit method.
```

### **Arguments**

all A logical (default FALSE). If TRUE, the names of all fit instruments are returned, including the inactive fit instruments.

### See Also

```
get_fit_instruments, get_sigmas
```

# **Examples**

```
mdl <- islm_mdl(period = "2017Q1/2018Q3", fit = TRUE)
print(mdl$get_instrument_names())
print(mdl$get_sigma_names())</pre>
```

get\_jacob

DynMdl methods: Return the Jacobian for the static or dynamic model

### **Description**

These methods of R6 class DynMd1 can be used to retrieve the Jacobian for the static or dynamic model.

The methods return a matrix object which can be further analysed using standard linear algebra functions. This is particularly useful when method solve complains about (nearly) singular Jacobians. For example, an SVD decomposition using function svd can be used to identify linearly dependent rows or columns.

### **Usage**

```
mdl$get_static_jacob(sparse = FALSE)
mdl$get_jacob(sparse = FALSE)
mdl$get_back_jacob(period, sparse = FALSE)
mdl is a DynMdl object
```

### **Arguments**

sparse a logical. If TRUE, then the matrix is returned as a sparse matrix period an period object or an object that can be coerced to a period

### Methods

- get\_jacob: The Jacobian for the dynamic model This is the Jacobian used when solving the model with the stacked-time Newton method.
- get\_static\_jacob: The Jacobian for the static version of the model. This Jacobian is used when solving the steady state.
- get\_back\_jacob: The Jacobian at a specific period for backward looking models, treating the lags as exogenous. This Jacobian is used to solve backward looking models.

### **Examples**

```
mdl <- islm_mdl("2018Q1/2019Q4")
print(mdl$get_static_jacob())
print(mdl$get_jacob())

## Not run:
# print the Jacobian for a backward looking model at period 2018Q3
print(backwards_mdl$get_back_jacob("2018Q3"))

## End(Not run)</pre>
```

```
get_labels/get_tex_names
```

DynMdl method: Returns the labels or LaTeX names of the model variables and parameters

### **Description**

These methods of R6 class DynMd1 return the labels (long names) or LaTeX names of the model variables and parameters. The return value is a named character vector.

The labels and LaTeX names are defined in the mod file (consult the documentation of Dynare, in Dynare labels are called 'long names'). Method set\_labels can be used to modify these labels. By default the labels are equal to the variable names.

### Usage

```
mdl$get_labels()
mdl$get_tex_names()
mdl is a DynMdl object
```

### Methods

- get\_labels: Returns the labels (long names), e.g. "Disposable income"
- get\_tex\_names: Returns the LaTeX names (e.g. "Y\_d")

### See Also

```
set_labels
```

```
get_max_lag/get_max_lead
```

DynMdl methods: Returns the maximum lag or lead

# Description

Methods get\_max\_lag and get\_max\_lead of R6 class DynMdl return the maximum lag and lead of the original model, respectively. These are the maximum lag and lead in the equations specified in the mod file. The actual maximum lag or lead will be different if max\_laglead\_1 == TRUE and if there are endogenous lags or leads greater than 1.

```
DynMdl methods:

mdl$get_max_lag()
mdl$get_max_lead()

mdl is a DynMdl object
```

get\_mdldef 23

get_mdldef	DynMd1 method: Returns technical details about the model.

# **Description**

This function returns a list with various components containing technical details of the model, such as the names of the variables, the lead-lag incidence matrix, etc.

# Usage

```
DynMdl method:

mdl$sget_mdldef()

mdl is a DynMdl object
```

get\_name-methods

DynMdl methods: Retrieve the names of model variables or parameters

### **Description**

These methods of R6 class DynMdl return the names of the model variables or parameters

If the DynMdl object is also a DynMdl object, then get\_endo\_names and get\_exo\_names do not include the names of the auxiliary endogenous and exogenous variables used in the fit method. Use get\_instrument\_names to obtain the names of the fit instruments.

# Usage

```
mdl$get_endo_names(type = c("all", "lags", "leads"))
mdl$get_exo_names()
mdl$get_par_names(pattern = ".+")
mdl is a DynMdl object
```

### **Arguments**

type a character describing the type of the endogenous variables: "lags" or "leads" for endogenous variables with lags or leads, respectively. The default is "all" (all endogenous variables).

pattern A regular expression. If specified, then only names matching the regular expression are returned.

24 get\_period-methods

#### Methods

- get\_endo\_names: Names of the endogenous model variables.
- get\_exo\_names: Names of the endogenous model variables.
- get\_par\_names: Names of the model parameters (excluding the sigma parameters used in the fit method).

#### See Also

```
get_instrument_names and get_sigma_names
```

### **Examples**

```
mdl <- islm_mdl()
# print the names of all variables with leads
print(mdl$get_endo_names(type = "lead"))
# print parameters starting with "c"
print(mdl$get_par_names(pattern = "^c.*"))</pre>
```

get\_period-methods

DynMdl method: return the model, data, lead or lag period

# **Description**

These methods of R6 class DynMdl return the model period, data period, lag period, lead period, or base period respectively.

The *model period* is the default period for which the model will be solved. The *data period* is the period for which the model contains the values for the endogenous and exogenous variables. If a model has lags, then the data period always include the *lag period*: the period before the model period where the lags needed to solve the model in the model period are stored. For a model with leads the model data period also includes a *lead\_period*. Thus, the data period always contains the lag period, model period and lead period, but it may also be longer. See the example below.

The *base\_period* is used when the model has trend variables. All trend variables will be equal to 1 at the base period.

```
mdl$get_period()
mdl$get_data_period()
mdl$get_lag_period()
mdl$get_lead_period()
```

get\_solve\_status 25

```
mdl$get_base_period()
mdl is a DynMdl object
```

#### Methods

- get\_period: Returns the model period
- get\_data\_period: Returns the data period
- get\_lag\_period: Returns the lag period, or NULL if the model has no lags
- get\_lead\_period: Returns the lead period or NULL if the model has no leads
- get\_base\_period: Returns the base period.

#### See Also

```
set_period and init_data
```

# **Examples**

```
# For this example we first create a model with a data period
# starting many periods before the model period.
mdl <- islm_mdl()
mdl$init_data("1997Q1/2022Q4")
mdl$set_period("2017Q4/2022Q3")

print(mdl$get_period())  # result: "2017Q1/2022Q3"
print(mdl$get_data_period())  # result: "1997Q1/2022Q4"

# This model has a maximum lag and lead of 1, so the lag
# and lag period are simple the period before and after the model period.
print(mdl$get_lag_period())  # result: "2017Q3"
print(mdl$get_lead_period())  # result: "2022Q4"</pre>
```

get\_solve\_status

DynMdl method: Returns the solve status of the last model solve.

### **Description**

This method of R6 class DynMdl returns the status of the last model solve as a text string. If the last model solve was succesfull, it returns the string "OK".

26 get\_vars\_pars

### Usage

```
DynMdl method:
mdl$get_solve_status()
mdl is a DynMdl object
```

#### **Details**

The possible return values are:

- NA\_character\_ (method solve has not yet been called)
- "OK"
- "ERROR" (an error has occurred, check the warnings).

#### See Also

```
solve and solve_steady
```

# **Examples**

```
## Not run:
mdl <- islm_mdl(period = "2017Q1/2018Q4")
mdl$set_endo_values(NA, names = "y", period = "2017Q1")
mdl$solve()
if (mdl$get_solve_status() != "OK") {
    stop("Error solving the model. Check the warnings!")
}
## End(Not run)</pre>
```

get\_vars\_pars

DynMdl methods: Returns a list of all model variables and parameters

# **Description**

This method of R6 class DynMdl returns a list of all model variables and parameters. This makes it easy to directly evaluate expressions involving both model variables and parameters.

If the DynMdl object is also a DynMdl object, then the variables do not include the the auxiliary endogenous and exogenous variables used in the fit method.

```
mdl$get_vars_pars(period = mdl$get_data_period(), trend = TRUE)
mdl is a DynMdl object
```

init\_data 27

### **Arguments**

```
period an period_range object or an object that can be coerced to a period_range #'
```

trend a logical. This argument is used for model with trend variables. If TRUE (the default), then the endogenous variables are multiplied with their trends (called deflators in the mod file)

#### See Also

```
get_data-methods, get_param, get_fit, get_fit_instruments and get_lagrange
```

### **Examples**

```
mdl <- islm_mdl(period = "2017Q1/2017Q3")

# create a list of all parameters and model variables for
# period 2017q1/2017q2
vars_pars <- mdl$get_vars_pars(period = "2017Q1/2017Q2")
print(vars_pars)

# evaluate an expression within list vars_pars
with(vars_pars, print(t0 + t1 * y))

# copy all parameters to the global environment, and evaluate
# an expressions in the global environment:
list2env(vars_pars, .GlobalEnv)
print(md - ms)</pre>
```

init\_data

DynMdl *method*: *initializes the model data*.

# **Description**

This method of R6 class DynMdl sets the model data period and initializes the model variables with static values of the exogenous and endogenous model variables. Also all fit targets are removed. If argument data has been specified then the steady state values are subsequently updated with the timeseries in data.

If the model period has not yet been specified (in function dyn\_mdl or method set\_period), then this method also sets the model period, the standard period for which the model will be solved. The model period is obtained from the data period by subtracting the lag and lead periods.

```
mdl$init_data(data_period = NULL, data = NULL, upd_mode = c("upd", "updval"))
mdl is a DynMdl object
```

28 islm\_mdl

### Arguments

data\_period\_period\_range object, or an object that can be coerced to period\_range. If not specified, then the data period is based on the period range of argument data (if this argument has been specified) and the model period.

data a ts or regts object with values for endogogenous and exogenous model variables, including fit instruments and Lagrange multipliers used in the fit method. If data has labels, then these labels are used to update the model labels. If the model has trends, then the timeseries in data should include the trends.

upd\_mode the update mode, a character string specifying how the timeseries in object data are transferred to the model data. For "upd" (standard update, default), the timeseries in data are used to replace the steady state values of the exogenous and endogenous model variables. For "updval", the static model variables are only replaced by valid (i.e. non-NA) values in data).

If neither data\_period nor data have been specified, then the data period is determined from the model period (which in that case must have been specified before init\_data is called).

### Warning

Method init\_data removes all fit targets.

### **Examples**

```
mdl <- islm_mdl()
mdl$init_data("2017Q2/2021Q3")</pre>
```

islm\_mdl

Returns an example ISLM model

# **Description**

This function returns an example ISLM model, If argument period has been specified, then this function also initializes the model data with the steady state values.

### Usage

```
islm_mdl(period, fit = FALSE)
```

# Arguments

period the model period for the ISLM model

fit a logical indicating whether the dynamical fit procedure should be used

#### Value

```
a DynMdl object.
```

put\_static\_endos 29

### **Examples**

```
mdl <- islm_mdl("2017Q1/2019Q4")
```

# Description

This method of R6 class DynMd1 transfers the static endogenous variables to the model data.

# Usage

```
DynMdl method:
mdl$put_static_endos(period = mdl$get_data_period())
mdl is a DynMdl object
```

# Arguments

period A period\_range object or an object that can be coerced to a period\_range, specifying the period for which the endogenous model data will be updated with the static endogenous variables.

# See Also

```
solve_steady, set_static_endos and get_static_endos.
```

# **Examples**

```
mdl <- islm_mdl(period = "2018Q1/2040Q3")

# transfer static endogenous variables for the full data period
mdl$put_static_endos()

# now only for the lead period
mdl$put_static_endos(period = mdl$get_lead_period())</pre>
```

30 residual\_check

	md1
read	

Reads a model from a RDS file

### **Description**

This function reads a model from an RDS file that has been written by method write\_mdl of an DynMdl object.

### Usage

```
read_mdl(file, dll_dir, silent = FALSE)
```

# Arguments

file the name of the RDS file

dll\_dir the directory where the dynamically linked library is stored. Primarily used for

testing. Only used if the model was created with the dll option (see function

dyn\_mdl).

silent A logical (default FALSE). It TRUE, then no output is written.

#### Value

```
a DynMdl object.
```

# See Also

```
write_mdl
```

### **Examples**

```
mdl <- islm_mdl("2017Q1/2019Q2")
mdl$write_mdl("islm_mod.rds")
mdl2 <- read_mdl("islm_mod.rds")</pre>
```

residual\_check

DynMdl method: Calculates the residuals of the equations

# **Description**

This method of R6 class DynMdl calculates the residuals for the full model period and returns the result as a regts timeseries object.

```
mdl$residual_check(tol, include_fit_eqs = FALSE)
mdl is a DynMdl object
```

run\_dynare 31

### **Arguments**

tol the tolerance parameter. If specified, then the return value does not include columns for the equations whose residuals are smaller than tol

include\_all\_eqs a logical value (default FALSE). If TRUE, then the all equations, including fit equations and auxiliary equations (if present), are included in the residual check. The auxiliary equations are extra equations created when the model has lags or leads greater than 1 and if dynmdl was called with max\_laglead\_1 = TRUE.

include\_fit\_eqs a logical value (default FALSE). If TRUE, then fit equations (if present) are included in the residual check. Ignored if include\_all\_eqs is TRUE.

debug\_eqs Debug equations (default FALSE). Only used for the internal calculation mode (calc == "internal", see dyn\_mdl). If TRUE then numerical problems in evaluation of mathematical functions or operators such a log are reported.

### See Also

```
static_residual_check
```

run\_dynare

Run a mod file Dynare with Matlab or Octave.

# Description

This function runs a mod file with Dynare using either Matlab or Octave. The input files for Dynare and Octave/Matlab are generated automatically. The command octave or matlab should be in the search path.

```
run_dynare(
  mod_file,
  period,
  data,
  steady = TRUE,
  perfect_foresight = !missing(period) || !missing(data),
  scratch_dir = tempfile(),
  dynare_path = NULL,
  steady_options,
  perfect_foresight_solver_options,
  initval_type = c("m", "xlsx"),
  use_octave = Sys.which("matlab") == "",
  exit_matlab = FALSE
)
```

32 run\_dynare

#### **Arguments**

mod\_file The name of a Dynare mod file. For models with trends, this can also be a fit mod

file created with function dyn\_mdl when argument fit\_mod\_file was specified. However, for model with trends the fit mod file is not a correct Dynare mod file, because the fit equations are already detrended while the original equations still

contain trends.

period A period\_range object or object that can be coerced to a period\_range. This

argument must be specified when the perfect foresight solver is called.

data a ts or regts object with values for endogogenous and exogenous model vari-

ables used in the perfect foresight solver. If the model has trends, then the

timeseries in data should include the trends.

steady A logical, indicating wether the steady state should be calculated (default is

TRUE). If the steady state is calculated then also the eigenvalues are calculated.

perfect\_foresight

A logical, indicating wether the perfect foresight solver should be called. The default is TRUE if argument period or data have been specified and FALSE oth-

erwise.

scratch\_dir Directory where the Matlablab and Dynare scripts are created. By default this

is a temporary directory that is automatically deleted when the R session termi-

nates.

dynare\_path Character string specifying the name of the directory of the Dynare installation.

On Linux it is usually not necessary to the specify this argument. On Windows it is necessary to specify the path of the Dynare installation. In you are running

R in the CPB environment the path to Dynare is set automatically.

steady\_options Options passed to the steady command of Dynare. This should be a named list,

which names corresponding to the Dynare options. Specify a NULL value if the option has no value. Consult the documentation of Dynare for a list of available

options. Example: steady\_options = list(tolf = 1e-7, nocheck = NULL)

perfect\_foresight\_solver\_options

Options passed to the perfect\_foresight\_solver command of Dynare. This should be a named list, which names corresponding to the Dynare options. Specify a NULL value if the option has no value. Consult the documentation of Dynare for a list of available options. Example: steady\_options = list(tolf

= 1e-7, no\_homotopy = NULL).

initval\_type A character specifying the type of initval file used in the Matlab/Octave job: "m"

for a Matlab file and "xlsx" for an xlsx-file.

use\_octave A logical. If TRUE, then Dynare is envoked with Octave, otherwise Matlab is

used. By default Matlab is used if available.

exit\_matlab A logical specifying if Matlab should immediately exit when the calcultions

have finished Matlab writes the output to a separate console. If exit\_matlab is FALSE (the default), then the R job waits until the user has closed this console, or entered exit in the console. Otherwise the console is automatically closed at the end of the calculation and all output is lost. This argument is ignored if Dynare is run with Octave. Octave does not open a seperate console: all output

appears in the same console used by R.

run\_initval 33

#### Value

A list with the following components

```
steady_endos (only if steady == TRUE): a steady state endogenous variables eigval (only if steady == TRUE): the eigenvalues of the steady state
```

endo\_data (only if perfect\_foresight\_solver == TRUE): the endogenous variables for

the solution of the perfect foresight solver

### **Examples**

run\_initval

DynMdl method: Evaluate to initval block to obtain new values for the static endogenous and exogenous variables based on the current parameters.

# Description

This function runs the equations in the initval block using the current values of parameters and static model variables. The static values of the exogenous and endogenous variables are updated with the new values calculated using the initval equations. Static endogenous variables are not updated in argument update\_endos = FALSE.

Variables that do not occur at the left hand side of an equation in the initval block are *not* modified. Thus they are not initialized to zero, in contrast to the evaluation of the initval block by the Dynare parser.

#### Usage

```
DynMdl method:
mdl$run_initval(update_endos = TRUE)
mdl is a DynMdl object
```

# Arguments

update\_endos A logical. If TRUE, then the static value of the endogenous variables are updated with the new values computed from the initval equations.

34 set/get\_param

set/get\_param

DynMdl methods: Set and get model parameters

### **Description**

DynMdl methods set\_param and set\_param\_values can be used to set the model parameters. Method get\_param returns model parameters (excluding sigma parameters used in the fit method), and method get\_all\_param returns parameters including the sigma parameters.

Methods set\_param and set\_param\_values treat the sigma parameters used in the fit procedure the same as ordinary parameters. However, the recommended methods to set or get sigma parameters are set\_sigma, set\_sigma\_values and get\_sigmas.

### Usage

```
mdl$set_param(params, names, name_err = c("stop", "warn", "silent"))
mdl$set_param_values(value, names, pattern)
mdl$get_param(pattern, names)
mdl$get_all_param(pattern, names)
mdl is a DynMdl object
```

# **Arguments**

params a named numeric vector with parameter values. The names are the names of the parameters. names a character vector with names of the parameters. For method set\_param, this argument *must* be specified if params is a vector without names.

name\_err this option specifies the action that should be taken when a specified name is not the name of a model parameter. For "stop" (the default), the execution of this function is stopped. For "warn" and "silent" the names that are no model parameters are skipped. "warn" does, however, give a warning.

pattern a regular expression. The action (get or set parameter values) is applied to all parameters with names matching pattern.

If neither names nor pattern has been specified in methods set\_param\_values or get\_param, then the action is applied to all model parameters.

### Methods

- set\_param: Set the parameters using a named numeric vector. The names of the vector should be the parameter names.
- set\_param\_values: Give one or more parameter a specified value.
- get\_param: Returns the parameters (excluding the sigma parameters used in the fit method)
- get\_all\_param: Returns parameters including the sigma parameters used in the fit method.

set/get\_sigma 35

### See Also

```
get_par_names, set_sigma, set_sigma_values and get_sigmas
```

# **Examples**

```
mdl <- islm_mdl()
# print parameters c0, c1, c2 and c3
print(mdl$get_param(pattern = "^c.*"))
# set parameter i0 to 101 and c0 to 110
mdl$set_param(c(i0 = 101, c0 = 110))
# set all parameters with names ending with "5" to zero:
mdl$set_param_values(0, pattern = "5$")
# print all parameters
print(mdl$get_param())</pre>
```

set/get\_sigma

DynMdl methods: Set and get the sigma parameters for the fit method

# Description

DynMdl methods set\_sigma and set\_sigma\_values can be used to set the sigma parameters for the fit instruments used in the fit method. The names of the sigma parameters are the names of the instruments suffixed with sigma\_. For example, the name of the sigma parameter corresponding to instrument "uc" is "sigma\_uc".

If a sigma parameter is smaller than 0, then the corresponding fit instrument is not active, and is keeped fixed at the current value, even though it is an endogenous model variable.

Method get\_sigmas returns all sigma parameters larger than or equal to zero.

```
mdl$set_sigma(sigmas, names, name_err = c("stop", "warn", "silent"))
mdl$set_sigma_values(value, names, pattern)
mdl$get_sigma(pattern, names)
mdl$get_sigmas()
mdl is a DynMdl object.
```

36 set/get\_sigma

# **Arguments**

sigmas a named numeric vector with values of the sigma parameters. The names are the name of the instruments (not the names of the sigma parameters).

names a character vector with names of fit instruments. For method set\_sigma, this argument *must* be specified if sigmas is a vector without names.

name\_err this option specifies the action that should be taken when a variable name is not a fit instrument. For "stop" (the default), the execution of this function is stopped. For "warn" and "silent", the names that are no fit instrument names are skipped. "warn" does, however, give a warning.

value a numeric vector of length 1.

pattern a regular expression. The action (get or set sigma parameter values) is applied to all sigma parameters with names matching pattern.

If neither names nor pattern has been specified in methods set\_param\_values or get\_param, then the action is applied to all model parameters.

#### Methods

- set\_sigmas: Set the sigma parameters using a named numeric vector. The names of the vector should be the names of the corresponding fit instruments.
- set\_sigma\_values: Give one or more sigma parameters a specified value.
- get\_sigma: Return sigma parameters.
- get\_sigmas: Returns all sigma parameters greater than or equal to zero.

### See Also

```
get_instrument_names, get_sigma_names, set_fit and clear_fit
```

### **Examples**

```
mdl <- islm_mdl(fit = TRUE)
mdl$set_sigma(c(umd = 12))

# print the sigma parameter for umd
print(mdl$get_sigma(names = "umd"))

# disable fit instruments umd and umc
mdl$set_sigma_values(-1, names = c("umd", "uc"))

# print all sigma parameters for active fit instruments
print(mdl$get_sigmas())

# print names of all active instruments (sigma >= 0):
print(mdl$get_instrument_names())

# set all sigmas parameters to 1
mdl$set_sigma_values(1)
```

```
set/get_static_endos/exos
```

DynMdl methods: set and get the static values of the model variables

# Description

set\_static\_exos, set\_static\_exo\_values, set\_static\_endos and set\_static\_data can be used to set one or more static values of the endogenous and/or exogenous model variables. The corresponding get methods can be used to retrieve them.

Each DynMdl object contains a set of static values for the exogenous and endogenous model variables. The static exogenous values are used to compute the steady state with function methode solve\_steady. The static endogenous values are both input and output of solve\_steady: they are used as an initial guess for the steady state, and replaced by the steady state solution.

The static values are initialized to the values specified in the initval block of the mod file, or to zero if they are not specified in the initval block. The static values can be modified with methods set\_static\_endos, set\_static\_endos, set\_static\_data or set\_static\_exo\_values.

get\_all\_static\_endos returns the static values for all endogenous variables, fit instruments and Lagrange multipliers. get\_all\_data also returns all static values of exogenous variables. These functions can be useful to save the complete solution of a model that be used as initial values for the endogenous variables in another model.

## Usage

```
DynMdl method:
```

```
mdl$set_static_endos(endos, names = names(endos), name_err = c("stop", "warn", "silent"))
mdl$set_static_exos(exos, names = names(endos), name_err = c("stop", "warn", "silent"))
mdl$set_static_exo_values(value, names, pattern)
mdl$set_static_data(data, names = names(data), name_err = c("stop", "warn", "silent"))
mdl$get_static_endos(pattern, names)
mdl$get_static_endos(pattern, names)
mdl$get_static_data(pattern, names)
mdl$get_all_static_endos()
mdl$get_all_static_data()
```

# **Arguments**

- endos A (named) numerical vector with new static values of the endogenous variables. If the vector has no names, than argument names must be specified.
- exos A (named) numerical vector with new static values of the exogenous variables. If the vector has no names, than argument names must be specified.
- data A (named) numerical vector with new static values of both endogenous and exogenous variables. If the vector has no names, than argument names must be specified.

```
value a numeric vector of length 1
names a character vector with names of model variables
```

pattern a regular expression

name\_err this option specifies the action that should be taken when a variable name is not a model variable. For "stop" (the default), the execution of this function is stopped. For "warn" and "silent" the names that are no model variables are skipped. "warn" does however give a warning.

#### Methods

- set\_static\_endos: Set the static values of one or more endogenous variables (including static fit instruments and static Lagrange multipliers).
- set\_static\_exos: Set the static values of one or more exogenous variables.
- set\_static\_exo\_values: Give more than one exogenous variable the same static value.
- set\_static\_data: Set the static values of one or more endogenous or exogenous variable (including static fit instruments and static Lagrange multipliers.)
- get\_static\_endos: Returns the static values of one or more endogenous variables, excluding fit instruments and Lagrange multipliers.
- get\_static\_exos: Returns the static values of one or more exogenous variables.
- get\_static\_data: Returns the static values of the model variables: exogenous and endogenous model variables and static fit instruments.
- get\_all\_static\_endos: Returns all static endogenous variables, including fit instruments and lagrange multipliers.
- get\_all\_static\_data: Returns all static endogenous and exogenous variables, including fit instruments and lagrange multipliers.

## See Also

```
solve_steady, check
```

```
mdl <- islm_mdl()
mdl$set_static_endos(c(y = 1250))

# set static values of all exogenous variables starting with m
# (for this model only "ms") to zero.
mdl$set_static_exo_values(333, pattern = "^m")
print(mdl$get_static_endos())</pre>
```

set\_data 39

set_data	DynMd1 method: transfers data from a timeseries object to the model
	data

# **Description**

This method of R6 class DynMdl transfers data from a timeseries object to the model data (both endogenous and exogenous). If the model implements the fit method, then set\_data can also be used to modify fit instruments and the Lagrange multipliers.

# Usage

## **Arguments**

- data a ts or regts object. If data has labels, then set\_data will also update the labels of the corresponding model variables. If the model has trends, then the timeseries in data should include the trends.
- names a character vector with variable names. Defaults to the column names of data. If data does not have column names, then argument names is mandatory
- upd\_mode the update mode, a character string specifying how the timeseries are updated: "upd" (standard update, default) or "updval" (update only with valid numbers). See details.
- fun a function used to update the model data. This should be a function with two arguments. The original model data is passed to the first argument of the function and data to the second argument. See the examples.
- name\_err this option specifies the action that should be taken when a variable name is not a model variable. For "stop" (the default), the execution of this function is stopped. For "warn" and "silent" the timeseries that are no model variables are skipped. "warn" does however give a warning.

#### **Details**

Method set\_data transfers data from a timeseries object to the model data. If data is a multivariate timeseries object, then each column is used to update the model variable with the same name as the column name. If data does not have column names, or if the column names do not correspond to the model variable names, then argument names should be specified.

By default, all values in data are used to update the corresponding model variable. Sometimes it is desirable to skip the NA values in data. This can be achieved by selecting "updval" for argument upd\_mode. Other non finite numbers (NaN, Inf, and -Inf) are also disregarded for this update mode. The argument upd\_mode controls how the timeseries are updated:

40 set\_fit

```
"update" Model variables are updated with the timeseries in data "updval" Model variables are updated with the non NA values in data
```

#### See Also

```
get_data-methods, set_values-methods and change_data-methods
```

## **Examples**

```
mdl <- islm_mdl(period = "2017Q1/2017Q3")</pre>
# create a multivariate regts object for exogenous variables g and md
exo \leftarrow regts(matrix(c(200, 210, 220, 250, 260, 270), ncol = 2),
             start = "2017Q1", names = c("g", "ms"))
# set and print data
mdl$set_data(exo)
print(mdl$get_exo_data())
# create a univariate regts object for exogenous variable ms,
# with a missing value in 2017Q2
ms \leftarrow regts(c(255, NA, 273), start = "2017Q1")
# update with update mode updval (ignore NA)
# note that here we have to specify argument names,
# because ms does not have column names
mdl$set_data(ms, names = "ms", upd_mode = "updval")
print(mdl$get_exo_data())
# in the next example, we use argument fun to apply an additive shock to the
# exogenous variables g and ms.
shock <- regts(matrix(c(-5, -10, -15, 3, 6, 6), ncol = 2),
             start = "2017Q1", names = c("g", "ms"))
mdl\$set_data(shock, fun = function(x1, x2) \{x1 + x2\})
# the statement above can be more concisely written as
mdl$set_data(shock, fun = `+`)
#`+` is a primitive function that adds its two arguments.
```

set\_fit

DynMdl method: transfers data from a timeseries object to the fit targets.

# **Description**

The method set\_fit of R6 class DynMdl transfers data from a timeseries object to the fit targets.

set\_fit 41

## Usage

## **Arguments**

```
data a ts or regts timeseries object
```

names a character vector with variable names, with the same length as the number of timeseries in data. Defaults to the column names of data. If data does not have column names, then argument names is mandatory

name\_err this option specifies the action that should be taken when a variable name is not an
endogenous model variable. For "stop" (the default), the execution of this function is stopped.
For "warn" and "silent" the timeseries that are no endogenous model variables are skipped.
"warn" does however give a warning.

#### **Details**

Method set\_fit transfers data from a timeseries object to the fit targets. It works similarly as method set\_data. If data is a multivariate timeseries object, then each column is used to update the fit target with the same name as the column name. If data does not have column names, or if the column names do not correspond to the model variable names, then argument names should be specified.

If data contains NA values, then the variable is not a fit target for the corresponding periods, which implies that the variable will be calculated according to the equations of the model.

# Warning

Method init\_data removes all fit targets.

#### See Also

```
get_fit, set_fit_steady, set_sigma, set_sigma_values, get_sigma and clear_fit
```

```
mdl <- islm_mdl(period = "2016Q1/2017Q3", fit = TRUE)

# create a regts with fit targets
y <- regts(c(1250, 1255, 1260), start = "2016Q1")
t <- regts(c(250, 255), start = "2016Q1")
fit_targets <- cbind(y, t)

# register the fit targets in the DynMdl object
mdl$set_fit(fit_targets)
print(mdl$get_fit())</pre>
```

42 set\_fit\_steady

set\_fit\_steady

DynMdl method: set fit targets for the steady state

## **Description**

This method of R6 class DynMdl sets the static fit targets, i.e. the fit targets used in the steady state calculation.

# Usage

```
mdl$set_fit_steady(data, names = names(data),
name_err = c("stop", "warn", "silent"))
mdl is a DynMdl object implementing the fit method.
```

# **Arguments**

data a named numeric vector with the fit target values. The names coresspond to the names of the endogenous model variables.

names a character vector with variable names, with the same length as the vector data. Defaults to the cnames of data. If data does not have names, then argument names is mandatory

name\_err this option specifies the action that should be taken when a variable name is not an endogenous model variable. For "stop" (the default), the execution of this function is stopped. For "warn" and "silent" the timeseries that are no endogenous model variables are skipped. "warn" does however give a warning.

#### **Details**

If data contains NA values, then the corresponding model variable is not a fit target.

#### Warning

Method init\_data removes all fit targets.

# See Also

```
get_fit_steady and clear_fit
```

```
mdl <- islm_mdl(fit = TRUE)

# create a regts with fit targets
y <- regts(c(1250, 1255, 1260), start = "2016Q1")
t <- regts(c(250, 255), start = "2016Q1")
fit_targets <- c(y = 1250, t = 250)</pre>
```

set\_fit\_values 43

```
# register the static fit targets in the DynMdl object
mdl$set_fit_steady(fit_targets)
print(mdl$get_fit_steady())
mdl$solve_steady()
print(mdl$get_static_endos())
```

set\_fit\_values

DynMdl method: Sets the values of the fit targets

# **Description**

This method of R6 class DynMdl can be used to set the values of the fit targets. See the documentation of function set\_fit for more information about fit targets.

## Usage

```
mdl$set_fit_values(value, names, pattern, period = mdl$get_data_period())
mdl is a DynMdl object implementing the fit method.
```

#### **Arguments**

value a numeric vector of length 1 or with the same length as the length of the range of period.

names a character vector with variable names

pattern a regular expression for selecting the names of fit targets.

period\_range object or an object that can be coerced to a period\_range.

#### See Also

```
set_fit and clear_fit
```

```
mdl <- islm_mdl(period = "2017Q1/2018Q3", fit = TRUE)
# set the values of ms in 2017Q1 and 2017Q2
mdl$set_fit_values(c(190, 195), names = "i", period = "2017Q1/2017Q2")
print(mdl$get_fit())</pre>
```

44 set\_period

set\_labels

DynMdl method: Sets labels for the model variables.

# **Description**

This method of R6 class DynMdl sets labels for the model variables.

# Usage

```
mdl$set_labels(labels)
mdl is a DynMdl object
```

## **Arguments**

labels a named character vector. The names are the names of the model variables

#### See Also

```
get_labels
```

# **Examples**

```
mdl <- islm_mdl()
mdl$set_labels(c(c = "Consumption", i = "investments"))</pre>
```

set\_period

DynMdl method: sets the model period

# **Description**

This method of R6 class DynMd1 sets the model period. This is the default period used when solving the model.

If the model data has not already been initialized with method <code>init\_data</code>, then <code>set\_period</code> also initializes the model data. In that case the model data period is set to the specified model period extended with a lag and lead period. Model timeseries are initialized with with the static values of the exogenous and endogenous model variables.

If the model data has already been initialized with method init\_data, then the new model period should be compatible with the model data period. In particular, the new model period extended with a lag and lead period should not contain periods outside the model data period.

## Usage

```
mdl$set_period(period)
mdl is a DynMdl object
```

set\_values-methods 45

## **Arguments**

period\_range object, or an object that can be coerced to period\_range

# **Examples**

```
mdl <- islm_mdl()
mdl$set_period("2017Q2/2021Q3")</pre>
```

set\_values-methods

DynMdl methods: Sets the values of the model data

# **Description**

This method of R6 class DynMd1 can be used to set the values of the model data.

# Usage

```
mdl$set_endo_values(value, names, pattern, period = mdl$get_data_period())
mdl$set_exo_values(value, names, pattern, period = mdl$get_data_period())
mdl is a DynMdl object
```

# **Arguments**

value a numeric vector of length 1 or with the same length as the length of the range of period. If the model has trends, then the values should include the trends.

names a character vector with variable names.

pattern a regular expression for selecting the names of variables.

period a period\_range object or an object that can be coerced to a period\_range.

If neither names nor pattern have been specified, then all endogenous or exogenous variables are set to the specified value.

## Methods

- set\_endo\_values: Endogenous model variables (including fit instruments and Lagrange multipliers for the fit method).
- set\_exo\_values: Exogenous model variables.

#### See Also

```
change_data-methods and set_data
```

46 solve

#### **Examples**

```
mdl <- islm_mdl(period = "2017Q1/2018Q3")
# set the values of ms in 2017Q1 and 2017Q2
mdl$set_exo_values(c(205, 206), names = "ms", period = "2017Q1/2017Q2")
# set the values for y and yd to 1000 for the full data period
mdl$set_endo_values(1000, pattern = "^yd?$")</pre>
```

solve

DynMdl method: Solves the model

# Description

This method of R6 class DynMdl solves the model.

solve does *not* raise an error when the solve was not successful. In that case a warning may be issued. Method get\_solve\_status can be used to check whether the solve was successfully terminated or not.

# Usage

DynMdl method:

## **Arguments**

- control A named list of control parameters passed to function umf\_solve\_nl or nleqslv, depending on argument solver. If control parameter trace has not been specified, then that parameter is set to TRUE when the model is solved using the stacked time method and FALSE when the model is solved using the backwards method (see also argument mode).
- mode A character specifying the solve mode. Possible values are "stacked\_time" and "backwards". By default, models with leads are solved with the stacked time method and models without leads are solved backwards.
- solver Specifies the solver employed to solve the model: "umfpackr" (sparse linear algebra) or "nleqslv" (dense linear algebra). For large models, the umfpackr solve can be much faster.
- start Method used to initialize starting values when solving the model with the backwards method. For "current" (the default) the current values of the endogenous variables are used as starting values. For "previous" the solution of the previous period is used to create starting values (except for the first period when the model is solved). This argument is ignored if the model if solved with the stacked time Newton method

solve\_dynare 47

debug\_eqs Debug equations (default FALSE). Only used for the internal calculation mode (calc == "internal", see dyn\_mdl). If TRUE then numerical problems in evaluation of mathematical functions or operators such a log are reported.

- homotopy A logical. If TRUE (the default), then the homotopy approach is used when directly solving the model fails. Consult the documentation of Dynare for more information about the homotopy aproach.
- silent A logical. If TRUE then all output is suppressed. In that case control parameters silent and trace (see argument control) are ignored.
- backrep A character specifying the type of iteration report when the model is solved using the backwards mode (see argument mode). If "period", then the number of iterations per period is printed. If "total", then only the total number of iterations is printed. This argument is ignored if argument silent is TRUE.
- ... Other arguments passed to the solver function (umf\_solve\_nl when the solver is"umfpackr"), Useful arguments for umf\_solve\_nl are global (select a global strategy) and umf\_control (this option can be used to specify the UMFPACK ordering method, see the example below). See the documentation of umf\_solve\_nl for more details.

#### See Also

```
solve_steady and get_solve_status
```

# **Examples**

solve\_dynare

DynMdl method: Solves the model with Dynare

#### **Description**

Solve the model with Dynare using Matlab or Octave.

48 solve\_dynare

#### Usage

## Arguments

- scratch\_dir Directory where the Matlablab and Dynare scripts are created. By default this is a temporary directory that is automatically deleted when the R session terminates.
- dynare\_path Character string specifying the name of the directory of the Dynare installation. On Linux it is usually not necessary to the specify this argument. On Windows it is necessary to specify the path of the Dynare installation. In you are running R in the CPB environment the path to Dynare is set automatically.
- model\_options Options passed to the model command of Dynare. This should be a named list, which names corresponding to the Dynare options. Specify a NULL value if the option has no value. Consult the documentation of Dynare for a list of available options. Example: model\_options = list(block = NULL, mfs = 2)
- solve\_options Options passed to the perfect\_foresight\_solver command of Dynare. This should be a named list, which names corresponding to the Dynare options. Specify a NULL value if the option has no value. Consult the documentation of Dynare for a list of available options. Example: steady\_options = list(tolf = 1e-7, no\_homotopy = NULL). The default options are list(tolf = 1e-8, tolx = 1e-8)
- initval\_type A character specifying the type of initval file used in the Matlab/Octave job: "m" for a Matlab file and "xlsx" for an xlsx-file.
- use\_octave A logical. If TRUE, then Dynare is envoked with Octave, otherwise Matlab is used. By default Matlab is used if available.
- exit\_matlab A logical specifying if Matlab should immediately exit when the calcultions have finished Matlab writes the output to a separate console. If exit\_matlab is FALSE (the default), then the R job waits until the user has closed this console, or entered exit in the console. Otherwise the console is automatically closed at the end of the calculation and all output is lost. This argument is ignored if Dynare is run with Octave. Octave does not open a seperate console: all output appears in the same console used by R.

```
## Not run:
    islm <- islm_mdl(period = "2018Q1/2023Q3")
    islm$set_exo_values(260, period = "2018q1", names = "g")
    islm$solve_dynare()
## End(Not run)</pre>
```

solve\_steady 49

solve\_steady

DynMdl *method: Solves the steady state.* 

## **Description**

This method of R6 class DynMdl solves the steady state.

This function uses the static exogenous and endogenous variables stored in the DynMdl object. The static endogenous variables are used as an initial guess for solving the steady state. After creating a DynMdl object, the static exogenous and endogenous variables are initialized to the values specified in the initval block of the mod file, or to zero if they are not specified in the initval block. The static variables can be modified with methods set\_static\_exos and set\_static\_endos.

The function get\_static\_endos can be used to retrieve the steady state solution.

solve\_steady does *not* raise an error when the solve was not successful. In that case a warning may be issued. Method get\_solve\_status can be used to check whether the solve was successfully terminated or not.

#### Usage

DynMdl method:

mdl is a DynMdl object

## **Arguments**

- control A named list of control parameters passed to function umf\_solve\_nl or nleqslv, depending on argument solver. If control parameter trace has not been specified, then that parameter is set to TRUE.
- solver Specifies the solver employed to solve the model: umfpackr (sparse linear algebra) or nleqslv (dense linear algebra). For large model, the umfpackr solve can be much faster.
- debug\_eqs Debug equations (default FALSE). Only used for the internal calculation mode (calc == "internal", see dyn\_mdl). If TRUE then numerical problems in evaluation of mathematical functions or operators such a log are reported.
- silent A logical. If TRUE then all output is suppressed. In that case control parameters silent and trace (see argument control) are ignored.
- ... Other arguments passed to the solver

## See Also

```
\tt set\_static\_endos, set\_static\_exos, get\_static\_endos, get\_static\_exos, put\_static\_endos, and get\_solve\_status
```

50 solve\_steady\_dynare

## **Examples**

```
mdl <- islm_mdl(period = "2018Q1/2080Q1")
mdl$solve_steady(control = list(trace = 1))

# print the solution
print(mdl$get_static_endos())

# update the model data with steady state values of endogenous variables
mdl$put_static_endos()</pre>
```

solve\_steady\_dynare

DynMdl method: Solves the steady state with Dynare

# Description

Solve the steady state and calculate the eigenvalues with Dynare using Matlab or Octave.

# Usage

```
DynMdl method:
```

mdl is a DynMdl object

# **Arguments**

- scratch\_dir Directory where the Matlablab and Dynare scripts are created. By default this is a temporary directory that is automatically deleted when the R session terminates.
- dynare\_path Character string specifying the name of the directory of the Dynare installation. On Linux it is usually not necessary to the specify this argument. On Windows it is necessary to specify the path of the Dynare installation. In you are running R in the CPB environment the path to Dynare is set automatically.
- model\_options Options passed to the model command of Dynare. This should be a named list,
   which names corresponding to the Dynare options. Specify a NULL value if the option has
   no value. Consult the documentation of Dynare for a list of available options. Example:
   model\_options = list(block = NULL, mfs = 2)
- solve\_options Options passed to the steady command of Dynare. This should be a named list, which names corresponding to the Dynare options. Specify a NULL value if the option has no value. Consult the documentation of Dynare for a list of available options. Example: steady\_options = list(tolf = 1e-7, no\_homotopy = NULL). The default is list(tolf = 1e-8)

static\_residual\_check 51

use\_octave A logical. If TRUE, then Dynare is envoked with Octave, otherwise Matlab is used. By default Matlab is used if available.

exit\_matlab A logical specifying if Matlab should immediately exit when the calcultions have finished Matlab writes the output to a separate console. If exit\_matlab is FALSE (the default), then the R job waits until the user has closed this console, or entered exit in the console. Otherwise the console is automatically closed at the end of the calculation and all output is lost. This argument is ignored if Dynare is run with Octave. Octave does not open a seperate console: all output appears in the same console used by R.

#### Value

The eigenvalues of the steady state.

## **Examples**

## **Description**

This method of R6 class DynMdl calculates the residuals for the static version of the model. The result is a named numeric vector, where the names are the equation numbers.

#### Usage

```
mdl$static_residual_check(tol, include_fit_eqs = FALSE)
mdl is a DynMdl object
```

model

#### **Arguments**

- tol the tolerance parameter. If specified, then return value does not include equations whose residuals are smaller than tol.
- include\_all\_eqs a logical value (default FALSE). If TRUE, then the all equations, including fit equations and auxiliary equations (if present), are included in the residual check. The auxiliary equations are extra equations created when the model has lags or leads greater than 1 and if dynmdl was called with max\_laglead\_1 = TRUE.
- include\_fit\_eqs a logical value (default FALSE). If TRUE, then fit equations (if present) are included in the residual check. Ignored if include\_all\_eqs is TRUE.
- debug\_eqs Debug equations (default FALSE). Only used for the internal calculation mode (calc == "internal", see dyn\_mdl). If TRUE then numerical problems in evaluation of mathematical functions or operators such a log are reported.

52 svd\_analysis

# See Also

residual\_check

svd_analysis	Perform an SVD analysis of a jacobian matrix.

# Description

Find linear combinations of rows and columns of the jacobian using an Singular Value Decomposition (SVD) of the jacobian.

# Usage

```
svd_analysis(jac, sd_tol = 1e-12, coef_tol = 1e-12)
```

# Arguments

jac	a square matrix, for example the matrix returned by DynMdl methods get_static_jacob, get_jacob or get_back_jacob.
sd_tol	singular value tolerance. Singular values smaller than this tolerance are ignored.
coef_tol	coefficient tolerance. The returned singular vector matrices do no include rows for which all elements are smaller than coef tol.

# Value

a list with class svd\_analysis, containing the following components

d	a vector with singular values smaller than sd_tol, in decreasing order.
u	a matrix with the left singular vectors corresponding to the singular values d. Rows for which all elements are smaller than coef_tol have been removed. The columns of this matrix can be interpreted as the (near) linear relations between the rows of the jacobian.
V	a matrix with the right singular vectors corresponding to the singular values d. Rows for which all elements are smaller than coef_tol have been removed. The columns of this matrix can be interpreted as the (near) linear relations between the columns of the jacobian.
svd	the result of the SVD decomposition as returned by function svd.
sd_tol	the value of argument sd_tol
coef tol	the value of argument coef_tol

# See Also

svd and function findLinearCombos in package caret.

write\_initval\_file 53

# **Examples**

```
# create a singular matrix with linearly dependend rows
set.seed(123)
x1 <- rnorm(4)
x2 <- rnorm(4)
x3 <- rnorm(4)
mat1 < - rbind(x1, x2, x3, x4 = x2 + x3)
mat1
svd_analysis(mat1)
# function findLinearCombos in package caret is also useful.
# this function resolves linear relations between the columns
# of matrix (therefore we pass the transpose of mat1)
caret::findLinearCombos(t(mat1))
# now example with linearly dependent columns
x1 <- rnorm(4)
x2 <- rnorm(4)
mat2 <- cbind(x1, x2, x3 = x2)
svd_analysis(mat2)
```

 $write\_initval\_file$ 

Writes the model data to a Dynare initval file

## Description

This method of R6 class DynMd1 writes all endogous and exogenous model variables to a so called "initval file" that can be read by Dynare. An initval\_file contains the paths of all model variables.

# **Arguments**

file the name of the initval file

```
mdl <- islm_mdl("2017Q1/2019Q2")

# write initval file as matlab file
mdl$write_initval_file("dynare_input/islm_initval.xlsx")

# write initval file in xlsx format
mdl$write_initval_file("dynare_input/islm_initval.xlsx")</pre>
```

54 write\_mdl

write\_mdl

Writes the model to an RDS file

# Description

This method of R6 class DynMdl serializes the model object and writes it to an RDS file. The model can be read back by function  $read_mdl$ .

# Arguments

```
file the name of the RDS file silent A logical (default FALSE). It TRUE, then no output is written.
```

# See Also

read\_mdl

```
mdl <- islm_mdl("2017Q1/2019Q2")
mdl$write_mdl("islm_mdl.rds")</pre>
```

# **Index**

```
*Topic data
                                                get_all_static_data
    DynMdl, 9
                                                         (set/get_static_endos/exos), 37
                                                get_all_static_endos, 10, 37
all.equal, 3, 3
                                                get_all_static_endos
                                                         (set/get_static_endos/exos), 37
change_data, 10, 11
                                                get_back_jacob, 11, 52
change_data (change_data-methods), 4
                                                get_back_jacob (get_jacob), 20
change_data-methods, 4
                                                get_base_period(get_period-methods), 24
change_endo_data, 10, 18
                                                get_data, 11
change_endo_data (change_data-methods),
                                                get_data(get_data-methods), 15
                                                get_data-methods, 15
change_exo_data, 10
                                                get_data_period, 10
change_exo_data (change_data-methods), 4
                                                get_data_period(get_period-methods), 24
change_static_data
                                                get_eigval, 7, 11, 16
        (change_static_data-methods), 5
                                                get_endo_data, 11
change_static_data-methods, 5
                                                get_endo_data (get_data-methods), 15
change_static_endos, 10
                                                get_endo_names, 9
change_static_endos
                                                get_endo_names (get_name-methods), 23
        (change_static_data-methods), 5
                                                get_equations, 11, 17
change_static_exos, 10
                                                get_exo_data, 11
change_static_exos
                                                get_exo_data (get_data-methods), 15
        (change_static_data-methods), 5
                                                get_exo_names, 9
check, 7, 11, 13, 16, 38
                                                get_exo_names (get_name-methods), 23
clear_fit, 8, 8, 18, 19, 36, 41-43
                                                get_fit, 12, 16, 27, 41
copy, 9, 11
                                                get_fit (get_fit-methods), 17
                                                get_fit-methods, 17
dyn_mdl, 12, 27, 30, 31, 47, 49, 51
                                                get_fit_instruments, 12, 16, 20, 27
DynMdl, 3-9, 9, 11, 12, 15-30, 33-35, 37,
                                                get_fit_instruments(get_fit-methods),
        39-54
                                                         17
                                                get_fit_steady, 19, 42
findLinearCombos, 52
                                                get_instrument_names, 11, 23, 24, 36
                                                get_instrument_names
get_all_data, 11, 15, 37
                                                         (get_instrument_names/get_sigma_names),
get_all_data(get_data-methods), 15
get_all_endo_data, 11, 15
                                                 get_instrument_names/get_sigma_names,
get_all_endo_data (get_data-methods), 15
                                                         20
get_all_exo_data (get_data-methods), 15
get_all_param, 10
                                                get_jacob, 11, 20, 52
get_all_param(set/get_param), 34
                                                get_labels, 10, 44
get_all_static_data, 10
                                                get_labels(get_labels/get_tex_names),
```

56 INDEX

21	<pre>get_tex_names</pre>
<pre>get_labels/get_tex_names, 21</pre>	<pre>(get_labels/get_tex_names), 21</pre>
	<pre>get_trend_data, (get_data-methods), 15</pre>
	get_vars_pars, 11, 16, 26
get_lagrange, 12, 15, 16, 27	
<pre>get_lagrange (get_fit-methods), 17</pre>	init_data, 10, 25, 27, 41, 42, 44
get_lead_period, 10	$islm_mdl, 28$
<pre>get_lead_period(get_period-methods), 24</pre>	
get_max_lag,9	nleqslv, 46, 49
get max lag/get max lag/get max lead).	
22	period, 13, 21
get max lag/get max leau. 22	period_range, 4, 13, 16, 18, 27-29, 32, 43, 45
get_max_lead, 9	put_static_endos, 29, 49
get may lead	
<pre>(get_max_lag/get_max_lead), 22</pre>	R6Class, 9
get_mdldef, 11, 23	read_mdl, 30, 54
get_name-methods, 23	regts, 13, 28, 30, 32, 39, 41
get_original_equations, <i>11</i>	residual_check, 11, 30, 52
<pre>get_original_equations (get_equations),</pre>	run_dynare, 31
17	run_initval, <i>12</i> , 33
get_par_names, 10, 35	set/get_param, 34
<pre>get_par_names (get_name-methods), 23</pre>	set/get_sigma, 35
get_param, 10, 27	set/get_static_endos/exos, 19, 37
get_param(set/get_param), 34	set_data, 5, 10, 18, 39, 41, 45
get_period, 10	set_endo_values, 10, 18
<pre>get_period (get_period-methods), 24</pre>	set_endo_values(set_values-methods), 45
get_period-methods, 24	set_exo_values, 10
get_sigma, 41	set_exo_values (set_values-methods), 45
get_sigma (set/get_sigma), 35	set_fit, 8, 11, 18, 19, 36, 40, 43
get_sigma_names, <i>11</i> , <i>24</i> , <i>36</i>	set_fit_steady, 8, 12, 19, 41, 42
get_sigma_names	set_fit_values, 8, 11, 18, 43
<pre>(get_instrument_names/get_sigma_names</pre>	ket lahels 9 21 22 44
20	set_param, 10
get_sigmas, <i>12</i> , <i>20</i> , <i>34</i> , <i>35</i>	set_param(set/get_param), 34
get_sigmas (set/get_sigma), 35	set_param_values, 10
get_solve_status, 11, 25, 46, 47, 49	set_param_values (set/get_param), 34
get_static_data, 10	set_period, 10, 25, 27, 44
get_static_data	set_sigma, 12, 34, 35, 41
(set/get_static_endos/exos), 37	set_sigma(set/get_sigma), 35
get_static_endos, 10, 29, 49	set_sigma_values, <i>12</i> , <i>34</i> , <i>35</i> , <i>41</i>
get_static_endos	set_sigma_values(set/get_sigma), 35
(set/get_static_endos/exos), 37	set_static_data, 6, 10, 19
get_static_exos, 10, 49	set_static_data
get_static_exos	<pre>(set/get_static_endos/exos), 37</pre>
(set/get_static_endos/exos), 37	set_static_endos, 10, 29, 49
get_static_jacob, 11, 52	set_static_endos
get_static_jacob, 71, 32 get_static_jacob (get_jacob), 20	<pre>(set/get_static_endos/exos), 37</pre>
	set static exo values. 6. 10

INDEX 57

```
set_static_exo_values
        (set/get_static_endos/exos), 37
set_static_exo_values,
         (set/get_static_endos/exos), 37
set_static_exos, 10, 49
set_static_exos
        (set/get_static_endos/exos), 37
set_values-methods, 45
solve, 11, 20, 26, 46
solve_dynare, 11, 47
solve_steady, 7, 11, 26, 29, 37, 38, 47, 49
solve_steady_dynare, 11, 50
static_residual_check, 11, 31, 51
svd, 20, 52
{\tt svd\_analysis}, {\tt 52}
ts, 28, 32, 39, 41
umf_solve_nl, 46, 47, 49
write_initval_file, 53
write_mdl, 30, 54
```