Package 'cplexAPI'

November 30, 2015

| Type Package |
|--|
| Title R Interface to C API of IBM ILOG CPLEX |
| Version 1.3.1 |
| Date 2015-11-26 |
| Depends R (>= 2.6.0) |
| Imports methods |
| Description This is the R Interface to the C API of IBM ILOG CPLEX. It necessarily depends on IBM ILOG CPLEX (>= 12.1). |
| SystemRequirements IBM ILOG CPLEX (>= 12.1) |
| License GPL-3 file LICENSE |
| LazyLoad yes |
| Collate generics.R cplexConst.R cplexErrorClass.R cplexPtrClass.R cplex.R cplexAPI.R cplex_checkAPI.R cplex_longparamAPI.R zzz.R |
| Author C. Jonathan Fritzemeier [cre, ctb], Gabriel Gelius-Dietrich [aut] |
| Maintainer C. Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de></clausjonathan.fritzemeier@uni-duesseldorf.de> |
| NeedsCompilation yes |
| Repository CRAN |
| Date/Publication 2015-11-30 15:53:47 |
| R topics documented: |
| cplexAPI-package 6 addChannelCPLEX 2 addColsCPLEX 9 addFpDestCPLEX 10 addIndConstrCPLEX 1 addMIPstartsCPLEX 12 addQConstrCPLEX 12 addRowsCPLEX 14 baroptCPLEX 15 baseWriteCPLEX 16 |

2

| basicPresolveCPLEX | 7 |
|---|----|
| boundSaCPLEX | 8 |
| checkAddColsCPLEX | 9 |
| checkAddRowsCPLEX | 20 |
| checkChgCoefListCPLEX | 21 |
| checkCopyColTypeCPLEX | 22 |
| checkCopyLpCPLEX | 23 |
| | 24 |
| checkCopyQPsepCPLEX | 26 |
| checkCopyQuadCPLEX | 27 |
| checkValsCPLEX | 28 |
| | 9 |
| | 0 |
| | 1 |
| · · | 2 |
| · · | 3 |
| | 4 |
| • • • • | 5 |
| | 6 |
| e | 7 |
| · · | 8 |
| | 9 |
| • | 0 |
| | 1 |
| | 2 |
| \mathcal{E} | 3 |
| | 4 |
| | 5 |
| C | 5 |
| 1 | 6 |
| | 7 |
| closeFileCPLEX | 8 |
| | 9 |
| | 0 |
| • | 1 |
| 1 1 | 2 |
| | 3 |
| 11 | 4 |
| | 55 |
| 1, 1 | 6 |
| 1, 0 | 7 |
| 1. | 8 |
| 1, | 9 |
| 1, - 1 | 0 |
| 1, - | 51 |
| 17 | 2 |
| • | 3 |
| 1 | 34 |
| | |

| delChannelCPLEX | |
|------------------------|-----|
| delColsCPLEX | 86 |
| delFpDestCPLEX | 87 |
| delIndConstrsCPLEX | 88 |
| delMIPstartsCPLEX | 89 |
| delNamesCPLEX | 90 |
| delProbCPLEX | 91 |
| delQConstrsCPLEX | 92 |
| delRowsCPLEX | 93 |
| delSetColsCPLEX | 94 |
| delSetRowsCPLEX | 95 |
| delTerminateCPLEX | 96 |
| disconnectChannelCPLEX | 97 |
| dualoptCPLEX | 98 |
| dualWriteCPLEX | |
| feasOptCPLEX | 100 |
| fileputCPLEX | 101 |
| flushChannelCPLEX | |
| flushStdChannelsCPLEX | 103 |
| freePresolveCPLEX | |
| getBaseCPLEX | |
| getBestObjValCPLEX | |
| getChannelsCPLEX | |
| getChgParmCPLEX | |
| getCoefCPLEX | |
| getColIndexCPLEX | |
| getColInfeasCPLEX | |
| getColNameCPLEX | |
| getColsCPLEX | |
| getColTypeCPLEX | |
| getConflictCPLEX | |
| getConflictExtCPLEX | |
| getCutoffCPLEX | |
| getDblParmCPLEX | |
| getDblQualCPLEX | |
| getDbsCntCPLEX | |
| getDjCPLEX | |
| getErrorStrCPLEX | |
| getGradCPLEX | |
| getIndConstrCPLEX | |
| getInfoDblParmCPLEX | |
| getInfoIntParmCPLEX | |
| getInfoLongParmCPLEX | |
| getInfoStrParmCPLEX | |
| getIntParmCPLEX | |
| getIntQualCPLEX | |
| getItCntCPLEX | |
| getLogFileCPLEX | |
| D | |

| getLongParmCPLEX | 133 |
|--|-----|
| getLowBndsIdsCPLEX | 134 |
| getLowerBndsCPLEX | 135 |
| getMethodCPLEX | 136 |
| getMIPrelGapCPLEX | 137 |
| getMIPstartIndexCPLEX | 138 |
| getMIPstartNameCPLEX | |
| getMIPstartsCPLEX | 140 |
| getNumColsCPLEX | 141 |
| getNumMIPstartsCPLEX | 142 |
| getNumNnzCPLEX | 143 |
| getNumQPnzCPLEX | 144 |
| getNumQuadCPLEX | 145 |
| getNumRowsCPLEX | 146 |
| getObjCPLEX | 147 |
| getObjDirCPLEX | 148 |
| getObjNameCPLEX | |
| getObjOffsetCPLEX | 150 |
| getObjValCPLEX | |
| getOrderCPLEX | |
| getParmNameCPLEX | |
| getParmNumCPLEX | |
| getParmTypeCPLEX | |
| getParmValCPLEX | |
| getPhase1CntCPLEX | |
| getPiCPLEX | |
| getPreStatCPLEX | |
| getProbNameCPLEX | |
| getProbTypeCPLEX | |
| getProbVarCPLEX | |
| getQConstrCPLEX | |
| getQPcoefCPLEX | |
| getQuadCPLEX | |
| getRedLpCPLEX | |
| getRhsCPLEX | |
| getRngValCPLEX | |
| getRowIndexCPLEX | |
| getRowInfeasCPLEX | |
| getRowNameCPLEX | |
| getRowsCPLEX | |
| getSenseCPLEX | |
| getSiftItCntCPLEX | |
| getSiftPase1CntCPLEX | |
| getSlackCPLEX | |
| getStatCPLEX | |
| getStatStrCPLEX | |
| getStrParmCPLEX | |
| getSubMethodCPLEX | |
| Scibilitation and a second sec | |

| getSubStatCPLEX | 180 |
|--------------------------------|-----|
| getTimeCPLEX | 181 |
| getUppBndsIdsCPLEX | 182 |
| getUpperBndsCPLEX | 183 |
| getVersionCPLEX | 184 |
| hybbaroptCPLEX | 185 |
| hybnetoptCPLEX | 186 |
| initProbCPLEX | |
| lpoptCPLEX | |
| mipoptCPLEX | |
| newColsCPLEX | |
| newRowsCPLEX | |
| objSaCPLEX | |
| openEnvCPLEX | |
| openFileCPLEX | |
| openProbCPLEX | |
| ordWriteCPLEX | |
| preslvWriteCPLEX | |
| presolveCPLEX | |
| primoptCPLEX | |
| printTerminateCPLEX | |
| qpoptCPLEX | |
| readCopyBaseCPLEX | |
| readCopyMIPstartsCPLEX | |
| readCopyOrderCPLEX | |
| readCopyParmCPLEX | |
| readCopyProbCPLEX | |
| readCopySolCPLEX | |
| refineConflictCPLEX | |
| refineConflictExtCPLEX | |
| refineMIPstartConflictCPLEX | |
| refineMIPstartConflictExtCPLEX | |
| return codeCPLEX | |
| rhsSaCPLEX | |
| setDblParmCPLEX | |
| setDefaultParmCPLEX | |
| setIntParmCPLEX | |
| | |
| setLogFileCPLEX | |
| setLongParmCPLEX | |
| setObjDirCPLEX | |
| setStrParmCPLEX | |
| setTerminateCPLEX | |
| siftoptCPLEX | |
| solnInfoCPLEX | |
| solutionCPLEX | |
| solWriteCPLEX | |
| status_codeCPLEX | |
| tightenRndsCPLEX | 226 |

6 cplexAPI-package

| cple | xAPI-package | RI | ntei | fac | e 1 | to (| CA | \PI | of | r II | BN | 11 | L |)C | G C | P | LI | ΞX | | | | | | |
|-------|--|----------|------|-----|-----|------|----|-----|----|------|----|----|---|----|-----|---|----|----|--|--|--|--|--|---------|
| Index | | | | | | | | | | | | | | | | | | | | | | | | 232 |
| | writeMIPstartsCP writeParmCPLEX writeProbCPLEX | . | | | | | | | | | | | | | | | | | | | | | | 230 |
| | tuneParmCPLEX unscaleProbCPLE | | | | | | | | | | | | | | | | | | | | | | | |

Description

A low level interface to IBM ILOG CPLEX.

Details

The package cplexAPI provides access to the callable library of IBM ILOG CPLEX from within R.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

Examples

```
# load package
library(cplexAPI)

# Open a CPLEX environment
env <- openEnvCPLEX()

# Create a problem object
prob <- initProbCPLEX(env)

# Assign a name to the problem object
chgProbNameCPLEX(env, prob, "sample")

# Prepare data structures for the problem object
# Number of columns and rows
nc <- 3
nr <- 3

# Objective function</pre>
```

addChannelCPLEX 7

```
obj <- c(5, 4, 3)
# Right hand side
rhs <- c(5, 11, 8)
# Sense of the right hand side
sense \leftarrow rep("L", 3)
# Variable lower bounds
1b < - rep(0, 3)
# Variable upper bounds
ub <- rep(CPX_INFBOUND, 3)</pre>
# Column and row names
cn <- c("x1", "x2", "x3")
rn <- c("q1", "q2", "q3")
# The constraint matrix is passed in column major order format
# Be careful here: all indices start with 0! Begin indices of rows
beg <- c(0, 3, 6)
# Number of non-zero elements per row
cnt \leftarrow rep(3, 3)
# Column indices
ind <- c(0, 1, 2, 0, 1, 2, 0, 1, 2)
# Non-zero elements
val <- c(2, 4, 3, 3, 1, 4, 1, 2, 2)
# Load problem data
copyLpwNamesCPLEX(env, prob, nc, nr, CPX_MAX, obj, rhs, sense,
                  beg, cnt, ind, val, lb, ub, NULL, cn, rn)
# Solve the problem using the simplex algorithm
lpoptCPLEX(env, prob)
# Retrieve solution after optimization
solutionCPLEX(env, prob)
# Free memory, allacated to the problem object
delProbCPLEX(env, prob)
closeEnvCPLEX(env)
```

8 addChannelCPLEX

Description

Low level interface function to the IBM ILOG CPLEX function CPXaddchannel. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
addChannelCPLEX(env, ptrtype = "cplex_chan")
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

ptrtype A name for the pointer object.

Details

Interface to the C function addChannel which calls the CPLEX function CPXaddchannel.

Value

If successful, addChannelCPLEX returns a pointer to the new channel object (an instance of class "cplexPtr"); otherwise, it returns NULL.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

delChannelCPLEX, disconnectChannelCPLEX, flushChannelCPLEX, flushStdChannelsCPLEX, getChannelsCPLEX

addColsCPLEX 9

| | addColsCPLEX | Adds Columns to a Specified CPLEX Problem Object | |
|--|--------------|--|--|
|--|--------------|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXaddcols. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|---|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ncols | Number of columns. |
| nnz | Number of nonzero constraint coefficients. |
| objf | Objective function coefficients. |
| matbeg | Array that specifies the nonzero elements of the columns being added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matind | Array that specifies the nonzero elements of the columns being added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matval | Array that specifies the nonzero elements of the columns being added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| lb | Lower bounds of the new variables. |
| ub | Upper bounds of the new variables. |
| cnames | Names of the new variables. |

Details

Interface to the C function addCols which calls the CPLEX function CPXaddcols.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

10 addFpDestCPLEX

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

checkAddColsCPLEX, addRowsCPLEX

addFpDestCPLEX

Add a File to the List of Message Destinations for a Channel

Description

Low level interface function to the IBM ILOG CPLEX function CPXaddfpdest. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
addFpDestCPLEX(env, newch, cpfile)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

newch Pointer to an IBM ILOG CPLEX channel as returned by addChannelCPLEX.

cpfile Pointer to an IBM ILOG CPLEX file as returned by openFileCPLEX.

Details

Interface to the C function addFpDest which calls the CPLEX function CPXaddfpdest.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

delFpDestCPLEX

addIndConstrCPLEX 11

| addIndConstrCPLEX | Adds an Indicator Constraint to the Specified CPLEX Problem Object |
|-------------------|--|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXaddindconstr. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| indvar | The binary variable that acts as the indicator for this constraint. |
| complemented | A Boolean value that specifies whether the indicator variable is complemented. |
| nzcnt | An integer that specifies the number of nonzero coefficients in the linear portion of the indicator constraint. |
| rhs | The righthand side value for the linear portion of the indicator constraint. |
| sense | The sense of the linear portion of the indicator constraint. |
| linind | A vector that with linval defines the linear portion of the indicator constraint. |
| linval | A vector that with linind defines the linear portion of the indicator constraint. |
| indname | The name of the constraint to be added (optional). |

Details

Interface to the C function addIndConstr which calls the CPLEX function CPXaddindconstr.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

12 addMIPstartsCPLEX

| addMIPstartsCPLEX Add Multiple MIP Starts to a CPLEX Problem Object |
|---|
| addMIPstartsCPLEX Add Multiple MIP Starts to a CPLEX Problem Object |

Description

Low level interface function to the IBM ILOG CPLEX function CPXaddmipstarts. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| mcnt | Number of MIP starts to be added. |
| nzcnt | Number of variable values to be added. |
| beg | Array of length mcnt used with varindices and values. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| varindices | Array of length nzcnt containing the numeric indices of the columns corresponding to the variables which are assigned starting values. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| values | Array of length nzcnt containing the values to use for the MIP starts. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| effortlevel | Array of length mcnt. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| mipstartname | Names of the MIP starts. |

Details

Interface to the C function addMIPstarts which calls the CPLEX function CPXaddmipstarts.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

addQConstrCPLEX 13

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

 ${\it add} Q {\it ConstrCPLEX}$

Add Quadratic Constraint to a Specified CPLEX Problem Object

Description

Low level interface function to the IBM ILOG CPLEX function CPXaddqconstr. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|---|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| lzn | Number of nonzero constraint coefficients in the linear part of the constraint. |
| qzn | Number of nonzero constraint coefficients in the quadratic part of the constraint. |
| rhs | Righthand side term. |
| sense | The sense of the constraint to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| lind | Linear part of the quadratic constraint to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| lval | Linear part of the constraint to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qrow | Quadratic part of the quadratic constraint to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qcol | Quadratic part of the quadratic constraint to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qval | Quadratic part of the quadratic constraint to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qname | Name of the constraint to be added. |

Details

 $Interface \ to \ the \ C \ function \ add Q Constr \ which \ calls \ the \ CPLEX \ function \ CPX add q constr.$

14 addRowsCPLEX

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

addRowsCPLEX

Add Constraints to a Specified CPLEX Problem Object

Description

Low level interface function to the IBM ILOG CPLEX function CPXaddrows. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ncols | Number of new columns in the constraints being added to the constraint matrix. |
| nrows | Number of rows. |
| nnz | Number of nonzero constraint coefficients. |
| matbeg | An array used with rmatind and rmatval to define the rows to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matind | An array used with rmatind and rmatval to define the rows to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matval | An array used with rmatind and rmatval to define the rows to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| rhs | Righthand side term for each constraint to be added. |
| sense | Sense of each constraint to be added. |
| cnames | Names of the new columns. |
| rnames | Names of the new rows. |

baroptCPLEX 15

Details

Interface to the C function addCols which calls the CPLEX function CPXaddcols.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

checkAddRowsCPLEX, addColsCPLEX, copyLpCPLEX, chgRngValCPLEX

| baroptCPLEX | Solve LP, QP or QCP Problem by Means of the Barrier Algorithm |
|-------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXbaropt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
baroptCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

Interface to the C function baropt which calls the CPLEX function CPXbaropt.

Value

Zero if successful, otherwise nonzero.

16 baseWriteCPLEX

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

solnInfoCPLEX, getStatCPLEX, solutionCPLEX

| baseWriteCPLEX | Write the Most Current Basis Associated With a CPLEX Problem Ob- |
|----------------|--|
| | ject to a File |

Description

Low level interface function to the IBM ILOG CPLEX function CPXmbasewrite. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
baseWriteCPLEX(env, lp, fname)
```

Arguments

| env An object of class "cplexPtr" as returned by openEn | vCPLEX. This is basically |
|---|---------------------------|
|---|---------------------------|

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

fname A filename.

Details

Interface to the C function baseWrite which calls the CPLEX function CPXmbasewrite.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

basicPresolveCPLEX 17

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

basicPresolveCPLEX

Perform Bound Strengthening and Detect Redundant Rows

Description

Low level interface function to the IBM ILOG CPLEX function CPXbasicpresolve. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

basicPresolveCPLEX(env, lp)

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function basicPresolve which calls the CPLEX function CPXbasicpresolve.

Value

If successfull, a list will be returned:

redlb strengthened lower bounds redub strengthened upper bounds

rstat status of the row

Otherwise an object of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

18 boundSaCPLEX

| boundSaCPLEX | Access Upper and Lower Sensitivity Ranges for Lower and Upper Variable Bounds |
|--------------|---|
|--------------|---|

Description

Low level interface function to the IBM ILOG CPLEX function CPXboundsa. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
boundSaCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | Beginning of the range of ranges to be returned. |
| end | End of the range of ranges to be returned. |

Details

Interface to the C function boundSa which calls the CPLEX function CPXboundsa.

Value

If successfull, a list will be returned:

1blowerlower bound lower range values1bupperlower bound upper range valuesublowerupper bound lower range valuesubupperupper bound upper range values

Otherwise an object of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

checkAddColsCPLEX 19

| checkAddColsCPLEX Validate Arguments of the Corresponding addColsCPLEX Routine | |
|--|--|
|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcheckaddcols. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|---|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ncols | Number of columns. |
| nnz | Number of nonzero constraint coefficients. |
| objf | Objective function coefficients. |
| matbeg | Array that specifies the nonzero elements of the columns being added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matind | Array that specifies the nonzero elements of the columns being added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matval | Array that specifies the nonzero elements of the columns being added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| lb | Lower bounds of the new variables. |
| ub | Upper bounds of the new variables. |
| cnames | Names of the new variables. |

Details

Interface to the C function checkAddCols which calls the CPLEX function CPXcheckaddcols.

Value

Nonzero if it detects an error in the data; it returns zero if it does not detect any data errors.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

20 checkAddRowsCPLEX

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

addColsCPLEX

checkAddRowsCPLEX

Validate Arguments of the Corresponding addRowsCPLEX Routine

Description

Low level interface function to the IBM ILOG CPLEX function CPXcheckaddrows. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ncols | Number of new columns in the constraints being added to the constraint matrix. |
| nrows | Number of rows. |
| nnz | Number of nonzero constraint coefficients. |
| matbeg | An array used with rmatind and rmatval to define the rows to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matind | An array used with rmatind and rmatval to define the rows to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matval | An array used with rmatind and rmatval to define the rows to be added. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| rhs | Righthand side term for each constraint to be added. |
| sense | Sense of each constraint to be added. |
| cnames | Names of the new columns. |
| rnames | Names of the new rows. |

Details

Interface to the C function checkAddRows which calls the CPLEX function CPXcheckaddrows.

Value

Nonzero if it detects an error in the data; it returns zero if it does not detect any data errors.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

addRowsCPLEX

checkChgCoefListCPLEX Validate Arguments of the Corresponding chgCoefListCPLEX Routine

Description

Low level interface function to the IBM ILOG CPLEX function CPXcheckchgcoeflist. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
checkChgCoefListCPLEX(env, lp, nnz, ia, ja, ra)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nnz | Number of nonzero constraint coefficients. |
| ia | Row indices of the nonzero elements. |
| ja | Column indices of the nonzero elements. |
| ra | Nonzero elements. |

Details

Interface to the C function checkChgCoefList which calls the CPLEX function CPXcheckchgcoeflist.

Value

Nonzero if it detects an error in the data; it returns zero if it does not detect any data errors.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

chgCoefListCPLEX

checkCopyColTypeCPLEX Validate Arguments of the Corresponding copyColTypeCPLEX Routine

Description

Low level interface function to the IBM ILOG CPLEX function CPXcheckcopyctype. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
checkCopyColTypeCPLEX(env, lp, xctype)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| xctvpe | A vector containing the type of each column in the constraint matrix. |

Details

Interface to the C function checkCopyColType which calls the CPLEX function CPXcheckcopyctype.

checkCopyLpCPLEX 23

Value

Nonzero if it detects an error in the data; it returns zero if it does not detect any data errors.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

copyColTypeCPLEX

| checkCopyLpCPLEX Validate Arguments of the Corresponding copyLpCPLEX Routine | |
|--|--|
|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcheckcopylp. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nCols | Number of columns in the constraint matrix. |
| nRows | Number of rows in the constraint matrix. |
| lpdir | Single integer value that specifies whether the problem is a minimization or maximization problem. |
| objf | The objective function coefficients. |
| rhs | The righthand side values for each constraint in the constraint matrix. |
| sense | The sense of each constraint in the constraint matrix. |
| matbeg | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |

| matcnt | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
|--------|---|
| matind | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matval | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| lb | Containing the lower bound on each of the variables. |
| ub | Containing the lower bound on each of the variables. |
| rngval | Containing the range value of each ranged constraint. |

Details

Interface to the C function checkCopyLp which calls the CPLEX function CPXcheckcopylp.

Value

Nonzero if it detects an error in the data; it returns zero if it does not detect any data errors.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

copyLpCPLEX

checkCopyLpwNamesCPLEX

 ${\it Validate\ Arguments\ of\ the\ Corresponding\ copyLpwNamesCPLEX\ Routine}$

Description

Low level interface function to the IBM ILOG CPLEX function CPXcheckcopylpwnames. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nCols | Number of columns in the constraint matrix. |
| nRows | Number of rows in the constraint matrix. |
| lpdir | Single integer value that specifies whether the problem is a minimization or maximization problem. |
| objf | The objective function coefficients. |
| rhs | The righthand side values for each constraint in the constraint matrix. |
| sense | The sense of each constraint in the constraint matrix. |
| matbeg | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matcnt | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matind | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matval | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| 1b | Containing the lower bound on each of the variables. |
| ub | Containing the lower bound on each of the variables. |
| rngval | Containing the range value of each ranged constraint. |
| cnames | Names of the matrix columns or, equivalently, the variable names. |
| rnames | Names of the matrix rows or, equivalently, the constraint names. |
| | |

Details

 $Interface \ to \ the \ C \ function \ check Copy LpwNames \ which \ calls \ the \ CPLEX \ function \ CPX check copy lpwnames.$

Value

Nonzero if it detects an error in the data; it returns zero if it does not detect any data errors.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

See Also

copyLpwNamesCPLEX

checkCopyQPsepCPLEX

Validate Arguments of the Corresponding copyQPsepCPLEX Routine

Description

Low level interface function to the IBM ILOG CPLEX function CPXcheckcopyqpsep. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
checkCopyQPsepCPLEX(env, lp, qsepvec)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

qsepvec A vector containing the quadratic coefficients.

Details

Interface to the C function checkCopyQPsep which calls the CPLEX function CPXcheckcopyqpsep.

Value

Nonzero if it detects an error in the data; it returns zero if it does not detect any data errors.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

copyQPsepCPLEX

| checkCopyQuadCPLEX | Validate Arguments of the Corresponding checkCopyQuadCPLEX Routine |
|--------------------|--|
|--------------------|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcheckcopyquad. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

checkCopyQuadCPLEX(env, 1p, qmatbeg, qmatcnt, qmatind, qmatval)

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|---------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| qmatbeg | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qmatcnt | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qmatind | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qmatval | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |

Details

Interface to the C function checkCopyQuad which calls the CPLEX function CPXcheckcopyquad.

Value

Nonzero if it detects an error in the data; it returns zero if it does not detect any data errors.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

28 checkValsCPLEX

See Also

copyQuadCPLEX

| checkValsCPLEX | Check an Array of Indices and a Corresponding Array of Values for Input Errors |
|----------------|--|
|----------------|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcheckvals. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
checkValsCPLEX(env, lp, nval, rind = NULL, cind = NULL, val = NULL)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nval | Number of values to be examined. |
| rind | Row indices. |
| cind | Column indices. |
| val | The values itself. |

Details

Interface to the C function checkVals which calls the CPLEX function CPXcheckvals.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

chgBndsCPLEX 29

| chgBndsCPLEX | Change the Lower or Upper Bounds on a Set of Variables of a Problem |
|--------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgbds. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgBndsCPLEX(env, lp, ncols, ind, lu, bd)
```

Arguments

Details

Interface to the C function chgBnds which calls the CPLEX function CPXchgbds.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
getLowerBndsCPLEX, getUpperBndsCPLEX
```

30 chgCoefCPLEX

| chgCoefCPLEX | Change a Single Coefficient in the Constraint Matrix, Linear Objective |
|--------------|--|
| _ | Coefficients, Righthand Side, or Ranges of a CPLEX Problem Object |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgcoef. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgCoefCPLEX(env, lp, i, j, val)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|---|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| i | An integer that specifies the numeric index of the row in which the coefficient is located. The linear objective row is referenced with $i = -1$. |
| j | An integer that specifies the numeric index of the column in which the coefficient is located. The RHS column is referenced with $j = -1$. The range value column is referenced with $j = -2$. If $j = -2$ is specified and row i is not a ranged row, an error status is returned. |
| val | The new value for the coefficient being changed. |

Details

 $Interface \ to \ the \ C \ function \ chgCoef \ which \ calls \ the \ CPLEX \ function \ CPX chgcoef.$

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getNumRowsCPLEX, getNumColsCPLEX, chgObjCPLEX, chgRhsCPLEX, chgRngValCPLEX

chgCoefListCPLEX 31

| chgCoefListCPLEX | Change a List of Matrix Coefficients of a CPLEX Problem Object | |
|------------------|--|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgcoeflist. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgCoefListCPLEX(env, lp, nnz, ia, ja, ra)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nnz | Number of nonzero constraint coefficients. |
| ia | Row indices of the nonzero elements. |
| ja | Column indices of the nonzero elements. |
| ra | Nonzero elements. |

Details

Interface to the C function chgcoeflist which calls the CPLEX function CPXchgcoeflist.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

chgColNameCPLEX

| chgColNameCPLEX | Change the Names of Variables in a CPLEX Problem Object |
|-----------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgcolname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

32

```
chgColNameCPLEX(env, lp, nnames, ind, names)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nnames | A vector that specifies the total number of variable names to be changed. |
| ind | A vector containing the numeric indices indices of the variables for which the names are to be changed. |
| names | A vector containing the strings of the new variable names for the columns specified in ind. |

Details

Interface to the C function chgColName which calls the CPLEX function CPXchgcolname.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

chgColsBndsCPLEX 33

| chgColsBndsCPLEX Change Lower and Upper Bounds on a Set of Variables of a Pro | oblem |
|---|-------|
|---|-------|

Description

Set lower and upper bounds on a set of variables in one step. If lb[i] == ub[i] the type of the bound is set to "B", otherwise lb[i] is set to "L" and ub[i] is set to "U".

Usage

```
chgColsBndsCPLEX(env, lp, j, lb, ub)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| j | An integer that specifies the numeric index of the column in which the coefficient is located. |
| 1b | A vector containing the lower bounds. |
| ub | A vector containing the upper bounds. |

Details

Interface to the C function chgColsBnds which calls the CPLEX function CPXchgbds.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
chgBndsCPLEX, tightenBndsCPLEX
```

34 chgColTypeCPLEX

| chgColTypeCPLEX | Change Types of a Set of Variables of a CPLEX Problem Object | |
|-----------------|--|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgctype. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgColTypeCPLEX(env, lp, ncols, ind, xctype)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ncols | Number of bounds to be changed. |
| ind | Indices of bounds to be changed. |
| xctype | A vector containing characters that represent the new types for the columns specified in indices. |

Details

Interface to the C function chgColType which calls the CPLEX function CPXchgctype.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

chgMIPstartsCPLEX 35

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgmipstarts. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically | |
|-----|--|--|
| | IDM II OC CDI EV | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

mcnt Number of MIP starts to be changed.

mipstartindices

Array of length ment containing the numeric indices of the MIP starts to be

changed.

nzcnt Number of entries to be changed.

beg Array of length mcnt used with varindices and values. Consult the IBM

ILOG CPLEX documentation for more detailed information.

varindices Aarray of length nzcnt containing the numeric indices of the columns corre-

sponding to the variables which are assigned starting values. Consult the IBM

ILOG CPLEX documentation for more detailed information.

values Array of length nzcnt containing the values to use for the MIP starts. Consult

the IBM ILOG CPLEX documentation for more detailed information.

effortlevel Array of length mcnt. Consult the IBM ILOG CPLEX documentation for more

detailed information.

Details

Interface to the C function chgMIPstarts which calls the CPLEX function CPXchgmipstarts.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

36 chgNameCPLEX

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| chgNameCPLEX Change the Name of a Constraint a Variable in a CPLEX Problem Object. |
|--|
|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgNameCPLEX(env, lp, key, ij, name)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| key | A character to specify whether a row name or a column name should be changed. |
| ij | An integer that specifies the numeric index of the column or row whose name is to be changed. |
| name | A pointer to a character string containing the new name. |

Details

Interface to the C function chgName which calls the CPLEX function CPXchgname.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

chgObjCPLEX 37

| jCPLEX Change Linear Objective Coefficie | LE) | chgObjCPLEX | c |
|--|-----|-------------|---|
| | | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgobj. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgObjCPLEX(env, lp, ncols, ind, val)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ncols | Number of bounds to be changed. |
| ind | Indices of bounds to be changed. |
| val | A vector containing the new values of the objective coefficients of the variables specified in ind. |

Details

Interface to the C function chg0bj which calls the CPLEX function CPXchgobj.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

| chgProbNameCPLEX | Change the Name of the Current Problem. |
|------------------------|--|
| Crigi i obrialicci EEX | Change the Name of the Current I robtem. |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgprobname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgProbNameCPLEX(env, lp, probname)
```

Arguments

| env | An object of class | "cplexPtr" as | returned by | openEnvCPLEX. | This is basically |
|-----|--------------------|---------------|-------------|---------------|-------------------|
| | | | | | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

probname The new name of the problem.

Details

Interface to the C function chgProbName which calls the CPLEX function CPXchgprobname.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

chgProbTypeCPLEX 39

| chgProbTypeCPLEX | Change the Current Problem to a Related Problem | |
|------------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgprobtype. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgProbTypeCPLEX(env, lp, ptype)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ptype | A single integer value specifying the problem type. |

Details

Interface to the C function chgProbType which calls the CPLEX function CPXchgprobtype.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
getProbTypeCPLEX, cplexConstants section "Problem Types".
```

40 chgQPcoefCPLEX

| chgQPcoefCPLEX | Change a Single Coefficient in the Quadratic Objective of a Quadratic Problem |
|----------------|---|
|----------------|---|

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgqpcoef. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgQPcoefCPLEX(env, lp, i, j, val)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| i | The first variable number. |
| j | The second variable number. |
| val | The new coefficient value. |

Details

Interface to the C function chgQPcoef which calls the CPLEX function CPXchgqpcoef.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

chgCoefCPLEX

chgRhsCPLEX 41

| chgRhsCPLEX Change Righthand Side Coefficient | CPLEX | chgRhsCPL |
|---|-------|-----------|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgrhs. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgRhsCPLEX(env, lp, nrows, ind, val)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nrows | Number of bounds to be changed. |
| ind | Indices of bounds to be changed. |
| val | A vector containing the new values of the objective coefficients of the variables specified in ind. |

Details

Interface to the C function chgRhs which calls the CPLEX function CPXchgrhs.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

42 chgRngValCPLEX

|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgrngval. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgRngValCPLEX(env, lp, nrows, ind, val)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nrows | Number of bounds to be changed. |
| ind | Indices of bounds to be changed. |
| val | A vector containing the new values of the objective coefficients of the variables specified in ind. |

Details

Interface to the C function chgRngVal which calls the CPLEX function CPXchgrngval.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

chgRowNameCPLEX 43

| CPLEX Change Names of Linear Constraints |
|--|
|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgrowname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgRowNameCPLEX(env, lp, nnames, ind, names)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nnames | A vector that specifies the total number of variable names to be changed. |
| ind | A vector containing the numeric indices indices of the variables for which the names are to be changed. |
| names | A vector containing the strings of the new variable names for the columns specified in ind. |

Details

Interface to the C function chgRowName which calls the CPLEX function CPXchgrowname.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

chgSenseCPLEX

| chgSenseCPLEX | Change Sense of a Set of Linear Constraints | |
|---------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgsense. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
chgSenseCPLEX(env, lp, nrows, ind, sense)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nrows | Number of bounds to be changed. |
| ind | Indices of bounds to be changed. |
| sense | A vector containing characters that tell the new sense of the linear constraints specified in ind. |

Details

Interface to the C function chgSense which calls the CPLEX function CPXchgsense.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

chgTerminateCPLEX 45

| nal | |
|-----|--|
|-----|--|

Description

The function chgTerminateCPLEX changes termination signal.

Usage

```
chgTerminateCPLEX(env, tval = 1)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

tval Single integer value.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

setTerminateCPLEX, delTerminateCPLEX, printTerminateCPLEX

| cleanupCoefCPLEX | change Problem Coefficients to Zero That are Smaller in Magnitude |
|------------------|---|
| | Than the Tolerance Specified in the Argument eps |

Description

Low level interface function to the IBM ILOG CPLEX function CPXcleanup. Consult the IBM ILOG CPLEX documentation for more detailed information.

46 cloneProbCPLEX

Usage

```
cleanupCoefCPLEX(env, lp, eps)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| eps | Single numeric value giving the tolerance. |

Details

Interface to the C function cleanupCoef which calls the CPLEX function CPXcleanup.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| cloneProbCPLEX | Copy a CPLEX Problem Object |
|----------------|-----------------------------|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXcloneprob. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
cloneProbCPLEX(env, lp, ptrtype = "cplex_prob")
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|---------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ptrtype | A name for the pointer object. |

closeEnvCPLEX 47

Details

Interface to the C function cloneProb which calls the CPLEX function CPXcloneprob.

Value

If successful a pointer to the new CPLEX problem object as returned by initProbCPLEX (an object of class "cplexPtr"), otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

closeEnvCPLEX

Free all of the Data Structures Associated With CPLEX

Description

Low level interface function to the IBM ILOG CPLEX function CPXcloseCPLEX. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

closeEnvCPLEX(env)

Arguments

env

An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment.

Details

Interface to the C function closeEnv which calls the CPLEX function CPXcloseCPLEX.

Value

Zero if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

48 closeFileCPLEX

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

openEnvCPLEX

closeFileCPLEX

Close a File

Description

Low level interface function to the IBM ILOG CPLEX function CPXfclose. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
closeFileCPLEX(cpfile)
```

Arguments

cpfile

A pointer to a file as returned by openFileCPLEX.

Details

Interface to the C function closeFile which calls the CPLEX function CPXfclose.

Value

Zero if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
fileputCPLEX, openFileCPLEX
```

closeProbCPLEX 49

closeProbCPLEX

Close CPLEX Environment And Remove CPLEX Problem Object

Description

The function closeProbCPLEX closes a CPLEX environment and removes a CPLEX problem object.

Usage

closeProbCPLEX(prob)

Arguments

prob

A list containing a pointer to an IBM ILOG CPLEX environment and a Pointer to an IBM ILOG CPLEX problem object. Both elements are objects of class "cplexPtr" as returned by openProbCPLEX.

Details

Interface to the C functions delProb and closeEnv calling CPLEX functions CPXcloseCPLEX and CPXfreeprob.

Value

An integer vector containing the return values of CPXcloseCPLEX and CPXfreeprob.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

openProbCPLEX

50 cLpWriteCPLEX

| cLpWriteCPLEX | Write an LP Format File Containing Identified Conflict |
|---------------|--|
| • | O J J |

Description

Low level interface function to the IBM ILOG CPLEX function CPXclpwrite. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
cLpWriteCPLEX(env, lp, fname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| fname | Single character value giving the filname to write to. |

Details

Interface to the C function cLpWriteCPLEX which calls the CPLEX function CPXclpwrite.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

completelpCPLEX 51

Description

Low level interface function to the IBM ILOG CPLEX function CPXcompletelp. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
completelpCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

Interface to the C function completelpCPLEX which calls the CPLEX function CPXcompletelp.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

52 copyBaseCPLEX

| copyBaseCPLEX | Copies a Basis Into a CPLEX Problem Object. | |
|---------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXcopybase. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
copyBaseCPLEX(env, lp, cstat, rstat)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| cstat | A vector containing the basis status of the columns in the constraint matrix. |
| rstat | A vector containing the basis status of the slack, or surplus, or artificial variable associated with each row in the constraint matrix. |

Details

Interface to the C function copyBase which calls the CPLEX function CPXcopybase.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

copyColTypeCPLEX 53

| copyColTypeCPLEX | Copy Variable Type Information Into a Given Problem |
|------------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgprobname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
copyColTypeCPLEX(env, lp, xctype)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| xctype | A vector containing the type of each column in the constraint matrix. |

Details

Interface to the C function copyColType which calls the CPLEX function CPXcopyctype.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

54 copyLpCPLEX

|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcopylp. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nCols | Number of columns in the constraint matrix. |
| nRows | Number of rows in the constraint matrix. |
| lpdir | Single integer value that specifies whether the problem is a minimization or maximization problem. |
| objf | The objective function coefficients. |
| rhs | The righthand side values for each constraint in the constraint matrix. |
| sense | The sense of each constraint in the constraint matrix. |
| matbeg | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matcnt | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matind | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matval | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| lb | Containing the lower bound on each of the variables. |
| ub | Containing the lower bound on each of the variables. |
| rngval | Containing the range value of each ranged constraint. |
| | |

Details

Interface to the C function copyLp which calls the CPLEX function CPXcopylp.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

copyLpwNamesCPLEX

Copy Data Defining an LP Problem to a CPLEX Problem Object.

Description

Low level interface function to the IBM ILOG CPLEX function CPXcopylpwnames. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nCols | Number of columns in the constraint matrix. |
| nRows | Number of rows in the constraint matrix. |
| lpdir | Single integer value that specifies whether the problem is a minimization or maximization problem. |
| objf | The objective function coefficients. |
| rhs | The righthand side values for each constraint in the constraint matrix. |
| sense | The sense of each constraint in the constraint matrix. |
| matbeg | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matcnt | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |

| matind | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
|--------|---|
| matval | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| 1b | Containing the lower bound on each of the variables. |
| ub | Containing the lower bound on each of the variables. |
| rngval | Containing the range value of each ranged constraint. |
| cnames | Names of the matrix columns or, equivalently, the variable names. |
| rnames | Names of the matrix rows or, equivalently, the constraint names. |

Details

Interface to the C function copyLpwNames which calls the CPLEX function CPXcopylpwnames.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| copyObjNameCPLEX | Copy a Name for the Objective Function Into a CPLEX Problem Object. |
|------------------|---|
|------------------|---|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcopyobjname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
copyObjNameCPLEX(env, lp, oname)
```

copyOrderCPLEX 57

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically | | |
|---|--|--|--|
| a pointer to an IBM ILOG CPLEX environment. | | | |

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

oname A pointer to a character string containing the objective name.

Details

Interface to the C function copyObjName which calls the CPLEX function CPXcopyobjname.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| copyOrderCPLEX Copy Priority Order to CPLEX Problem Object | |
|--|--|
|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcopyorder. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
copyOrderCPLEX(env, lp, cnt, indices, priority = NULL, direction = NULL)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|---------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| cnt | Number of entries. |
| indices | Indices of the columns corresponding to the integer variables that are assigned priorities. |

priority Priorities assigned to the integer variables.

direction Branching direction assigned to the integer variables.

Details

Interface to the C function copyOrder which calls the CPLEX function CPXcopyorder.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

copyPartBaseCPLEX Copies a partial basis into an LP problem object.

Description

Low level interface function to the IBM ILOG CPLEX function CPXcopypartialbase. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
copyPartBaseCPLEX(env, lp, ncind, cind, cstat, nrind, rind, rstat)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ncind | An integer that specifies the number of variable or column status values specified. |
| cind | A vector that contains the indices of the variables for which status values are being specified. |
| cstat | A vector where the ith entry contains the status for variable cind[i]. |
| nrind | An integer that specifies the number of slack, surplus, or artificial status values specified. |

copyQPsepCPLEX 59

| rind | A vector rent that | contains the ir | ndices of the | slack surnlu | s, or artificial variables |
|--------|---------------------|-----------------|---------------|---------------|----------------------------|
| I IIIU | 11 vector rent that | comanis the n | idices of the | siack, surpiu | s, or artificial variables |

for which status values are being specified.

rstat A vector of where the i-th entry contains the status for slack, surplus, or artificial

rind[i].

Details

Interface to the C function copyPartBase which calls the CPLEX function CPXcopypartialbase.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| copyQPsepCPLEX | Copy the Quadratic Objective Matrix Q for a Separable QP Problem |
|----------------|--|
|----------------|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcopyqpsep. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
copyQPsepCPLEX(env, lp, qsepvec)
```

Arguments

| env | An object of class ' | "cplexPtr" as returned | 1 by openEnvCPLEX. | This is basically |
|-----|----------------------|------------------------|--------------------|-------------------|
| | | | | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

qsepvec A vector containing the quadratic coefficients.

Details

Interface to the C function copyQPsep which calls the CPLEX function CPXcopyqpsep.

60 copyQuadCPLEX

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| copyQuadCPLEX | Copy a Quadratic Objective Matrix Q When Q is not Diagonal. |
|---------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXcopyquad. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
copyQuadCPLEX(env, lp, qmatbeg, qmatcnt, qmatind, qmatval)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|---------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| qmatbeg | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qmatcnt | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qmatind | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| qmatval | Array that defines the constraint matrix. Consult the IBM ILOG CPLEX documentation for more detailed information. |

Details

Interface to the C function copyQuad which calls the CPLEX function $\ensuremath{\mathsf{CPXcopyquad}}.$

copyStartCPLEX 61

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| copyStartCPLEX | Provides Starting Information for Use in a Subsequent Call to a Simplex Optimization Routine. |
|----------------|---|
|----------------|---|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcopystart. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|---|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| cstat | A vector containing the basis status of the columns in the constraint matrix. |
| rstat | A vector containing the basis status of the slack, surplus, or artificial variable associated with each row in the constraint matrix. |
| cprim | A vector containing the initial primal values of the column variables. |
| rprim | A vector containing the initial primal values of the slack (row) variables. |
| cdual | A vector containing the initial values of the reduced costs for the column variables. |
| rdual | A vector containing the initial values of the dual variables for the rows. |

Details

Interface to the C function copyStart which calls the CPLEX function CPXcopyStart.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| cplexConstants | Constants, Parameters, Return and Status Codes of IBM ILOG CPLEX | |
|----------------|---|--|
|----------------|---|--|

Description

This is a list containing constants used by IBM ILOG CPLEX. Cunsult the IBM ILOG CPLEX manual for more information, in praticular for the use of control parameters.

General Parameters

```
CPX_INFBOUND 1.0E+20 CPX_STR_PARAM_MAX 512
```

Types of parameters

```
CPX_PARAMTYPE_NONE 0
CPX_PARAMTYPE_INT 1
CPX_PARAMTYPE_DOUBLE 2
CPX_PARAMTYPE_STRING 3
CPX_PARAMTYPE_LONG 4
```

Values returned for stat by solution

| CPX_STAT_OPTIMAL | 1 |
|--------------------------------|----|
| CPX_STAT_UNBOUNDED | 2 |
| CPX_STAT_INFEASIBLE | 3 |
| CPX_STAT_INForUNBD | 4 |
| CPX_STAT_OPTIMAL_INFEAS | 5 |
| CPX_STAT_NUM_BEST | 6 |
| CPX_STAT_ABORT_IT_LIM | 10 |
| CPX_STAT_ABORT_TIME_LIM | 11 |
| CPX_STAT_ABORT_OBJ_LIM | 12 |
| CPX_STAT_ABORT_USER | 13 |
| CPX_STAT_FEASIBLE_RELAXED_SUM | 14 |
| CPX_STAT_OPTIMAL_RELAXED_SUM | 15 |
| CPX_STAT_FEASIBLE_RELAXED_INF | 16 |
| CPX_STAT_OPTIMAL_RELAXED_INF | 17 |
| CPX_STAT_FEASIBLE_RELAXED_QUAD | 18 |
| CPX_STAT_OPTIMAL_RELAXED_QUAD | 19 |
| CPX_STAT_FEASIBLE | 23 |
| CPX_STAT_ABORT_DETTIME_LIM | 25 |

Solution type return values from CPXsolninfo

```
CPX_NO_SOLN 0
CPX_BASIC_SOLN 1
CPX_NONBASIC_SOLN 2
CPX_PRIMAL_SOLN 3
```

Values of presolve stats for columns and rows

```
CPX_PRECOL_LOW
                     -1
                          fixed to original lb
                     -2 fixed to original ub
CPX_PRECOL_UP
                     -3 fixed to some other value
CPX_PRECOL_FIX
                          aggregated y = a \times x + b
CPX_PRECOL_AGG
CPX_PRECOL_OTHER -5
                          cannot be expressed by a linear combination of active variables in the presolved model crushing w
CPX_PREROW_RED
                          redundant row removed in presolved model
                     -2
                         used to aggregate a variable
CPX_PREROW_AGG
                          other, for example merge two inequalities into a single equation
CPX_PREROW_OTHER
                    -3
```

Generic constants

CPX_ON 1 CPX_OFF 0 CPX_MAX -1 CPX_MIN 1

Primal simplex pricing algorithm

CPX_PPRIIND_PARTIAL -1
CPX_PPRIIND_AUTO 0
CPX_PPRIIND_DEVEX 1
CPX_PPRIIND_STEEP 2
CPX_PPRIIND_STEEPQSTART 3
CPX_PPRIIND_FULL 4

Dual simplex pricing algorithm

| CPX_DPRIIND_AUTO | 0 |
|-------------------------|---|
| CPX_DPRIIND_FULL | 1 |
| CPX_DPRIIND_STEEP | 2 |
| CPX_DPRIIND_FULL_STEEP | 3 |
| CPX_DPRIIND_STEEPQSTART | 4 |
| CPX_DPRIIND_DEVEX | 5 |

PARALLELMODE values

CPX_PARALLEL_AUTO 0
CPX_PARALLEL_AUTO 1
CPX_PARALLEL_OPPORTUNISTIC -1

Values for CPX_PARAM_WRITELEVEL

| CPX_WRITELEVEL_ALLVARS | 1 |
|------------------------------------|---|
| CPX_WRITELEVEL_DISCRETEVARS | 2 |
| CPX_WRITELEVEL_NONZEROVARS | 3 |
| CPX WRITELEVEL NONZERODISCRETEVARS | 4 |

Values for CPX_PARAM_SOLUTIONTARGET

| CPX_SOLUTIONTARGET_AUTO | 0 |
|----------------------------------|---|
| CPX_SOLUTIONTARGET_OPTIMALCONVEX | 1 |
| CPX_SOLUTIONTARGET_FIRSTORDER | 2 |
| CPX_SOLUTIONTARGET_OPTIMALGLOBAL | 3 |

LP/QP solution algorithms

 $Used \ as \ possible \ values for \ CPX_PARAM_LPMETHOD, CPX_PARAM_QPMETHOD, CPX_PARAM_BARCROSSALG, \ CPXgetmethod, \dots$

| CPX_ALG_NONE | -1 |
|--------------------|----|
| CPX_ALG_AUTOMATIC | 0 |
| CPX_ALG_PRIMAL | 1 |
| CPX_ALG_DUAL | 2 |
| CPX_ALG_NET | 3 |
| CPX_ALG_BARRIER | 4 |
| CPX_ALG_SIFTING | 5 |
| CPX_ALG_CONCURRENT | 6 |
| CPX_ALG_BAROPT | 7 |
| CPX_ALG_PIVOTIN | 8 |
| CPX_ALG_PIVOTOUT | 9 |
| CPX_ALG_PIVOT | 10 |
| CPX_ALG_FEASOPT | 11 |
| CPX_ALG_MIP | 12 |
| CPX_ALG_ROBUST | 13 |
| | |

Basis status values

| CPX_AT_LOWER | 0 |
|----------------|---|
| CPX_BASIC | 1 |
| CPX_AT_UPPER | 2 |
| CPX_FREE_SUPER | 3 |

Variable types for ctype array

| CPX_CONTINUOUS | "C" |
|----------------|-----|
| CPX_BINARY | "B" |
| CPX_INTEGER | "I" |
| CPX_SEMICONT | "S" |
| CPX_SEMIINT | "N" |

PREREDUCE settings

| CPX_PREREDUCE_PRIMALANDDUAL | 3 |
|------------------------------|---|
| CPX_PREREDUCE_DUALONLY | 2 |
| CPX_PREREDUCE_PRIMALONLY | 1 |
| CPX_PREREDUCE_NOPRIMALORDUAL | 0 |

Conflict statuses

| CPX_STAT_CONFLICT_FEASIBLE | 30 |
|---------------------------------------|----|
| CPX_STAT_CONFLICT_MINIMAL | 31 |
| CPX_STAT_CONFLICT_ABORT_CONTRADICTION | 32 |
| CPX_STAT_CONFLICT_ABORT_TIME_LIM | 33 |
| CPX_STAT_CONFLICT_ABORT_IT_LIM | 34 |
| CPX_STAT_CONFLICT_ABORT_NODE_LIM | 35 |
| CPX_STAT_CONFLICT_ABORT_OBJ_LIM | 36 |
| CPX_STAT_CONFLICT_ABORT_MEM_LIM | 37 |
| CPX_STAT_CONFLICT_ABORT_USER | 38 |
| CPX STAT CONFLICT ABORT DETTIME LIM | 39 |

Conflict status values

| CPX_CONFLICT_EXCLUDED | -1 |
|------------------------------|----|
| CPX_CONFLICT_POSSIBLE_MEMBER | 0 |
| CPX_CONFLICT_POSSIBLE_LB | 1 |
| CPX_CONFLICT_POSSIBLE_UB | 2 |
| CPX_CONFLICT_MEMBER | 3 |
| | |

| CPX_CONFLICT_LB | 4 |
|-----------------|---|
| CPX_CONFLICT_UB | 5 |

Problem Types

Types 4, 9, and 12 are internal, the others are for users.

| CPXPROB_LP | 0 |
|-------------------|----|
| CPXPROB_MILP | 1 |
| CPXPROB_FIXEDMILP | 3 |
| CPXPROB_NODELP | 4 |
| CPXPROB_QP | 5 |
| CPXPROB_MIQP | 7 |
| CPXPROB_FIXEDMIQP | 8 |
| CPXPROB_NODEQP | 9 |
| CPXPROB_QCP | 10 |
| CPXPROB_MIQCP | 11 |
| CPXPROB_NODEQCP | 12 |

CPLEX Parameter numbers

| CPX_PARAM_ADVIND | 1001 |
|-----------------------|------|
| CPX_PARAM_AGGFILL | 1002 |
| CPX_PARAM_AGGIND | 1003 |
| CPX_PARAM_BASINTERVAL | 1004 |
| CPX_PARAM_CFILEMUL | 1005 |
| CPX_PARAM_CLOCKTYPE | 1006 |
| CPX_PARAM_CRAIND | 1007 |
| CPX_PARAM_DEPIND | 1008 |
| CPX_PARAM_DPRIIND | 1009 |
| CPX_PARAM_PRICELIM | 1010 |
| CPX_PARAM_EPMRK | 1013 |
| CPX_PARAM_EPOPT | 1014 |
| CPX_PARAM_EPPER | 1015 |
| CPX_PARAM_EPRHS | 1016 |
| CPX_PARAM_FASTMIP | 1017 |
| CPX_PARAM_SIMDISPLAY | 1019 |
| CPX_PARAM_ITLIM | 1020 |
| CPX_PARAM_ROWREADLIM | 1021 |
| CPX_PARAM_NETFIND | 1022 |
| CPX_PARAM_COLREADLIM | 1023 |
| CPX_PARAM_NZREADLIM | 1024 |
| CPX_PARAM_OBJLLIM | 1025 |
| CPX_PARAM_OBJULIM | 1026 |

| CPX_PARAM_PERIND | 1027 |
|-----------------------------|------|
| CPX_PARAM_PERLIM | 1028 |
| CPX_PARAM_PPRIIND | 1029 |
| CPX_PARAM_PREIND | 1030 |
| CPX_PARAM_REINV | 1031 |
| CPX_PARAM_REVERSEIND | 1032 |
| CPX_PARAM_RFILEMUL | 1033 |
| CPX_PARAM_SCAIND | 1034 |
| CPX_PARAM_SCRIND | 1035 |
| CPX_PARAM_SINGLIM | 1037 |
| CPX_PARAM_SINGTOL | 1038 |
| CPX_PARAM_TILIM | 1039 |
| CPX_PARAM_XXXIND | 1041 |
| CPX_PARAM_PREDUAL | 1044 |
| CPX_PARAM_EPOPT_H | 1044 |
| | |
| CPX_PARAM_EPRHS_H | 1050 |
| CPX_PARAM_PREPASS | 1052 |
| CPX_PARAM_DATACHECK | 1056 |
| CPX_PARAM_REDUCE | 1057 |
| CPX_PARAM_PRELINEAR | 1058 |
| CPX_PARAM_LPMETHOD | 1062 |
| CPX_PARAM_QPMETHOD | 1063 |
| CPX_PARAM_WORKDIR | 1064 |
| CPX_PARAM_WORKMEM | 1065 |
| CPX_PARAM_THREADS | 1067 |
| CPX_PARAM_CONFLICTDISPLAY | 1074 |
| CPX_PARAM_SIFTDISPLAY | 1076 |
| CPX_PARAM_SIFTALG | 1077 |
| CPX_PARAM_SIFTITLIM | 1078 |
| CPX_PARAM_MPSLONGNUM | 1081 |
| CPX_PARAM_MEMORYEMPHASIS | 1082 |
| CPX_PARAM_NUMERICALEMPHASIS | 1083 |
| CPX_PARAM_FEASOPTMODE | 1084 |
| CPX_PARAM_PARALLELMODE | 1109 |
| CPX_PARAM_TUNINGMEASURE | 1110 |
| CPX_PARAM_TUNINGREPEAT | 1111 |
| CPX_PARAM_TUNINGTILIM | 1112 |
| CPX_PARAM_TUNINGDISPLAY | 1113 |
| CPX_PARAM_WRITELEVEL | 1114 |
| CPX_PARAM_RANDOMSEED | 1124 |
| CPX_PARAM_DETTILIM | 1127 |
| CPX_PARAM_FILEENCODING | 1129 |
| CPX_PARAM_APIENCODING | 1130 |
| CPX_PARAM_SOLUTIONTARGET | 1131 |
| CPX PARAM CLONELOG | 1132 |
| CPX_PARAM_TUNINGDETTILIM | 1132 |
| CPX_PARAM_ALL_MIN | 1000 |
| CPX_PARAM_ALL_MAX | 6000 |
| CI A_I AI\AI_ALL_I\A\ | 0000 |

Values for CPX_PARAM_TUNINGMEASURE

CPX_TUNE_AVERAGE 1
CPX_TUNE_MINMAX 2

Values for incomplete tuning

CPX_TUNE_ABORT 1
CPX_TUNE_TILIM 2
CPX_TUNE_DETTILIM 3

Quality query identifiers

| CPX_MAX_PRIMAL_INFEAS | 1 |
|--------------------------------|----|
| CPX_MAX_SCALED_PRIMAL_INFEAS | 2 |
| CPX_SUM_PRIMAL_INFEAS | 3 |
| CPX_SUM_SCALED_PRIMAL_INFEAS | 4 |
| CPX_MAX_DUAL_INFEAS | 5 |
| CPX_MAX_SCALED_DUAL_INFEAS | 6 |
| CPX_SUM_DUAL_INFEAS | 7 |
| CPX_SUM_SCALED_DUAL_INFEAS | 8 |
| CPX_MAX_INT_INFEAS | 9 |
| CPX_SUM_INT_INFEAS | 10 |
| CPX_MAX_PRIMAL_RESIDUAL | 11 |
| CPX_MAX_SCALED_PRIMAL_RESIDUAL | 12 |
| CPX_SUM_PRIMAL_RESIDUAL | 13 |
| CPX_SUM_SCALED_PRIMAL_RESIDUAL | 14 |
| CPX_MAX_DUAL_RESIDUAL | 15 |
| CPX_MAX_SCALED_DUAL_RESIDUAL | 16 |
| CPX_SUM_DUAL_RESIDUAL | 17 |
| CPX_SUM_SCALED_DUAL_RESIDUAL | 18 |
| CPX_MAX_COMP_SLACK | 19 |
| CPX_SUM_COMP_SLACK | 21 |
| CPX_MAX_X | 23 |
| CPX_MAX_SCALED_X | 24 |
| CPX_MAX_PI | 25 |
| | |

| CPX_MAX_SCALED_PI | 26 |
|---------------------------|----|
| CPX_MAX_SLACK | 27 |
| CPX_MAX_SCALED_SLACK | 28 |
| CPX_MAX_RED_COST | 29 |
| CPX_MAX_SCALED_RED_COST | 30 |
| CPX_SUM_X | 31 |
| CPX_SUM_SCALED_X | 32 |
| CPX_SUM_PI | 33 |
| CPX_SUM_SCALED_PI | 34 |
| CPX_SUM_SLACK | 35 |
| CPX_SUM_SCALED_SLACK | 36 |
| CPX_SUM_RED_COST | 37 |
| CPX_SUM_SCALED_RED_COST | 38 |
| CPX_KAPPA | 39 |
| CPX_OBJ_GAP | 40 |
| CPX_DUAL_OBJ | 41 |
| CPX_PRIMAL_OBJ | 42 |
| CPX_MAX_QCPRIMAL_RESIDUAL | 43 |
| CPX_SUM_QCPRIMAL_RESIDUAL | 44 |
| CPX_MAX_QCSLACK_INFEAS | 45 |
| CPX_SUM_QCSLACK_INFEAS | 46 |
| CPX_MAX_QCSLACK | 47 |
| CPX_SUM_QCSLACK | 48 |
| CPX_MAX_INDSLACK_INFEAS | 49 |
| CPX_SUM_INDSLACK_INFEAS | 50 |
| CPX_EXACT_KAPPA | 51 |
| CPX_KAPPA_STABLE | 52 |
| CPX_KAPPA_SUSPICIOUS | 53 |
| CPX_KAPPA_UNSTABLE | 54 |
| CPX_KAPPA_ILLPOSED | 55 |
| CPX_KAPPA_MAX | 56 |
| CPX_KAPPA_ATTENTION | 57 |
| | |

feasopt options

| CPX_FEASOPT_MIN_SUM | 0 |
|----------------------|---|
| CPX_FEASOPT_OPT_SUM | 1 |
| CPX_FEASOPT_MIN_INF | 2 |
| CPX_FEASOPT_OPT_INF | 3 |
| CPX_FEASOPT_MIN_QUAD | 4 |
| CPX FEASOPT OPT OUAD | 5 |

File: barconst.h

| CPX_STAT_OPTIMAL_FACE_UNBOUNDED | 20 |
|---------------------------------|----|
| CPX_STAT_ABORT_PRIM_OBJ_LIM | 21 |
| CPX_STAT_ABORT_DUAL_OBJ_LIM | 22 |
| CPX_STAT_FIRSTORDER | 24 |

Barrier parameters

| CPX_PARAM_BARDSTART | 3001 |
|------------------------|------|
| CPX_PARAM_BAREPCOMP | 3002 |
| CPX_PARAM_BARGROWTH | 3003 |
| CPX_PARAM_BAROBJRNG | 3004 |
| CPX_PARAM_BARPSTART | 3005 |
| CPX_PARAM_BARALG | 3007 |
| CPX_PARAM_BARCOLNZ | 3009 |
| CPX_PARAM_BARDISPLAY | 3010 |
| CPX_PARAM_BARITLIM | 3012 |
| CPX_PARAM_BARMAXCOR | 3013 |
| CPX_PARAM_BARORDER | 3014 |
| CPX_PARAM_BARSTARTALG | 3017 |
| CPX_PARAM_BARCROSSALG | 3018 |
| CPX_PARAM_BARQCPEPCOMP | 3020 |

Optimizing Problems

| CPX_BARORDER_AUTO | 0 |
|-------------------|---|
| CPX_BARORDER_AMD | 1 |
| CPX_BARORDER_AMF | 2 |
| CPX_BARORDER_ND | 3 |

MIP emphasis settings

| CPX_MIPEMPHASIS_BALANCED | 0 |
|-----------------------------|---|
| CPX_MIPEMPHASIS_FEASIBILITY | 1 |
| CPX_MIPEMPHASIS_OPTIMALITY | 2 |
| CPX_MIPEMPHASIS_BESTBOUND | 3 |

CPX_MIPEMPHASIS_HIDDENFEAS 4

Values for sostype and branch type

| CPX_TYPE_VAR | "0" |
|---------------|-----|
| CPX_TYPE_SOS1 | "1" |
| CPX_TYPE_SOS2 | "2" |
| CPX_TYPE_USER | "X" |
| CPX_TYPE_ANY | "A" |

Variable selection values

| CPX_VARSEL_MININFEAS | -1 |
|--------------------------|----|
| CPX_VARSEL_DEFAULT | 0 |
| CPX_VARSEL_MAXINFEAS | 1 |
| CPX_VARSEL_PSEUDO | 2 |
| CPX_VARSEL_STRONG | 3 |
| CPX VARSEL PSEUDOREDUCED | 4 |

Node selection values

| CPX_NODESEL_DFS | 0 |
|-------------------------|---|
| CPX_NODESEL_BESTBOUND | 1 |
| CPX_NODESEL_BESTEST | 2 |
| CPX NODESEL BESTEST ALT | 3 |

Values for generated priority order

```
CPX_MIPORDER_COST 1
CPX_MIPORDER_BOUNDS 2
CPX_MIPORDER_SCALEDCOST 3
```

Values for direction array

CPX_BRANCH_GLOBAL 0
CPX_BRANCH_DOWN -1
CPX_BRANCH_UP 1

Values for CPX_PARAM_BRDIR

CPX_BRDIR_DOWN -1
CPX_BRDIR_AUTO 0
CPX_BRDIR_UP 1

Values for CPX_PARAM_MIPSEARCH

CPX_MIPSEARCH_AUTO 0
CPX_MIPSEARCH_TRADITIONAL 1
CPX_MIPSEARCH_DYNAMIC 2

Values for CPX_PARAM_MIPKAPPASTATS

CPX_MIPKAPPA_OFF -1
CPX_MIPKAPPA_AUTO 0
CPX_MIPKAPPA_SAMPLE 1
CPX_MIPKAPPA_FULL 2

Effort levels for MIP starts

CPX_MIPSTART_AUTO 0
CPX_MIPSTART_CHECKFEAS 1
CPX_MIPSTART_SOLVEFIXED 2
CPX_MIPSTART_SOLVEMIP 3

CPX_MIPSTART_REPAIR

MIP Problem status codes

| CPXMIP_OPTIMAL | 101 |
|------------------------------|-----|
| CPXMIP_OPTIMAL_TOL | 102 |
| CPXMIP_INFEASIBLE | 103 |
| CPXMIP_SOL_LIM | 104 |
| CPXMIP_NODE_LIM_FEAS | 105 |
| CPXMIP_NODE_LIM_INFEAS | 106 |
| CPXMIP_TIME_LIM_FEAS | 107 |
| CPXMIP_TIME_LIM_INFEAS | 108 |
| CPXMIP_FAIL_FEAS | 109 |
| CPXMIP_FAIL_INFEAS | 110 |
| CPXMIP_MEM_LIM_FEAS | 111 |
| CPXMIP_MEM_LIM_INFEAS | 112 |
| CPXMIP_ABORT_FEAS | 113 |
| CPXMIP_ABORT_INFEAS | 114 |
| CPXMIP_OPTIMAL_INFEAS | 115 |
| CPXMIP_FAIL_FEAS_NO_TREE | 116 |
| CPXMIP_FAIL_INFEAS_NO_TREE | 117 |
| CPXMIP_UNBOUNDED | 118 |
| CPXMIP_INForUNBD | 119 |
| CPXMIP_FEASIBLE_RELAXED_SUM | 120 |
| CPXMIP_OPTIMAL_RELAXED_SUM | 121 |
| CPXMIP_FEASIBLE_RELAXED_INF | 122 |
| CPXMIP_OPTIMAL_RELAXED_INF | 123 |
| CPXMIP_FEASIBLE_RELAXED_QUAD | 124 |
| CPXMIP_OPTIMAL_RELAXED_QUAD | 125 |
| CPXMIP_ABORT_RELAXED | 126 |
| CPXMIP_FEASIBLE | 127 |
| CPXMIP_POPULATESOL_LIM | 128 |
| CPXMIP_OPTIMAL_POPULATED | 129 |
| CPXMIP_OPTIMAL_POPULATED_TOL | 130 |
| CPXMIP_DETTIME_LIM_FEAS | 131 |
| CPXMIP_DETTIME_LIM_INFEAS | 132 |

Valid purgeable values for adding usercuts and lazyconstraints

CPX_USECUT_FORCE 0
CPX_USECUT_PURGE 1

CPX_USECUT_FILTER 2

$For \, {\tt CPXgetnodeintfeas}$

| CPX_INTEGER_FEASIBLE | 0 |
|------------------------------|---|
| CPX_INTEGER_INFEASIBLE | 1 |
| CPX IMPLIED INTEGER FEASIBLE | 2 |

MIP Parameter numbers

| CPX_PARAM_BRDIR | 2001 |
|-----------------------|------|
| CPX_PARAM_BTTOL | 2002 |
| CPX_PARAM_CLIQUES | 2003 |
| CPX_PARAM_COEREDIND | 2004 |
| CPX_PARAM_COVERS | 2005 |
| CPX_PARAM_CUTLO | 2006 |
| CPX_PARAM_CUTUP | 2007 |
| CPX_PARAM_EPAGAP | 2008 |
| CPX_PARAM_EPGAP | 2009 |
| CPX_PARAM_EPINT | 2010 |
| CPX_PARAM_MIPDISPLAY | 2012 |
| CPX_PARAM_MIPINTERVAL | 2013 |
| CPX_PARAM_INTSOLLIM | 2015 |
| CPX_PARAM_NODEFILEIND | 2016 |
| CPX_PARAM_NODELIM | 2017 |
| CPX_PARAM_NODESEL | 2018 |
| CPX_PARAM_OBJDIF | 2019 |
| CPX_PARAM_MIPORDIND | 2020 |
| CPX_PARAM_RELOBJDIF | 2022 |
| CPX_PARAM_STARTALG | 2025 |
| CPX_PARAM_SUBALG | 2026 |
| CPX_PARAM_TRELIM | 2027 |
| CPX_PARAM_VARSEL | 2028 |
| CPX_PARAM_BNDSTRENIND | 2029 |
| CPX_PARAM_HEURFREQ | 2031 |
| CPX_PARAM_MIPORDTYPE | 2032 |
| CPX_PARAM_CUTSFACTOR | 2033 |
| CPX_PARAM_RELAXPREIND | 2034 |
| CPX_PARAM_PRESLVND | 2037 |
| CPX_PARAM_BBINTERVAL | 2039 |
| CPX_PARAM_FLOWCOVERS | 2040 |
| | |

| CPX_PARAM_IMPLBD | 2041 |
|------------------------------|------|
| CPX_PARAM_PROBE | 2042 |
| CPX_PARAM_GUBCOVERS | 2044 |
| CPX_PARAM_STRONGCANDLIM | 2045 |
| CPX_PARAM_STRONGITLIM | 2046 |
| CPX_PARAM_FRACCAND | 2048 |
| CPX_PARAM_FRACCUTS | 2049 |
| CPX_PARAM_FRACPASS | 2050 |
| CPX_PARAM_FLOWPATHS | 2051 |
| CPX_PARAM_MIRCUTS | 2052 |
| CPX_PARAM_DISJCUTS | 2053 |
| CPX_PARAM_AGGCUTLIM | 2054 |
| CPX_PARAM_MIPCBREDLP | 2055 |
| CPX_PARAM_CUTPASS | 2056 |
| CPX_PARAM_MIPEMPHASIS | 2058 |
| CPX_PARAM_SYMMETRY | 2059 |
| CPX_PARAM_DIVETYPE | 2060 |
| CPX_PARAM_RINSHEUR | 2061 |
| CPX_PARAM_SUBMIPNODELIM | 2062 |
| CPX_PARAM_LBHEUR | 2063 |
| CPX_PARAM_REPEATPRESOLVE | 2064 |
| CPX_PARAM_PROBETIME | 2065 |
| CPX_PARAM_POLISHTIME | 2066 |
| CPX PARAM REPAIRTRIES | 2067 |
| CPX_PARAM_EPLIN | 2068 |
| CPX_PARAM_EPRELAX | 2073 |
| CPX_PARAM_FPHEUR | 2098 |
| CPX_PARAM_EACHCUTLIM | 2102 |
| CPX_PARAM_SOLNPOOLCAPACITY | 2103 |
| CPX_PARAM_SOLNPOOLREPLACE | 2104 |
| CPX_PARAM_SOLNPOOLGAP | 2105 |
| CPX_PARAM_SOLNPOOLAGAP | 2106 |
| CPX_PARAM_SOLNPOOLINTENSITY | 2107 |
| CPX_PARAM_POPULATELIM | 2108 |
| CPX_PARAM_MIPSEARCH | 2100 |
| CPX_PARAM_MIQCPSTRAT | 2110 |
| CPX_PARAM_ZEROHALFCUTS | 2110 |
| CPX_PARAM_POLISHAFTEREPAGAP | 2126 |
| CPX_PARAM_POLISHAFTEREPGAP | 2127 |
| CPX_PARAM_POLISHAFTERNODE | 2127 |
| | |
| CPX_PARAM_POLISHAFTERINTSOL | 2129 |
| CPX_PARAM_POLISHAFTERTIME | 2130 |
| CPX_PARAM_MCFCUTS | 2134 |
| CPX_PARAM_MIPKAPPASTATS | 2137 |
| CPX_PARAM_AUXROOTTHREADS | 2139 |
| CPX_PARAM_INTSOLFILEPREFIX | 2143 |
| CPX_PARAM_PROBEDETTIME | 2150 |
| CPX_PARAM_POLISHAFTERDETTIME | 2151 |

| CPX_PARAM_LANDPCUTS | 2152 |
|--------------------------|------|
| CPX_PARAM_RAMPUPDURATION | 2163 |
| CPX_PARAM_RAMPUPDETTILIM | 2164 |
| CPX PARAM RAMPUPTILIM | 2165 |

Values for CPX_PARAM_SOLNPOOLREPLACE

| CPX_SOLNPOOL_FIF0 | 0 |
|-------------------------------|---|
| CPX_SOLNPOOL_OBJ | 1 |
| CPX_SOLNPOOL_DIV | 2 |
| CPX_SOLNPOOL_FILTER_DIVERSITY | 1 |
| CPX_SOLNPOOL_FILTER_RANGE | 2 |

File: gcconst.h

| CPX_CON_LOWER_BOUND | 1 |
|---------------------|---|
| CPX_CON_UPPER_BOUND | 2 |
| CPX_CON_LINEAR | 3 |
| CPX_CON_QUADRATIC | 4 |
| CPX_CON_SOS | 5 |
| CPX CON INDICATOR | 6 |

internal types

| CPX_CON_MINEXPR | 7 |
|----------------------|----|
| CPX_CON_MAXEXPR | 8 |
| CPX_CON_PWL | 9 |
| CPX_CON_ABS | 9 |
| CPX_CON_DISJCST | 10 |
| CPX_CON_INDDISJCST | 11 |
| CPX_CON_SETVAR | 12 |
| CPX_CON_SETVARMEMBER | 13 |
| CPX_CON_SETVARCARD | 14 |
| CPX_CON_SETVARSUM | 15 |
| CPX_CON_SETVARMIN | 16 |
| CPX_CON_SETVARMAX | 17 |
| CPX_CON_SETVARSUBSET | 18 |

| CPX_CON_SETVARDOMAIN | 19 |
|-----------------------------|----|
| CPX_CON_SETVARUNION | 20 |
| CPX_CON_SETVARINTERSECTION | 21 |
| CPX_CON_SETVARNULLINTERSECT | 22 |
| CPX_CON_SETVARINTERSECT | 23 |
| CPX_CON_SETVAREQ | 24 |
| CPX_CON_SETVARNEQ | 25 |
| CPX_CON_SETVARNEQCST | 26 |
| CPX CON LAST CONTYPE | 27 |

Network parameters

| CPX_PARAM_NETITLIM | 5001 |
|----------------------|------|
| CPX_PARAM_NETEPOPT | 5002 |
| CPX_PARAM_NETEPRHS | 5003 |
| CPX_PARAM_NETPPRIIND | 5004 |
| CPX PARAM NETDISPLAY | 5005 |

NETOPT display values

| CPXNET_NO_DISPLAY_OBJECTIVE | 0 |
|-----------------------------|---|
| CPXNET_TRUE_OBJECTIVE | 1 |
| CPXNET PENALIZED OBJECTIVE | 2 |

NETOPT pricing parameters

| CPXNET_PRICE_AUTO | 0 |
|-----------------------------|---|
| CPXNET_PRICE_PARTIAL | 1 |
| CPXNET_PRICE_MULT_PART | 2 |
| CPXNET_PRICE_SORT_MULT_PART | 3 |

Copying data

CPX_PARAM_QPNZREADLIM 4001

Specify how to calculate duals for QCPs

CPX_PARAM_CALCQCPDUALS 4003

presolve

CPX_PARAM_QPMAKEPSDIND 4010

Error codes

Callable library miscellaneous routines

CPXERR_NEGATIVE_SURPLUS 1207 CPXERR_NO_SENSIT 1260

new parameter names introduced in IBM ILOG CPLEX version 12.6

Callable library miscellaneous routines

| CPXPARAM_Advance | 1001 |
|--------------------------------------|------|
| CPXPARAM_Barrier_Algorithm | 3007 |
| CPXPARAM_Barrier_ColNonzeros | 3009 |
| CPXPARAM_Barrier_ConvergeTol | 3002 |
| CPXPARAM_Barrier_Crossover | 3018 |
| CPXPARAM_Barrier_Display | 3010 |
| CPXPARAM_Barrier_Limits_Corrections | 3013 |
| CPXPARAM_Barrier_Limits_Growth | 3003 |
| CPXPARAM_Barrier_Limits_Iteration | 3012 |
| CPXPARAM_Barrier_Limits_ObjRange | 3004 |
| CPXPARAM_Barrier_Ordering | 3014 |
| CPXPARAM_Barrier_QCPConvergeTol | 3020 |
| CPXPARAM_Barrier_StartAlg | 3017 |
| CPXPARAM_ClockType | 1006 |
| CPXPARAM_Conflict_Display | 1074 |
| CPXPARAM_DetTimeLimit | 1127 |
| CPXPARAM_DistMIP_Rampup_DetTimeLimit | 2164 |

| CPXPARAM_DistMIP_Rampup_Duration | 2163 |
|------------------------------------|------|
| CPXPARAM_DistMIP_Rampup_TimeLimit | 2165 |
| CPXPARAM_Emphasis_Memory | 1082 |
| CPXPARAM_Emphasis_MIP | 2058 |
| CPXPARAM_Emphasis_Numerical | 1083 |
| CPXPARAM_Feasopt_Mode | 1084 |
| CPXPARAM_Feasopt_Tolerance | 2073 |
| CPXPARAM_LPMethod | 1062 |
| CPXPARAM_MIP_Cuts_Cliques | 2003 |
| CPXPARAM_MIP_Cuts_Covers | 2005 |
| CPXPARAM_MIP_Cuts_Disjunctive | 2053 |
| CPXPARAM_MIP_Cuts_FlowCovers | 2040 |
| CPXPARAM_MIP_Cuts_Gomory | 2049 |
| CPXPARAM_MIP_Cuts_GUBCovers | 2044 |
| CPXPARAM_MIP_Cuts_Implied | 2041 |
| CPXPARAM_MIP_Cuts_LiftProj | 2152 |
| CPXPARAM_MIP_Cuts_MCFCut | 2134 |
| CPXPARAM_MIP_Cuts_MIRCut | 2052 |
| CPXPARAM_MIP_Cuts_PathCut | 2051 |
| CPXPARAM_MIP_Cuts_ZeroHalfCut | 2111 |
| CPXPARAM_MIP_Display | 2012 |
| CPXPARAM_MIP_Interval | 2013 |
| CPXPARAM_MIP_Limits_AggForCut | 2054 |
| CPXPARAM_MIP_Limits_AuxRootThreads | 2139 |
| CPXPARAM_MIP_Limits_CutPasses | 2056 |
| CPXPARAM_MIP_Limits_CutsFactor | 2033 |
| CPXPARAM_MIP_Limits_EachCutLimit | 2102 |
| CPXPARAM_MIP_Limits_GomoryCand | 2048 |
| CPXPARAM_MIP_Limits_GomoryPass | 2050 |
| CPXPARAM_MIP_Limits_Nodes | 2017 |
| CPXPARAM_MIP_Limits_PolishTime | 2066 |
| CPXPARAM_MIP_Limits_Populate | 2108 |
| CPXPARAM_MIP_Limits_ProbeDetTime | 2150 |
| CPXPARAM_MIP_Limits_ProbeTime | 2065 |
| CPXPARAM_MIP_Limits_RepairTries | 2067 |
| CPXPARAM_MIP_Limits_Solutions | 2015 |
| CPXPARAM_MIP_Limits_StrongCand | 2045 |
| CPXPARAM_MIP_Limits_StrongIt | 2046 |
| CPXPARAM_MIP_Limits_SubMIPNodeLim | 2062 |
| CPXPARAM_MIP_Limits_TreeMemory | 2027 |
| CPXPARAM_MIP_OrderType | 2032 |
| CPXPARAM_MIP_PolishAfter_AbsMIPGap | 2126 |
| CPXPARAM_MIP_PolishAfter_DetTime | 2151 |
| CPXPARAM_MIP_PolishAfter_MIPGap | 2127 |
| CPXPARAM_MIP_PolishAfter_Nodes | 2128 |
| CPXPARAM_MIP_PolishAfter_Solutions | 2129 |
| CPXPARAM_MIP_PolishAfter_Time | 2130 |
| CPXPARAM_MIP_Pool_AbsGap | 2106 |
| | |

| CPXPARAM_MIP_Pool_Capacity | 2103 |
|--|------|
| CPXPARAM_MIP_Pool_Intensity | 2107 |
| CPXPARAM_MIP_Pool_RelGap | 2105 |
| CPXPARAM_MIP_Pool_Replace | 2104 |
| CPXPARAM_MIP_Strategy_Backtrack | 2002 |
| CPXPARAM_MIP_Strategy_BBInterval | 2039 |
| CPXPARAM_MIP_Strategy_Branch | 2001 |
| CPXPARAM_MIP_Strategy_CallbackReducedLP | 2055 |
| CPXPARAM_MIP_Strategy_Dive | 2060 |
| CPXPARAM_MIP_Strategy_File | 2016 |
| CPXPARAM_MIP_Strategy_FPHeur | 2098 |
| CPXPARAM_MIP_Strategy_HeuristicFreq | 2031 |
| CPXPARAM_MIP_Strategy_KappaStats | 2137 |
| CPXPARAM_MIP_Strategy_LBHeur | 2063 |
| CPXPARAM_MIP_Strategy_MIQCPStrat | 2110 |
| CPXPARAM_MIP_Strategy_NodeSelect | 2018 |
| CPXPARAM_MIP_Strategy_Order | 2020 |
| CPXPARAM_MIP_Strategy_PresolveNode | 2037 |
| CPXPARAM_MIP_Strategy_Probe | 2042 |
| CPXPARAM_MIP_Strategy_RINSHeur | 2061 |
| CPXPARAM_MIP_Strategy_Search | 2109 |
| CPXPARAM_MIP_Strategy_StartAlgorithm | 2025 |
| CPXPARAM_MIP_Strategy_SubAlgorithm | 2026 |
| CPXPARAM_MIP_Strategy_VariableSelect | 2028 |
| CPXPARAM_MIP_Tolerances_AbsMIPGap | 2008 |
| CPXPARAM_MIP_Tolerances_Integrality | 2010 |
| CPXPARAM_MIP_Tolerances_LowerCutoff | 2006 |
| CPXPARAM_MIP_Tolerances_MIPGap | 2009 |
| CPXPARAM_MIP_Tolerances_ObjDifference | 2019 |
| CPXPARAM_MIP_Tolerances_RelObjDifference | 2022 |
| CPXPARAM_MIP_Tolerances_UpperCutoff | 2007 |
| CPXPARAM_Network_Display | 5005 |
| CPXPARAM_Network_Iterations | 5001 |
| CPXPARAM_Network_NetFind | 1022 |
| CPXPARAM_Network_Pricing | 5004 |
| CPXPARAM_Network_Tolerances_Feasibility | 5003 |
| CPXPARAM_Network_Tolerances_Optimality | 5002 |
| CPXPARAM_Output_CloneLog | 1132 |
| CPXPARAM_Output_IntSolFilePrefix | 2143 |
| CPXPARAM_Output_MPSLong | 1081 |
| CPXPARAM_Output_WriteLevel | 1114 |
| CPXPARAM_Parallel | 1109 |
| CPXPARAM_Preprocessing_Aggregator | 1003 |
| CPXPARAM_Preprocessing_BoundStrength | 2029 |
| CPXPARAM_Preprocessing_CoeffReduce | 2004 |
| CPXPARAM_Preprocessing_Dependency | 1008 |
| CPXPARAM_Preprocessing_Dual | 1044 |
| CPXPARAM_Preprocessing_Fill | 1002 |

| CPXPARAM_Preprocessing_Linear | 1058 |
|---|--------------|
| CPXPARAM_Preprocessing_NumPass | 1052 |
| CPXPARAM_Preprocessing_Presolve | 1030 |
| CPXPARAM_Preprocessing_QCPDuals | 4003 |
| CPXPARAM_Preprocessing_QPMakePSD | 4010 |
| CPXPARAM_Preprocessing_Reduce | 1057 |
| CPXPARAM_Preprocessing_Relax | 2034 |
| CPXPARAM_Preprocessing_RepeatPresolve | 2064 |
| CPXPARAM_Preprocessing_Symmetry | 2059 |
| CPXPARAM_QPMethod | 1063 |
| CPXPARAM_RandomSeed | 1124 |
| CPXPARAM_Read_APIEncoding | 1130 |
| CPXPARAM_Read_Constraints | 1021 |
| CPXPARAM_Read_DataCheck | 1056 |
| CPXPARAM_Read_FileEncoding | 1129 |
| CPXPARAM_Read_Nonzeros | 1024 |
| CPXPARAM_Read_QPNonzeros | 4001 |
| | |
| CPXPARAM_Read_Scale | 1034 |
| CPXPARAM_Read_Variables | 1023 |
| CPXPARAM_ScreenOutput | 1035 |
| CPXPARAM_Sifting_Algorithm | 1077 1076 |
| CPXPARAM_Sifting_Display | |
| CPXPARAM_Sifting_Iterations | 1078 |
| CPXPARAM_Simplex_Crash | 1007 |
| CPXPARAM_Simplex_DGradient | 1009 |
| CPXPARAM_Simplex_Display | 1019 |
| CPXPARAM_Simplex_Limits_Iterations | 1020 |
| CPXPARAM_Simplex_Limits_LowerObj | 1025 |
| CPXPARAM_Simplex_Limits_Perturbation | 1028 |
| CPXPARAM_Simplex_Limits_Singularity | 1037 |
| CPXPARAM_Simplex_Limits_UpperObj | 1026 |
| CPXPARAM_Simplex_Perturbation_Constant | 1015 |
| CPXPARAM_Simplex_Perturbation_Indicator | 1027 |
| CPXPARAM_Simplex_PGradient | 1029 |
| CPXPARAM_Simplex_Pricing | 1010 |
| CPXPARAM_Simplex_Refactor | 1031 |
| CPXPARAM_Simplex_Tolerances_Feasibility | 1016 |
| CPXPARAM_Simplex_Tolerances_Markowitz | 1013 |
| CPXPARAM_Simplex_Tolerances_Optimality | 1014 |
| CPXPARAM_SolutionTarget | 1131 |
| CPXPARAM_Threads | 1067 |
| CPXPARAM_TimeLimit | 1039 |
| CPXPARAM_Tune_DetTimeLimit | 1139 |
| CPXPARAM_Tune_Display | 1113 |
| CPXPARAM_Tune_Measure | 1110 |
| CPXPARAM_Tune_Repeat | 1111 |
| CPXPARAM_Tune_TimeLimit | 1112 |
| CPXPARAM_WorkDir | 1064 |
| | |

cplexError-class 83

CPXPARAM_WorkMem

1065

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

return_codeCPLEX, status_codeCPLEX, getParmValCPLEX

cplexError-class

Class "cplexError"

Description

Objects of class cpxerr are returned by various functions of **cplexAPI**, in order to distinguish a status (error) code from a successfull result.

Objects from the Class

Objects can be created by calls of the form cplexError(err), with err beeing an error code of IBM ILOG CPLEX.

Slots

errnum: Object of class "integer" containing the error code.

Methods

err signature(object = "cplexError"): Prints an error message string corresponding to the
error code.

errmsg signature(object = "cplexError"): Returns an error message string corresponding
to the error code.

errnum signature(object = "cplexError"): Gets the error code.

errnum<- signature(object = "cplexError"): Sets the error code.</pre>

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

84 cplexPtr-class

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

cplexPtr-class

Class "cplexPtr"

Description

Structure of the class "cplexPtr". Objects of that class are used to hold pointers to C structures used by IBM ILOG CPLEX.

Objects from the Class

```
Objects can be created by calls of the form env <- openEnvCPLEX() and/or prob <- initProbCPLEX(env)).
```

Slots

```
cplexPtrType: Object of class "character" giving the pointer type.
cplexPointer: Object of class "externalptr" containing the pointer to a C structure.
```

Methods

isCPLEXchanPointer signature(object = "cplexPtr"): returns TRUE if cplexPointer(object)
is a pointer to a CPLEX channel, otherwise FALSE.

isCPLEXenvPointer signature(object = "cplexPtr"): returns TRUE if cplexPointer(object) is a pointer to a CPLEX environment, otherwise FALSE.

isCPLEXfilePointer signature(object = "cplexPtr"): returns TRUE if cplexPointer(object) is a pointer to a CPLEX file, otherwise FALSE.

isCPLEXprobPointer signature(object = "cplexPtr"): returns TRUE if cplexPointer(object) is a pointer to a CPLEX problem object, otherwise FALSE.

isCPLEXtermPointer signature(object = "cplexPtr"): returns TRUE if cplexPointer(object) is a pointer to a CPLEX termination signal, otherwise FALSE.

isNULLpointerCPLEX signature(object = "cplexPtr"): returns TRUE if cplexPointer(object) is a NULL pointer, otherwise FALSE.

cplexPointer signature(object = "cplexPtr"): gets the cplexPointer slot.

summary signature(object = "cplexPtr"): prints a summary of the problem object to the command line. If a solution is available, it prints also information retrieved by **solutionCPLEX** and **solnInfoCPLEX**. If no solution is available, it prints the corresponding error message. The method returns invisibly NULL. The CPLEX environment pointer is needed as second argument env to summary.

```
cplexPtrType signature(object = "cplexPtr"): gets the cplexPtrType slot.
cplexPtrType<- signature(object = "cplexPtr"): sets the cplexPtrType slot.</pre>
```

delChannelCPLEX 85

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

openEnvCPLEX and initProbCPLEX

delChannelCPLEX

Flushes all Message Destinations for a Channel

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelchannel. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

delChannelCPLEX(env, newch)

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

newch A pointer to the channel containing the message destinations as returned by

CPXaddchannel.

Details

Interface to the C function delChannel which calls the CPLEX function CPXdelchannel.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

86 delColsCPLEX

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

 $add Channel CPLEX, \ disconnect Channel CPLEX, \ flush Channel CPLEX, \ flush Std Channel sCPLEX, \ get Channel sCPLEX$

delColsCPLEX Delete all Columns in a Specified Range

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelcols. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delColsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | Integer value, numeric index of the first column to be deleted. |
| end | Integer value, numeric index of the last column to be deleted. |

Details

Interface to the C function delCols which calls the CPLEX function CPXdelcols.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

delFpDestCPLEX 87

| delFpDestCPLEX | Remove a File from the List of Message Destinations for a Channel |
|----------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelfpdest. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delFpDestCPLEX(env, newch, cpfile)
```

Arguments

| env | An object of class | "cplexPtr" | as returned by | openEnvCPLEX. | This is basically |
|-----|--------------------|------------|----------------|---------------|-------------------|
| | | | | | |

a pointer to an IBM ILOG CPLEX environment.

newch A pointer to the channel for which destinations are to be deleted as returned by

CPXaddchannel.

cpfile Pointer to an IBM ILOG CPLEX file as returned by openFileCPLEX.

Details

Interface to the C function delFpDest which calls the CPLEX function CPXdelfpdest.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

addFpDestCPLEX

88 delIndConstrsCPLEX

| delIndConstrsCPLEX Del | ete a Range of | Indicator | Constraints |
|------------------------|----------------|-----------|-------------|
|------------------------|----------------|-----------|-------------|

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelindconstrs. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delIndConstrsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer that specifies the numeric index of the first indicator constraint to be deleted. |
| end | An integer that specifies the numeric index of the last indicator constraint to be deleted. |

Details

Interface to the C function delIndConstrs which calls the CPLEX function CPXdelindconstrs.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

delMIPstartsCPLEX 89

| d | elMIPstartsCPLEX | Delete a Range MIP Starts | |
|---|------------------|---------------------------|--|
| | | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelmipstarts. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delMIPstartsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the numeric index of the first MIP start to be deleted. |
| end | An integer specifying the numeric index of the last MIP start to be deleted. |

Details

Interface to the C function delMIPstarts which calls the CPLEX function CPXdelmipstarts.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

90 delNamesCPLEX

| de1 | NamesCPL | FΥ |
|-----|----------|----|

Remove all Names Assigned to Rows and Columns

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelnames. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delNamesCPLEX(env, lp)
```

Arguments

| | env | An object of class ' | "cplexPtr" as returned | d by openEnvCPLEX. This is basically | Į |
|--|-----|----------------------|------------------------|--------------------------------------|---|
|--|-----|----------------------|------------------------|--------------------------------------|---|

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function delNames which calls the CPLEX function CPXdelnames.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

delProbCPLEX 91

| delProbCPLEX | Remove Specified CPLEX Problem Object |
|--------------|---------------------------------------|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXfreeprob. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delProbCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function delProb which calls the CPLEX function CPXfreeprob.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

initProbCPLEX

92 delQConstrsCPLEX

| delQConstrsCPLEX | Delete a Range of Quadratic Constraints | |
|------------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelqconstrs. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delQConstrsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer that specifies the numeric index of the first quadratic constraint to be deleted. |
| end | An integer that specifies the numeric index of the last quadratic constraint to be deleted. |

Details

 $Interface \ to \ the \ C \ function \ del Q Constrs \ which \ calls \ the \ CPLEX \ function \ CPX del q constrs.$

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

delRowsCPLEX 93

| delRowsCPLEX | Delete a Range of Rows | |
|--------------|------------------------|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelrows. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delRowsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | Integer value, numeric index of the first row to be deleted. |
| end | Integer value, numeric index of the last row to be deleted. |

Details

Interface to the C function delRows which calls the CPLEX function CPXdelrows.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

94 delSetColsCPLEX

| PLEX Delete a Set of Columns |
|------------------------------|
| Detete a set of Columns |

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelsetcols. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delSetColsCPLEX(env, lp, delstat)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|---------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| delstat | An array specifying the columns to be deleted. |

Details

Interface to the C function delSetCols which calls the CPLEX function CPXdelsetcols.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

delSetRowsCPLEX 95

| S | Delete a Set of Rows | delSetRowsCPLEX |
|---|----------------------|-----------------|
|---|----------------------|-----------------|

Description

Low level interface function to the IBM ILOG CPLEX function CPXdelsetrows. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delSetRowsCPLEX(env, lp, delstat)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|---------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| delstat | An array specifying the rows to be deleted. |

Details

Interface to the C function delSetRows which calls the CPLEX function CPXdelsetrows.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

96 delTerminateCPLEX

| delTerminateCPLEX | Terminate CPLEX gracefully |
|----------------------|-----------------------------|
| dellelillillatecelex | Terminale CI LLA gracejully |

Description

Low level interface function to the IBM ILOG CPLEX function CPXsetterminate. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
delTerminateCPLEX(env, tsig)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

tsig Pointer to termination signal as returned by setTerminateCPLEX.

Details

Interface to the C function setTerminate which calls the CPLEX function CPXsetterminate.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

setTerminateCPLEX, printTerminateCPLEX, chgTerminateCPLEX

disconnectChannelCPLEX

Flush all Message Destinations Associated with a Channel

Description

Low level interface function to the IBM ILOG CPLEX function CPXdisconnectchannel. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

disconnectChannelCPLEX(env, newch)

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

newch A pointer to the channel containing the message destinations as returned by

CPXaddchannel.

Details

Interface to the C function disconnectChannel which calls the CPLEX function CPXdisconnectchannel.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

addChannelCPLEX, delChannelCPLEX, flushChannelCPLEX, flushStdChannelsCPLEX, getChannelsCPLEX

98 dualoptCPLEX

| dualopt(| :PL | ΕX |
|----------|-----|----|
|----------|-----|----|

Find a Problem Solution Using the Dual Simplex Algorithm

Description

Low level interface function to the IBM ILOG CPLEX function CPXdualopt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
dualoptCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function dualopt which calls the CPLEX function CPXdualopt.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

solnInfoCPLEX, getStatCPLEX, solutionCPLEX

dualWriteCPLEX 99

| dualWriteCPLEX | Write a Dual Formulation of the Current CPLEX Problem Object |
|----------------|--|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXdualwrite. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
dualWriteCPLEX(env, lp, fname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| fname | Single character value giving the filname to write to. |

Details

Interface to the C function dualWrite which calls the CPLEX function CPXdualwrite.

Value

Zero if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

100 feasOptCPLEX

| feasOptCPLEX Compute a Minimum-Cost Relaxation |
|--|
|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXfeasopt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
feasOptCPLEX(env, lp, rhs = FALSE, rng = FALSE, lb = FALSE, ub = FALSE)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| rhs | If set to FALSE no right hand side value is allowed to be relaxed. |
| rng | If set to FALSE no range values are allowed to be relaxed. |
| lb | If set to FALSE no lower bound of any variable is allowed to be relaxed. |
| ub | If set to FALSE no lower bound of any variable is allowed to be relaxed. |

Details

Interface to the C function feasOpt which calls the CPLEX function CPXfeasopt.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

solutionCPLEX, getRowInfeasCPLEX, getColInfeasCPLEX, solnInfoCPLEX, getStatCPLEX

fileputCPLEX 101

| fileputCPLEX Write to File |
|----------------------------|
|----------------------------|

Description

Low level interface function to the IBM ILOG CPLEX function CPXfputs. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
fileputCPLEX(cpfile, stuff = "")
```

Arguments

cpfile A pointer to a file as returned by openFileCPLEX.

stuff A character string to be written to the file.

Details

Interface to the C function fileput which calls the CPLEX function CPXfputs.

Value

A nonnegative value if successful, otherwise EOF.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
closeFileCPLEX, openFileCPLEX
```

102 flushChannelCPLEX

flushChannelCPLEX

Flush All Message Destinations Associated With a Channel

Description

Low level interface function to the IBM ILOG CPLEX function CPXflushchannel. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

flushChannelCPLEX(env, newch)

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

newch Pointer to a channel object as returned by addChannelCPLEX.

Details

Interface to the C function flushChannel which calls the CPLEX function CPXflushchannel.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

add Channel CPLEX, del Channel CPLEX, disconnect Channel CPLEX, flush Std Channel s CPLEX, get Channel s CPLEX, del Channel s CPLEX,

flushStdChannelsCPLEX 103

flushStdChannelsCPLEX Flushes the Output Buffers of the Four Standard Channels

Description

Low level interface function to the IBM ILOG CPLEX function CPXflushstdchannels. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

flushStdChannelsCPLEX(env)

Arguments

env

An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment.

Details

Interface to the C function flushStdChannels which calls the CPLEX function CPXflushstdchannels.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

addChannelCPLEX, delChannelCPLEX, disconnectChannelCPLEX, flushChannelCPLEX, getChannelsCPLEX

104 freePresolveCPLEX

freePresolveCPLEX

Free Presolved Problem From the LP Problem Object

Description

Low level interface function to the IBM ILOG CPLEX function CPXfreepresolve. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
freePresolveCPLEX(env, lp)
```

Arguments

| | env | An object of class ' | "cplexPtr" as | returned by o | penEnvCPLEX. | This is basically |
|--|-----|----------------------|---------------|---------------|--------------|-------------------|
|--|-----|----------------------|---------------|---------------|--------------|-------------------|

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function freePresolve which calls the CPLEX function CPXfreepresolve.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getBaseCPLEX 105

| getBaseCPLEX | Access Basis Resident in a CPLEX Problem Object. |
|--------------|--|
| S | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetbase. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getBaseCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getBase which calls the CPLEX function CPXgetbase.

Value

If successful a list is returned:

cstat basis status of the columns in the CPLEX problem object

rstat basis status of the artificial, slack, or surplus variable associated with each row

in the constraint matrix

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

| getBestObjValCPLEX | Access the Currently Best Known Bound of all the Remaining Open Nodes in a Branch-And-Cut Tree |
|--------------------|--|
|--------------------|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetbestobjval. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getBestObjValCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

 $Interface \ to \ the \ C \ function \ getBestObjVal \ which \ calls \ the \ CPLEX \ function \ CPX getbestobjval.$

Value

Objective value if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getChannelsCPLEX 107

| getChannelsCPLEX | Obtain Pointers to the Four Default Channels |
|------------------|--|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetchannels. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getChannelsCPLEX(env, ptrtype = "cplex_chan")
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

ptrtype A name for the pointer object.

Details

Interface to the C function getChannels which calls the CPLEX function CPXgetchannels.

Value

If successful a list is returned:

cpxresults address of the channel corresponding to cpxresults
cpxwarning address of the channel corresponding to cpxwarning
cpxerror address of the channel corresponding to cpxerror
cpxlog address of the channel corresponding to cpxlog

otherwise an instance of class "cplexError". Each list element is an object of class "cplexPtr".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

addChannelCPLEX, delChannelCPLEX, disconnectChannelCPLEX, flushChannelCPLEX, flushStdChannelsCPLEX

108 getChgParmCPLEX

| getChgParmCPLEX | Get Parameter Numbers for Parameters Which are Not Set at Their Default Values |
|-----------------|---|
| | Default Values |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetchgparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getChgParmCPLEX(env)
```

Arguments

env

An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment.

Details

Interface to the C function getChgParm which calls the CPLEX function CPXgetchgparam.

Value

A vector containing integer values (unique parameter identifiers) for parameters which are not set at their default values, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getCoefCPLEX 109

| getCoefCPLEX | Access a Single Constraint Matrix Coefficient | |
|--------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetcoef. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getCoefCPLEX(env, lp, i, j)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| i | An integer specifying the numeric index of the row. |
| j | An integer specifying the numeric index of the column. |

Details

Interface to the C function getCoef which calls the CPLEX function CPXgetcoef.

Value

Matrix coefficient value if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

110 getColIndexCPLEX

| getColIndexCPLEX | Search for the Index Number of the Specified Column | |
|------------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetcolindex. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getColIndexCPLEX(env, lp, cname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| cname | A column name to search for. |

Details

Interface to the C function getColIndex which calls the CPLEX function CPXgetcolindex.

Value

Column number if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getColInfeasCPLEX 111

| getColInfeasCPLEX Compute Infeasibility of a Given Solution for a Range of Variables | getColInfeasCPLEX | Compute Infeasibility of a Given Solution for a Range of Variables | |
|--|-------------------|--|--|
|--|-------------------|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetcolinfeas. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getColInfeasCPLEX(env, lp, begin, end, sol = NULL)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of variables whose infeasibility is to be returned. |
| end | An integer specifying the end of the range of variables whose infeasibility is to be returned. |
| sol | The solution whose infeasibility is to be computed. |

Details

Interface to the C function getColInfeas which calls the CPLEX function CPXgetcolinfeas.

Value

infeasibility values if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

112 getColNameCPLEX

| getColNameCPLEX Access a Range of Column Names |
|--|
|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetcolname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getColNameCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of column names to be returned. |
| end | An integer specifying the end of the range of column names to be returned. |

Details

 $Interface \ to \ the \ C \ function \ {\tt getColName} \ which \ calls \ the \ CPLEX \ function \ {\tt CPXgetcolname}.$

Value

Column names if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getColsCPLEX 113

| getColsCPLEX Accesses a Range of Columns of the Constraint Matrix | |
|---|--|
|---|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetcols. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getColsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of columns to be returned. |
| end | An integer specifying the end of the range of columns to be returned. |

Details

Interface to the C function getCols which calls the CPLEX function CPXgetcols.

Value

If successful a list is returned:

| matbeg | Array that specifies the nonzero elements of the columns. ILOG CPLEX documentation for more detailed information. | Consult the IBM |
|--------|---|-----------------|
| matind | Array that specifies the nonzero elements of the columns. ILOG CPLEX documentation for more detailed information. | Consult the IBM |
| matval | Array that specifies the nonzero elements of the columns. ILOG CPLEX documentation for more detailed information. | Consult the IBM |

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

114 getColTypeCPLEX

| getColTypeCPLEX Access Types for a Range of Variables |
|---|
|---|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetctype. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getColTypeCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of the types to be returned. |
| end | An integer specifying the end of the range of the types to be returned. |

Details

Interface to the C function getColType which calls the CPLEX function CPXgetctype.

Value

Column types if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants

getConflictCPLEX 115

| +C | Determine Constraints and Wasiable Delevation to a Conflict |
|------------------|---|
| getConflictCPLEX | Return Linear Constraints and Variables Belonging to a Conflict |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetconflict. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getConflictCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getConflict which calls the CPLEX function CPXgetconflict.

Value

If successful a list is returned:

confstat status of the conflict

confnumrows number of rows in the conflict

rowind indices of the constraints that participate in the conflict

rowbdstat conflict status of the rows

confnumcols number of columns in the conflict

colind indices of the variables that participate in the conflict

colbdstat conflict status of the columns

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

See Also

cplexConstants

getConflictExtCPLEX Get Conflict Status Codes

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetconflictext. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getConflictExtCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | The index of the first group. |
| end | The index of the last group. |

Details

Interface to the C function getConflictExt which calls the CPLEX function CPXgetconflictext.

Value

Specified values denoting the conflict status if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getCutoffCPLEX 117

| getCutoffCPLEX Access MIP Cutoff Value Being Used During Mixed Integer Optimization. |
|--|
|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetcutoff. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getCutoffCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

 $Interface \ to \ the \ C \ function \ {\tt getCutoff} \ which \ calls \ the \ CPLEX \ function \ {\tt CPXgetcutoff}.$

Value

Value of the cutoff if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

118 getDblParmCPLEX

getDblParmCPLEX

Obtain the Current Value of a CPLEX Parameter of Type Double

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetdblparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getDblParmCPLEX(env, parm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

Details

Interface to the C function getDblParm which calls the CPLEX function CPXgetdblparam.

Value

Parameter value if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants

getDblQualCPLEX 119

| getDblQualCPLEX | Access Double-Valued Information About the Quality of the Current Solution of a Problem |
|-----------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetdblquality. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getDblQualCPLEX(env, lp, w)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| w | An Integer specifying the quality value to be retrieved. |

Details

Interface to the C function getDblQual which calls the CPLEX function CPXgetdblquality.

Value

Requested quality value if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
cplexConstants
```

120 getDbsCntCPLEX

| getl | ObsCntCPLEX | Access the Number of Dual Super-Basic Variables in the Current Solution |
|------|-------------|---|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetdsbcnt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getDbsCntCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

 $Interface \ to \ the \ C \ function \ {\tt getDbsCnt} \ \ which \ calls \ the \ CPLEX \ function \ {\tt CPXgetdsbcnt}.$

Value

Number of dual super-basic variables if a solution exists, otherwise zero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getDjCPLEX 121

| getDjCPLEX | Accesses Reduced Costs for a Range of Variables of a Linear or Quadratic Program |
|------------|--|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetdj. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getDjCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of reduced-cost values to be returned. |
| end | An integer specifying the end of the range of reduced-costs values to be returned. |

Details

Interface to the C function getDj which calls the CPLEX function CPXgetdj.

Value

Reduced costs if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

122 getErrorStrCPLEX

getErrorStrCPLEX

Return an Error Message String Corresponding to an Error Code

Description

Low level interface function to the IBM ILOG CPLEX function CPXgeterrorstring. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getErrorStrCPLEX(err, env = NULL)
```

Arguments

err The error code to be translated.

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

Details

Interface to the C function getErrorStr which calls the CPLEX function CPXgeterrorstring.

Value

A single character value containing the error message string.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
getStatStrCPLEX
```

getGradCPLEX 123

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetgrad. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getGradCPLEX(env, lp, j)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| j | An integer specifying the index of the column of interest. |

Details

Interface to the C function getGrad which calls the CPLEX function CPXgetgrad.

Value

If successful a list is returned:

head listing of the indices of the basic variables in the order in which they appear in

the basis.

y coefficients of the j-th column relative to the current basis.

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

124 getIndConstrCPLEX

| getIndConstrCPLEX | Access a Specified Indicator Constraint on the Variables of a CPLEX Problem Object. |
|-------------------|---|
| | v |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetindconstr. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getIndConstrCPLEX(env, lp, which)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| which | An integer specifying which indicator constraint to return. |

Details

 $Interface \ to \ the \ C \ function \ {\tt getIndConstr} \ which \ calls \ the \ CPLEX \ function \ {\tt CPXgetindconstr}.$

Value

If successful a list is returned:

| indvar | Index of the binary indicator variable. Consult the IBM ILOG CPLEX documentation for more detailed information. |
|--------------|--|
| complemented | Boolean value that specifies whether the indicator variable is complemented. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| rhs | Righthand side value of the linear portion of the indicator constraint. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| sense | Sense of the linear portion of the constraint. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| linind | Variable indices of the entries of linval. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| linval | Coefficients of the linear portion of the specified indicator constraint. Consult the IBM ILOG CPLEX documentation for more detailed information. |

otherwise an instance of class "cplexError".

getInfoDblParmCPLEX

125

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

getInfoDblParmCPLEX

Obtain Default, Minimum and Maximum Values of a Parameter of Type Double

Description

Low level interface function to the IBM ILOG CPLEX function CPXinfodblparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getInfoDblParmCPLEX(env, parm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

Details

Interface to the C function getInfoDblParm which calls the CPLEX function CPXinfodblparam.

Value

If successful a list is returned:

defvalue default value
minvalue minimum value
maxvalue maximum value

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants

Description

Low level interface function to the IBM ILOG CPLEX function CPXinfointparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getInfoIntParmCPLEX(env, parm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

Details

Interface to the C function getInfoIntParm which calls the CPLEX function CPXinfointparam.

Value

If successful a list is returned:

defvalue default value
minvalue minimum value
maxvalue maximum value

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants

 $\begin{tabular}{lll} getInfoLongParmCPLEX & Obtain Default, Minimum and Maximum Values of a Parameter of \\ & Type \ CPXLONG \end{tabular}$

Description

Low level interface function to the IBM ILOG CPLEX function CPXinfolongparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getInfoLongParmCPLEX(env, parm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

Details

 $Interface \ to \ the \ C \ function \ getInfoLongParm \ which \ calls \ the \ CPLEX \ function \ CPX infolongparam.$

Value

If successful a list is returned:

defvalue default value
minvalue minimum value
maxvalue maximum value

otherwise an instance of class "cplexError".

Note

In order to get a 64 bit integer value from CPXinfolongparam, datatype numeric is used. All return values will be numeric.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getInfoIntParmCPLEX, cplexConstants

getInfoStrParmCPLEX

Obtain Default Value of a String Parameter

Description

Low level interface function to the IBM ILOG CPLEX function CPXinfostrparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getInfoStrParmCPLEX(env, parm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

Details

Interface to the C function getInfoStrParm which calls the CPLEX function CPXinfostrparam.

Value

A single character value.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getIntParmCPLEX 129

See Also

cplexConstants

getIntParmCPLEX

Obtain the Current Value of a CPLEX Parameter of Type CPXINT

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetintparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getIntParmCPLEX(env, parm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

Details

Interface to the C function getIntParm which calls the CPLEX function CPXgetintparam.

Value

Parameter value if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants

130 getIntQualCPLEX

| getIntQualCPLEX Access Integer-Valued Information About the Quality of the Current Solution of a Problem | ?nt |
|---|-----|
|---|-----|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetintquality. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getIntQualCPLEX(env, lp, w)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| W | An Integer specifying the quality value to be retrieved. |

Details

Interface to the C function getIntQual which calls the CPLEX function CPXgetintquality.

Value

Requested quality value if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getItCntCPLEX 131

| opt] | T + C + | $^{+}$ C | DΙ | ΕV |
|------|---------|----------|----|----|

Access the Total Number of Simplex Iterations to Solve an LP Problem

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetitcnt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getItCntCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically |
|-----|---|
| | a pointer to an IBM ILOG CPLEX environment. |
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically |

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getItCnt which calls the CPLEX function CPXgetitcnt.

Value

Total iteration count if solution exists, otherwise zero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

132 getLogFileCPLEX

| | A 1 C1 |
|-----------------|----------------|
| getLogFileCPLEX | Access log fil |

Access log file to Which Messages are Written

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetlogfile. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getLogFileCPLEX(env, ptrtype = "cplex_file")
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

ptrtype A name for the pointer object.

Details

Interface to the C function getLogFile which calls the CPLEX function CPXgetlogfile.

Value

If successful, a pointer to the CPLEX file is returnd (an instance of class "cplexPtr"), otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
setLogFileCPLEX
```

getLongParmCPLEX 133

| getLongParmCPLEX | Obtain Current Value of a Parameter of Type CPXLONG | |
|------------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetlongparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getLongParmCPLEX(env, parm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

Details

Interface to the C function getLongParm which calls the CPLEX function CPXgetlongparam.

Value

Parameter value if successful, otherwise an instance of class "cplexError".

Note

In order to get a 64 bit integer value from CPXgetlongparam, datatype numeric is used. The return value will be numeric.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
getIntParmCPLEX, cplexConstants
```

| $\alpha \alpha + 1$ | owRno | CT A | ICCDI | ΕV |
|---------------------|-------|------|-------|----|
| geti | owano | SIO | ISCPI | ΓX |

Retrieve Lower Bounds on Variables

Description

The function retrieves the lower bounds on specified variables.

Usage

```
getLowBndsIdsCPLEX(env, lp, ind)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ind | Column indices of variables (remember: first index is 0). |

Value

A numeric vector containing the lower bounds on the specified variables. If not successfull an instance of class "cplexError" is returned.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getLowerBndsCPLEX

getLowerBndsCPLEX 135

| getLowerBndsCPLEX | Access a Range of Lower Bounds on Variables | |
|-------------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetlb. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getLowerBndsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | Beginning of the range of lower bounds to be returned. |
| end | End of the range of lower bounds to be returned. |

Details

Interface to the C function getLowerBnds which calls the CPLEX function CPXgetlb.

Value

A numeric vector containing the lower bounds on the specified variables. If not successfull an instance of class "cplexError" is returned.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

136 getMethodCPLEX

|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetmethod. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getMethodCPLEX(env, lp)
```

Arguments

| env | An object of class | 'cplexPtr" | as returned by | openEnvCPLEX. | This is basically |
|-----|--------------------|------------|----------------|---------------|-------------------|
| | | | | | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getMethod which calls the CPLEX function CPXgetmethod.

Value

A single integer value specifying the solution algorithm.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants section "LP/QP solution algorithms".

getMIPrelGapCPLEX 137

| oetMTPre] | LGapCPLEX |
|-------------|------------|
| SC CLITLICI | LUADUI LLA |

Access Relative Objective Gap for a MIP Optimization

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetmiprelgap. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getMIPrelGapCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getMIPrelGap which calls the CPLEX function CPXgetmiprelgap.

Value

Relative Objective Gap if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
getObjValCPLEX, getBestObjValCPLEX
```

getMIPstartIndexCPLEX Search for the Index Number of the Specified MIP Start

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetmipstartindex. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getMIPstartIndexCPLEX(env, lp, iname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| iname | A MIP start name to search for. |

Details

Interface to the C function getMIPstartIndex which calls the CPLEX function CPXgetmipstartindex.

Value

Index number of the specified MIP start if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetmipstartname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getMIPstartNameCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of MIP starts to be returned. |
| end | An integer specifying the end of the range of MIP starts to be returned. |

Details

Interface to the C function getMIPstartName which calls the CPLEX function CPXgetmipstartname.

Value

Names of the MIP starts if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

140 getMIPstartsCPLEX

| getMIPstartsCPLEX Access a Range of MIP Starts of a CPLEX Problem Object |
|--|
|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetmipstarts. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getMIPstartsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of MIP starts to be returned. |
| end | An integer specifying the end of the range of MIP starts to be returned. |

Details

 $Interface \ to \ the \ C \ function \ get \texttt{MIPstarts} \ which \ calls \ the \ CPLEX \ function \ CPX get \texttt{mipstarts}.$

Value

If successful a list is returned:

| beg | Array specifying where each of the requested MIP starts begins in the arrays varindices and values. Consult the IBM ILOG CPLEX documentation for more detailed information. |
|-------------|--|
| varindices | Array containing the numeric indices of the columns corresponding to the variables which are assigned starting values. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| values | Array containing the values of the MIP starts. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| effortlevel | Array containing the effort level for each MIP start requested. Consult the IBM ILOG CPLEX documentation for more detailed information. |

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

getNumColsCPLEX 141

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

getNumColsCPLEX

Access the Number of Columns in the Constraint Matrix

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetnumcols. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getNumColsCPLEX(env, lp)
```

Arguments

| env | An object of class | "cplexPtr" as | returned by openEnv | CPLEX. This is basically |
|-----|--------------------|---------------|---------------------|--------------------------|
| | | | | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getNumCols which calls the CPLEX function CPXgetnumcols.

Value

If successful the number of variables is returned. If env or 1p do not exist, zero is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getNumMIPstartsCPLEX Access the Number of MIP Starts in the CPLEX Problem Object

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetnummipstarts. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getNumMIPstartsCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

Interface to the C function getNumMIPstarts which calls the CPLEX function CPXgetnummipstarts.

Value

If successful the number of MIP starts is returned. If env or 1p do not exist, zero is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getNumNnzCPLEX 143

| getNumNnzCPLEX | Access the Number of Nonzero Elements in the Constraint Matrix |
|----------------|--|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetnumnz. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getNumNnzCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

 $Interface \ to \ the \ C \ function \ getNumNnz \ which \ calls \ the \ CPLEX \ function \ CPXgetnumnz.$

Value

Zero if the problem object or environment does not exist, otherwise the number of nonzero elements.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

| + N OD CDI | ΓV |
|---------------|------------|
| getNumOPnzCPL | ΓX |

Return the Number of Nonzeros in the Q Matrix

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetnumqpnz. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getNumQPnzCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

Interface to the C function getNumQPnz which calls the CPLEX function CPXgetnumqpnz.

Value

If successful the number of nonzeros in the Q matrix is returned. If env or 1p do not exist, zero is returned.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getNumQuadCPLEX 145

| getNumQuadCPLEX | Return the Number of Variables That Have Quadratic Objective Coefficients |
|-----------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetnumquad. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getNumQuadCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

Interface to the C function getNumQuad which calls the CPLEX function CPXgetnumquad.

Value

If successful the number of variables that have quadratic objective coefficients is returned. If env or lp do not exist, zero is returned.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

| OPT NUMBOWS CPI | ΓV |
|-----------------|----|
| | |

Access the Number of Rows in the Constraint Matrix

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetnumcols. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getNumRowsCPLEX(env, lp)
```

Arguments

| env | An object of class | "cplexPtr" as | returned by openEnv | CPLEX. This is basically |
|-----|--------------------|---------------|---------------------|--------------------------|
| | | | | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getNumRows which calls the CPLEX function CPXgetnumrows.

Value

If successful the number of rows is returned. If env or 1p do not exist, zero is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getObjCPLEX 147

| getObjCPLEX | Access a Range of Objective Function Coefficients of a CPLEX Problem Object |
|-------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetobj. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getObjCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of objective function coefficients to be returned |
| end | An integer specifying the end of the range of objective function coefficients to be returned. |

Details

Interface to the C function get0bj which calls the CPLEX function CPXgetobj.

Value

Specified objective coefficients if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

148 getObjDirCPLEX

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetobjsen. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getObjDirCPLEX(env, lp)
```

Arguments

| env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basicall |
|---|
|---|

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getObjDir which calls the CPLEX function CPXgetobjsen.

Value

Zero if the problem object or environment does not exist, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getObjNameCPLEX 149

| OPT | へんすい | lamai | CDI | -v |
|-----|------|-------|-----|----|
| | | | | |

Access the Name of the Objective Row of a CPLEX Problem Object

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetobjname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getObjNameCPLEX(env, lp)
```

Arguments

| env | An object of class | "cplexPtr" as returned b | y openEnvCPLEX. This is basically |
|-----|--------------------|--------------------------|-----------------------------------|
| | | | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getObjName which calls the CPLEX function CPXgetobjname.

Value

Name of the objective row if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

150 getObjOffsetCPLEX

| get | ObjOffsetCPLEX | Objective Offset Between the Original Problem and the Presolved Problem. |
|-----|----------------|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetobjoffset. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getObjOffsetCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

 $Interface \ to \ the \ C \ function \ {\tt get0bj0ffset} \ which \ calls \ the \ CPLEX \ function \ {\tt CPXgetobjoffset}.$

Value

Objective offset value if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getObjValCPLEX 151

| getObjValCPLEX | Access Solution Objective Value |
|----------------|---------------------------------|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetobjval. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getObjValCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

Interface to the C function getObjVal which calls the CPLEX function CPXgetobjval.

Value

Objective value if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

152 getOrderCPLEX

| getOrderCPLEX | Access MIP Priority Order Information |
|---------------|---------------------------------------|
|---------------|---------------------------------------|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetorder. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getOrderCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getOrder which calls the CPLEX function CPXgetorder.

Value

If successful a list is returned:

indices indices of the variables in the order

priority priority values

direction preferred branching directions

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
cplexConstants
```

getParmNameCPLEX 153

getParmNameCPLEX

Obtain the Name of a CPLEX Parameter, Given the Symbolic Constant

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetparamname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getParmNameCPLEX(env, wparm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

wparm Constant or reference number of the desired parameter.

Details

Interface to the C function getParmName which calls the CPLEX function CPXgetparamname.

Value

A single character value.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

154 getParmNumCPLEX

getParmNumCPLEX

Obtain the Reference Number of a CPLEX Parameter

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetparamnum. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getParmNumCPLEX(env, nparm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

nparm A single character value containing the name of the parameter.

Details

Interface to the C function getParmNum which calls the CPLEX function CPXgetparamnum.

Value

A single integer value.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getParmTypeCPLEX 155

| getParmTypeCPLEX O | Obtain the Type of a CPLEX Parameter |
|--------------------|--------------------------------------|
|--------------------|--------------------------------------|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetparamtype. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getParmTypeCPLEX(env, parm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

Details

Interface to the C function getParmType which calls the CPLEX function CPXgetparamtype.

Value

A single integer value if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

156 getPhase1CntCPLEX

getParmValCPLEX

Values and Names of Parameters Having Non-Default Values

Description

The function getParmValCPLEX retrieves the names and actual values of all IBM ILOG CPLEX parameters, which do not have their default values.

Usage

```
getParmValCPLEX(env)
```

Arguments

env

An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment.

Value

Either a list containing all non-default parameters and their values or NULL.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants and getChgParmCPLEX

getPhase1CntCPLEX

Access Number of Phase I Iterations

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetphase1cnt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getPhase1CntCPLEX(env, lp)
```

getPiCPLEX 157

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

Interface to the C function getPhase1Cnt which calls the CPLEX function CPXgetphase1cnt.

Value

Zero if no solution exists, otherwise Phase I iteration count.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| getPiCPLEX | Access Dual Values for a Range of Constraints | |
|------------|---|--|
| getP1CPLEX | Access Dual values for a Range of Constraints | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetpi. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getPiCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of dual values to be returned. |
| end | An integer specifying the end of the range of dual values to be returned. |

158 getPreStatCPLEX

Details

Interface to the C function getPi which calls the CPLEX function CPXgetpi.

Value

Values of the dual variables if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

getPreStatCPLEX

Access Presolve Status Information for Columns and Rows

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetprestat. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getPreStatCPLEX(env, lp)
```

Arguments

| env | An object of class | "cplexPtr" as | returned by or | penEnvCPLEX. | This is basically |
|-----|--------------------|---------------|----------------|--------------|-------------------|
| | | | | | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getPreStat which calls the CPLEX function CPXgetprestat.

getProbNameCPLEX 159

Value

If successful a list is returned:

prestat status of the presolved problem
pcstat presolve status values of the columns
prstat presolve status values of the rows

ocstat presolve status values of the columns of the presolved problem orstat presolve status values of the rows of the presolved problem

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants

getProbNameCPLEX Access Problem Name

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetprobname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getProbNameCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getProbName which calls the CPLEX function CPXgetprobname.

getProbTypeCPLEX

Value

Name of the problem if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

getProbTypeCPLEX

Access Problem Type

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetprobtype. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getProbTypeCPLEX(env, lp)
```

Arguments

| env An object of class "cplexPtr" as returned by | openEnvCPLEX. This is basically |
|--|---------------------------------|
|--|---------------------------------|

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getProbType which calls the CPLEX function CPXgetprobtype.

Value

A single integer value specifying the problem type.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

getProbVarCPLEX 161

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

 ${\tt chgProbTypeCPLEX}, {\tt cplexConstants} \ section \ ``Problem \ Types".$

| getProbVarCPLEX | Access the Solution Values for a Range of Problem Variables | |
|-----------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetx. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getProbVarCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of variable values to be returned. |
| end | An integer specifying the end of the range of variable values to be returned. |

Details

Interface to the C function getProbVar which calls the CPLEX function CPXgetx.

Value

Values of the primal variables if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

162 getQConstrCPLEX

| getQConstrCPLEX | Access a Specified Quadratic Constraint on the Variables of a CPLEX Problem Object. |
|-----------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetqconstr. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getQConstrCPLEX(env, lp, which)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| which | An integer specifying which quadratic constraint to return. |

Details

Interface to the C function getQConstr which calls the CPLEX function CPXgetqconstr.

Value

If successful a list is returned:

| rhs | Righthand-side value of the quadratic constraint. Consult the IBM ILOG CPLEX documentation for more detailed information. |
|---------|---|
| sense | Character specifying the sense of the constraint. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| linind | Variable indices of the entries of linval. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| linval | Linear coefficients of the specified constraint. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| quadrow | Variable indices of the entries of quadval. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| quadcol | Variable indices of the entries of quadval. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| quadval | Quadratic coefficients of the specified constraint. Consult the IBM ILOG CPLEX documentation for more detailed information. |

otherwise an instance of class "cplexError".

getQPcoefCPLEX 163

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

| getQPcoefCPLEX | Access the Quadratic Coefficient in the Matrix Q | |
|----------------|--|--|
|----------------|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetqpcoef. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getQPcoefCPLEX(env, lp, i, j)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| i | The row number in Q. |
| j | The row column in Q. |

Details

Interface to the C function getQPcoef which calls the CPLEX function CPXgetqpcoef.

Value

Specified quadratic coefficient in the matrix Q if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

164 getQuadCPLEX

| getQuadCPLEX | Access a Range of Columns of the Matrix Q of a Model With a Quadratic Objective Function |
|--------------|--|
|--------------|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetquad. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getQuadCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of columns to be returned. |
| end | An integer specifying the end of the range of columns to be returned. |

Details

Interface to the C function getQuad which calls the CPLEX function CPXgetquad.

Value

If successful a list is returned:

| qmatbeg | Array that specifies the nonzero elements of the columns. ILOG CPLEX documentation for more detailed information. | |
|---------|---|--|
| qmatind | Array that specifies the nonzero elements of the columns. ILOG CPLEX documentation for more detailed information. | |
| qmatval | Array that specifies the nonzero elements of the columns. ILOG CPLEX documentation for more detailed information. | |

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getRedLpCPLEX 165

| getRedLpCPLEX | Get a Pointer for the Presolved Problem | |
|---------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetredlp. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getRedLpCPLEX(env, lp, ptrtype = "cplex_prob")
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|---------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ptrtype | A name for the pointer object. |

Details

Interface to the C function getRedLp which calls the CPLEX function CPXgetredlp.

Value

Pointer for the presolved problem if successful (an instance of class "cplexPtr"), otherwise an instance of class "cplexError" or NULL.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

166 getRhsCPLEX

| getRhsCPLEX | Access Righthand Side Coefficients for a Range of Constraints | |
|-------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetrhs. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getRhsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of righthand side terms to be returned. |
| end | An integer specifying the end of the range of righthand side terms to be returned. |

Details

Interface to the C function getRhs which calls the CPLEX function CPXgetrhs.

Value

Specified righthand side coefficients if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getRngValCPLEX 167

| getRngValCPLEX | Accesses Righthand Side Coefficients Range Coefficients | |
|----------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetrngval. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getRngValCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the set of rows for which RHS range coefficients are returned. |
| end | An integer specifying the end of the set of rows for which RHS range coefficients are returned. |

Details

Interface to the C function getRngVal which calls the CPLEX function CPXgetrngval.

Value

Specified RHS range coefficients if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

168 getRowIndexCPLEX

| getRowIndexCPLEX | Search for the Index Number of a Specified Row | |
|------------------|--|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetrowindex. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getRowIndexCPLEX(env, lp, rname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

rname

Interface to the C function getRowIndex which calls the CPLEX function CPXgetrowindex.

Value

Specified row index if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

A row name to search for.

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getRowInfeasCPLEX 169

| getRowInfeasCPLEX Compute Infeasibility of a Given Solution for a Range of Linear straints | · Con- |
|--|--------|
|--|--------|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetrowinfeas. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getRowInfeasCPLEX(env, lp, begin, end, sol = NULL)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of linear constraints whose infeasibility is to be returned. |
| end | An integer specifying the beginning of the range of linear constraints whose infeasibility is to be returned. |
| sol | The solution whose infeasibility is to be computed. |

Details

Interface to the C function getRowInfeas which calls the CPLEX function CPXgetrowinfeas.

Value

Infeasibility values if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetrowname. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getRowNameCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of row names to be returned. |
| end | An integer specifying the end of the range of row names to be returned. |

Details

 $Interface \ to \ the \ C \ function \ {\tt getRowName} \ which \ calls \ the \ CPLEX \ function \ {\tt CPXgetrowname}.$

Value

Specified row names if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getRowsCPLEX 171

| getRowsCPLEX Accesses a Range of Rows of the Constraint Matrix |
|--|
|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetrows. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getRowsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of rows to be returned. |
| end | An integer specifying the end of the range of rows to be returned. |

Details

Interface to the C function getRows which calls the CPLEX function CPXgetrows.

Value

If successful a list is returned:

| matbeg | Array that specifies the nonzero elements of the rows. Consult the IBM ILOG CPLEX documentation for more detailed information. |
|--------|--|
| matind | Array that specifies the nonzero elements of the rows. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| matval | Array that specifies the nonzero elements of the rows. Consult the IBM ILOG CPLEX documentation for more detailed information. |

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

172 getSenseCPLEX

| _ | ccess the Sense for a Range of Constraints in a CPLEX Problem Object. |
|---|---|
|---|---|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetsense. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getSenseCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of constraint senses to be returned. |
| end | An integer specifying the end of the range of constraint senses to be returned. |

Details

Interface to the C function getSense which calls the CPLEX function CPXgetsense.

Value

Specified constraint senses if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getSiftItCntCPLEX 173

| getSi | £+. | T+C | n+1 | CDI | EV |
|-------|-----|------|-----|-----|----|
| gersi | ŤΤ | LT(. | nti | LPI | ΗX |

Access Total Number of Sifting Iterations

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetsiftitcnt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getSiftItCntCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically |
|-----|---|
| | a pointer to an IBM ILOG CPLEX environment. |
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically |

An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getSiftItCnt which calls the CPLEX function CPXgetsiftitcnt.

Value

Zero if no solution exists, otherwise nonzero the total iteration count.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getSiftPase1CntCPLEX Access Number of Phase I Sifting Iterations

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetsiftphase1cnt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getSiftPase1CntCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

 $Interface \ to \ the \ C \ function \ getSiftPase1Cnt \ which \ calls \ the \ CPLEX \ function \ CPX getsiftphase1cnt.$

Value

Zero if no solution exists, otherwise nonzero the Phase I iteration count.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getSlackCPLEX 175

| getSlackCPLEX | Accesses Slack Values for a Range of Linear Constraints | |
|---------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetslack. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getSlackCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | An integer specifying the beginning of the range of slack values to be returned. |
| end | An integer specifying the end of the range of slack values to be returned. |

Details

Interface to the C function getSlack which calls the CPLEX function CPXgetslack.

Value

Specified slack or surplus variables if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getStatCPLEX

| getStatCPLEX Access the Solution Status of the Problem | getStatCPLEX | Access the Solution Status of the Problem | |
|--|--------------|---|--|
|--|--------------|---|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetstat. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getStatCPLEX(env, lp)
```

Arguments

| env | An object of class ' | 'cnlevPtr" as ref | urned by openEnvCPLI | Y This is basically |
|-----|----------------------|-------------------|----------------------|----------------------|
| env | All object of class | CDIEXE LE as lei | umed by obenenycel. | A. THIS IS DASICALLY |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getStat which calls the CPLEX function CPXgetstat.

Value

A single integer value giving the solution status.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants section "Values returned for stat by solution".

getStatStrCPLEX 177

getStatStrCPLEX

Return an Status Message String Corresponding to an Status Code

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetstatstring. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getStatStrCPLEX(env, stat)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

stat The status code to be translated.

Details

Interface to the C function getStatStr which calls the CPLEX function CPXgetstatstring.

Value

A single character value containing the status message string.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
getErrorStrCPLEX
```

178 getStrParmCPLEX

| getStrParmCPLEX Obtain the Current Value of a CPLEX String Parameter | |
|--|--|
|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetstrparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getStrParmCPLEX(env, parm)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

Details

Interface to the C function getStrParm which calls the CPLEX function CPXgetstrparam.

Value

A single character value.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getSubMethodCPLEX 179

| getSubMethodCPLEX | Ac |
|-------------------|----|
| getSubmethoaCPLEX | AC |

Accesses Solution Method of the Last Subproblem Optimization

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetsubmethod. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getSubMethodCPLEX(env, lp)
```

Arguments

| env | An object of class " | 'cplexPtr" | as returned by | openEnvCPLEX. | This is basically |
|-----|----------------------|------------|----------------|---------------|-------------------|
|-----|----------------------|------------|----------------|---------------|-------------------|

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getSubMethod which calls the CPLEX function CPXgetsubmethod.

Value

Integer value specifying the solution method.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

180 getSubStatCPLEX

| ~~+C. | ıhStatı | CDLEV |
|-------|---------|-------|
| | | |

Access Solution Status of the Last Subproblem Optimization

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetsubstat. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getSubStatCPLEX(env, lp)
```

Arguments

| | env | An object of class ' | "cplexPtr" as returned | d by openEnvCPLEX. This is basically | Į |
|--|-----|----------------------|------------------------|--------------------------------------|---|
|--|-----|----------------------|------------------------|--------------------------------------|---|

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function getSubStat which calls the CPLEX function CPXgetsubstat.

Value

Zero if no solution exists, nonzero otherwise.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

getTimeCPLEX 181

getTimeCPLEX

Get a Time Stamp

Description

Low level interface function to the IBM ILOG CPLEX function CPXfclose. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getTimeCPLEX(env)
```

Arguments

env

An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment.

Details

Interface to the C function getTime which calls the CPLEX function CPXgettime.

Value

If successful a single numeric value, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

fileputCPLEX, openFileCPLEX

getUppBndsIdsCPLEX

Retrieve Upper Bounds on Variables

Description

The function retrieves the upper bounds on specified variables.

Usage

```
getUppBndsIdsCPLEX(env, lp, ind)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ind | Column indices of variables (remember: first index is 0). |

Value

A numeric vector containing the upper bounds on the specified variables. If not successfull an instance of class "cplexError" is returned.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getUpperBndsCPLEX

|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXgetub. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getUpperBndsCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | Beginning of the range of upper bounds to be returned. |
| end | End of the range of upper bounds to be returned. |

Details

Interface to the C function getUpperBnds which calls the CPLEX function CPXgetub.

Value

A numeric vector containing the lower bounds on the specified variables. If not successfull an instance of class "cplexError" is returned.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

184 getVersionCPLEX

getVersionCPLEX

Get Version Number of the CPLEX Library.

Description

Low level interface function to the IBM ILOG CPLEX function CPXversion. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
getVersionCPLEX(env)
```

Arguments

env

An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment.

Details

Interface to the C function getVersion which calls the CPLEX function getVersionCPLEX.

Value

Single character string specifying the version of the cplex library or NULL if the environment does not exist.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

hybbaroptCPLEX 185

| hybbaroptCPLEX | Solve the Specified Problem by the CPLEX Barrier Optimizer | |
|----------------|--|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXhybbaropt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
hybbaroptCPLEX(env, 1p, method)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically |
|-----|--|
| | a pointer to an IBM ILOG CPLEX environment. |

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

method A single integer value giving the crossover method to be implemented.

Details

Interface to the C function hybbaropt which calls the CPLEX function CPXhybbaropt.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

 $solnInfoCPLEX, getStatCPLEX, solutionCPLEX, cplexConstants\ section\ ``LP/QP\ solution\ algorithms".$

186 hybnetoptCPLEX

| hybnetoptCPLEX | Use CPLEX Network Optimizer |
|----------------|-----------------------------|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXhybnetopt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
hybnetoptCPLEX(env, lp, method)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| method | A single integer value giving the type of simplex method to follow the network |

Details

Interface to the C function hybnetopt which calls the CPLEX function CPXhybnetopt.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

optimization.

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

 $solnInfoCPLEX, getStatCPLEX, solutionCPLEX, cplexConstants\ section\ ``LP/QP\ solution\ algorithms''.$

initProbCPLEX 187

| initProbCPLEX Create a CPLEX Problem Object in the CPLEX Environment | initProbCPLEX | Create a CPLEX Problem Object in the CPLEX Environment | |
|--|---------------|--|--|
|--|---------------|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXcreateprob. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
initProbCPLEX(env, pname = "CPLEX_PROB", ptrtype = "cplex_prob")
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

pname A single character string containing the name of the problem object.

ptrtype A name for the pointer object.

Details

Interface to the C function CPXcreate which calls the CPLEX function CPXcreateprob.

Value

If successful, a pointer to the CPLEX problem object is returnd (an instance of class "cplexPtr"), otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

delProbCPLEX

188 lpoptCPLEX

| lpoptCPLEX | Find a Solution to a Problem Using One of the CPLEX Linear Optimizers |
|------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXlpopt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
lpoptCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically |
|-----|---|
| | a pointer to an IBM ILOG CPLEX environment. |
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically |

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function lpopt which calls the CPLEX function CPXlpopt.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
solnInfoCPLEX, getStatCPLEX, solutionCPLEX
```

mipoptCPLEX 189

| mipoptCPLEX | Find a Solution to a Mixed Integer Program |
|-------------|--|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXmipopt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
mipoptCPLEX(env, lp)
```

Arguments

| env | An object of class ' | 'cplexPtr" | as returned by o | penEnvCPLEX. | This is basically |
|-----|----------------------|------------|------------------|--------------|-------------------|
| | | | | | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function mipopt which calls the CPLEX function CPXmipopt.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
solnInfoCPLEX, getStatCPLEX, solutionCPLEX
```

190 newColsCPLEX

| newColsCPLEX Add Empty Columns to a Specified CPLEX Problem Object | |
|--|--|
| newColsCPLEX Add Empty Columns to a Specified CPLEX Problem Object | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXnewcols. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ncols | Number of variables to add. |
| obj | Objective function coefficients. |
| 1b | Lower bounds on the new variables. |
| ub | Upper bounds on the new variables. |
| xctype | Type of the new variables. |
| cnames | Names of the new variables. |

Details

Interface to the C function newCols which calls the CPLEX function CPXnewcols.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

newRowsCPLEX 191

See Also

cplexConstants section "Variable types for ctype array".

newRowsCPLEX Add Empty Constraints to a Specified CPLEX Problem Object

Description

Low level interface function to the IBM ILOG CPLEX function CPXnewrows. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nrows | Number of new rows. |
| rhs | Right hand side term for each new constraint. |
| sense | Sense of each new constraint (see IBM ILOG CPLEX documentation for possible values). |
| rngval | Range values for each new constraint. |
| rnames | Names for the new rows. |

Details

Interface to the C function newRows which calls the CPLEX function CPXnewrows.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

192 objSaCPLEX

| objSaCPLEX | Access Upper and Lower Sensitivity Ranges for Objective Function Coefficients |
|------------|---|
|------------|---|

Description

Low level interface function to the IBM ILOG CPLEX function CPXobjsa. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
objSaCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | Beginning of the range of ranges to be returned. |
| end | End of the range of ranges to be returned. |

Details

Interface to the C function objSa which calls the CPLEX function CPXobjsa.

Value

If successful a list is returned:

lower range values
upper upper range values
otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

openEnvCPLEX 193

openEnvCPLEX

Initialize a CPLEX Environment

Description

Low level interface function to the IBM ILOG CPLEX function CPXopenCPLEX. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
openEnvCPLEX(ptrtype = "cplex_env")
```

Arguments

ptrtype

A name for the pointer object.

Details

Interface to the C function openEnv which calls the CPLEX function CPXopenCPLEX.

Value

If successful, a pointer to the CPLEX environment is returnd (an instance of class "cplexPtr"), otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

closeEnvCPLEX

194 openFileCPLEX

| openFileCPLEX ${\it O}$ | pen a File |
|-------------------------|------------|
|-------------------------|------------|

Description

Low level interface function to the IBM ILOG CPLEX function CPXfopen. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
openFileCPLEX(fname, ftype = "w", ptrtype = "cplex_file")
```

Arguments

fname Character string giving the file name to be opened.

ftype Character string according to the syntax of the standard C function fopen.

ptrtype A name for the pointer object.

Details

Interface to the C function openFile which calls the CPLEX function CPXfopen.

Value

A pointer to the log file (an instance of class "cplexPtr") or NULL.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
closeFileCPLEX, fileputCPLEX
```

openProbCPLEX 195

| openProbCPLEX | Create new CPLEX Environment And New CPLEX Problem Object |
|---------------|---|
| | |

Description

The function openProbCPLEX creates a new CPLEX environment and a new CPLEX problem object.

Usage

Arguments

pname A single character string containing the name of the problem object.

ptrtypeENV A name for the IBM ILOG CPLEX environment pointer object.

ptrtypePROB A name for the IBM ILOG CPLEX problem pointer object.

Details

Interface to the C functions openEnv and initProb calling CPLEX functions CPXopenCPLEX and CPXcreateprob.

Value

env A pointer to the CPLEX environment as returned by openEnvCPLEX.

1p A pointer to the CPLEX problem object as returned by initProbCPLEX.

If openEnvCPLEX() failes, env will be of class "cplexError" and lp will be NULL. Each list element is an object of class "cplexPtr".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
closeProbCPLEX, openEnvCPLEX, initProbCPLEX
```

196 ordWriteCPLEX

| ordWriteCPLEX | Write Priority Order to ORD File |
|---------------|----------------------------------|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXordwrite. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
ordWriteCPLEX(env, lp, fname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

fname Filename.

Details

Interface to the C function ordWrite which calls the CPLEX function CPXordwrite.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

preslvWriteCPLEX 197

| preslvWriteCPLEX | Write a Presolved Version of the Problem to File |
|------------------|--|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXpreslvwrite. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
preslvWriteCPLEX(env, lp, fname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| fname | Single character value giving the file name to write to. |

Details

Interface to the C function preslvWrite which calls the CPLEX function CPXpreslvwrite.

Value

If successful a dingle numeric value containing the objective value difference between the original problem and the presolved problem, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

readCopyProbCPLEX

198 presolveCPLEX

|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXpresolve. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
presolveCPLEX(env, lp, method)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|--------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| method | A single integer value specifying the optimization algorithm to be used to solve the problem after the presolve is completed. |

Details

Interface to the C function presolve which calls the CPLEX function CPXpresolve.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants section "LP/QP solution algorithms".

primoptCPLEX 199

| primoptCPLEX | Find a Solution to a Problem Using the Primal Simplex Method | |
|--------------|--|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXprimopt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
primoptCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function primopt which calls the CPLEX function CPXprimopt.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
solnInfoCPLEX, getStatCPLEX, solutionCPLEX
```

200 qpoptCPLEX

 $\verb"printTerminateCPLEX"$

Print Termination Signal

Description

The function chgTerminateCPLEX prints termination signal.

Usage

```
printTerminateCPLEX(env)
```

Arguments

env

An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

setTerminateCPLEX, delTerminateCPLEX, chgTerminateCPLEX

qpoptCPLEX

Find a Solution to a Continuous Quadratic Program

Description

Low level interface function to the IBM ILOG CPLEX function CPXqpopt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
qpoptCPLEX(env, lp)
```

Arguments

| | env | An object of class | "cplexPtr" | as returned by o | penEnvCPLEX. | This is basically |
|--|-----|--------------------|------------|------------------|--------------|-------------------|
|--|-----|--------------------|------------|------------------|--------------|-------------------|

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function qpopt which calls the CPLEX function CPXqpopt.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
{\tt solnInfoCPLEX}, {\tt getStatCPLEX}, {\tt solutionCPLEX}
```

| readCopyBaseCPLEX | Read Basis From a BAS File and Copy it Into a CPLEX Problem Ob- |
|-------------------|---|
| | ject |

Description

Low level interface function to the IBM ILOG CPLEX function CPXreadcopybase. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
readCopyBaseCPLEX(env, lp, fname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| fname | Single character value giving the filname to read from. |

Details

Interface to the C function readCopyBase which calls the CPLEX function CPXreadcopybase.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

readCopyMIPstartsCPLEX

Read a File in the Format MST

Description

Low level interface function to the IBM ILOG CPLEX function CPXreadcopymipstarts. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
readCopyMIPstartsCPLEX(env, lp, fname)
```

Arguments

| env | An object of class | "cplexPtr' | ' as returned by | openEnvCPLEX. | This is basically |
|-----|--------------------|------------|------------------|---------------|-------------------|
|-----|--------------------|------------|------------------|---------------|-------------------|

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

fname Name of the file to read from.s

Details

Interface to the C function readCopyMIPstarts which calls the CPLEX function CPXreadcopymipstarts.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

readCopyOrderCPLEX

Read ORD File

Description

Low level interface function to the IBM ILOG CPLEX function CPXreadcopyorder. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
readCopyOrderCPLEX(env, lp, fname)
```

Arguments

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

fname Single character value giving the filname to read from.

Details

Interface to the C function readCopyOrder which calls the CPLEX function CPXreadcopyorder.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

readCopyParmCPLEX

Reads Parameter Names And Settings From a File

Description

Low level interface function to the IBM ILOG CPLEX function CPXreadcopyparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
readCopyParmCPLEX(env, fname)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

fname Filename.

Details

Interface to the C function readCopyParm which calls the CPLEX function CPXreadcopyparam.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

| readCopyProbCPL | -v |
|-------------------|------------|
| readi onveroni ei | ⊢ x |
| | |

Read an MPS, LP, or SAV File Into an Existing CPLEX Problem Object

Description

Low level interface function to the IBM ILOG CPLEX function CPXreadcopyprob. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
readCopyProbCPLEX(env, lp, fname, ftype = NULL)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| fname | Single character value giving the filname to read from. |
| ftype | Single character value giving the type of the file to read from. |

Details

Interface to the C function readCopyProb which calls the CPLEX function CPXreadcopyprob.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

206 readCopySolCPLEX

| readCopySolCPLEX | Reads a Solution From a SOL Format File |
|---------------------|--|
| r caacopy core. EEA | nedas a solution i rom a soll formar i tie |

Description

Low level interface function to the IBM ILOG CPLEX function CPXreadcopysol. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
readCopySolCPLEX(env, lp, fname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| fname | Single character value giving the filname to read from. |

Details

Interface to the C function readCopySol which calls the CPLEX function CPXreadcopysol.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

refineConflictCPLEX 207

| 0 | |
|---------------------|--|
| refineConflictCPLEX | Identify a Minimal Conflict for the Infeasibility of the Linear Con- |
| | straints and the Variable Bounds |

Description

Low level interface function to the IBM ILOG CPLEX function CPXrefineconflict. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
refineConflictCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically |
|-----|---|
| | a pointer to an IBM ILOG CPLEX environment. |
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically |

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function refineConflict which calls the CPLEX function CPXrefineconflict.

Value

If successful a list is returned:

confnumrows number of linear constraints in the conflict confnumcols number of variable bounds in the conflict otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
getConflictCPLEX
```

208 refineConflictExtCPLEX

refineConflictExtCPLEX

Identify a Minimal Conflict

Description

Low level interface function to the IBM ILOG CPLEX function CPXrefineconflictext. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|---------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| grpcnt | The number of constraint groups to be considered. |
| concnt | Length of arrays grpind and grptype. |
| grppref | Preferences for the groups. |
| grpbeg | The constraint indices. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| grpind | The constraint indices. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| grptype | The constraint indices. Consult the IBM ILOG CPLEX documentation for more detailed information. |

Details

 $Interface \ to \ the \ C \ function \ refine Conflict Ext \ which \ calls \ the \ CPLEX \ function \ CPX refine conflict ext.$

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

refineMIPstartConflictCPLEX

Refine a Conflict in Order to Determine Why a Given MIP Start is Not Feasible

Description

Low level interface function to the IBM ILOG CPLEX function CPXrefinemipstartconflict. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
refineMIPstartConflictCPLEX(env, lp, mipstartindex)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

mipstartindex The index of the MIP start.

Details

Interface to the C function refineMIPstartConflict which calls the CPLEX function CPXrefinemipstartconflict.

Value

If successful a list is returned:

confnumrows number of linear constraints in the conflict confnumcols number of variable bounds in the conflict

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getConflictCPLEX

refine MIP start Conflict Ext CPLE X

Identify a Minimal Conflict

Description

Low level interface function to the IBM ILOG CPLEX function CPXrefinemipstartconflictext. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|---------------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| mipstartindex | The index of the MIP start. |
| grpcnt | The number of constraint groups to be considered. |
| concnt | Length of arrays grpind and grptype. |
| grppref | Preferences for the groups. |
| grpbeg | The constraint indices. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| grpind | The constraint indices. Consult the IBM ILOG CPLEX documentation for more detailed information. |
| grptype | The constraint indices. Consult the IBM ILOG CPLEX documentation for more detailed information. |

Details

 $Interface \ to \ the \ C \ function \ refine \texttt{MIPstartConflictExt} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \ CPLEX \ function \ CPX refine \texttt{mipstartconflictext} \ which \ calls \ the \$

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

return_codeCPLEX 211

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

return_codeCPLEX

Translates a IBM ILOG CPLEX Return Code into a Human Readable String

Description

Translates a IBM ILOG CPLEX return code into a human readable string.

Usage

return_codeCPLEX(code)

Arguments

code

Return (error) code from IBM ILOG CPLEX.

Value

An error message string corresponding to an return (error) code.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

212 rhsSaCPLEX

| rhsSaCPLEX | Access Upper and Lower Sensitivity Ranges for Righthand Side Values of a Range of Constraints |
|------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXrhssa. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
rhsSaCPLEX(env, lp, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| begin | Beginning of the range of ranges to be returned. |
| end | End of the range of ranges to be returned. |

Details

Interface to the C function rhsSa which calls the CPLEX function CPXrhssa.

Value

If successful a list is returned:

lower righthand side lower range values upper righthand side upper range values otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

setDblParmCPLEX 213

| setDblParmCPLEX | Set the Value of a CPLEX Parameter of Type Double | |
|-----------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXsetdblparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
setDblParmCPLEX(env, parm, value)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

value The new value of the parameter.

Details

Interface to the C function setDblParm which calls the CPLEX function CPXsetdblparam.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

214 setDefaultParmCPLEX

setDefaultParmCPLEX

Reset All CPLEX Parameters And Settings to Default Values

Description

Low level interface function to the IBM ILOG CPLEX function CPXsetdefaults. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
setDefaultParmCPLEX(env)
```

Arguments

env

An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment.

Details

Interface to the C function setDefaultParm which calls the CPLEX function CPXsetdefaults.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

setIntParmCPLEX 215

| setIntParmCPLEX | Set the Value of a CPLEX Parameter of Type CPXINT | |
|-----------------|---|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXsetintparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
setIntParmCPLEX(env, parm, value)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

value The new value of the parameter (integer value).

Details

Interface to the C function setIntParm which calls the CPLEX function CPXsetintparam.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

216 setLogFileCPLEX

| | _ | | |
|------|-----|--------|----|
| setl | ∩g⊦ | ileCPI | ŀΧ |

Modifies the log file to which Messages are Written

Description

Low level interface function to the IBM ILOG CPLEX function CPXsetlogfile. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
setLogFileCPLEX(env, cpfile = NULL)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

cpfile A pointer to a file as returned by openFileCPLEX.

Details

Interface to the C function getLogFile which calls the CPLEX function CPXgetlogfile.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
getLogFileCPLEX
```

setLongParmCPLEX 217

| setLongParmCPLEX Set the Value of a Parameter of Type CPXLONG | setLongParmCPLEX | Set the Value of a Parameter of Type CPXLONG | |
|---|------------------|--|--|
|---|------------------|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXsetlongparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
setLongParmCPLEX(env, parm, value)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

value New value for the parameter.

Details

Interface to the C function setLongParm which calls the CPLEX function CPXsetlongparam.

Value

Zero if successful, otherwise nonzero.

Note

In order to transfer a 64 bit integer value to CPXsetlongparam, datatype numeric is used. Parameter value is a numeric value.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
setIntParmCPLEX, cplexConstants
```

218 setObjDirCPLEX

| setObjDirCPLEX | Change the Sense of the Optimization for a Problem |
|----------------|--|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXchgobjsen. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
setObjDirCPLEX(env, lp, lpdir)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| lpdir | A single integer value specifying the sense of the problem. |

Details

Interface to the C function setObjDir which calls the CPLEX function CPXchgobjsen.

Value

NULL

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants section "Generic constants".

setStrParmCPLEX 219

| SetStrparmcplex Set the value of a CPLEX String Parameter | setStrParmCPLEX | Set the Value of a CPLEX String Parameter |
|---|-----------------|---|
|---|-----------------|---|

Description

Low level interface function to the IBM ILOG CPLEX function CPXsetstrparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
setStrParmCPLEX(env, parm, value)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

parm Constant or reference number of the desired parameter.

value The new value of the parameter (character value).

Details

Interface to the C function setStrParm which calls the CPLEX function CPXsetstrparam.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants

220 setTerminateCPLEX

setTerminateCPLEX Release Termination Signal

Description

Low level interface function to the IBM ILOG CPLEX function CPXsetterminate with argument terminate_p set to NULL. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
setTerminateCPLEX(env, ptrtype = "cplex_term")
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

ptrtype A name for the pointer object.

Details

Interface to the C function delTerminate which calls the CPLEX function CPXsetterminate with argument terminate_p set to NULL.

Value

If successful, a pointer to a termination signal is returned, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

delTerminateCPLEX, printTerminateCPLEX, chgTerminateCPLEX

siftoptCPLEX 221

| siftoptCPLEX Solve a Reduced Model |
|------------------------------------|
|------------------------------------|

Description

Low level interface function to the IBM ILOG CPLEX function CPXsiftopt. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
siftoptCPLEX(env, lp)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Details

Interface to the C function siftopt which calls the CPLEX function CPXsiftopt.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

222 solnInfoCPLEX

| solnInfoCPLEX | Access Solution Information | |
|---------------|-----------------------------|--|
| | | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXsolninfo. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
solnInfoCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function solnInfo which calls the CPLEX function CPXsolninfo.

Value

If successful a list is returned:

method Integer value specifying the method to produce the current solution.

type Integer value specifying the type of current solution.

primal_feasible

Integer value specifying if the current solution is known to be primal feasible.

dual_feasible Integer value specifying if the current solution is known to be dual feasible.

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

```
cplexConstants, solutionCPLEX
```

solutionCPLEX 223

| solutionCPLEX Access Solution Values Produced by Optimization Routines | |
|--|--|
|--|--|

Description

Low level interface function to the IBM ILOG CPLEX function CPXsolution. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
solutionCPLEX(env, lp)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function solution which calls the CPLEX function CPXsolution.

Value

If successful a list is returned:

lpstat result of the optimization objective function value

x values of the variables for the problem

values of the dual variables

slack values of the slack or surplus variables

dj values of the reduced costs

otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

224 solWriteCPLEX

See Also

cplexConstants, solnInfoCPLEX

| solWriteCPLEX Write a Solution File |
|-------------------------------------|
| CPLEX Write a Solution File |

Description

Low level interface function to the IBM ILOG CPLEX function CPXsolwrite. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
solWriteCPLEX(env, lp, fname)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-----|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |

Single character value giving the filname to write to.

Details

fname

Interface to the C function solWrite which calls the CPLEX function CPXsolwrite.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

getProbTypeCPLEX, cplexConstants section "Problem Types".

status_codeCPLEX 225

| status_codeCPLEX | Translates an IBM ILOG CPLEX Status Value into a Human Readable String |
|------------------|---|
|------------------|---|

Description

Translates a IBM ILOG CPLEX status code into a human readable string.

Usage

```
status_codeCPLEX(env, code)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

code Status code from IBM ILOG CPLEX as returned by getStatCPLEX.

Value

A character string orresponding to the value of an IBM ILOG CPLEX status code as returned by getStatCPLEX.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants, getStatStrCPLEX

226 tightenBndsCPLEX

| tightenBndsCPLEX | Change the Lower or Upper Bounds on a Set of Variables of a Problem |
|------------------|---|
| | |

Description

Low level interface function to the IBM ILOG CPLEX function CPXtightenbds. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
tightenBndsCPLEX(env, lp, ncols, ind, lu, bd)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| ncols | Number of bounds to be changed. |
| ind | Indices of bounds to be changed. |
| lu | A character vector, specifying whether an entry in bd is a upper or a lower bound on variable ind[j]. |
| bd | Values of the lower or upper bounds of the variables present in ind. |

Details

Interface to the C function tightenBnds which calls the CPLEX function CPXtightenbds.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

chgBndsCPLEX

tuneParmCPLEX 227

| tuneParmCPLEX | Tune Parameters of the Environment For Improved Optimizer Perfor- |
|---------------|---|
| | mance |

Description

Low level interface function to the IBM ILOG CPLEX function CPXtuneparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| nIntP | Number of integer parameters to be fixed during tuning. |
| intP | Parameter numbers of the integer parameters which remain fixed. |
| intPv | Values for the parameters listed in intP. |
| nDblP | Number of double parameters to be fixed during tuning. |
| dblP | Parameter numbers of the double parameters which remain fixed. |
| dblPv | Values for the parameters listed in dblP. |
| nStrP | Number of string parameters to be fixed during tuning. |
| strP | Parameter numbers of the string parameters which remain fixed. |
| strPv | Values for the parameters listed in strP. |

Details

Interface to the C function tuneParam which calls the CPLEX function CPXtuneparam.

Value

Zero if successful, otherwise an instance of class "cplexError".

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

228 unscaleProbCPLEX

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

unscaleProbCPLEX

Remove Any Scaling Applied to the Resident Problem

Description

Low level interface function to the IBM ILOG CPLEX function CPXunscaleprob. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
unscaleProbCPLEX(env, lp)
```

Arguments

| env | An object of class ' | "cplexPtr" as returned I | by openEnvCPLEX. This is basically |
|-----|----------------------|--------------------------|------------------------------------|
| | | | |

a pointer to an IBM ILOG CPLEX environment.

lp An object of class "cplexPtr" as returned by initProbCPLEX. This is basically

a pointer to an IBM ILOG CPLEX problem object.

Details

Interface to the C function unscaleProb which calls the CPLEX function CPXunscaleprob.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich <geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

writeMIPstartsCPLEX 229

writeMIPstartsCPLEX

Write a Range of MIP Starts to a File in MST Format

Description

Low level interface function to the IBM ILOG CPLEX function CPXwritemipstarts. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
writeMIPstartsCPLEX(env, lp, fname, begin, end)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| fname | Filename to write to. |
| begin | An integer specifying the beginning of the range of MIP starts to be written. |
| end | An integer specifying the end of the range of MIP starts to be written. |

Details

Interface to the C function writeMIPstarts which calls the CPLEX function CPXwritemipstarts.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

230 writeParmCPLEX

writeParmCPLEX

Write Names and Current Settings of CPLEX Parameters to File

Description

Low level interface function to the IBM ILOG CPLEX function CPXwriteparam. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
writeParmCPLEX(env, fname)
```

Arguments

env An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically

a pointer to an IBM ILOG CPLEX environment.

fname Filename.

Details

Interface to the C function writeParm which calls the CPLEX function CPXwriteparam.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie @uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

See Also

cplexConstants

writeProbCPLEX 231

| writeProbCPLEX Write a CPLEX Problem Object to File |
|---|
|---|

Description

Low level interface function to the IBM ILOG CPLEX function CPXwriteprob. Consult the IBM ILOG CPLEX documentation for more detailed information.

Usage

```
writeProbCPLEX(env, lp, fname, ftype = NULL)
```

Arguments

| env | An object of class "cplexPtr" as returned by openEnvCPLEX. This is basically a pointer to an IBM ILOG CPLEX environment. |
|-------|--|
| lp | An object of class "cplexPtr" as returned by initProbCPLEX. This is basically a pointer to an IBM ILOG CPLEX problem object. |
| fname | Single character value giving the file name to write to. |
| ftype | Single character value giving the type of the file to write to. |

Details

Interface to the C function writeProb which calls the CPLEX function CPXwriteprob.

Value

Zero if successful, otherwise nonzero.

Author(s)

Gabriel Gelius-Dietrich < geliudie@uni-duesseldorf.de>

Maintainer: Claus Jonathan Fritzemeier <clausjonathan.fritzemeier@uni-duesseldorf.de>

References

The IBM ILOG CPLEX home page at https://www.ibm.com/developerworks/university/academicinitiative/.

Index

| *Topic optimize | cloneProbCPLEX,46 |
|--------------------------------------|----------------------------|
| addChannelCPLEX, 7 | closeEnvCPLEX, 47 |
| addColsCPLEX, 9 | closeFileCPLEX,48 |
| addFpDestCPLEX, 10 | closeProbCPLEX,49 |
| addIndConstrCPLEX, 11 | cLpWriteCPLEX, 50 |
| addMIPstartsCPLEX, 12 | completelpCPLEX, 51 |
| addQConstrCPLEX, 13 | copyBaseCPLEX, 52 |
| addRowsCPLEX, 14 | copyColTypeCPLEX, 53 |
| baroptCPLEX, 15 | copyLpCPLEX, 54 |
| baseWriteCPLEX, 16 | copyLpwNamesCPLEX, 55 |
| basicPresolveCPLEX, 17 | copyObjNameCPLEX, 56 |
| boundSaCPLEX, 18 | copyOrderCPLEX, 57 |
| checkAddColsCPLEX, 19 | copyPartBaseCPLEX, 58 |
| checkAddRowsCPLEX, 20 | copyQPsepCPLEX, 59 |
| <pre>checkChgCoefListCPLEX, 21</pre> | copyQuadCPLEX, 60 |
| <pre>checkCopyColTypeCPLEX, 22</pre> | copyStartCPLEX, 61 |
| checkCopyLpCPLEX, 23 | cplexAPI-package, 6 |
| checkCopyLpwNamesCPLEX, 24 | cplexConstants, 62 |
| checkCopyQPsepCPLEX, 26 | cplexError-class, 83 |
| checkCopyQuadCPLEX, 27 | cplexPtr-class, 84 |
| checkValsCPLEX, 28 | delChannelCPLEX, 85 |
| chgBndsCPLEX, 29 | delColsCPLEX, 86 |
| chgCoefCPLEX, 30 | delFpDestCPLEX, 87 |
| chgCoefListCPLEX,31 | delIndConstrsCPLEX,88 |
| chgColNameCPLEX, 32 | delMIPstartsCPLEX,89 |
| chgColsBndsCPLEX, 33 | delNamesCPLEX, 90 |
| chgColTypeCPLEX, 34 | delProbCPLEX,91 |
| chgMIPstartsCPLEX, 35 | delQConstrsCPLEX,92 |
| chgNameCPLEX, 36 | delRowsCPLEX, 93 |
| chgObjCPLEX, 37 | delSetColsCPLEX, 94 |
| chgProbNameCPLEX, 38 | delSetRowsCPLEX, 95 |
| chgProbTypeCPLEX, 39 | delTerminateCPLEX, 96 |
| chgQPcoefCPLEX, 40 | disconnectChannelCPLEX, 97 |
| chgRhsCPLEX, 41 | dualoptCPLEX, 98 |
| chgRngValCPLEX, 42 | dualWriteCPLEX,99 |
| chgRowNameCPLEX, 43 | feasOptCPLEX, 100 |
| chgSenseCPLEX, 44 | fileputCPLEX, 101 |
| chgTerminateCPLEX, 45 | flushChannelCPLEX, 102 |
| cleanupCoefCPLEX, 45 | flushStdChannelsCPLEX, 103 |

| freePresolveCPLEX, 104 | getOrderCPLEX, 152 |
|-------------------------------------|-----------------------------------|
| getBaseCPLEX, 105 | getParmNameCPLEX, 153 |
| getBestObjValCPLEX, 106 | getParmNumCPLEX, 154 |
| getChannelsCPLEX, 107 | <pre>getParmTypeCPLEX, 155</pre> |
| getChgParmCPLEX, 108 | <pre>getParmValCPLEX, 156</pre> |
| getCoefCPLEX, 109 | getPhase1CntCPLEX, 156 |
| <pre>getColIndexCPLEX, 110</pre> | getPiCPLEX, 157 |
| getColInfeasCPLEX, 111 | getPreStatCPLEX, 158 |
| getColNameCPLEX, 112 | getProbNameCPLEX, 159 |
| getColsCPLEX, 113 | <pre>getProbTypeCPLEX, 160</pre> |
| getColTypeCPLEX, 114 | getProbVarCPLEX, 161 |
| getConflictCPLEX, 115 | getQConstrCPLEX, 162 |
| <pre>getConflictExtCPLEX, 116</pre> | getQPcoefCPLEX, 163 |
| getCutoffCPLEX, 117 | getQuadCPLEX, 164 |
| getDblParmCPLEX, 118 | getRedLpCPLEX, 165 |
| getDblQualCPLEX, 119 | getRhsCPLEX, 166 |
| getDbsCntCPLEX, 120 | getRngValCPLEX, 167 |
| getDjCPLEX, 121 | <pre>getRowIndexCPLEX, 168</pre> |
| getErrorStrCPLEX, 122 | getRowInfeasCPLEX, 169 |
| getGradCPLEX, 123 | getRowNameCPLEX, 170 |
| getIndConstrCPLEX, 124 | getRowsCPLEX, 171 |
| getInfoDblParmCPLEX, 125 | getSenseCPLEX, 172 |
| getInfoIntParmCPLEX, 126 | <pre>getSiftItCntCPLEX, 173</pre> |
| getInfoLongParmCPLEX, 127 | getSiftPase1CntCPLEX, 174 |
| getInfoStrParmCPLEX, 128 | getSlackCPLEX, 175 |
| getIntParmCPLEX, 129 | getStatCPLEX, 176 |
| getIntQualCPLEX, 130 | getStatStrCPLEX, 177 |
| getItCntCPLEX, 131 | getStrParmCPLEX, 178 |
| getLogFileCPLEX, 132 | getSubMethodCPLEX, 179 |
| getLongParmCPLEX, 133 | getSubStatCPLEX, 180 |
| getLowBndsIdsCPLEX, 134 | getTimeCPLEX, 181 |
| getLowerBndsCPLEX, 135 | getUppBndsIdsCPLEX, 182 |
| getMethodCPLEX, 136 | getUpperBndsCPLEX, 183 |
| getMIPrelGapCPLEX, 137 | getVersionCPLEX, 184 |
| getMIPstartIndexCPLEX, 138 | hybbaroptCPLEX, 185 |
| getMIPstartNameCPLEX, 139 | hybnetoptCPLEX, 186 |
| getMIPstartsCPLEX, 140 | initProbCPLEX, 187 |
| getNumColsCPLEX, 141 | lpoptCPLEX, 188 |
| getNumMIPstartsCPLEX, 142 | mipoptCPLEX, 189 |
| getNumNnzCPLEX, 143 | newColsCPLEX, 190 |
| getNumQPnzCPLEX, 144 | newRowsCPLEX, 191 |
| getNumQuadCPLEX, 145 | objSaCPLEX, 192 |
| getNumRowsCPLEX, 146 | openEnvCPLEX, 193 |
| getObjCPLEX, 147 | openFileCPLEX, 194 |
| getObjDirCPLEX, 148 | openProbCPLEX, 195 |
| getObjNameCPLEX, 149 | ordWriteCPLEX, 196 |
| getObjOffsetCPLEX, 150 | preslvWriteCPLEX, 197 |
| getObjValCPLEX, 151 | presolveCPLEX, 198 |

| primoptCPLEX, 199 | boundSaCPLEX, 18 |
|---|---|
| printTerminateCPLEX, 200 | |
| qpoptCPLEX, 200 | checkAddColsCPLEX, 10, 19 |
| readCopyBaseCPLEX, 201 | checkAddRowsCPLEX, 15, 20 |
| readCopyMIPstartsCPLEX, 202 | <pre>checkChgCoefListCPLEX, 21</pre> |
| readCopyOrderCPLEX, 203 | <pre>checkCopyColTypeCPLEX, 22</pre> |
| readCopyParmCPLEX, 204 | checkCopyLpCPLEX, 23 |
| readCopyProbCPLEX, 205 | checkCopyLpwNamesCPLEX, 24 |
| readCopySolCPLEX, 206 | checkCopyQPsepCPLEX, 26 |
| refineConflictCPLEX, 207 | checkCopyQuadCPLEX, 27 |
| refineConflictExtCPLEX, 208 | checkValsCPLEX, 28 |
| refineMIPstartConflictCPLEX, 209 | chgBndsCPLEX, 29, 33, 226 |
| refineMIPstartConflictExtCPLEX, | chgCoefCPLEX, 30, 40 |
| 210 | chgCoefListCPLEX, 22, 31 |
| return_codeCPLEX, 211 | chgColNameCPLEX, 32 |
| rhsSaCPLEX, 212 | chgColsBndsCPLEX, 33 |
| setDblParmCPLEX, 213 | chgColTypeCPLEX, 34 |
| setDefaultParmCPLEX, 214 | chgMIPstartsCPLEX, 35 |
| setIntParmCPLEX, 215 | chgNameCPLEX, 36 |
| setLogFileCPLEX, 216 | chgObjCPLEX, <i>30</i> , <i>37</i> |
| setLongParmCPLEX, 217 | chgProbNameCPLEX, 38 |
| setObjDirCPLEX,218 | chgProbTypeCPLEX, 39, 161 |
| setStrParmCPLEX, 219 | chgQPcoefCPLEX, 40 |
| setTerminateCPLEX, 220 | chgRhsCPLEX, 30, 41 |
| siftoptCPLEX, 221 | chgRngValCPLEX, 15, 30, 42 |
| solnInfoCPLEX, 222 | chgRowNameCPLEX, 43 |
| solutionCPLEX, 223 | chgSenseCPLEX, 44 |
| solWriteCPLEX, 224 | chgTerminateCPLEX, 45, 96, 200, 220 |
| status_codeCPLEX, 225 | cleanupCoefCPLEX, 45 |
| tightenBndsCPLEX, 226 | cloneProbCPLEX, 46 |
| tuneParmCPLEX, 227 | closeEnvCPLEX, 47, 193 |
| unscaleProbCPLEX, 228 | closeFileCPLEX, 48, <i>101</i> , <i>194</i> |
| writeMIPstartsCPLEX, 229 | closeProbCPLEX, 49, 195 |
| writeParmCPLEX, 230 | cLpWriteCPLEX, 50 |
| writeProbCPLEX, 231 | completelpCPLEX, 51 |
| *Topic package | constantsCPLEX (cplexConstants), 62 |
| cplexAPI-package, 6 | copyBaseCPLEX, 52 |
| | copyColTypeCPLEX, 23, 53 |
| addChannelCPLEX, 7, 10, 86, 97, 102, 103, 107 | copyLpCPLEX, <i>15</i> , <i>24</i> , <i>5</i> 4 |
| addColsCPLEX, 9, 15, 20 | copyLpwNamesCPLEX, 26, 55 |
| addFpDestCPLEX, 10, 87 | copyObjNameCPLEX, 56 |
| addIndConstrCPLEX, 11 | copyOrderCPLEX, 57 |
| addMIPstartsCPLEX, 12 | copyPartBaseCPLEX, 58 |
| addQConstrCPLEX, 13 | copyQPsepCPLEX, $26,59$ |
| addRowsCPLEX, 10, 14, 21 | copyQuadCPLEX, 28, 60 |
| | copyStartCPLEX, 61 |
| baroptCPLEX, 15 | cplex_Constants (cplexConstants), 62 |
| baseWriteCPLEX, 16 | cplexAPI (cplexAPI-package), 6 |
| basicPresolveCPLEX, 17 | cplexAPI-package, 6 |
| | |

| cplexConstants, 39, 62, 108, 114, 116, 118, | CPX_BASIC (cplexConstants), 62 |
|---|--|
| 119, 126–129, 133, 136, 148, | CPX_BASIC_SOLN(cplexConstants), 62 |
| 152–156, 159, 161, 176, 178, 179, | CPX_BINARY (cplexConstants), 62 |
| 185, 186, 191, 196, 198, 204, 211, | CPX_BRANCH_DOWN (cplexConstants), 62 |
| 213–215, 217–219, 222, 224, 225, | CPX_BRANCH_GLOBAL (cplexConstants), 62 |
| 230 | CPX_BRANCH_UP(cplexConstants), 62 |
| cplexError, 17, 18, 47, 48, 99, 105–119, 121, | CPX_BRDIR_AUTO (cplexConstants), 62 |
| 123–127, 129, 130, 132–135, | CPX_BRDIR_DOWN(cplexConstants), 62 |
| 137–140, 147, 149–152, 155, | CPX_BRDIR_UP (cplexConstants), 62 |
| 158–172, 175, 181–183, 187, 192, | CPX_CON_ABS (cplexConstants), 62 |
| 193, 195, 197, 207, 209, 212, 220, | CPX_CON_DISJCST (cplexConstants), 62 |
| 222, 223, 227 | CPX_CON_INDDISJCST (cplexConstants), 62 |
| cplexError (cplexError-class), 83 | <pre>CPX_CON_INDICATOR (cplexConstants), 62</pre> |
| cplexError-class, 83 | <pre>CPX_CON_LAST_CONTYPE (cplexConstants),</pre> |
| cplexPointer (cplexPtr-class), 84 | 62 |
| cplexPointer,cplexPtr-method | CPX_CON_LINEAR (cplexConstants), 62 |
| (cplexPtr-class), 84 | CPX_CON_LOWER_BOUND (cplexConstants), 62 |
| cplexPtr, 8–23, 25–47, 49–55, 57–61, | CPX_CON_MAXEXPR (cplexConstants), 62 |
| 85–100, 102–210, 212–231 | CPX_CON_MINEXPR (cplexConstants), 62 |
| cplexPtr (cplexPtr-class), 84 | CPX_CON_PWL (cplexConstants), 62 |
| cplexPtr-class, 84 | <pre>CPX_CON_QUADRATIC (cplexConstants), 62</pre> |
| cplexPtrType (cplexPtr-class), 84 | CPX_CON_SETVAR (cplexConstants), 62 |
| cplexPtrType,cplexPtr-method | CPX_CON_SETVARCARD (cplexConstants), 62 |
| (cplexPtr-class), 84 | <pre>CPX_CON_SETVARDOMAIN(cplexConstants),</pre> |
| <pre>cplexPtrType<- (cplexPtr-class), 84</pre> | 62 |
| cplexPtrType<-,cplexPtr-method | CPX_CON_SETVAREQ(cplexConstants), 62 |
| (cplexPtr-class), 84 | CPX_CON_SETVARINTERSECT |
| CPX_ALG_AUTOMATIC (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_ALG_BAROPT (cplexConstants), 62 | CPX_CON_SETVARINTERSECTION |
| CPX_ALG_BARRIER (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_ALG_CONCURRENT (cplexConstants), 62 | CPX_CON_SETVARMAX (cplexConstants), 62 |
| CPX_ALG_DUAL (cplexConstants), 62 | <pre>CPX_CON_SETVARMEMBER (cplexConstants),</pre> |
| CPX_ALG_FEASOPT (cplexConstants), 62 | 62 |
| CPX_ALG_MIP (cplexConstants), 62 | CPX_CON_SETVARMIN(cplexConstants), 62 |
| CPX_ALG_NET (cplexConstants), 62 | CPX_CON_SETVARNEQ(cplexConstants), 62 |
| CPX_ALG_NONE (cplexConstants), 62 | <pre>CPX_CON_SETVARNEQCST (cplexConstants),</pre> |
| CPX_ALG_PIVOT (cplexConstants), 62 | 62 |
| CPX_ALG_PIVOTIN (cplexConstants), 62 | CPX_CON_SETVARNULLINTERSECT |
| CPX_ALG_PIVOTOUT (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_ALG_PRIMAL (cplexConstants), 62 | <pre>CPX_CON_SETVARSUBSET (cplexConstants),</pre> |
| CPX_ALG_ROBUST (cplexConstants), 62 | 62 |
| CPX_ALG_SIFTING (cplexConstants), 62 | CPX_CON_SETVARSUM(cplexConstants), 62 |
| CPX_AT_LOWER (cplexConstants), 62 | CPX_CON_SETVARUNION(cplexConstants), 62 |
| CPX_AT_UPPER (cplexConstants), 62 | CPX_CON_SOS (cplexConstants), 62 |
| CPX_BARORDER_AMD (cplexConstants), 62 | CPX_CON_UPPER_BOUND (cplexConstants), 62 |
| CPX_BARORDER_AMF (cplexConstants), 62 | <pre>CPX_CONFLICT_EXCLUDED (cplexConstants),</pre> |
| CPX_BARORDER_AUTO (cplexConstants), 62 | 62 |
| CPX BARORDER ND (cplexConstants), 62 | CPX CONFLICT LB (cplexConstants), 62 |

| CPX_CONFLICT_MEMBER (cplexConstants), 62 | 62 |
|---|--|
| CPX_CONFLICT_POSSIBLE_LB | CPX_MAX_INDSLACK_INFEAS |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_CONFLICT_POSSIBLE_MEMBER | <pre>CPX_MAX_INT_INFEAS (cplexConstants), 62</pre> |
| (cplexConstants), 62 | CPX_MAX_PI (cplexConstants), 62 |
| CPX_CONFLICT_POSSIBLE_UB | <pre>CPX_MAX_PRIMAL_INFEAS (cplexConstants),</pre> |
| (cplexConstants), 62 | 62 |
| CPX_CONFLICT_UB (cplexConstants), 62 | CPX_MAX_PRIMAL_RESIDUAL |
| CPX_CONTINUOUS (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_DPRIIND_AUTO (cplexConstants), 62 | CPX_MAX_QCPRIMAL_RESIDUAL |
| CPX_DPRIIND_DEVEX(cplexConstants), 62 | (cplexConstants), 62 |
| CPX_DPRIIND_FULL (cplexConstants), 62 | CPX_MAX_QCSLACK(cplexConstants), 62 |
| CPX_DPRIIND_FULL_STEEP | CPX_MAX_QCSLACK_INFEAS |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_DPRIIND_STEEP (cplexConstants), 62 | <pre>CPX_MAX_RED_COST (cplexConstants), 62</pre> |
| CPX_DPRIIND_STEEPQSTART | CPX_MAX_SCALED_DUAL_INFEAS |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_DUAL_OBJ (cplexConstants), 62 | CPX_MAX_SCALED_DUAL_RESIDUAL |
| CPX_EXACT_KAPPA (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_FEASOPT_MIN_INF (cplexConstants), 62 | CPX_MAX_SCALED_PI (cplexConstants), 62 |
| <pre>CPX_FEASOPT_MIN_QUAD (cplexConstants),</pre> | CPX_MAX_SCALED_PRIMAL_INFEAS |
| 62 | (cplexConstants), 62 |
| CPX_FEASOPT_MIN_SUM(cplexConstants), 62 | CPX_MAX_SCALED_PRIMAL_RESIDUAL |
| CPX_FEASOPT_OPT_INF (cplexConstants), 62 | (cplexConstants), 62 |
| <pre>CPX_FEASOPT_OPT_QUAD (cplexConstants),</pre> | CPX_MAX_SCALED_RED_COST |
| 62 | (cplexConstants), 62 |
| CPX_FEASOPT_OPT_SUM(cplexConstants), 62 | <pre>CPX_MAX_SCALED_SLACK (cplexConstants),</pre> |
| CPX_FREE_SUPER (cplexConstants), 62 | 62 |
| CPX_IMPLIED_INTEGER_FEASIBLE | CPX_MAX_SCALED_X (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_MAX_SLACK (cplexConstants), 62 |
| CPX_INFBOUND(cplexConstants), 62 | CPX_MAX_X (cplexConstants), 62 |
| CPX_INTEGER (cplexConstants), 62 | CPX_MIN(cplexConstants), 62 |
| CPX_INTEGER_FEASIBLE (cplexConstants), | CPX_MIPEMPHASIS_BALANCED |
| 62 | (cplexConstants), 62 |
| CPX_INTEGER_INFEASIBLE | CPX_MIPEMPHASIS_BESTBOUND |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_KAPPA (cplexConstants), 62 | CPX_MIPEMPHASIS_FEASIBILITY |
| CPX_KAPPA_ATTENTION(cplexConstants), 62 | (cplexConstants), 62 |
| CPX_KAPPA_ILLPOSED (cplexConstants), 62 | CPX_MIPEMPHASIS_HIDDENFEAS |
| CPX_KAPPA_MAX (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_KAPPA_STABLE (cplexConstants), 62 | CPX_MIPEMPHASIS_OPTIMALITY |
| CPX_KAPPA_SUSPICIOUS (cplexConstants), | (cplexConstants), 62 |
| 62 | CPX_MIPKAPPA_AUTO(cplexConstants), 62 |
| CPX_KAPPA_UNSTABLE (cplexConstants), 62 | <pre>CPX_MIPKAPPA_FULL (cplexConstants), 62</pre> |
| CPX_MAX (cplexConstants), 62 | CPX_MIPKAPPA_OFF (cplexConstants), 62 |
| CPX_MAX_COMP_SLACK(cplexConstants), 62 | CPX_MIPKAPPA_SAMPLE (cplexConstants), 62 |
| CPX_MAX_DUAL_INFEAS (cplexConstants), 62 | CPX_MIPORDER_BOUNDS (cplexConstants), 62 |
| CPX MAX DUAL RESIDUAL (cplexConstants). | CPX MIPORDER COST (cplexConstants), 62 |

| CPX_MIPORDER_SCALEDCOST | CPX_PARAM_BAREPCOMP (cplexConstants), 62 |
|--|--|
| (cplexConstants), 62 | CPX_PARAM_BARGROWTH(cplexConstants), 62 |
| CPX_MIPSEARCH_AUTO (cplexConstants), 62 | CPX_PARAM_BARITLIM(cplexConstants), 62 |
| <pre>CPX_MIPSEARCH_DYNAMIC (cplexConstants),</pre> | CPX_PARAM_BARMAXCOR (cplexConstants), 62 |
| 62 | CPX_PARAM_BAROBJRNG (cplexConstants), 62 |
| CPX_MIPSEARCH_TRADITIONAL | CPX_PARAM_BARORDER (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_PARAM_BARPSTART (cplexConstants), 62 |
| CPX_MIPSTART_AUTO (cplexConstants), 62 | CPX_PARAM_BARQCPEPCOMP |
| CPX_MIPSTART_CHECKFEAS | (cplexConstants), 62 |
| (cplexConstants), 62 | <pre>CPX_PARAM_BARSTARTALG(cplexConstants),</pre> |
| CPX_MIPSTART_REPAIR (cplexConstants), 62 | 62 |
| CPX_MIPSTART_SOLVEFIXED | <pre>CPX_PARAM_BASINTERVAL (cplexConstants),</pre> |
| (cplexConstants), 62 | 62 |
| <pre>CPX_MIPSTART_SOLVEMIP (cplexConstants),</pre> | <pre>CPX_PARAM_BBINTERVAL (cplexConstants),</pre> |
| 62 | 62 |
| CPX_NO_SOLN (cplexConstants), 62 | <pre>CPX_PARAM_BNDSTRENIND (cplexConstants),</pre> |
| <pre>CPX_NODESEL_BESTBOUND (cplexConstants),</pre> | 62 |
| 62 | CPX_PARAM_BRDIR (cplexConstants), 62 |
| CPX_NODESEL_BESTEST (cplexConstants), 62 | CPX_PARAM_BTTOL (cplexConstants), 62 |
| CPX_NODESEL_BESTEST_ALT | CPX_PARAM_CALCQCPDUALS |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_NODESEL_DFS (cplexConstants), 62 | CPX_PARAM_CFILEMUL (cplexConstants), 62 |
| CPX_NONBASIC_SOLN (cplexConstants), 62 | CPX_PARAM_CLIQUES (cplexConstants), 62 |
| CPX_OBJ_GAP (cplexConstants), 62 | CPX_PARAM_CLOCKTYPE (cplexConstants), 62 |
| CPX_OFF (cplexConstants), 62 | CPX_PARAM_CLONELOG(cplexConstants), 62 |
| CPX_ON(cplexConstants), 62 | CPX_PARAM_COEREDIND(cplexConstants), 62 |
| CPX_PARALLEL_AUTO (cplexConstants), 62 | <pre>CPX_PARAM_COLREADLIM(cplexConstants),</pre> |
| CPX_PARALLEL_DETERMINISTIC | 62 |
| (cplexConstants), 62 | CPX_PARAM_CONFLICTDISPLAY |
| CPX_PARALLEL_OPPORTUNISTIC | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_PARAM_COVERS (cplexConstants), 62 |
| CPX_PARAM_ADVIND (cplexConstants), 62 | CPX_PARAM_CRAIND (cplexConstants), 62 |
| CPX_PARAM_AGGCUTLIM(cplexConstants), 62 | CPX_PARAM_CUTLO(cplexConstants), 62 |
| CPX_PARAM_AGGFILL (cplexConstants), 62 | CPX_PARAM_CUTPASS (cplexConstants), 62 |
| CPX_PARAM_AGGIND (cplexConstants), 62 | <pre>CPX_PARAM_CUTSFACTOR (cplexConstants),</pre> |
| CPX_PARAM_ALL_MAX (cplexConstants), 62 | 62 |
| CPX_PARAM_ALL_MIN (cplexConstants), 62 | CPX_PARAM_CUTUP (cplexConstants), 62 |
| <pre>CPX_PARAM_APIENCODING (cplexConstants),</pre> | CPX_PARAM_DATACHECK(cplexConstants), 62 |
| 62 | CPX_PARAM_DEPIND (cplexConstants), 62 |
| CPX_PARAM_AUXROOTTHREADS | CPX_PARAM_DETTILIM (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_PARAM_DISJCUTS (cplexConstants), 62 |
| CPX_PARAM_BARALG (cplexConstants), 62 | CPX_PARAM_DIVETYPE (cplexConstants), 62 |
| CPX_PARAM_BARCOLNZ (cplexConstants), 62 | CPX_PARAM_DPRIIND (cplexConstants), 62 |
| <pre>CPX_PARAM_BARCROSSALG (cplexConstants),</pre> | <pre>CPX_PARAM_EACHCUTLIM(cplexConstants),</pre> |
| 62 | 62 |
| CPX_PARAM_BARDISPLAY (cplexConstants), | CPX_PARAM_EPAGAP (cplexConstants), 62 |
| 62 | CPX_PARAM_EPGAP (cplexConstants), 62 |
| CPX PARAM BARDSTART (cplexConstants), 62 | CPX_PARAM_EPINT(cplexConstants), 62 |

| CPX_PARAM_EPLIN (cplexConstants), 62 | 62 |
|--|--|
| CPX_PARAM_EPMRK (cplexConstants), 62 | CPX_PARAM_MIRCUTS (cplexConstants), 62 |
| CPX_PARAM_EPOPT (cplexConstants), 62 | <pre>CPX_PARAM_MPSLONGNUM (cplexConstants),</pre> |
| CPX_PARAM_EPOPT_H (cplexConstants), 62 | 62 |
| CPX_PARAM_EPPER (cplexConstants), 62 | <pre>CPX_PARAM_NETDISPLAY (cplexConstants),</pre> |
| CPX_PARAM_EPRELAX (cplexConstants), 62 | 62 |
| CPX_PARAM_EPRHS (cplexConstants), 62 | CPX_PARAM_NETEPOPT (cplexConstants), 62 |
| CPX_PARAM_EPRHS_H (cplexConstants), 62 | CPX_PARAM_NETEPRHS (cplexConstants), 62 |
| CPX_PARAM_FASTMIP (cplexConstants), 62 | CPX_PARAM_NETFIND (cplexConstants), 62 |
| CPX_PARAM_FEASOPTMODE (cplexConstants), | CPX_PARAM_NETITLIM (cplexConstants), 62 |
| 62 | CPX_PARAM_NETPPRIIND (cplexConstants), |
| CPX_PARAM_FILEENCODING | 62 |
| (cplexConstants), 62 | <pre>CPX_PARAM_NODEFILEIND (cplexConstants),</pre> |
| CPX_PARAM_FLOWCOVERS (cplexConstants), | 62 |
| 62 | CPX_PARAM_NODELIM(cplexConstants), 62 |
| CPX_PARAM_FLOWPATHS (cplexConstants), 62 | CPX_PARAM_NODESEL (cplexConstants), 62 |
| CPX_PARAM_FPHEUR (cplexConstants), 62 | CPX_PARAM_NUMERICALEMPHASIS |
| CPX_PARAM_FRACCAND (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PARAM_FRACCUTS (cplexConstants), 62 | CPX_PARAM_NZREADLIM (cplexConstants), 62 |
| CPX_PARAM_FRACPASS (cplexConstants), 62 | CPX_PARAM_OBJDIF (cplexConstants), 62 |
| CPX_PARAM_GUBCOVERS (cplexConstants), 62 | CPX_PARAM_OBJLLIM (cplexConstants), 62 |
| CPX_PARAM_HEURFREQ (cplexConstants), 62 | CPX_PARAM_OBJULIM (cplexConstants), 62 |
| CPX_PARAM_IMPLBD (cplexConstants), 62 | CPX_PARAM_PARALLELMODE |
| CPX_PARAM_INTSOLFILEPREFIX | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_PARAM_PERIND (cplexConstants), 62 |
| CPX_PARAM_INTSOLLIM (cplexConstants), 62 | CPX_PARAM_PERLIM (cplexConstants), 62 |
| CPX_PARAM_ITLIM (cplexConstants), 62 | CPX_PARAM_POLISHAFTERDETTIME |
| CPX_PARAM_LANDPCUTS (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PARAM_LBHEUR (cplexConstants), 62 | CPX_PARAM_POLISHAFTEREPAGAP |
| CPX_PARAM_LPMETHOD (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PARAM_MCFCUTS (cplexConstants), 62 | CPX_PARAM_POLISHAFTEREPGAP |
| CPX_PARAM_MEMORYEMPHASIS | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_PARAM_POLISHAFTERINTSOL |
| CPX_PARAM_MIPCBREDLP (cplexConstants), | (cplexConstants), 62 |
| 62 | CPX_PARAM_POLISHAFTERNODE |
| CPX_PARAM_MIPDISPLAY (cplexConstants), | (cplexConstants), 62 |
| 62 | CPX_PARAM_POLISHAFTERTIME |
| CPX_PARAM_MIPEMPHASIS (cplexConstants), | (cplexConstants), 62 |
| 62 | CPX_PARAM_POLISHTIME (cplexConstants), |
| CPX_PARAM_MIPINTERVAL (cplexConstants), | 62 |
| 62 | <pre>CPX_PARAM_POPULATELIM(cplexConstants),</pre> |
| CPX_PARAM_MIPKAPPASTATS | 62 |
| (cplexConstants), 62 | CPX_PARAM_PPRIIND (cplexConstants), 62 |
| CPX_PARAM_MIPORDIND (cplexConstants), 62 | CPX_PARAM_PREDUAL (cplexConstants), 62 |
| CPX_PARAM_MIPORDTYPE (cplexConstants), | CPX_PARAM_PREIND (cplexConstants), 62 |
| 62 | CPX_PARAM_PRELINEAR (cplexConstants), 62 |
| CPX_PARAM_MIPSEARCH (cplexConstants), 62 | CPX_PARAM_PREPASS (cplexConstants), 62 |
| CPX PARAM MIOCPSTRAT (cplexConstants). | CPX PARAM PRESLVND (cplexConstants), 62 |
| | |

| CPX_PARAM_PRICELIM (cplexConstants), 62 | 62 |
|--|--|
| CPX_PARAM_PROBE (cplexConstants), 62 | CPX_PARAM_SOLNPOOLINTENSITY |
| CPX_PARAM_PROBEDETTIME | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_PARAM_SOLNPOOLREPLACE |
| CPX_PARAM_PROBETIME (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PARAM_QPMAKEPSDIND | CPX_PARAM_SOLUTIONTARGET |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PARAM_QPMETHOD (cplexConstants), 62 | CPX_PARAM_STARTALG (cplexConstants), 62 |
| CPX_PARAM_QPNZREADLIM (cplexConstants), | CPX_PARAM_STRONGCANDLIM |
| 62 | (cplexConstants), 62 |
| CPX_PARAM_RAMPUPDETTILIM | CPX_PARAM_STRONGITLIM(cplexConstants), |
| (cplexConstants), 62 | 62 |
| CPX_PARAM_RAMPUPDURATION | CPX_PARAM_SUBALG (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_PARAM_SUBMIPNODELIM |
| CPX_PARAM_RAMPUPTILIM (cplexConstants), | (cplexConstants), 62 |
| 62 | CPX_PARAM_SYMMETRY (cplexConstants), 62 |
| CPX_PARAM_RANDOMSEED (cplexConstants), | CPX_PARAM_THREADS (cplexConstants), 62 |
| 62 | CPX_PARAM_TILIM(cplexConstants), 62 |
| CPX_PARAM_REDUCE (cplexConstants), 62 | CPX_PARAM_TRELIM(cplexConstants), 62 |
| CPX_PARAM_REINV (cplexConstants), 62 | CPX_PARAM_TUNINGDETTILIM |
| * * | |
| CPX_PARAM_RELAXPREIND (cplexConstants), | (cplexConstants), 62 |
| 62 | CPX_PARAM_TUNINGDISPLAY |
| CPX_PARAM_RELOBJDIF (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PARAM_REPAIRTRIES (cplexConstants), | CPX_PARAM_TUNINGMEASURE |
| 62 | (cplexConstants), 62 |
| CPX_PARAM_REPEATPRESOLVE | CPX_PARAM_TUNINGREPEAT |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PARAM_REVERSEIND (cplexConstants), | <pre>CPX_PARAM_TUNINGTILIM(cplexConstants),</pre> |
| 62 | 62 |
| CPX_PARAM_RFILEMUL (cplexConstants), 62 | CPX_PARAM_VARSEL (cplexConstants), 62 |
| CPX_PARAM_RINSHEUR (cplexConstants), 62 | CPX_PARAM_WORKDIR (cplexConstants), 62 |
| <pre>CPX_PARAM_ROWREADLIM(cplexConstants),</pre> | CPX_PARAM_WORKMEM (cplexConstants), 62 |
| 62 | <pre>CPX_PARAM_WRITELEVEL (cplexConstants),</pre> |
| CPX_PARAM_SCAIND (cplexConstants), 62 | 62 |
| CPX_PARAM_SCRIND (cplexConstants), 62 | CPX_PARAM_XXXIND (cplexConstants), 62 |
| CPX_PARAM_SIFTALG (cplexConstants), 62 | CPX_PARAM_ZEROHALFCUTS |
| <pre>CPX_PARAM_SIFTDISPLAY (cplexConstants),</pre> | (cplexConstants), 62 |
| 62 | <pre>CPX_PARAMTYPE_DOUBLE (cplexConstants),</pre> |
| CPX_PARAM_SIFTITLIM(cplexConstants), 62 | 62 |
| <pre>CPX_PARAM_SIMDISPLAY (cplexConstants),</pre> | <pre>CPX_PARAMTYPE_INT (cplexConstants), 62</pre> |
| 62 | CPX_PARAMTYPE_LONG (cplexConstants), 62 |
| CPX_PARAM_SINGLIM (cplexConstants), 62 | <pre>CPX_PARAMTYPE_NONE (cplexConstants), 62</pre> |
| CPX_PARAM_SINGTOL (cplexConstants), 62 | <pre>CPX_PARAMTYPE_STRING (cplexConstants),</pre> |
| CPX_PARAM_SOLNPOOLAGAP | 62 |
| (cplexConstants), 62 | CPX_PPRIIND_AUTO (cplexConstants), 62 |
| CPX_PARAM_SOLNPOOLCAPACITY | CPX_PPRIIND_DEVEX (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_PPRIIND_FULL (cplexConstants), 62 |
| CPX_PARAM_SOLNPOOLGAP (cplexConstants), | CPX_PPRIIND_PARTIAL (cplexConstants), 62 |

| CPX_PPRIIND_STEEP (cplexConstants), 62 | CPX_STAT_ABORT_TIME_LIM |
|--|--|
| CPX_PPRIIND_STEEPQSTART | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_ABORT_USER (cplexConstants), 62 |
| CPX_PRECOL_AGG (cplexConstants), 62 | CPX_STAT_CONFLICT_ABORT_CONTRADICTION |
| CPX_PRECOL_FIX (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PRECOL_LOW (cplexConstants), 62 | CPX_STAT_CONFLICT_ABORT_DETTIME_LIM |
| CPX_PRECOL_OTHER (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PRECOL_UP (cplexConstants), 62 | CPX_STAT_CONFLICT_ABORT_IT_LIM |
| CPX_PREREDUCE_DUALONLY | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_CONFLICT_ABORT_MEM_LIM |
| CPX_PREREDUCE_NOPRIMALORDUAL | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_CONFLICT_ABORT_NODE_LIM |
| CPX_PREREDUCE_PRIMALANDDUAL | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_CONFLICT_ABORT_OBJ_LIM |
| CPX_PREREDUCE_PRIMALONLY | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_CONFLICT_ABORT_TIME_LIM |
| CPX_PREROW_AGG (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PREROW_OTHER (cplexConstants), 62 | CPX_STAT_CONFLICT_ABORT_USER |
| CPX_PREROW_RED (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_PRIMAL_OBJ (cplexConstants), 62 | CPX_STAT_CONFLICT_FEASIBLE |
| CPX_PRIMAL_SOLN (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_SEMICONT (cplexConstants), 62 | CPX_STAT_CONFLICT_MINIMAL |
| CPX_SEMIINT (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_SOLNPOOL_DIV (cplexConstants), 62 | CPX_STAT_FEASIBLE (cplexConstants), 62 |
| CPX_SOLNPOOL_FIFO (cplexConstants), 62 | CPX_STAT_FEASIBLE_RELAXED_INF |
| CPX_SOLNPOOL_FILTER_DIVERSITY | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_FEASIBLE_RELAXED_QUAD |
| CPX_SOLNPOOL_FILTER_RANGE | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_FEASIBLE_RELAXED_SUM |
| CPX_SOLNPOOL_OBJ (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_SOLUTIONTARGET_AUTO | CPX_STAT_FIRSTORDER (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_INFEASIBLE (cplexConstants), 62 |
| CPX_SOLUTIONTARGET_FIRSTORDER | CPX_STAT_INForUNBD (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_NUM_BEST (cplexConstants), 62 |
| CPX_SOLUTIONTARGET_OPTIMALCONVEX | CPX_STAT_OPTIMAL (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_OPTIMAL_FACE_UNBOUNDED |
| CPX_SOLUTIONTARGET_OPTIMALGLOBAL | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_OPTIMAL_INFEAS |
| CPX_STAT_ABORT_DETTIME_LIM | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_OPTIMAL_RELAXED_INF |
| CPX_STAT_ABORT_DUAL_OBJ_LIM | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_OPTIMAL_RELAXED_QUAD |
| <pre>CPX_STAT_ABORT_IT_LIM (cplexConstants),</pre> | (cplexConstants), 62 |
| 62 | CPX_STAT_OPTIMAL_RELAXED_SUM |
| CPX_STAT_ABORT_OBJ_LIM | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_STAT_UNBOUNDED (cplexConstants), 62 |
| CPX_STAT_ABORT_PRIM_OBJ_LIM | CPX_STR_PARAM_MAX (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_SUM_COMP_SLACK (cplexConstants), 62 |
| | |

| CPX_SUM_DUAL_INFEAS (cplexConstants), 62 | 62 |
|--|---|
| <pre>CPX_SUM_DUAL_RESIDUAL (cplexConstants),</pre> | <pre>CPX_VARSEL_MININFEAS (cplexConstants),</pre> |
| 62 | 62 |
| CPX_SUM_INDSLACK_INFEAS | <pre>CPX_VARSEL_PSEUDO (cplexConstants), 62</pre> |
| (cplexConstants), 62 | CPX_VARSEL_PSEUDOREDUCED |
| CPX_SUM_INT_INFEAS (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_SUM_PI (cplexConstants), 62 | CPX_VARSEL_STRONG (cplexConstants), 62 |
| <pre>CPX_SUM_PRIMAL_INFEAS (cplexConstants),</pre> | CPX_WRITELEVEL_ALLVARS |
| 62 | (cplexConstants), 62 |
| CPX_SUM_PRIMAL_RESIDUAL | CPX_WRITELEVEL_AUTO (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_WRITELEVEL_DISCRETEVARS |
| CPX_SUM_QCPRIMAL_RESIDUAL | (cplexConstants), 62 |
| (cplexConstants), 62 | CPX_WRITELEVEL_NONZERODISCRETEVARS |
| CPX_SUM_QCSLACK (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_SUM_QCSLACK_INFEAS | CPX_WRITELEVEL_NONZEROVARS |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPX_SUM_RED_COST (cplexConstants), 62 | CPXaddchannel, <i>85</i> , <i>87</i> , <i>97</i> |
| CPX_SUM_SCALED_DUAL_INFEAS | CPXaddchannel (addChannelCPLEX), 7 |
| (cplexConstants), 62 | CPXaddcols (addColsCPLEX), 9 |
| CPX_SUM_SCALED_DUAL_RESIDUAL | CPXaddfpdest (addFpDestCPLEX), 10 |
| (cplexConstants), 62 | CPXaddindconstr (addIndConstrCPLEX), 11 |
| CPX_SUM_SCALED_PI (cplexConstants), 62 | CPXaddmipstarts(addMIPstartsCPLEX), 12 |
| CPX_SUM_SCALED_PRIMAL_INFEAS | CPXaddqconstr(addQConstrCPLEX), 13 |
| (cplexConstants), 62 | CPXaddrows (addRowsCPLEX), 14 |
| CPX_SUM_SCALED_PRIMAL_RESIDUAL | CPXbaropt (baroptCPLEX), 15 |
| (cplexConstants), 62 | CPXbasicpresolve(basicPresolveCPLEX), |
| CPX_SUM_SCALED_RED_COST | 17 |
| (cplexConstants), 62 | CPXboundsa (boundSaCPLEX), 18 |
| CPX_SUM_SCALED_SLACK (cplexConstants), | CPXcheckaddcols (checkAddColsCPLEX), 19 |
| 62 | CPXcheckaddrows (checkAddRowsCPLEX), 20 |
| CPX_SUM_SCALED_X (cplexConstants), 62 | CPXcheckchgcoeflist |
| CPX_SUM_SLACK (cplexConstants), 62 | (checkChgCoefListCPLEX), 21 |
| CPX_SUM_X (cplexConstants), 62 | CPXcheckcopyctype |
| CPX_TUNE_ABORT (cplexConstants), 62 | (checkCopyColTypeCPLEX), 22 |
| CPX_TUNE_AVERAGE (cplexConstants), 62 | CPXcheckcopylp (checkCopyLpCPLEX), 23 |
| CPX_TUNE_DETTILIM (cplexConstants), 62 | CPXcheckcopylpwnames |
| CPX_TUNE_MINMAX (cplexConstants), 62 | (checkCopyLpwNamesCPLEX), 24 |
| CPX_TUNE_TILIM(cplexConstants), 62 | CPXcheckcopyqpsep |
| CPX_TYPE_ANY (cplexConstants), 62 | (checkCopyQPsepCPLEX), 26 |
| CPX_TYPE_SOS1 (cplexConstants), 62 | CPXcheckcopyquad (checkCopyQuadCPLEX), |
| CPX_TYPE_SOS2 (cplexConstants), 62 | 27 |
| CPX_TYPE_USER (cplexConstants), 62 | CPXcheckvals (checkValsCPLEX), 28 |
| CPX_TYPE_VAR (cplexConstants), 62 | CPXchgbds (chgBndsCPLEX), 29 |
| CPX_USECUT_FILTER (cplexConstants), 62 | CPXchgcoef (chgCoefCPLEX), 30 |
| CPX_USECUT_FORCE (cplexConstants), 62 | CPXchgcoeflist (chgCoefListCPLEX), 31 |
| CPX_USECUT_PURGE (cplexConstants), 62 | CPXchgcolname (chgColNameCPLEX), 32 |
| CPX_VARSEL_DEFAULT (cplexConstants), 62 | CPXchgctype (chgColTypeCPLEX), 34 |
| CPX_VARSEL_MAXINFEAS (cplexConstants), | CPXchgmipstarts (chgMIPstartsCPLEX), 35 |
| | = |

| CPXchgname (chgNameCPLEX), 36 | CPXflushstdchannels |
|---|---|
| CPXchgobj (chgObjCPLEX), 37 | (flushStdChannelsCPLEX), 103 |
| CPXchgobjsen(setObjDirCPLEX), 218 | CPXfopen (openFileCPLEX), 194 |
| CPXchgprobname (chgProbNameCPLEX), 38 | CPXfputs(fileputCPLEX), 101 |
| CPXchgprobtype (chgProbTypeCPLEX), 39 | CPXfreepresolve(freePresolveCPLEX), 104 |
| CPXchgqpcoef (chgQPcoefCPLEX), 40 | CPXfreeprob (delProbCPLEX), 91 |
| CPXchgrhs (chgRhsCPLEX), 41 | CPXgetbase (getBaseCPLEX), 105 |
| CPXchgrngval (chgRngValCPLEX), 42 | <pre>CPXgetbestobjval (getBestObjValCPLEX),</pre> |
| CPXchgrowname (chgRowNameCPLEX), 43 | 106 |
| CPXchgsense (chgSenseCPLEX), 44 | CPXgetchannels (getChannelsCPLEX), 107 |
| CPXcleanup(cleanupCoefCPLEX), 45 | CPXgetchgparam(getChgParmCPLEX), 108 |
| CPXcloneprob (cloneProbCPLEX), 46 | CPXgetcoef (getCoefCPLEX), 109 |
| CPXcloseCPLEX (closeEnvCPLEX), 47 | CPXgetcolindex(getColIndexCPLEX), 110 |
| CPXclpwrite(cLpWriteCPLEX), 50 | CPXgetcolinfeas(getColInfeasCPLEX), 111 |
| CPXcompletelp(completelpCPLEX), 51 | CPXgetcolname(getColNameCPLEX), 112 |
| CPXcopybase (copyBaseCPLEX), 52 | CPXgetcols(getColsCPLEX), 113 |
| CPXcopyctype (copyColTypeCPLEX), 53 | CPXgetconflict(getConflictCPLEX), 115 |
| CPXcopylp (copyLpCPLEX), 54 | CPXgetconflictext |
| CPXcopylpwnames (copyLpwNamesCPLEX), 55 | (getConflictExtCPLEX), 116 |
| CPXcopyobjname (copyObjNameCPLEX), 56 | CPXgetctype (getColTypeCPLEX), 114 |
| CPXcopyorder (copyOrderCPLEX), 57 | CPXgetcutoff (getCutoffCPLEX), 117 |
| CPXcopypartialbase (copyPartBaseCPLEX), | CPXgetdblparam(getDblParmCPLEX), 118 |
| 58 | CPXgetdblquality(getDblQualCPLEX), 119 |
| CPXcopyqpsep (copyQPsepCPLEX), 59 | CPXgetdj(getDjCPLEX), 121 |
| CPXcopyquad (copyQuadCPLEX), 60 | CPXgetdsbcnt (getDbsCntCPLEX), 120 |
| CPXcopystart (copyStartCPLEX), 61 | <pre>CPXgeterrorstring (getErrorStrCPLEX),</pre> |
| CPXcreateprob(initProbCPLEX), 187 | 122 |
| CPXdelchannel (delChannelCPLEX), 85 | CPXgetgrad (getGradCPLEX), 123 |
| CPXdelcols (delColsCPLEX), 86 | CPXgetindconstr(getIndConstrCPLEX), 124 |
| CPXdelfpdest (delFpDestCPLEX), 87 | CPXgetintparam(getIntParmCPLEX), 129 |
| CPXdelindconstrs(delIndConstrsCPLEX), | CPXgetintquality(getIntQualCPLEX), 130 |
| 88 | CPXgetitcnt(getItCntCPLEX), 131 |
| CPXdelmipstarts(delMIPstartsCPLEX), 89 | CPXgetlb(getLowerBndsCPLEX), 135 |
| CPXdelnames (delNamesCPLEX), 90 | CPXgetlogfile(getLogFileCPLEX), 132 |
| CPXdelqconstrs(delQConstrsCPLEX), 92 | CPXgetlongparam(getLongParmCPLEX), 133 |
| CPXdelrows (delRowsCPLEX), 93 | CPXgetmethod(getMethodCPLEX), 136 |
| CPXdelsetcols (delSetColsCPLEX), 94 | CPXgetmiprelgap(getMIPrelGapCPLEX), 137 |
| CPXdelsetrows (delSetRowsCPLEX), 95 | CPXgetmipstartindex |
| CPXdisconnectchannel | (getMIPstartIndexCPLEX), 138 |
| (disconnectChannelCPLEX), 97 | CPXgetmipstartname |
| CPXdualopt (dualoptCPLEX), 98 | (getMIPstartNameCPLEX), 139 |
| CPXdualwrite(dualWriteCPLEX), 99 | CPXgetmipstarts(getMIPstartsCPLEX), 140 |
| CPXERR_NEGATIVE_SURPLUS | CPXgetnumcols(getNumColsCPLEX), 141 |
| (cplexConstants), 62 | CPXgetnummipstarts |
| CPXERR_NO_SENSIT (cplexConstants), 62 | (getNumMIPstartsCPLEX), 142 |
| CPXfclose (closeFileCPLEX), 48 | CPXgetnumnz (getNumNnzCPLEX), 143 |
| CPXfeasopt (feasOptCPLEX), 100 | CPXgetnumqpnz (getNumQPnzCPLEX), 144 |
| CPXflushchannel(flushChannelCPLEX), 102 | CPXgetnumquad (getNumQuadCPLEX), 145 |

| CPXgetnumrows (getNumRowsCPLEX), 146 | CPXlpopt (lpoptCPLEX), 188 |
|---|---|
| CPXgetobj (getObjCPLEX), 147 | CPXmbasewrite(baseWriteCPLEX), 16 |
| CPXgetobjname(getObjNameCPLEX), 149 | CPXMIP_ABORT_FEAS (cplexConstants), 62 |
| CPXgetobjoffset(getObjOffsetCPLEX), 150 | CPXMIP_ABORT_INFEAS (cplexConstants), 62 |
| CPXgetobjsen(getObjDirCPLEX), 148 | <pre>CPXMIP_ABORT_RELAXED (cplexConstants),</pre> |
| CPXgetobjval (getObjValCPLEX), 151 | 62 |
| CPXgetorder (getOrderCPLEX), 152 | CPXMIP_DETTIME_LIM_FEAS |
| CPXgetparamname(getParmNameCPLEX), 153 | (cplexConstants), 62 |
| CPXgetparamnum (getParmNumCPLEX), 154 | CPXMIP_DETTIME_LIM_INFEAS |
| CPXgetparamtype (getParmTypeCPLEX), 155 | (cplexConstants), 62 |
| CPXgetphase1cnt (getPhase1CntCPLEX), 156 | CPXMIP_FAIL_FEAS (cplexConstants), 62 |
| CPXgetpi (getPiCPLEX), 157 | CPXMIP_FAIL_FEAS_NO_TREE |
| CPXgetprestat (getPreStatCPLEX), 158 | (cplexConstants), 62 |
| CPXgetprobname (getProbNameCPLEX), 159 | CPXMIP_FAIL_INFEAS (cplexConstants), 62 |
| CPXgetprobtype (getProbTypeCPLEX), 160 | CPXMIP_FAIL_INFEAS_NO_TREE |
| CPXgetqconstr (getQConstrCPLEX), 162 | (cplexConstants), 62 |
| CPXgetqpcoef (getQPcoefCPLEX), 163 | CPXMIP_FEASIBLE (cplexConstants), 62 |
| CPXgetquad (getQuadCPLEX), 164 | CPXMIP_FEASIBLE_RELAXED_INF |
| CPXgetredlp (getRedLpCPLEX), 165 | (cplexConstants), 62 |
| CPXgetrhs (getRhsCPLEX), 166 | CPXMIP_FEASIBLE_RELAXED_QUAD |
| CPXgetrngval (getRngValCPLEX), 167 | (cplexConstants), 62 |
| CPXgetrowindex (getRowIndexCPLEX), 168 | CPXMIP_FEASIBLE_RELAXED_SUM |
| CPXgetrowinfeas (getRowInfeasCPLEX), 169 | (cplexConstants), 62 |
| CPXgetrowname (getRowNameCPLEX), 170 | CPXMIP_INFEASIBLE (cplexConstants), 62 |
| CPXgetrows (getRowsCPLEX), 171 | CPXMIP_INForUNBD (cplexConstants), 62 |
| CPXgetsense (getSenseCPLEX), 172 | CPXMIP_MEM_LIM_FEAS (cplexConstants), 62 |
| CPXgetsiftitcnt (getSiftItCntCPLEX), 173 | <pre>CPXMIP_MEM_LIM_INFEAS (cplexConstants),</pre> |
| CPXgetsiftphase1cnt | 62 |
| (getSiftPase1CntCPLEX), 174 | <pre>CPXMIP_NODE_LIM_FEAS (cplexConstants),</pre> |
| CPXgetslack(getSlackCPLEX), 175 | 62 |
| CPXgetstat (getStatCPLEX), 176 | CPXMIP_NODE_LIM_INFEAS |
| CPXgetstatstring (getStatStrCPLEX), 177 | (cplexConstants), 62 |
| CPXgetstrparam (getStrParmCPLEX), 178 | CPXMIP_OPTIMAL (cplexConstants), 62 |
| CPXgetsubmethod(getSubMethodCPLEX), 179 | <pre>CPXMIP_OPTIMAL_INFEAS (cplexConstants),</pre> |
| CPXgetsubstat (getSubStatCPLEX), 180 | 62 |
| CPXgettime(getTimeCPLEX), 181 | CPXMIP_OPTIMAL_POPULATED |
| CPXgetub (getUpperBndsCPLEX), 183 | (cplexConstants), 62 |
| CPXgetx (getProbVarCPLEX), 161 | CPXMIP_OPTIMAL_POPULATED_TOL |
| ODVI 11 (ODLEY) 105 | |
| CPXhybbaropt (hybbaroptCPLEX), 185 | (cplexConstants), 62 |
| CPXhybnetopt (hybnetoptCPLEX), 185 CPXhybnetopt (hybnetoptCPLEX), 186 | |
| | (cplexConstants), 62 |
| CPXhybnetopt (hybnetoptCPLEX), 186 | <pre>(cplexConstants), 62 CPXMIP_OPTIMAL_RELAXED_INF</pre> |
| CPXhybnetopt(hybnetoptCPLEX), 186 CPXinfodblparam(getInfoDblParmCPLEX), | <pre>(cplexConstants), 62 CPXMIP_OPTIMAL_RELAXED_INF (cplexConstants), 62</pre> |
| CPXhybnetopt (hybnetoptCPLEX), 186 CPXinfodblparam (getInfoDblParmCPLEX), 125 | (cplexConstants), 62 CPXMIP_OPTIMAL_RELAXED_INF |
| CPXhybnetopt (hybnetoptCPLEX), 186 CPXinfodblparam (getInfoDblParmCPLEX), 125 CPXinfointparam (getInfoIntParmCPLEX), | (cplexConstants), 62 CPXMIP_OPTIMAL_RELAXED_INF |
| CPXhybnetopt (hybnetoptCPLEX), 186 CPXinfodblparam (getInfoDblParmCPLEX), | <pre>(cplexConstants), 62 CPXMIP_OPTIMAL_RELAXED_INF</pre> |
| CPXhybnetopt (hybnetoptCPLEX), 186 CPXinfodblparam (getInfoDblParmCPLEX), 125 CPXinfointparam (getInfoIntParmCPLEX), 126 CPXinfolongparam | (cplexConstants), 62 CPXMIP_OPTIMAL_RELAXED_INF |

| CPXMIP_SOL_LIM(cplexConstants), 62 | CPXPARAM_Barrier_StartAlg |
|--|--|
| CPXMIP_TIME_LIM_FEAS (cplexConstants), | (cplexConstants), 62 |
| 62 | <pre>CPXPARAM_ClockType (cplexConstants), 62</pre> |
| CPXMIP_TIME_LIM_INFEAS | CPXPARAM_Conflict_Display |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXMIP_UNBOUNDED (cplexConstants), 62 | <pre>CPXPARAM_DetTimeLimit (cplexConstants),</pre> |
| CPXmipopt (mipoptCPLEX), 189 | 62 |
| CPXNET_NO_DISPLAY_OBJECTIVE | CPXPARAM_DistMIP_Rampup_DetTimeLimit |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXNET_PENALIZED_OBJECTIVE | CPXPARAM_DistMIP_Rampup_Duration |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXNET_PRICE_AUTO (cplexConstants), 62 | CPXPARAM_DistMIP_Rampup_TimeLimit |
| CPXNET_PRICE_MULT_PART | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Emphasis_Memory |
| <pre>CPXNET_PRICE_PARTIAL (cplexConstants),</pre> | (cplexConstants), 62 |
| 62 | <pre>CPXPARAM_Emphasis_MIP (cplexConstants),</pre> |
| CPXNET_PRICE_SORT_MULT_PART | 62 |
| (cplexConstants), 62 | CPXPARAM_Emphasis_Numerical |
| <pre>CPXNET_TRUE_OBJECTIVE (cplexConstants),</pre> | (cplexConstants), 62 |
| 62 | <pre>CPXPARAM_Feasopt_Mode (cplexConstants),</pre> |
| CPXnewcols (newColsCPLEX), 190 | 62 |
| CPXnewrows (newRowsCPLEX), 191 | CPXPARAM_Feasopt_Tolerance |
| CPXobjsa (objSaCPLEX), 192 | (cplexConstants), 62 |
| CPXopenCPLEX (openEnvCPLEX), 193 | CPXPARAM_LPMethod (cplexConstants), 62 |
| CPXordwrite(ordWriteCPLEX), 196 | CPXPARAM_MIP_Cuts_Cliques |
| CPXPARAM_Advance (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_Algorithm | CPXPARAM_MIP_Cuts_Covers |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_ColNonzeros | CPXPARAM_MIP_Cuts_Disjunctive |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_ConvergeTol | CPXPARAM_MIP_Cuts_FlowCovers |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_Crossover | CPXPARAM_MIP_Cuts_Gomory |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_Display | CPXPARAM_MIP_Cuts_GUBCovers |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_Limits_Corrections | CPXPARAM_MIP_Cuts_Implied |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_Limits_Growth | CPXPARAM_MIP_Cuts_LiftProj |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_Limits_Iteration | CPXPARAM_MIP_Cuts_MCFCut |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_Limits_ObjRange | CPXPARAM_MIP_Cuts_MIRCut |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_Ordering | CPXPARAM_MIP_Cuts_PathCut |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Barrier_QCPConvergeTol | CPXPARAM_MIP_Cuts_ZeroHalfCut |
| (cplexConstants), 62 | (cplexConstants), 62 |

| CPXPARAM_MIP_Display (cplexConstants), | CPXPARAM_MIP_PolishAfter_Nodes |
|--|---|
| 62 | (cplexConstants), 62 |
| <pre>CPXPARAM_MIP_Interval (cplexConstants),</pre> | CPXPARAM_MIP_PolishAfter_Solutions |
| 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_AggForCut | CPXPARAM_MIP_PolishAfter_Time |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_AuxRootThreads | CPXPARAM_MIP_Pool_AbsGap |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_CutPasses | CPXPARAM_MIP_Pool_Capacity |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_CutsFactor | CPXPARAM_MIP_Pool_Intensity |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_EachCutLimit | CPXPARAM_MIP_Pool_RelGap |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_GomoryCand | CPXPARAM_MIP_Pool_Replace |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_GomoryPass | CPXPARAM_MIP_Strategy_Backtrack |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_Nodes | CPXPARAM_MIP_Strategy_BBInterval |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_PolishTime | CPXPARAM_MIP_Strategy_Branch |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_Populate | CPXPARAM_MIP_Strategy_CallbackReducedLP |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_ProbeDetTime | CPXPARAM_MIP_Strategy_Dive |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_ProbeTime | CPXPARAM_MIP_Strategy_File |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_RepairTries | CPXPARAM_MIP_Strategy_FPHeur |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_Solutions | CPXPARAM_MIP_Strategy_HeuristicFreq |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_StrongCand | CPXPARAM_MIP_Strategy_KappaStats |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_StrongIt | CPXPARAM_MIP_Strategy_LBHeur |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_SubMIPNodeLim | CPXPARAM_MIP_Strategy_MIQCPStrat |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_Limits_TreeMemory | CPXPARAM_MIP_Strategy_NodeSelect |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_OrderType | CPXPARAM_MIP_Strategy_Order |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_PolishAfter_AbsMIPGap | CPXPARAM_MIP_Strategy_PresolveNode |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_PolishAfter_DetTime | CPXPARAM_MIP_Strategy_Probe |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_MIP_PolishAfter_MIPGap | CPXPARAM_MIP_Strategy_RINSHeur |
| (cplexConstants), 62 | (cplexConstants), 62 |

| CPXPARAM_MIP_Strategy_Search | (cplexConstants), 62 |
|--|--|
| (cplexConstants), 62 | CPXPARAM_Preprocessing_Dependency |
| CPXPARAM_MIP_Strategy_StartAlgorithm | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_Dual |
| CPXPARAM_MIP_Strategy_SubAlgorithm | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_Fill |
| CPXPARAM_MIP_Strategy_VariableSelect | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_Linear |
| CPXPARAM_MIP_Tolerances_AbsMIPGap | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_NumPass |
| CPXPARAM_MIP_Tolerances_Integrality | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_Presolve |
| CPXPARAM_MIP_Tolerances_LowerCutoff | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_QCPDuals |
| CPXPARAM_MIP_Tolerances_MIPGap | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_QPMakePSD |
| CPXPARAM_MIP_Tolerances_ObjDifference | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_Reduce |
| CPXPARAM_MIP_Tolerances_RelObjDifference | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_Relax |
| CPXPARAM_MIP_Tolerances_UpperCutoff | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_RepeatPresolve |
| CPXPARAM_Network_Display | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Preprocessing_Symmetry |
| CPXPARAM_Network_Iterations | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_QPMethod(cplexConstants), 62 |
| CPXPARAM_Network_NetFind | CPXPARAM_RandomSeed (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Read_APIEncoding |
| CPXPARAM_Network_Pricing | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Read_Constraints |
| CPXPARAM_Network_Tolerances_Feasibility | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Read_DataCheck |
| CPXPARAM_Network_Tolerances_Optimality | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Read_FileEncoding |
| CPXPARAM_Output_CloneLog | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Read_Nonzeros |
| CPXPARAM_Output_IntSolFilePrefix | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Read_QPNonzeros |
| CPXPARAM_Output_MPSLong | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Read_Scale (cplexConstants), 62 |
| CPXPARAM_Output_WriteLevel | CPXPARAM_Read_Variables |
| (cplexConstants), 62 | (cplexConstants), 62 |
| CPXPARAM_Parallel(cplexConstants), 62 | <pre>CPXPARAM_ScreenOutput (cplexConstants),</pre> |
| CPXPARAM_Preprocessing_Aggregator | 62 |
| (cplexConstants), 62 | CPXPARAM_Sifting_Algorithm |
| CPXPARAM_Preprocessing_BoundStrength | (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPARAM_Sifting_Display |
| CPXPARAM Preprocessing CoeffReduce | (cplexConstants), 62 |

| CPXPARAM_Sifting_Iterations | CPXPARAM_WorkDir(cplexConstants), 62 |
|--|--|
| (cplexConstants), 62 | CPXPARAM_WorkMem(cplexConstants), 62 |
| CPXPARAM_Simplex_Crash | CPXpreslvwrite(preslvWriteCPLEX), 197 |
| (cplexConstants), 62 | CPXpresolve(presolveCPLEX), 198 |
| CPXPARAM_Simplex_DGradient | CPXprimopt (primoptCPLEX), 199 |
| (cplexConstants), 62 | CPXPROB_FIXEDMILP (cplexConstants), 62 |
| CPXPARAM_Simplex_Display | CPXPROB_FIXEDMIQP (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPROB_LP (cplexConstants), 62 |
| CPXPARAM_Simplex_Limits_Iterations | CPXPROB_MILP (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPROB_MIQCP (cplexConstants), 62 |
| CPXPARAM_Simplex_Limits_LowerObj | CPXPROB_MIQP (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPROB_NODELP (cplexConstants), 62 |
| CPXPARAM_Simplex_Limits_Perturbation | CPXPROB_NODEQCP (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPROB_NODEQP (cplexConstants), 62 |
| CPXPARAM_Simplex_Limits_Singularity | CPXPROB_QCP (cplexConstants), 62 |
| (cplexConstants), 62 | CPXPROB_QP (cplexConstants), 62 |
| CPXPARAM_Simplex_Limits_UpperObj | CPXqpopt (qpoptCPLEX), 200 |
| (cplexConstants), 62 | CPXreadcopybase (readCopyBaseCPLEX), 201 |
| CPXPARAM_Simplex_Perturbation_Constant | CPXreadcopymipstarts |
| (cplexConstants), 62 | (readCopyMIPstartsCPLEX), 202 |
| CPXPARAM_Simplex_Perturbation_Indicator | CPXreadcopyorder (readCopyOrderCPLEX), |
| (cplexConstants), 62 | 203 |
| CPXPARAM_Simplex_PGradient | <pre>CPXreadcopyparam (readCopyParmCPLEX),</pre> |
| (cplexConstants), 62 | 204 |
| CPXPARAM_Simplex_Pricing | CPXreadcopyprob (readCopyProbCPLEX), 205 |
| (cplexConstants), 62 | CPXreadcopysol (readCopySolCPLEX), 206 |
| CPXPARAM_Simplex_Refactor | CPXrefineconflict |
| (cplexConstants), 62 | (refineConflictCPLEX), 207 |
| CPXPARAM_Simplex_Tolerances_Feasibility | CPXrefineconflictext |
| (cplexConstants), 62 | (refineConflictExtCPLEX), 208 |
| CPXPARAM_Simplex_Tolerances_Markowitz | CPXrefinemipstartconflict |
| (cplexConstants), 62 | <pre>(refineMIPstartConflictCPLEX),</pre> |
| CPXPARAM_Simplex_Tolerances_Optimality | 209 |
| (cplexConstants), 62 | CPXrefinemipstartconflictext |
| CPXPARAM_SolutionTarget | (refineMIPstartConflictExtCPLEX) |
| (cplexConstants), 62 | 210 |
| CPXPARAM_Threads (cplexConstants), 62 | CPXrhssa (rhsSaCPLEX), 212 |
| CPXPARAM_TimeLimit (cplexConstants), 62 | CPXsetdblparam(setDblParmCPLEX), 213 |
| CPXPARAM_Tune_DetTimeLimit | <pre>CPXsetdefaults (setDefaultParmCPLEX),</pre> |
| (cplexConstants), 62 | 214 |
| CPXPARAM_Tune_Display (cplexConstants), | CPXsetintparam(setIntParmCPLEX), 215 |
| 62 | CPXsetlogfile(setLogFileCPLEX), 216 |
| <pre>CPXPARAM_Tune_Measure (cplexConstants),</pre> | CPXsetlongparam(setLongParmCPLEX), 217 |
| 62 | CPXsetstrparam (setStrParmCPLEX), 219 |
| <pre>CPXPARAM_Tune_Repeat (cplexConstants),</pre> | CPXsetterminate (delTerminateCPLEX), 96 |
| 62 | CPXsiftopt(siftoptCPLEX), 221 |
| CPXPARAM_Tune_TimeLimit | CPXsolninfo(solnInfoCPLEX), 222 |
| (cplexConstants), 62 | CPXsolution(solutionCPLEX), 223 |

| CPXsolwrite(solWriteCPLEX), 224 | getChannelsCPLEX, 8, 86, 97, 102, 103, 107 |
|---|--|
| CPXtightenbds (tightenBndsCPLEX), 226 | getChgParmCPLEX, 108, 156 |
| CPXtuneparam(tuneParmCPLEX), 227 | getCoefCPLEX, 109 |
| CPXunscaleprob (unscaleProbCPLEX), 228 | <pre>getColIndexCPLEX, 110</pre> |
| CPXversion(getVersionCPLEX), 184 | getColInfeasCPLEX, 100, 111 |
| CPXwritemipstarts | getColNameCPLEX, 112 |
| (writeMIPstartsCPLEX), 229 | getColsCPLEX, 113 |
| CPXwriteparam (writeParmCPLEX), 230 | getColTypeCPLEX, 114 |
| CPXwriteprob (writeProbCPLEX), 231 | getConflictCPLEX, 115, 207, 209 |
| | getConflictExtCPLEX, 116 |
| delChannelCPLEX, 8, 85, 97, 102, 103, 107 | getCutoffCPLEX, 117 |
| delColsCPLEX, 86 | getDblParmCPLEX, 118 |
| delFpDestCPLEX, 10, 87 | getDblQualCPLEX, 119 |
| delIndConstrsCPLEX, 88 | getDbsCntCPLEX, 120 |
| delMIPstartsCPLEX, 89 | getDjCPLEX, 121 |
| delNamesCPLEX, 90 | getErrorStrCPLEX, 122, 177 |
| delProbCPLEX, 91, 187 | getGradCPLEX, 123 |
| delQConstrsCPLEX, 92 | getIndConstrCPLEX, 124 |
| delRowsCPLEX, 93 | getInfoDblParmCPLEX, 125 |
| delSetColsCPLEX, 94 | getInfoIntParmCPLEX, 126, 128 |
| delSetRowsCPLEX, 95 | getInfoLongParmCPLEX, 127 |
| delTerminateCPLEX, 45, 96, 200, 220 | getInfoStrParmCPLEX, 128 |
| disconnectChannelCPLEX, 8, 86, 97, 102, | getIntParmCPLEX, 129, 133 |
| 103, 107 | getIntQualCPLEX, 130 |
| dualoptCPLEX, 98 | getItCntCPLEX, 131 |
| dualWriteCPLEX, 99 | getLogFileCPLEX, 132, 216 |
| () - I O | getLongParmCPLEX, 133 |
| err (cplexError-class), 83 | getLowBndsIdsCPLEX, 134 |
| err,cplexError-method | getLowerBndsCPLEX, 29, 134, 135 |
| (cplexError-class), 83 | getMethodCPLEX, 136 |
| errmsg (cplexError-class), 83 | getMIPrelGapCPLEX, 137 |
| errmsg,cplexError-method | getMIPstartIndexCPLEX, 138 |
| (cplexError-class), 83 | getMIPstartNameCPLEX, 139 |
| errnum (cplexError-class), 83 | getMIPstartsCPLEX, 140 |
| errnum, cplexError-method | getNumColsCPLEX, 30, 141 |
| (cplexError-class), 83 | getNumMIPstartsCPLEX, 142 |
| errnum<- (cplexError-class), 83 | getNumNnzCPLEX, 143 |
| errnum<-,cplexError-method | getNumQPnzCPLEX, 144 |
| (cplexError-class), 83 | getNumQuadCPLEX, 145 |
| feasOptCPLEX, 100 | getNumRowsCPLEX, 30, 146 |
| fileputCPLEX, 48, 101, 181, 194 | getObjCPLEX, 147 |
| flushChannelCPLEX, 8, 86, 97, 102, 103, 107 | getObjDirCPLEX, 148 |
| flushStdChannelsCPLEX, 8, 86, 97, 102, 103, 107 | getObjNameCPLEX, 149 |
| | getObjOffsetCPLEX, 150 |
| 107 freePresolveCPLEX, 104 | getObjValCPLEX, 137, 151 |
| II CCI I CSUIVECELEA, 104 | getOrderCPLEX, 152 |
| getBaseCPLEX, 105 | getParmNameCPLEX, 153 |
| getBestObjValCPLEX, 106, 137 | getParmNumCPLEX, 154 |
| 500000 Taro. LE., 100, 107 | 0001 01 111101101 EE/1, 10 1 |

| getParmTypeCPLEX, 155 | isCPLEXenvPointer,cplexPtr-method |
|--|---|
| getParmValCPLEX, 83, 156 | (cplexPtr-class), 84 |
| getPhase1CntCPLEX, 156 | <pre>isCPLEXfilePointer(cplexPtr-class), 84</pre> |
| getPiCPLEX, 157 | isCPLEXfilePointer,cplexPtr-method |
| getPreStatCPLEX, 158 | (cplexPtr-class), 84 |
| getProbNameCPLEX, 159 | isCPLEXprobPointer(cplexPtr-class), 84 |
| getProbTypeCPLEX, 39, 160, 224 | isCPLEXprobPointer,cplexPtr-method |
| getProbVarCPLEX, 161 | (cplexPtr-class), 84 |
| getQConstrCPLEX, 162 | isCPLEXtermPointer(cplexPtr-class), 84 |
| getQPcoefCPLEX, 163 | isCPLEXtermPointer,cplexPtr-method |
| getQuadCPLEX, 164 | (cplexPtr-class), 84 |
| getRedLpCPLEX, 165 | isNULLpointerCPLEX (cplexPtr-class), 84 |
| getRhsCPLEX, 166 | isNULLpointerCPLEX,cplexPtr-method |
| getRngValCPLEX, 167 | (cplexPtr-class), 84 |
| getRowIndexCPLEX, 168 | // |
| getRowInfeasCPLEX, 100, 169 | lpoptCPLEX, 188 |
| getRowNameCPLEX, 170 | |
| getRowsCPLEX, 171 | mipoptCPLEX, 189 |
| getSenseCPLEX, 172 | |
| getSiftItCntCPLEX, 173 | newColsCPLEX, 190 |
| _ | newRowsCPLEX, 191 |
| getSiftPase1CntCPLEX, 174 | |
| getSlackCPLEX, 175 | objSaCPLEX, 192 |
| getStatCPLEX, 16, 98, 100, 176, 185, 186, | openEnvCPLEX, 8–23, 25–48, 50–55, 57–61, |
| 188, 189, 199, 201, 225 | 85–100, 102–192, 193, 195–210, |
| getStatStrCPLEX, 122, 177, 225 | 212–231 |
| getStrParmCPLEX, 178 | openFileCPLEX, 10, 48, 87, 101, 181, 194, 216 |
| getSubMethodCPLEX, 179 | openProbCPLEX, 49, 195 |
| getSubStatCPLEX, 180 | ordWriteCPLEX, 196 |
| getTimeCPLEX, 181 | |
| getUppBndsIdsCPLEX, 182 | preslvWriteCPLEX, 197 |
| getUpperBndsCPLEX, 29, 182, 183 | presolveCPLEX, 198 |
| getVersionCPLEX, 184 | primoptCPLEX, 199 |
| | printTerminateCPLEX, 45, 96, 200, 220 |
| hybbaroptCPLEX, 185 | • |
| hybnetoptCPLEX, 186 | qpoptCPLEX, 200 |
| | |
| initProbCPLEX, 9, 11-23, 25-44, 46, 47, | readCopyBaseCPLEX, 201 |
| 50–55, 57–61, 85, 86, 88–95, | readCopyMIPstartsCPLEX, 202 |
| 98–100, 104–106, 109–117, | readCopyOrderCPLEX, 203 |
| 119–121, 123, 124, 130, 131, | readCopyParmCPLEX, 204 |
| 134–152, 157–176, 179, 180, 182, | readCopyProbCPLEX, 197, 205 |
| <i>183</i> , <i>185</i> , <i>186</i> , 187, <i>188–192</i> , | readCopySolCPLEX, 206 |
| 195–199, 201–203, 205–210, 212, | refineConflictCPLEX, 207 |
| 218, 221–224, 226–229, 231 | refineConflictExtCPLEX, 208 |
| <pre>isCPLEXchanPointer(cplexPtr-class), 84</pre> | refineMIPstartConflictCPLEX, 209 |
| <pre>isCPLEXchanPointer,cplexPtr-method</pre> | refineMIPstartConflictExtCPLEX, 210 |
| (cplexPtr-class), 84 | return_codeCPLEX, 83, 211 |
| isCPLEXenvPointer (cplexPtr-class), 84 | rhsSaCPLEX, 212 |

```
setDblParmCPLEX, 213
setDefaultParmCPLEX, 214
setIntParmCPLEX, 215, 217
setLogFileCPLEX, 132, 216
setLongParmCPLEX, 217
setObjDirCPLEX, 218
setStrParmCPLEX, 219
setTerminateCPLEX, 45, 96, 200, 220
siftoptCPLEX, 221
solnInfoCPLEX, 16, 84, 98, 100, 185, 186,
        188, 189, 199, 201, 222, 224
solutionCPLEX, 16, 84, 98, 100, 185, 186,
        188, 189, 199, 201, 222, 223
solWriteCPLEX, 224
status_codeCPLEX, 83, 225
summary,cplexPtr-method
        (cplexPtr-class), 84
tightenBndsCPLEX, 33, 226
tuneParmCPLEX, 227
unscaleProbCPLEX, 228
writeMIPstartsCPLEX, 229
writeParmCPLEX, 230
writeProbCPLEX, 231
```