# **Boost.Ratio 0.2.0**

### Howard Hinnant Beman Dawes Vicente J. Botet Escriba

Copyright © 2008 Howard Hinnant
Copyright © 2006 , 2008 Beman Dawes
Copyright © 2009 -2010 Vicente J. Botet Escriba

Distributed under the Boost Software License, Version 1.0. (See accompanying file LICENSE\_1\_0.txt or copy at http://www.boost.org/LICENSE\_1\_0.txt)

## **Table of Contents**

Overview	
Motivation	2
Description	2
Users'Guide	2
Getting Started	2
Tutorial	4
Examples	5
External Resources	9
Reference	9
Header <boost ratio.hpp=""></boost>	9
<pre>Header <boost ratio_io.hpp=""></boost></pre>	13
Appendices	15
Appendix A: History	15
Appendix B: Rationale	16
Appendix C: Implementation Notes	16
Appendix D: FAQ	16
Appendix E: Acknowledgements	16
Appendix F: Tests	17
Appendix G: Tickets	18
Appendix H: Future plans	18



#### Warning

Ratio is not part of the Boost libraries.

## **Overview**

#### **How to Use This Documentation**

This documentation makes use of the following naming and formatting conventions.

- Code is in fixed width font and is syntax-highlighted.
- Replaceable text that you will need to supply is in italics.
- Free functions are rendered in the code font followed by (), as in free\_function().



- If a name refers to a class template, it is specified like this: class\_template<>; that is, it is in code font and its name is followed by <> to indicate that it is a class template.
- If a name refers to a function-like macro, it is specified like this: MACRO(); that is, it is uppercase in code font and its name is followed by () to indicate that it is a function-like macro. Object-like macros appear without the trailing ().
- Names that refer to *concepts* in the generic programming sense are specified in CamelCase.



#### Note

In addition, notes such as this one specify non-essential information that provides additional background or rationale.

Finally, you can mentally add the following to any code fragments in this document:

```
// Include all of Ratio files
#include <boost/ratio.hpp>
using namespace boost;
```

### **Motivation**

**Boost.Ratio** aims to implement the compile time ratio facility in C++0x, as proposed in **N2661 - A Foundation to Sleep On**. That document provides background and motivation for key design decisions and is the source of a good deal of information in this documentation.

## **Description**

The **Boost.Ratio** library provides:

- A class template, ratio, for specifying compile time rational constants such as 1/3 of a nanosecond or the number of inches per
  meter. ratio represents a compile time ratio of compile time constants with support for compile time arithmetic with overflow
  and division by zero protection
- It provides a textual representation of boost::ratio<N, D> in the form of a std::basic\_string. Other types such as boost::duration can use these strings to aid in their I/O.

## **Users'Guide**

## **Getting Started**

### **Installing Ratio**

#### **Getting Boost.Ratio**

You can get the last stable release of **Boost.Chrono** by downloading chrono.zip from the Boost Vault. Directories ratio.

You can also access the latest (unstable?) state from the Boost Sandbox. Just go to here and follow the instructions there for anonymous SVN access.

#### Where to install Boost.Ratio?

The simple way is to decompress (or checkout from SVN) the file in your BOOST\_ROOT directory.

Othesewise, if you decompress in a different directory, you will need to comment some lines, and uncomment and change others in the build/Jamfile and test/Jamfile. Sorry for this, but I have not reached yet to write a Jamfile that is able to work in both environements and use the BOOST\_ROOT variable. Any help is welcome.



#### **Building Boost.Ratio**

Boost.Ratio is a header only library, so no need to compile anything.

#### Requirements

**Boost.Ratio** depends on some Boost libraries. For these specific parts you must use either Boost version 1.39.0 or the version in SVN trunk (even if older versions should works also).

In particular, Boost.Ratio depends on:

**Boost.Config** for configuration purposes, ...

**Boost.Integer** for cstdint conformance, and integer traits ...

**Boost.MPL** for MPL Assert and bool, logical ...

Boost.StaticAssert for STATIC\_ASSERT, ...

**Boost.TypeTraits** for is\_base, is\_convertible ...

**Boost.Utility/EnableIf** for enable\_if, ...

#### **Building an executable that uses Boost.Ratio**

No link is needed.

#### **Exceptions safety**

All functions in the library are exception-neutral and provide strong guarantee of exception safety as long as the underlying parameters provide it.

#### **Thread safety**

All functions in the library are thread-unsafe except when noted explicitly.

#### **Tested compilers**

The implementation will eventually work with most C++03 conforming compilers. Current version has been tested on:

Windows with

- MSVC 10.0
- MSVC 9.0 Express
- MSVC 8.0

Scientific Linux with

• GCC 4.1.2

Cygwin with

- GCC 3.4.4
- GCC 4.3.2

MinGW with

• GCC 4.4.0



• GCC 4.5.0

Initial version was tested on:

MacOS with GCC 4.2.4

Ubuntu Linux with GCC 4.2.4



#### **Note**

Please let us know how this works on other platforms/compilers.



#### Note

Please send any questions, comments and bug reports to boost <at> lists <dot> boost <dot> org.

### **Tutorial**

ratio is a general purpose utility inspired by Walter Brown allowing one to easily and safely compute rational values at compile time. The ratio class catches all errors (such as divide by zero and overflow) at compile time. It is used in the duration and time\_point classes to efficiently create units of time. It can also be used in other "quantity" libraries (both std-defined and user-defined), or anywhere there is a rational constant which is known at compile time. The use of this utility can greatly reduce the chances of run time overflow because the ratio (and any ratios resulting from ratio arithmetic) are always reduced to lowest terms.

ratio is a template taking two intmax\_ts, with the second defaulted to 1. In addition to copy constructors and assignement, it only has two public members, both of which are static const intmax\_t. One is the numerator of the ratio and the other is the denominator. The ratio is always normalized such that it is expressed in lowest terms, and the denominator is always positive. When the numerator is 0, the denominator is always 1.

#### **Example:**

```
typedef ratio<5, 3> five_thirds;
// five_thirds::num == 5, five_thirds::den == 3

typedef ratio<25, 15> also_five_thirds;
// also_five_thirds::num == 5, also_five_thirds::den == 3

typedef ratio_divide<five_thirds, also_five_thirds>::type one;
// one::num == 1, one::den == 1
```

This facility also includes convenience typedefs for the SI prefixes atto through exa corresponding to their internationally recognized definitions (in terms of ratio). This is a tremendous syntactic convenience. It will prevent errors in specifying constants as one no longer has to double count the number of zeros when trying to write million or billion.

#### **Example:**



```
typedef ratio_multiply<ratio<5>, giga>::type _5giga;
// _5giga::num == 5000000000, _5giga::den == 1

typedef ratio_multiply<ratio<5>, nano>::type _5nano;
// _5nano::num == 1, _5nano::den == 200000000
```

### **Examples**

#### **SI-units**

Type-safe "physics" code interoperating with boost::chrono:: duration types and taking advantage of the boost::ratio infrastructure and design philosophy.

length - mimics boost::chrono:: duration except restricts representation to double. Uses boost::ratio facilities for length units conversions

```
template <class Ratio>
class length {
private:
    double len_;
public:
    typedef Ratio ratio;
    length() : len_(1) {}
    length(const double& len) : len_(len) {}
    template <class R>
    length(const length<R>& d)
            : len_(d.count() * boost::ratio_divide<Ratio, R>::type::den /
                               boost::ratio_divide<Ratio, R>::type::num) {}
    double count() const {return len_;}
    length& operator+=(const length& d) {len_ += d.count(); return *this;}
    length& operator==(const length& d) {len_ -= d.count(); return *this;}
    length operator+() const {return *this;}
    length operator-() const {return length(-len_);}
    length& operator*=(double rhs) {len_ *= rhs; return *this;}
    length& operator/=(double rhs) {len_ /= rhs; return *this;}
};
```

Sparse sampling of length units

length takes ratio instead of two integral types so that definitions can be made like so:

```
typedef length<boost::ratio_multiply<boost::ratio<12>, inch::ratio>::type> foot; // 12 inchs
typedef length<boost::ratio_multiply<boost::ratio<5280>, foot::ratio>::type> mile; // 5280 feet
```

Need a floating point definition of seconds



```
typedef boost::chrono:: duration<double> seconds; // unity
```

Demo of (scientific) support for sub-nanosecond resolutions

```
typedef boost::chrono:: duration<double, boost:: pico> picosecond; // 10^-12 seconds
typedef boost::chrono:: duration<double, boost:: femto> femtosecond; // 10^-15 seconds
typedef boost::chrono:: duration<double, boost:: atto> attosecond; // 10^-18 seconds
```

A very brief proof-of-concept for SIUnits-like library. Hard-wired to floating point seconds and meters, but accepts other units.

```
template <class R1, class R2>
class quantity
    double q_;
public:
    typedef R1 time_dim;
    typedef R2 distance_dim;
    quantity() : q_(1) {}
    double get() const {return q_;}
    void set(double q) {q_ = q;}
};
template <>
class quantity<boost::ratio<1>, boost::ratio<0> >
    double q_;
public:
    quantity() : q_(1) {}
    quantity(seconds d) : q_(d.count()) {} // note: only User1::seconds needed here
    double get() const {return q_;}
    void set(double q) \{q_{\underline{}} = q_i\}
};
template <>
class quantity<boost::ratio<0>, boost::ratio<1> >
    double q_;
public:
    quantity() : q_(1) {}
    \label{eq:quantity} \texttt{quantity}(\texttt{meter d}) \; : \; \texttt{q}_(\texttt{d}.\texttt{count}()) \; \{ \} \quad // \; \texttt{note:} \quad \texttt{only User1::meter needed here}
    double get() const {return q_;}
    void set(double q) {q_ = q;}
};
template <>
class quantity<boost::ratio<0>, boost::ratio<0> >
    double q_;
public:
    quantity() : q_(1) {}
    quantity(double d) : q_(d) \{ \}
    double get() const {return q_;}
    void set(double q) {q_ = q;}
};
```

Example of SI-Units



#### Quantity arithmetics

```
template <class R1, class R2, class R3, class R4>
quantity<typename boost::ratio_subtract<R1, R3>::type,
         typename boost::ratio_subtract<R2, R4>::type>
operator/(const quantity<R1, R2>& x, const quantity<R3, R4>& y)
    typedef quantity<typename boost::ratio_subtract<R1, R3>::type,
                    typename boost::ratio_subtract<R2, R4>::type> R;
    Rr;
    r.set(x.get() / y.get());
    return r;
template <class R1, class R2, class R3, class R4>
quantity<typename boost::ratio_add<R1, R3>::type,
         typename boost::ratio_add<R2, R4>::type>
operator*(const quantity<R1, R2>& x, const quantity<R3, R4>& y)
    typedef quantity<typename boost::ratio_add<R1, R3>::type,
                     typename boost::ratio_add<R2, R4>::type> R;
    r.set(x.get() * y.get());
    return r;
template <class R1, class R2>
quantity<R1, R2>
operator + (const \ quantity < R1 \ , \ R2 > \& \ x \ , \ const \ quantity < R1 \ , \ R2 > \& \ y)
{
    typedef quantity<R1, R2> R;
    Rr;
    r.set(x.get() + y.get());
    return r;
template <class R1, class R2>
quantity<R1, R2>
operator-(const quantity<R1, R2>& x, const quantity<R1, R2>& y)
    typedef quantity<R1, R2> R;
    Rr;
    r.set(x.get() - y.get());
    return r;
```

Example type-safe physics function



```
Distance
compute_distance(Speed v0, Time t, Acceleration a)
{
    return v0 * t + Scalar(.5) * a * t * t; // if a units mistake is made here it won't compile
}
```

Exercise example type-safe physics function and show interoperation of custom time durations (User1::seconds) and standard time durations (boost::hours). Though input can be arbitrary (but type-safe) units, output is always in SI-units (a limitation of the simplified Units lib demoed here).

```
int main()
    typedef boost::ratio<8, BOOST_INTMAX_C(0x7FFFFFFFD)> R1;
    typedef boost::ratio<3, BOOST_INTMAX_C(0x7FFFFFFFD)> R2;
    typedef User1::quantity<boost::ratio_subtract<boost::ratio<0>, boost::ratio<1> >::type,
                           boost::ratio_subtract<boost::ratio<1>, boost::ratio<0> >::type > RR;
    typedef boost::ratio_subtract<R1, R2>::type RS;
    std::cout << RS::num << '/' << RS::den << '\n';
    std::cout << "*********\n";
    std::cout << "* testUser1 *\n";</pre>
    std::cout << "*********\n";
    User1::Distance d( User1::mile(110) );
    User1::Time t( boost::chrono:: hours(2) );
    RR r=d / t;
    //r.set(d.get() / t.get());
    User1::Speed rc= r;
    User1::Speed s = d / t;
    std::cout << "Speed = " << s.get() << " meters/sec\n";
   User1::Acceleration a = User1::Distance( User1::foot(32.2) ) / User1::Time() / User1::Time();
    std::cout << "Acceleration = " << a.get() << " meters/sec^2\n";</pre>
    User1::Distance df = compute_distance(s, User1::Time( User1::seconds(0.5) ), a);
    std::cout << "Distance = " << df.get() << " meters\n";
    std::cout << "There are "
        << User1::mile::ratio::den << '/' << User1::mile::ratio::num << " miles/meter";</pre>
    User1::meter mt = 1;
    User1::mile mi = mt;
    std::cout << " which is approximately " << mi.count() << '\n';</pre>
    std::cout << "There are "
        << User1::mile::ratio::num << '/' << User1::mile::ratio::den << " meters/mile";</pre>
    mi = 1;
    mt = mi;
    std::cout << " which is approximately " << mt.count() << '\n';</pre>
    User1::attosecond as(1);
    User1::seconds sec = as;
    std::cout << "1 attosecond is " << sec.count() << " seconds\n";</pre>
    std::cout << "sec = as; // compiles\n";</pre>
    sec = User1::seconds(1);
    as = sec;
    std::cout << "1 second is " << as.count() << " attoseconds\n";</pre>
    std::cout << "as = sec; // compiles\n";</pre>
    std::cout << "\n";
  return 0;
```

See the source file test/ratio\_test.cpp



### **External Resources**

C++ Standards Committee's current Working Paper

The most authoritative reference material for the library is the C++ Standards Committee's current Working Paper (WP). 20.9 Time utilities "time", 20.4 Compile-time rational arithmetic

"ratio", 20.6.7 Other transformations "meta.trans.other"

N2661 - A Foundation to Sleep On

From Howard E. Hinnant, Walter E. Brown, Jeff Garland and Marc Paterno. Is very informative and provides motivation for key design decisions

LWG 1281. CopyConstruction and Assignment between ratios having the same normalized form

From Vicente Juan Botet Escriba.

N3131: Compile-time rational arithmetic and overflow

From Anthony Williams.

## Reference

# Header <boost/ratio.hpp>

ratio is a facility which is useful in specifying compile time rational constants. Compile time rational arithmetic is supported with protection against overflow and divide by zero. Such a facility is very handy when needing to efficiently represent 1/3 of a nanosecond, or specifying an inch in terms of meters (for example 254/10000 meters - which ratio will reduce to 127/5000 meters).



```
// configuration macros
#define BOOST_RATIO_USES_STATIC_ASSERT
#define BOOST_RATIO_USES_MPL_ASSERT
#define BOOST_RATIO_USES_ARRAY_ASSERT
namespace boost {
   template <boost::intmax_t N, boost::intmax_t D = 1> class ratio;
   // ratio arithmetic
   template <class R1, class R2> struct ratio_add;
   template <class R1, class R2> struct ratio_subtract;
   template <class R1, class R2> struct ratio_multiply;
   template <class R1, class R2> struct ratio_divide;
   // ratio comparison
   template <class R1, class R2> struct ratio_equal;
   template <class R1, class R2> struct ratio_not_equal;
   template <class R1, class R2> struct ratio_less;
   template <class R1, class R2> struct ratio_less_equal;
   template <class R1, class R2> struct ratio_greater;
   template <class R1, class R2> struct ratio_greater_equal;
   // convenience SI typedefs
   typedef ratio<1LL, 100000000000000000LL> atto;
   1000000LL> micro;
   typedef ratio<1LL,
   typedef ratio<1LL,
                                 1000LL> milli;
                                  100LL> centi;
   typedef ratio<1LL,
   typedef ratio<1LL,
                                   10LL> deci;
   typedef ratio<
                              10LL, 1LL> deca;
                             100LL, 1LL> hecto;
   typedef ratio<
   typedef ratio<
                            1000LL, 1LL> kilo;
                       10000LL, 1LL> mega;
   typedef ratio<
                    10000000LL, 1LL> giga;
   typedef ratio<
                 1000000001 . 1LL>
   typedef ratio<1000000000000000000LL, 1LL>
```

### **Configuration macros**

When BOOST\_NO\_STATIC\_ASSERT is defined, the user can select the way static assertions are reported. Define

- BOOST\_RATIO\_USES\_STATIC\_ASSERT: define it if you want to use Boost.StaticAssert
- BOOST\_RATIO\_USES\_MPL\_ASSERT: define it if you want to use Boost.MPL static asertions
- BOOST\_RATIO\_USES\_ARRAY\_ASSERT: define it if you want to use internal static asertions

The default behavior is as BOOST\_RATIO\_USES\_ARRAY\_ASSERT was defined.

When BOOST\_RATIO\_USES\_MPL\_ASSERT is not defined the following symbols are defined as



```
#define BOOST_RATIO_OVERFLOW_IN_ADD "overflow in ratio add"
#define BOOST_RATIO_OVERFLOW_IN_SUB "overflow in ratio sub"
#define BOOST_RATIO_OVERFLOW_IN_MUL "overflow in ratio mul"
#define BOOST_RATIO_OVERFLOW_IN_DIV "overflow in ratio div"
#define BOOST_RATIO_RATIO_NUMERATOR_IS_OUT_OF_RANGE "ratio numerator is out of range"
#define BOOST_RATIO_RATIO_DIVIDE_BY_0 "ratio divide by 0"
#define BOOST_RATIO_RATIO_DENOMINATOR_IS_OUT_OF_RANGE "ratio denominator is out of range"
```

Depending on the static assertion used system you will have an hint of the failing assertion either through the symbol or through the texte.

### Class Template ratio<>

```
template <boost::intmax_t N, boost::intmax_t D>
class ratio {
public:
    static const boost::intmax_t num;
    static const boost::intmax_t den;
    typedef ratio<num, den> type;

    ratio() = default;

    template <intmax_t _N2, intmax_t _D2>
    ratio(const ratio<_N2, _D2>&);

    template <intmax_t _N2, intmax_t _D2>
    ratio& operator=(const ratio<_N2, _D2>&) {return *this;}
};
```

A diagnostic will be emitted if ratio is instantiated with D = 0, or if the absolute value of N or D can not be represented. **Note:** These rules ensure that infinite ratios are avoided and that for any negative input, there exists a representable value of its absolute value which is positive. In a two's complement representation, this excludes the most negative value.

Let gcd denote the greatest common divisor of N's absolute value and of D's absolute value.

- num has the value sign(N) \*sign(D) \*abs(N)/gcd.
- den has the value abs(D)/gcd.

The nested typedef type denotes the normalized form of this ratio type. It should be used when the template parameters doesn't give a normalized form.

Two ratio classes ratio<N1,D1> and ratio<N2,D2> have the same normalized form if ratio<N1,D1>::type is the same type as ratio<N2,D2>::type

#### Construction and assignment

```
template <intmax_t N2, intmax_t D2>
  ratio(const ratio<N2, D2>& r);
```

Effects: Constructs a ratio object.

Remarks: This constructor will not participate in overload resolution unless r has the same normalized form as \*this.

```
template <intmax_t N2, intmax_t D2>
  ratio& operator=(const ratio<N2, D2>& r);
```

Effects: Assigns a ratio object.



Returns: \*this.

Remarks: This operator will not participate in overload resolution unless r has the same normalized form as \*this.

#### ratio arithmetic

For each of the class templates in this clause, each template parameter refers to a ratio. If the implementation is unable to form the indicated ratio due to overflow, a diagnostic will be issued.

```
template <class R1, class R2> struct ratio_add {
  typedef [/see below] type;
};
```

The nested typedef type is a synonym for ratio<R1::num \* R2::den + R2::num \* R1::den, R1::den \* R2::den>::type.

```
template <class R1, class R2> struct ratio_subtract {
  typedef [/see below] type;
};
```

The nested typedef type is a synonym for ratio<R1::num \* R2::den - R2::num \* R1::den, R1::den \* R2::den>::type.

```
template <class R1, class R2> struct ratio_multiply {
  typedef [/see below] type;
};
```

The nested typedef type is a synonym for ratio<R1::num \* R2::num, R1::den \* R2::den>::type.

```
template <class R1, class R2> struct ratio_divide {
  typedef [/see below] type;
};
```

The nested typedef type is a synonym for ratio<R1::num \* R2::den, R2::num \* R1::den>::type.

### ratio comparison

If R1::num = R2::num && R1::den = R2::den, ratio\_equal derives from true\_type, else derives from false\_type.

```
template <class R1, class R2>
struct ratio_less
   : public boost::integral_constant<bool, [/see below] > {};
```

 $If \ R1::num * R2::den < R2::num * R1::den, \ ratio\_less \ derives \ from \ true\_type, \ else \ derives \ from \ false\_type.$ 



### SI typedefs

```
// convenience SI typedefs
typedef ratio<1LL, 100000000000000000LL> atto;
typedef ratio<1LL, 100000000000000LL> femto;
                     1000000000000LL> pico;
typedef ratio<1LL,
typedef ratio<1LL,
                         1000000000LL> nano;
typedef ratio<1LL,
                              1000000LL> micro;
typedef ratio<1LL,
                                 1000LL> milli;
                                   100LL> centi;
typedef ratio<1LL,
typedef ratio<1LL,
                                    10LL> deci;
typedef ratio<
                               10LL, 1LL> deca;
typedef ratio<
                              100LL, 1LL> hecto;
                             1000LL, 1LL> kilo;
typedef ratio<
                         1000000LL, 1LL> mega;
typedef ratio<
typedef ratio<
typedef ratio<</pre>
                     1000000000LL, 1LL> giga;
                   10000000000000LL, 1LL> tera;
typedef ratio< 10000000000000LL, 1LL> peta;
typedef ratio<100000000000000000LL, 1LL> exa;
```

#### **Limitations and Extensions**

Next follows limitation respect to the C++0x recomendations:

• Four of the typedefs in the recomendation which can be conditionally supported are not supported: yocto, zepto, zetta and yotta.

- Ratio values should be constexpr: constexpr don't used as no compiler supports it today. const is used instead when appropriated.
- Rational Arithmetic should use template aliases: In the absence of compiler support of template aliases the C++03 emulation define a nested typedef type.

The current implementation provides in addition:

the copy constructor and assignement between ratios having the same normalized form.

# Header <boost/ratio\_io.hpp>

It provides a textual representation of boost::ratio<N, D> in the form of a std::basic\_string. Other types such as boost::duration can use these strings to aid in their I/O.



This source has been adapted from the experimental header <ratio\_io> from Howard Hinnant. Porting to Boost has been trivial.

```
namespace boost {
   template <class Ratio, class CharT>
   struct ratio_string
   {
      static std::basic_string<CharT> short_name() {return long_name();}
      static std::basic_string<CharT> long_name();
   };
}
```

For each ratio<N, D> there exists a ratio\_string<ratio<N, D>, CharT> for which you can query two strings: short\_name and long\_name. For those ratio's that correspond to an SI prefix long\_name corresponds to the internationally recognized prefix, stored as a basic\_string<CharT>. For example ratio\_string<mega, char>::long\_name() returns string("mega"). For those ratio's that correspond to an SI prefix short\_name corresponds to the internationally recognized symbol, stored as a basic\_string<CharT>. For example ratio\_string<mega, char>::short\_name() returns string("M"). For all other ratio's, both long\_name() and short\_name() return a basic\_string containing "[ratio::num/ratio::den]".

ratio\_string<ratio<N, D>, CharT> is only defined for four character types:

- char
- char16\_t
- char32\_t
- wchar\_t

When the character is char, UTF-8 will be used to encode the names. When the character is char16\_t, UTF-16 will be used to encode the names. When the character is char32\_t, UTF-32 will be used to encode the names. When the character is wchar\_t, the encoding will be UTF-16 if wchar\_t is 16 bits, and otherwise UTF-32.

The short\_name for micro is defined by Unicode to be U+00B5.

#### **Examples:**



```
#include <boost/ratio/ratio_io.hpp>
#include <iostream>
int main()
    using namespace std;
    using namespace boost;
    cout << "ratio_string<deca, char>::long_name() = "
         << ratio_string<deca, char>::long_name() << '\n';</pre>
    cout << "ratio_string<deca, char>::short_name() = '
         << ratio_string<deca, char>::short_name() << '\n';</pre>
    cout << "ratio_string<giga, char>::long_name() = "
         << ratio_string<giga, char>::long_name() << '\n';
    cout << "ratio_string<giga, char>::short_name() = "
         << ratio_string<giga, char>::short_name() << '\n';</pre>
    cout << "ratio_string<ratio<4, 6>, char>::long_name() = "
         << ratio_string<ratio<4, 6>, char>::long_name() << '\n';</pre>
    cout << "ratio_string<ratio<4, 6>, char>::short_name() = "
         << ratio_string<ratio<4, 6>, char>::short_name() << '\n';</pre>
```

#### The output will be

```
ratio_string<deca, char>::long_name() = deca
ratio_string<deca, char>::short_name() = da
ratio_string<giga, char>::long_name() = giga
ratio_string<giga, char>::short_name() = G
ratio_string<ratio<4, 6>, char>::long_name() = [2/3]
ratio_string<ratio<4, 6>, char>::short_name() = [2/3]
```

# **Appendices**

## Appendix A: History

### Version 0.2.0, September 22, 2010

#### **Featurs:**

Added ratio\_string traits.

#### Fixes:

ratio\_less overflow avoided following the algorithm from libc++.

#### Test:

A more complete test has been included adapted from the test of from libc++/ratio.

## **Version 0.1.0, September 10, 2010**

#### Features:

• Ratio has been extracted from Boost.Chrono.



## **Appendix B: Rationale**

# Why ratio needs CopyConstruction and Assignment from ratios having the same normalized form

Current N3000 doesn't allows to copy-construct or assign ratio instances of ratio classes having the same normalized form.

This simple example

```
ratio<1,3> r1;
ratio<3,9> r2;
r1 = r2; // (1)
```

fails to compile in (1). Other example

```
ratio<1,3> r1;
ratio_substract<ratio<2,3>,ratio<1,3> > r2=r1; // (2)
```

The type of ratiosubstract<ratio<2,3>,ratio <1,3>> could be ratio<3,9> so the compilation could fail in (2). It could also be ratio<1,3> and the compilation succeeds.

#### Why ratio needs the nested normalizer typedef type

In N3000 20.4.2 and similar clauses

3 The nested typedef type shall be a synonym for ratio<T1, T2> where T1 has the value R1::num \* R2::den - R2::num \* R1::den and T2 has the value R1::den \* R2::den.

The meaning of synonym let think that the result should be a normalized ratio equivalent to ratio<T1, T2>, but there is not an explicit definition of what synonym means in this context.

If the CopyConstruction and Assignment ([LWG 1281) is not added we need a typedef for accessing the normalized ratio, and change 20.4.2 to return only this normalized result. In this case the user will need to

```
ratio<1,3>::type r1;
ratio<3,9>::type r2;
r1 = r2; // compiles as both types are the same.
```

## **Appendix C: Implementation Notes**

#### How Boost.Ratio manage with compile-time rational arithmetic overflow?

When the result is representable, but a simple application of arithmetic rules would result in overflow, e.g. ratio\_multiply<ratio<INTMAX\_MAX, 2>, ratio<2, INTMAX\_MAX>> can be reduced to ratio<1,1>, but the direct result of ratio<INTMAX\_MAX\*2, INT-MAX\_MAX\*2> would result in overflow.

Boost.Ratio implementes some simplifications in order to reduce the possibility of overflow. The general idea is to use the gcd of some of the possible products that can overflow, and simplify before doing the product.

## **Appendix D: FAQ**

## Appendix E: Acknowledgements

The library's code was derived from Howard Hinnant's time2\_demo prototype. Many thanks to Howard for making his code available under the Boost license. The original code was modified by Beman Dawes to conform to Boost conventions.



time2\_demo contained this comment:

Much thanks to Andrei Alexandrescu, Walter Brown, Peter Dimov, Jeff Garland, Terry Golubiewski, Daniel Krugler, Anthony Williams.

Thanks to Adrew Chinoff for his help polishing the documentation.

# **Appendix F: Tests**

In order to test you need to do.

bjam libs/ratio/test

You can also run a specific suite of test by doing

cd libs/chrono/test
bjam ratio

#### ratio

Name	kind	Description	Result	Ticket
typedefs.pass	run	check the num/den are correct for the predefined typedefs	Pass	#
ratio.pass	run	check the num/den are correctly simplified	Pass	#
ratio1.fail	compile-fails	The template argument D shall not be zero	Pass	#
ratio2.fail	compile-fails	the absolute values of the template arguments N and D shall be representable by type intmax_t	Pass	#
ratio3.fail	compile-fails	the absolute values of the template arguments N and D shall be representable by type intmax_t	Pass	#

#### comparison

Name	kind	Description	Result	Ticket
ratio_equal.pass	run	check ratio_equal metafunction class	Pass	#
ratio_not_equal.pass	run	check ratio_not_equal metafunction class	Pass	#
ratio_less.pass	run	check ratio_less metafunction class	Pass	#
ratio_less_equal.pass	run	check ratio_less_equal metafunction class	Pass	#
ratio_greater.pass	run	check ratio_greater metafunction class	Pass	#
ratio_greater_equal.pass	run	check ratio_greater_equal metafunction class	Pass	#



#### arithmetic

Name	kind	Description	Result	Ticket
ratio_add.pass	run	check ratio_add metafunction class	Pass	#
ratio_substract.pass	run	check ratio_substract metafunction class	Pass	#
ratio_multiply.pass	run	check ratio_multiply metafunction class	Pass	#
ratio_divide.pass	run	check ratio_divide metafunction class	Pass	#
ratio_add.fail	compile-fails	check ratio_add overflow metafunction class	Pass	#
ratio_substract.fail	compile-fails	check ratio_substract underflow metafunction class	Pass	#
ratio_multiply.fail	compile-fails	check ratio_multiply overflow metafunction class	Pass	#
ratio_divide.fail	compile-fails	check ratio_divide overflow metafunction class	Pass	#

# **Appendix G: Tickets**

Ticket	Description	Resolution	State
1	result of metafunctions ratio_multiply and ratio_divide were not normalized ratios	Use of the nested ratio typedef type on ratio arithmetic operations.	Closed
2	INTMAX_C is not always defined	Replace INTMAX_C by BOOST_INTMAX_C until boost/cstdint.hpp ensures INTMAX_C is always defined.	Closed
3	MSVC reports a warning instead of an error when there is an integral constant overflow	manage with MSVC reporting a warning instead of an error when there is an integral constant overflow	Closed
4	ration_less overflow on cases where it can be avoided	Change the algorithm as implemented in libc++	Closed

L

# **Appendix H: Future plans**

#### For later releases

Implement multiple arguments ratio arithmetic.

