WS4 Documentation & Reference

Anton Slavin anton@slavin.ee

Version 0.5 October 4, 2022

Introduction

TODO. WS4 is available at https://github.com/tonysln/ws4.

Contents

T	вас	ekgrouna	3
	1.1	WeatherSTAR 4000	3
	1.2	Restoration Efforts	3
	1.3	Simulators	3
	1.4	Differences	4
2	Fea	tures	5
	2.1	Available Screens ("Products")	5
	2.2	Locations	9
	2.3	Music	9
3	Sty	le Details	11
	3.1	Colors	11
	3.2	Fonts	12
	3.3	Icons	12
	3.4	Layout	12
	3.5	Computing Autorated Scores	13

4	Structure		14
	4.1	Storing Assets	14
	4.2	Drawing Graphics	14
	4.3	Fetching Data	14
5	Imp	plementation	15

1 Background

1.1 WeatherSTAR 4000

The primary purpose of WeatherStar units is to disseminate weather information for local forecast segments on The Weather Channel. The forecast and observation data – which is compiled from local offices of the National Weather Service (NWS), the Storm Prediction Center (SPC), and The Weather Channel (which began producing in-house forecasts in 2002, replacing the NWS-sourced zone forecasts that were utilized for the STAR's descriptive, regional and extended forecast products) – is received from the vertical blanking interval of the TWC video feed and from data transmitted via satellite; the localized data is then sent to the unit that inserts the data and accompanying programmed graphics over the TWC feed. The WeatherStar systems are typically programmed to cue the local forecast segments and Lower Display Line (LDL) at given times. The units are programmed to feature customized segments known as "flavors," pre-determined segment lengths for each local forecast segment, varying by the time of broadcast, accommodating the inclusion or exclusion of certain products from a segment's product list [3].

The Weather Star 4000 was the first WeatherStar model capable of displaying graphics. First developed in 1988, it was introduced in early 1990. Due to the cost of upgrading to more advanced units including the IntelliStar, the Weather Star 4000 remained in use in some smaller communities as late as 2014, although it was already being gradually phased out in some areas in favor of the more recent models at that time [3].

1.2 Restoration Efforts

Recently, multiple restoration efforts have started to restore the original WeatherSTAR 4000 units after purchasing them from markets or ...

Some notable cases include ...

...

1.3 Simulators

Besides original hardware restoration efforts, multiple simulators have been created by fans and programmers, including:

- Taiganet WS4K simulator by Bill et al
- WS4000+ online simulator

• ...

Additionally, fans have been recreating manual scenes using video editing software, such as ...

1.4 Differences

In comparison to the simulators and other efforts, WS4 does not aim to be a faithful replication of the original system. Instead, the goal is to create a modern, simple, fast, modular system with very close graphics and layouts, without the excruciating details copied over. The goal is to have a system that would run on a wide variety of hardware with easy setup. Most importantly, it is expected to be very stable in case any of the components fail - such as being able to draw graphics continuously despite not receiving any data for prolonged amount of time and then resuming normal operation.

2 Features

2.1 Available Screens ("Products")

Current Conditions



The Current Conditions Page is the first page that displays during the Local Forecast. It shows in every Local Forecast. It is driven by the primary and alternate sites of the STAR 4000. It displays the current weather conditions for that location. It is not forecast data, nor is it related to where the forecast comes from [2].

Latest Observations

```
THE Latest Observations 19:27
                °F WEATHER
                10 M Cloudy
Batavia
                             NNW6
Cincinnati Apt 8 P Cloudy
                                8
Dayton
                -1 Fair
                                 6
Hamilton
                -1 Fair
                             Calm
Lexington
                14 Lgt Snow
                             NW10
                10 Fair
Lunken Field
                             Calm
Wilmington
                 4 Fair
                             NNW5
        10 mi. Ceiling Unlin
Visib:
```

The Local Observations Page is the second page that usually displays during the Local Forecast. It shows in every Local Forecast. It is driven by the seven closest weather observation sites to the STAR 4000. It displays the current weather conditions for those locations. It is not forecast data [2].

Regional Observations Map



The Regional Observations Map only displays once an hour (usually the forecast :58 minutes after the hour) and is the fourth page that displays during the Local Forecast in that flavor. It is driven by the weather observation sites of the largest cities in the region around the STAR that will fit on the map. It displays the current weather conditions for those locations. It is not forecast data [2].

36-Hour Forecast Pages

The three 36-Hour Forecast pages display near the middle of The Local Forecast. It is driven by National Weather Service (NWS) zone, not primary or alternate site, and is considered narrative data. The forecast is generated by the NWS specifically for each county in the U.S. The forecast is not generated by The Weather Channel.

The first period of the time interval switches during the main update times. In the morning, after about 5 am local time, a 36-hour forecast should begin with the time period "This Morning" or "Today", not "Tonight". In the evening, after about 5 pm local time, the 36-hour forecast should begin with the period "This evening", "Overnight", or "Tonight", not "This Afternoon". If these time periods are still old, there may be a problem with the narrative data [2].



Regional Forecast Map



The Regional Forecast Map only displays once an hour (usually the forecast :58 minutes after the hour). It displays the forecast weather condition (icon) and high temperature for those locations in the region around the STAR on a map. It is forecast data [2].

Extended Forecast

The Extended Forecast displays in every Local Forecast and usually displays after the 36-Hour Forecast or Regional Forecast Map during the Local Forecast. The data (FE data) is driven by extended weather forecasts made TWC meteorologists for areas across the



country. It displays the forecast weather condition (icon), low and high temperature for those locations for a three day period. It is forecast data.

The FE data for these pages is sent at 5 am to adjust the days, and then updated 3 more times during the day. The 5 am update adjusts the day one day forward. For example, before 5 am on Tuesday, the 3 to 5 days will display as "Wed", "Thu", and "Fri". After 5 am on Tuesday, the days will display as "Thu", "Fri", and "Sat". Those days will display until 5 am Wednesday [2].

Almanac



The Almanac page displays once an hour (usually the forecast :58 minutes after the hour). The data is calculated on the STAR host based on the latitude/longitude of the climate station assigned to the Weather Display Area (WDA) the STAR is assigned. The data is then sent to the STARs a couple of times a day. It displays the sunrise/sunset times for the next 2 days. It also displays the next 4 moon phases and the dates of each phase.

The times are based on the local tie of the headend and follow the daylight savings time (DST) rules of the time zone and local laws of the headend (the states of Arizona and Hawaii, Puerto Rico, the Virgin Islands, and some counties in Indiana do not observe DST). The sunrise/sunset data is updated at midnight, local time [2].

Air Quality

...

Marine Forecast

...

Tides

...

Travel Forecast

• • •

Airport

...

2.2 Locations

Ideally all over the world... Highlights USA, Europe, Asia, Antarctica...

For USA, great API from the NWS and NOAA.

Other areas harder...

2.3 Music

Music from non-licensed sources, so not shared but easily supported. Some artists list for free (Patrick O'Hearn), also on YouTube...

Narration not supported.

- 1. Launch the AutoratingCalculator tool by double-clicking on its icon in Windows Explorer.
- 2. From the menu bar, select File>Import... or press Ctrl+I.

- 3. Select a group list file (*.txt, *.csv) to import from, e.g. DIT1234-Apr2013-groups.txt.
- 4. Autorating Calculator will then ask you for a new file name to save the new score list as (*.xml), e.g. DIT1234-Apr2013-Assgn1.xml.
- Make sure the .xml score filename selected does not already exist. Otherwise the existing score file may be overwritten without warning!
- 5. AutoratingCalculator imports the group lists and displays the student IDs and names in the main panel (Figure 1).

Figure 1: Imported group list

3 Style Details

What follows is a detailed description of all elements used in drawing screens for WS4. This can be used as a reference point for future builds, forks, updates and other similar projects. The goal is to collect the most exact and latest information and keep updating it here as a main reference point.

Starting off with simpler things like colors and fonts, this section will end with descriptions of how the layout is drawn in WS4, what are the components that go into it and in which order.

3.1 Colors

The following colors are defined for use in the whole WS4 application, for all screens. Each color is represented in hexadecimal and RGB forms, and contains examples on where the color is most often used in the interface.

Color	Hex	RGB	Usage
	#0e0e0e	(14,14,14)	Shadows
	#141414	(20,20,20)	Backdrops
	#d7d7d7	(215,215,215)	White Text
	#afafaf	(175,175,175)	LDL Gray Line
	#3d3d3d	(61, 61, 61)	Almanac BG
	#cdb900	(205,185,0)	Yellow Text
	#828af5	(130,138,245)	EF Panel Border
	#1c0a57	(28,10,87)	Main Background
	#233270	(35,50,112)	LDL Background
	#87230f	(135,35,15)	LDL Emergency BG
	#2e1251	(46,18,81)	Main Gradient Bot
	#c05d02	(192,93,2)	Main Gradient Top
	#c35b00	(195,91,0)	Top Bar BG 1
	#b25200	(178,82,0)	Top Bar BG 2
	#9d4b13	(157,75,19)	Top Bar BG 3
	#8e421a	(142,66,26)	Top Bar BG 4
	#7b3824	(123,56,36)	Top Bar BG 5
	#692e2e	(105,46,46)	Top Bar BG 6
	#592a3e	(89,42,62)	Top Bar BG 7
	#472240	(71,34,64)	Top Bar BG 8
	#7d3c28	(125,60,40)	Almanac Top BG
	#2652b2	(38,82,178)	Blue Pane Layer 1
	#254ba3	(37,75,163)	Blue Pane Layer 2
	#254698	(37,70,152)	Blue Pane Layer 3
	#24408c	(36,64,140)	Blue Pane Layer 4

#233a80	(35, 58, 128)	Blue Pane Layer 5
#223474	(34,52,116)	Blue Pane Layer 6
#222f69	(34,47,105)	Blue Pane Layer 7
#212b60	(33,43,96)	Blue Pane Layer 8
#21285a	(33,40,90)	Blue Pane Layer 9
#565bca	(86,91,202)	EF Panel Seg 1
#424eca	(66,78,202)	EF Panel Seg 2
#2c42ca	(44,66,202)	EF Panel Seg 3
#2539ca	(37,57,202)	EF Panel Seg 4
#0931ca	(9,49,202)	EF Panel Seg 5
#0028cb	(0,40,203)	EF Panel Seg 6
#0024cb	(0,36,203)	EF Panel Seg 7
#0022cb	(0,34,203)	EF Panel Seg 8

The colors were chosen by looking through hundreds of reference videos, photos, and simulator screenshots.

More detailed information on the usage of colors can be found in upcoming sections for layout ...

3.2 Fonts

Double-click on the name of a student in the list to display the peer review score entry window.

Font	Usage
Star4000	Most Text Labels
Star4000 Large	EF Temp Values
Star4000 Large Compressed	Map Temp Values
Star4000 Extended	CC Left-Side Info
STAR4000 SMALL	Clock, LO Headers

The fonts have been acquired from TWC Classics courtesy of Nick Smith [1].

3.3 Icons

You can also load the peer ratings entry window of a student by keying in the ID number in the search box, and then click on the Search button.

3.4 Layout

Some main elements present in screens ...

- 1. Main background (single color)
- 2. Main gradient ...

- 3. Top bar ...
- 4. Center panel ...
- 5. LDL (with two lines on top) over all content ...

Then any icons that have to be drawn and animated ...

Text on top of main elements ...

- 1. Date and time
- 2. Title of screen
- 3. Static text
- 4. Dynamic text
- 5. LDL overlay text

3.5 Computing Autorated Scores

- 1. When peer ratings of all students in a group has been entered and committed, click on the Compute Weights and Scores button. The computed weights and scores will be saved to file immediately.
- 2. Click on the Group Overview tab to see autorated weights and scores for each student in the group.

Figure 2: Autorated Weights and Scores of Group Members

- 4 Structure
- 4.1 Storing Assets
- 4.2 Drawing Graphics
- 4.3 Fetching Data

You may open an existing assignment score file (*.xml) to inspect scores, as well as to change settings and recalculate scores.

- 1. To open an existing score file, access the menu item File>Open...or press Ctrl+O.
- 2. Locate and select the *.xml file to open.

5 Implementation

The autorated scores can be exported for further processing in Excel

- 1. Select File>Export...from the menu, or Ctrl+E.
- 2. Select a file name to save the exported data in. The file will be saved with a .csv extension.
- 3. In Windows Explorer, locate the .csv file and double-click on it to open it in Excel.
- 4. If warning messages are displayed, keep on clicking OK or Yes to ignore them.
- 5. When the data is displayed, you may save the file as an .xlsx or .xsl Excel file, and continue processing it.

Figure 3: Exported data in Excel

References

- [1] Downloads / TWC Classics. https://twcclassics.com/downloads.html. Accessed: 2022-10-02.
- [2] The Weather Channel. WeatherSTAR 4000 Product Guide. https://web.archive.org/web/20061206001546/http://support.weather.com:80/affiliates/tech_support/display/product/star_4000/star4000_prod_gde.pdf. Accessed: 2022-10-02.
- [3] Wikipedia contributors. Weatherstar Wikipedia, the free encyclopedia. https://en.wikipedia.org/w/index.php?title=WeatherStar&oldid=1102858254, 2022. Accessed: 2022-10-02.