



TEST PROJECT

IT NETWORK SYSTEMS
ADMINISTRATION

LKS2020_NETWORK_Actual

Basic configuration

- 1. Configure hostnames for ALL devices according to the topology.
- 2. Configure domain name lksn2020.id for ALL network devices on the topology.
- 3. Create user lksn2020 on ALL devices.
 - (a) Remote and local console authentication should use local username database.
 - (b)After successful authentication user should automatically land in privileged mode (level 15)
- 4. Configure privileged mode access on **FW-01** and **TOF** using username's password. Example username **nusantara** with password **indonesia** should be able to enter privileged mode with password **indonesia**.
- 5. Create all necessary interfaces, subinterfaces and SVIs on ALL devices. Use IP addressing according to the table below.

Device	Interface	IP address
MOW	Gi0/0	132.87.2.100/24
	G0/1	192.168.254.1/30
KVX	Gi0/0	94.121.72.18/24
	G0/1	192.168.30.254/24
YKS	Gi0/0	18.31.192.12/24
	G0/1	192.168.40.254/24
FW-01	G1/0/1	192.168.254.2/30
	Vlan 10	192.168.10.254/24
	Vlan 20	192.168.20.254/24
DSW-01	Vlan 10	192.168.10.11/24
DSW-02	Vlan 20	192.168.20.12/24
RTK	Gi1/0/1	100.10.9.6/30
	Gi1/0/2	94.121.72.96/24

	Gi1/0/8	132.87.2.1/24
	Gi1/0/21	100.71.60.254/29
	Gi1/0/24	18.31.192.71/24
	Gi1/0/9	172.40.20.254/24
	Gi1/0/10	193.166.9.254/24
TOF	Gi1/6	100.10.9.5/30
	Gi1/2	172.16.100.254/24
TJM-01	Gi1/2	100.71.60.252/29
	Gi1/3	172.20.0.251/24
TJM-02	Gi1/2	100.71.60.251/29
	Gi1/3	172.20.0.252/24

HQ and Branch LAN

- Create VLANs on DSW-01 and DSW-02, assign names and ports according to the topology diagram. When adding any new VLAN to DSW-01, this VLAN should be automatically distributed to DSW-02.
- DSW-01 should initiate trunk negotiation via DTP and be STP root in ALL VLANs.
 Use non-default STP protocol. Make necessary configuration to prevent STP root change attacks.
- 3. Configure link aggregation between DSW-01 and DSW-02. Use any LAG protocol.
- 4. Make sure that end user devices are not waiting for STP recalculation when plugged into the network.
- 5. Configure DHCP scopes on Moscow, Kazan, Tyumen, Yakutsk and Sakhalin sites.
- 6. Ensure protection from DHCP attacks as well as from ARP-spoofing attacks on Moscow site.

Public Internet

 Configure internet routing domain according to the topology diagram. Use BGP with AS numbers from 65000-65005


Enterprise Routing

- 1. Configure enterprise routing domain according to the topology diagram. Use any dynamic routing protocol.
- 2. All traffic must be encrypted with IPsec while traversing via public internet.
- 3. Ensure end-to-end connectivity between all end user virtual machines inside enterprise routing domain.

Advanced Configuration

- Synchronize time on all network equipment using NTP (time zone WITA +8). Use
 RTK as the root NTP server. Configure hierarchical NTP infrastructure use MOW as a corporate NTP server.
- Enable SSH on all network devices and implement local user lksn2020 with password Passw0rd\$ with privilege level 15 (use only for VTY lines). Make sure SSH is accessible via anywhere.
- 3. Configure role-based access control on RTK router:
 - (a) Create user1, user2, user3, user4 and user5 with cisco1 password.
 - i. user1 should be authorized to issue all privileged mode commands except "show version" and "show ip route" but should be able to issue "show ip *" commands.
 - ii. **user2** should be authorized to issue all user (unprivileged) mode commands including "**show version**" but not "**show ip route**".
 - (b) Create view-context "show_view":
 - i. Include "show version" command
 - ii. Include all unprivileged commands of "show ip *"
 - iii. Include "who" command
 - iv. **user3** should land in this context after successful authentication on local or remote console.
 - (c) Create view-context "ping_view":
 - i. Include "ping" command
 - ii. Include "traceroute" command
 - iii. **user4** should land in this context after successful authentication on local or remote console.
 - (d) Create superview-context that combines these 2 contexts. **user5** should land in this superview-context after successful authentication on local or remote console.
 - (e) Make sure that users cannot issue any other commands within contexts that are assigned to them (except show banner and show parser, which are implicitly included in any view).
- 4. TJM-02 should act as stateless failover for all traffic from Tyumen towards the internet and enterprise routing domain and vice versa. In case of TJM-01 failure TJM-02 should take over all roles of TJM-01 so all network services will continue normal operation.
- 5. Implement necessary security measures on MOW site border to expose minimum services towards public internet.

Topology



Routing Diagram

