

# *Multi-Resolution Viscosity Limiter in the BLAST High-Order Finite Element Hydrodynamics Code*

LLNL HEDP Summer Student Presentations  
August 28, 2013

Truman E. Ellis

R. Rieben, Tz. Kolev, and V. Dobrev



This work was performed under the auspices of the U.S. Department of Energy by Lawrence Livermore National Laboratory under contract DE-AC52-07NA27344. Lawrence Livermore National Security, LLC



# Hydrodynamics

The evolution of the particles of a compressible fluid/solid in a Lagrangian reference frame is governed by the following system of differential equations:

## Euler's Equations

**Momentum Conservation:**  $\rho \frac{dv}{dt} = \nabla \cdot \sigma$

**Mass Conservation:**  $\frac{1}{\rho} \frac{d\rho}{dt} = -\nabla \cdot v$

**Energy Conservation:**  $\rho \frac{de}{dt} = \sigma : \nabla v$

**Equation of State:**  $p = EOS(e, \rho)$

**Equation of Motion:**  $\frac{dx}{dt} = v$

## Kinematics

$x$	-	position
$v$	-	velocity

## Thermodynamics

$\rho$	-	density
$e$	-	internal energy

## Stress Tensor


$$\sigma = -pI + \sigma_a$$

$p$	-	pressure
$\sigma_a$	-	artificial stress


- Time derivatives are along particle trajectories
- Space derivatives are with respect to a fixed coordinate system
- Domain:**  $\Omega(t) = \{x(t)\}$ ; **Total Energy:**  $E(t) = \int_{\Omega(t)} (\rho|v|^2/2 + \rho e)$

# The BLAST High Order Finite Element Hydrodynamics Code

- ▶ Curvilinear finite elements are used to more accurately represent deformations.
- ▶ Kinematic variables are represented with continuous fields, thermodynamic variables are represented with discontinuous fields (material interface).
- ▶ Strong mass conservation is achieved by defining density as a function within each zone.
- ▶ Uses the MFEM framework which allows arbitrarily high order basis functions.
- ▶ Corner forces are FLOP-intensive and can be computed independently for each zone and assembled later.



Triple-Point problem with Q8-Q7



Rayleigh-Taylor Instability with Q8-Q7

- ▶ <https://computation.llnl.gov/casc/blast/blast.html>
- ▶ Dobrev VA, Kolev TzV, Rieben RN. High order curvilinear finite element methods for Lagrangian hydrodynamics. SIAM J Sci Comput.

## Artificial Viscosity in BLAST

"Our idea is to introduce (artificial) dissipative terms into the equations so as to give the shocks a thickness comparable to (but preferably somewhat larger than) the spacing of the points of the network... Then the differential equations ...may be used for the entire calculation, just as though there were no shocks at all." – Von Neumann and Richtmyer

Ideally, an artificial viscosity implementation should:

- ▶ Always reduces kinetic energy (dissipate shocks)
- ▶ Vanish in smooth regions and in rarefaction
- ▶ Vanish in uniform contraction and rigid rotation
- ▶ Satisfy Rankine-Hugoniot jump conditions away from the shock
- ▶ Be Galilean invariant

## Artificial Stress in BLAST

$$\sigma_a = \mu \frac{1}{2} (\nabla v + v \nabla), \quad \text{where} \quad \mu \equiv \rho (q_2 l_s^2 |\Delta_s v| + q_1 l_s c_s).$$

- ▶ This allows us to robustly handle shocks, but limits our convergence to first order in smooth flow.

## Sub-Cell Shock Capturing of Persson and Peraire

- ▶ Shocks create oscillations in the highest polynomial modes.
- ▶ Persson and Peraire <sup>1</sup> do a change of basis to a hierarchical family of orthogonal polynomials, such that

$$u = \sum_{i=1}^{N(k)} u_i \psi_i,$$

where  $u$  is some function of the solution (velocity, entropy, etc).

- ▶ Define a truncated expansion

$$\tilde{u} = \sum_{i=1}^{N(k-1)} u_i \psi_i.$$

- ▶ Compute a piece-wise constant smoothness indicator using numerical quadrature,

$$s_z = \log_{10} \frac{(u - \tilde{u}, u - \tilde{u})_z}{(u, u)_z}.$$

- ▶ Turn this into an artificial viscosity that vanishes for smooth, resolved flow.
- ▶ In practice, this allows their high-order DG methods to achieve sub-zonal shock capturing.

---

<sup>1</sup>P. Persson, J. Peraire, Sub-Cell Shock Capturing for Discontinuous Galerkin Methods, 44th AIAA Aerospace Sciences Meeting and Exhibit, Reno, Nevada, 2007. AIAA-2007-513

## Multi-Resolution Viscosity Limiter in BLAST

- ▶ Persson and Peraire use discontinuous spaces, which makes the orthogonal basis expansion straight-forward.
- ▶ In BLAST, it makes more sense to do an  $L^2$  projection using our continuous velocity space.
- ▶ For  $\mathbf{v} \in Q_k$ , find  $\tilde{\mathbf{v}} \in Q_{k-1}$  such that

$$\int_{\Omega} \tilde{\mathbf{v}} \mathbf{w} dx = \int_{\Omega} \mathbf{v} \mathbf{w} dx \quad \forall \mathbf{w} \in Q_{k-1}.$$

In matrix vector form, this is

$$\mathbf{M}_{k-1} \tilde{\mathbf{v}} = \mathbf{g}_v.$$

- ▶ Use the difference as a shock detector which we call the smoothness.

$$s_z = \log_{10} ||\mathbf{v} - \tilde{\mathbf{v}}||_z^2.$$

- ▶ Define a viscosity limiter,

$$\psi_l = \begin{cases} 0 & \text{if } s_z \leq s_0 - \kappa \\ \frac{1}{2} \left( 1 + \sin \frac{\pi(s_z - s_0)}{2\kappa} \right) & \text{if } s_0 - \kappa < s_z < s_0 + \kappa \\ 1 & \text{if } s_z \geq s_0 + \kappa \end{cases}$$

where  $s_0$  and  $\kappa$  are tunable parameters that define the cutoff and transition region.

- ▶ Use the new limited viscosity.

$$\mu_l = \psi_l \mu$$

## High-order FEM overview: Time integration

Let  $Y = (\mathbf{v}; \mathbf{e}; \mathbf{x})$ . Then the semi-discrete equations can be written in the form:

$$\frac{dY}{dt} = \mathcal{F}(Y, t)$$

$$\mathcal{F}(Y, t) = \begin{pmatrix} \mathcal{F}_v(\mathbf{v}, \mathbf{e}, \mathbf{x}) \\ \mathcal{F}_e(\mathbf{v}, \mathbf{e}, \mathbf{x}) \\ \mathcal{F}_x(\mathbf{v}, \mathbf{e}, \mathbf{x}) \end{pmatrix} = \begin{pmatrix} -\mathbf{M}_v^{-1} \mathbf{F} \cdot \mathbf{1} \\ \mathbf{M}_e^{-1} \mathbf{F}^\top \cdot \mathbf{v} \\ \mathbf{v} \end{pmatrix}$$

Standard high-order time integration techniques (e.g. explicit Runge-Kutta methods) can be applied to this system of nonlinear ODEs.

The  $L^2$  projection is done at each stage of the integration and used in the artificial viscosity when computing  $\mathbf{F}$ .

For example, consider the **energy conserving** RK2Avg method:

$$\tilde{\mathbf{v}} = \mathbf{M}_{k-1}^{-1} \mathbf{g}_v$$

$$\mathbf{v}^{n+\frac{1}{2}} = \mathbf{v}^n - (\Delta t/2) \mathbf{M}_v^{-1} \mathbf{F}^n \cdot \mathbf{1}$$

$$\mathbf{e}^{n+\frac{1}{2}} = \mathbf{e}^n + (\Delta t/2) \mathbf{M}_e^{-1} (\mathbf{F}^n)^\top \cdot \mathbf{v}^{n+\frac{1}{2}}$$

$$\mathbf{x}^{n+\frac{1}{2}} = \mathbf{x}^n + (\Delta t/2) \mathbf{v}^{n+\frac{1}{2}}$$

$$\tilde{\mathbf{v}} = \mathbf{M}_{k-1}^{-1} \mathbf{g}_v$$

$$\mathbf{v}^{n+1} = \mathbf{v}^n - \Delta t \mathbf{M}_v^{-1} \mathbf{F}^{n+\frac{1}{2}} \cdot \mathbf{1}$$


$$\mathbf{e}^{n+1} = \mathbf{e}^n + \Delta t \mathbf{M}_e^{-1} (\mathbf{F}^{n+\frac{1}{2}})^\top \cdot \tilde{\mathbf{v}}^{n+\frac{1}{2}}$$

$$\mathbf{x}^{n+1} = \mathbf{x}^n + \Delta t \tilde{\mathbf{v}}^{n+\frac{1}{2}}$$

# Taylor Green Vortex, $s_0 = -11$ , $\kappa = 1$


- On coarse meshes, the indicator does not detect sufficient smoothness in the solution to turn off viscosity.
- With sufficient resolution, the indicator shuts down all viscosity and we recover higher order convergence rates.

Q2-Q1




Smoothness


Q4-Q3



Smoothness




Limiter



Limiter


Taylor-Green Convergence



## Taylor Green Vortex, $s_0 = -11$ , $\kappa = 1$


- On coarse meshes, the indicator does not detect sufficient smoothness in the solution to turn off viscosity.
- With sufficient resolution, the indicator shuts down all viscosity and we recover higher order convergence rates.

Q2-Q1




Smoothness

Q4-Q3




Smoothness

Limiter




Limiter








Limiter

Taylor-Green Convergence



# Taylor Green Vortex, $s_0 = -11$ , $\kappa = 1$


- On coarse meshes, the indicator does not detect sufficient smoothness in the solution to turn off viscosity.
- With sufficient resolution, the indicator shuts down all viscosity and we recover higher order convergence rates.



# Taylor Green Vortex, $s_0 = -11$ , $\kappa = 1$


- On coarse meshes, the indicator does not detect sufficient smoothness in the solution to turn off viscosity.
- With sufficient resolution, the indicator shuts down all viscosity and we recover higher order convergence rates.

Q2-Q1



Smoothness


Q4-Q3



Smoothness




Limiter








Limiter

Taylor-Green Convergence








# Sod Shock Tube, $s_0 = -9.5$ , $\kappa = 0.5$

Q4-Q3 elements on a 50x1 mesh




# Sod Shock Tube, $s_0 = -9.5$ , $\kappa = 0.5$

Q4-Q3 elements on a 50x1 mesh




# Sedov Blast Wave, $s_0 = -9.5$ , $\kappa = 0.5$


Q2-Q1 elements on an 80x80 mesh




Smoothness




Viscosity with Limiter




Density with Limiter



Limiter




Viscosity without Limiter




Velocity with Limiter

# Noh Implosion, $s_0 = -9.5$ , $\kappa = 0.5$


Q2-Q1 elements on an 128x128 mesh




Smoothness




Viscosity with Limiter




Density with Limiter



Limiter




Viscosity without Limiter




Velocity with Limiter


## Noh Implosion, $s_0 = -9.5$ , $\kappa = 0.5$




Density with Limiter



Density without Limiter









Mesh with Limiter



Mesh without Limiter

# Triple Point Shockwave, $s_0 = -9.5$ , $\kappa = 0.5$



# Conclusions

## What have we done?

- ▶ Current implementation of artificial viscosity limits our convergence to first order.
- ▶ Need a limiter which turns off viscosity for smooth flow.
- ▶ Project velocity onto a lower order space and measure the difference as a shock detector.
- ▶ Turn off viscosity any time the detector falls below a certain threshold.

## Does it make a difference?

- ▶ We recover high order convergence for Taylor-Green after we achieve sufficient resolution.
- ▶ For most shock problems we eliminate excess viscosity.
- ▶ Our limiter eliminates too much viscosity in the Noh problem.
- ▶ Field variables appear little changed in other problems.

## What can we do to improve on these results?

- ▶ Consider making  $s_0$  and  $\kappa$  functions of  $h$  and/or  $p$ .
- ▶ Try using physical mass matrices in  $L^2$  projection.
- ▶ Experiment with other trigger variables.
- ▶ Explore the possibility expanding velocity in terms of orthonormal Legendre polynomials.
- ▶ Try using the detector as a viscosity itself, rather than a limiter.