



# **Bits and Bitwise Operations**

Bits, Numerals Systems and Bitwise Operations











**SoftUni Team Technical Trainers** 







https://softuni.bg

## **Table of Contents**



- 1. What is a Bit, Byte, KB, MB?
- 2. Numerals Systems
  - Decimal, Binary, Hexadecimal
  - Conversion between Numeral Systems
- 3. Representation of Data in Computer Memory
  - Representing Integers, Real Numbers and Text
- 4. Bitwise Operations: &, I, ^, ~
  - Reading / Writing Bits from Integers



# Have a Question?



# sli.do

# #fund-common



#### Bit





- Takes only one of two values: either a 0 or 1
- 1 bit can store anything with two separate states
  - Logical values (true / false)
  - Algebraic signs (+ / -)
  - Activation states (on / off)
- Bits are organized in computer memory in sequences of 8 bits, called bytes (octets)



# Bit, Byte, KB, MB, GB, TB, PB



- Bit single 0 or 1, representing a bit of data
- Byte (octet) == 8 bits == the smallest addressable unit in the computer memory
- KB (kilobyte) == 1024 bytes (sometimes 1000 bytes)
- MB (megabyte) == 1024 KB == 1048576 bytes
- GB (gigabyte) == 1024 MB == 1073741824 bytes
- TB (terabyte) == 1024 GB == 1099511627776 bytes
- PB (petabyte) == 1024 TB == 1125899906842624 bytes



# 101<sub>b</sub> 0x8

# **Numerals Systems**

Decimal, Binary and Hexadecimal

# **Numeral Systems**





- Positional numeral systems == the value of each digit depends on its position
  - These numeral systems has a base (e.g. 2, 10, 16)

Decimal	Binary	Hexadecimal			
(base = 10)	(base = 2)	(base = 16)			
30	111110	1E			
45	101101	2D			
60	111100	3C			



#### **Decimal Numbers**



- Decimal numbers (base 10)
  - Represented using 10 digits:
    - **0**, 1, 2, 3, 4, 5, 6, 7, 8, 9
  - Each position represents a power of 10

$$401 = 4*10^{2} + 0*10^{1} + 1*10^{0} =$$

$$= 4*100 + 0*10 + 1*1 =$$

$$= 400 + 0 + 1 = 401$$

• A decimal number  $d_{n-1}d_{n-2}...d_1d_0 = d_0*10^0 + d_1*10^1 + d_2*10^2 + ... + d_{n-1}*10^{n-1}$ 



# **Binary Numbers**



- The binary system is used in computer systems
- Binary numbers (base 2)
  - Represented by sequence of 0 or 1

Each position represents a power of 2

$$101_b = 1*2^2 + 0*2^1 + 1*2^0 = 4 + 0 + 1 = 5$$

$$1010_{b} = 1*2^{3} + 0*2^{2} + 1*2^{1} + 0*2^{0} = 8 + 0 + 2 + 0 = 10$$



# **Binary and Decimal Conversion**



#### Binary to decimal

 Multiply each digit to its magnitude (power of 2)

$$1011_{b} = 1*2^{3} + 0*2^{2} + 1*2^{1} + 1*2^{0} =$$

$$= 1*8 + 0*4 + 1*2 + 1*1 =$$

$$= 8 + 0 + 2 + 1 =$$

$$= 11$$

#### Decimal to binary

Divide to the base (2) until
 0 is reached and take the
 reminders in reversed order


```
11 / 2 = 5 (1) // last digit
5 / 2 = 2 (1) // previous digit
2 / 2 = 1 (0) // previous digit
1 / 2 = 0 (1) // fist digit
Result: 1011
```



# **Problem: Binary Digits Count**



- You are given a positive integer n and a binary digit b (0 or 1)
- Write a program that finds the count of b digits in the binary representation of n



# **Solution: Binary Digits Count**



- 1. Read the input from the user: n and b
- Convert the input to binary system (collect the reminders of division by 2)
- 3. Count the digits b in the reminders of n
- 4. Print the count

Another solution is to use bitwise operations (think how later)

#### **Hexadecimal Numbers**



- Hexadecimal numbers (base 16)
  - Represented using 16 literals (hex digits)
    - 0, 1, 2, 3, 4, 5, 6, 7, 8, 9, A, B, C, D, E and F
- Usually prefixed with 0x in computer science
- Each position represents a power of 16

$$0xB7F6 = B*16^3 + 7*16^2 + F*16^1 + 6*16^0 =$$

$$= 11*4096 + 7*256 + 15*16 + 6*1 =$$

$$= 45056 + 1792 + 240 + 6 = 47094$$



#### **Hex** ← Decimal Conversions



#### Hexadecimal to decimal

 Multiply each digit to its weight (power of 16)

#### Decimal to hexadecimal

 Divide by 16 and take the reminders in reversed order



# **Hex** ← Binary Conversions



- The conversion from binary to hexadecimal (and back) is straightforward
  - Each hex digit corresponds to a sequence of 4 binary digits

```
A2E3F = 1010 0010 1110 0011 1111

A = 1010

2 = 0010

E = 1110

3 = 0011

F = 1111
```

```
1010 0010 1110 0011 1111 = A2E3F

1010_b = 10_{dec} = A_{hex}

0010_b = 2_{dec} = 2_{hex}

1110_b = 14_{dec} = E_{hex}

0011_b = 3_{dec} = 3_{hex}

1111_b = 15_{dec} = F_{hex}
```



# Representation of Data

Integers, Floating-Point Numbers and Text

# Representing Integers in Memory



- Integer numbers are sequences of bits
- Can be signed (in most cases) or unsigned
  - The sign == the Most Significant Bit (MSB)
  - Leading 0 → positive number
  - Leading 1 → negative number
- Example (8-bit signed integers)



# Representation of Signed Integers



- Positive 8-bit numbers have the format OXXXXXXX
  - The value is the decimal value of their last 7 bits (XXXXXXXX)
- Negative 8-bit numbers have the format 1YYYYYYYY
  - The value is -128 (-27) + the decimal value of YYYYYYY

$$10010010_{b} = -2^{7} + 0010010_{b} =$$
 $= -128 + 18 =$ 
 $= -110$ 

# **Largest and Smallest Signed Integers**



The largest signed 8-bit integer is:

$$127 = (2^7 - 1) = 21111111_b$$

The smallest negative 8-bit integer is:

$$-128 = -(2^7) = 10000000_b$$

-27

The largest signed 32-bit integer is:

$$2147483647 = (2^{31} - 1) = 2111...1111_b$$

**2**<sup>31</sup>-1

The smallest negative 32-bit integer is:

$$-2147483648 = -(2^{31}) = 1000...0000_{b}$$

**-2**<sup>31</sup>

# Integers and Their Ranges in Programming



Bits	Sign	Range	Data Types
8-bit	signed	-128 127 (-2 <sup>7</sup> 2 <sup>7</sup> -1)	<b>sbyte</b> in C#, <b>byte</b> in Java
8-bit	unsigned	0 255 (2 <sup>0</sup> 2 <sup>8</sup> -1)	<b>byte</b> in C#
16-bit	signed	-32768 32767 (-2 <sup>15</sup> 2 <sup>15</sup> -1)	<pre>short in C#, short in Java</pre>
32-bit	signed	-2,147,483,648 2,147,483,647 (-2 <sup>31</sup> 2 <sup>31</sup> -1)	<pre>int in C#, int in Java</pre>

# **Representing Real Numbers**





- Computers use the floating-point number format,
   defined by the IEEE 754 technical standard
- The IEEE-754 standard defines:
  - Arithmetic and exchange formats representations of the binary and decimal floating-point data
  - Rounding rules for floating-point numbers
  - Operations arithmetic and other operations
  - Special numbers such as infinity and NaN

# **Storing Floating-Point Numbers**



Floating-point numbers are stored as sequence of bits:

sign bit, exponent and mantissa

32 Bits

Play with the **IEEE-754 converter online**:

https://h-schmidt.net/FloatConverter/IEEE754.html



- Note: errors in calculations and precision may occur
  - Some numbers (e.g. 0.3) cannot be represented in the above format without rounding (as a sum of negative powers of 2)

# **Representing Text**





- Letters, digits, punctuation chars, etc.
- The ASCII standard represent chars as 8-bit integers
  - Defines the ASCII code for 127 chars, e.g.

Bir	nary	Dec	Hex	Char
0b01	000001	65	0x41	A
0b01	000010	66	0x42	В
0b00	101011	43	0x2B	+



# Representing Unicode Text



■ The Unicode standard represents 100,000+ text characters as 16-bit integers (see unicode.org)



Decimal	Hex	Char	Explanation
65	0x0041	Α	Latin "A"
1097	0x0449	Щ	Cyrillic letter "Sht"
1576	0x0628	<u></u>	Arabic letter "Beh"
127928	0x1F3B8		Emoji "Guitar"


- UTF-16 uses 2 bytes (16 bits) for each char
- UTF-8 uses 1, 2, 3 or 4 bytes for each char




# **Sequences of Characters**



- Strings represent text data in programming
  - Strings are arrays of characters, typically represented like this:



- The string can have its size as prefix (used in most languages)
   or can end with \0 (null-terminated string used in C)
- Characters in the string can be:
  - 16-bit (UTF-16) default in C#, Java, JS, Python
  - 8-bit (ASCII / windows-1251) default in C, C++



# **Bitwise Operations**

Bitwise Operators and Bit Shifts

# **Bitwise Operators**



- Bitwise operators works with the binary representations of the numbers, applying bit by bit calculations
- The operator ~ turns all ② to 1 and all 1 to ② (like! for boolean expressions but bit by bit)
- The operators |, & and ^ behave like | |, && and ^ for boolean expressions but bit by bit

Operator	1	1	1	1	&	&	&	&	٨	٨	٨	٨
Operand1	0	0	1	1	0	0	1	1	0	0	1	1
Operand2	0	1	0	1	0	1	0	1	0	1	0	1
Result	0	1	1	1	0	0	0	1	0	1	1	0



# **Bitwise Operators – Examples**



Bitwise NOT (~)

```
5 // 0101
~5 // 1010
```

Bitwise AND (&)

```
5  // 0101
3  // 0011
5 & 3  // 0001
```

Bitwise OR ( )

```
5  // 0101
3  // 0011
5  3  // 0111
```

Bitwise XOR (^)

```
5 // 0101
3 // 0011
5 ^ 3 // 0110
```

#### **Bit Shifts**




- Bit shifts are bitwise operations, where
  - Bits are moved (shifted) to the left or right
  - The bits that fall outside the number are lost and replaced by 0



 1
 1
 0
 1
 0
 0
 1
 1
 0

 1
 0
 1
 0
 0
 1
 1
 0

Right shift (>> operator)





# Bitwise Operations: Get the Last Bit



- How to get the last bit from a number n?
  - The bits are numbered from 0, from right to the left
  - The position of the last (rightmost) bit is 0

```
n = 125 // 01111101
mask = 1 // & 00000001
n & mask // 00000001 = 1
```

```
7 6 5 4 3 2 1 0
n = 0 1 1 1 1 1 0 1
lastBit = 1
```

Last bit – formula:

# **Bitwise Operations: Get Bit at Position**



• How to get the bit at position p from a number n?

```
n = 125  // 01111101

p = 5  // 5<sup>th</sup> position

125 >> p  // 00000011 = 3

3 & 1  // 00000001 = 1
```

p = 5

7 6 5 4 3 2 1 0

n = 0 1 1 1 1 1 0 1

bit value = 1

Bit at position – formula:

# Bitwise Operations: Set Bit at Position



- How to set the bit at given position p to 0 or 1?
  - Clear a bit (0) at position p

Set a bit (1) at position p

Assign a bit b (0 or 1) at position p – formula:

$$n = n \& \sim (1 << p) | (b << p)$$

# Why We Need Bitwise Operations?



#### Networking protocols

- Many devices communicate using bit-level protocols
- E.g. the SYN flag in the TCP protocol header is the bit #1 from the 14<sup>th</sup> byte in the TCP packets
  - Web browsers use bitwise operations to connect to a Web site
- Many binary file formats use bits to save space
  - E.g. PNG images use 3 bits to specify the color format used
- Data compression replaces byte sequences with bit sequences
  - E.g. the DEFLATE algorithm in ZIP files

# Problem: Bit #1 (the Bit Before the Last)




Write a program that prints the bit at position 1 of an integer

51 
$$\implies$$
 1 51 == 00110011 24  $\implies$  0 24 == 00011000

13  $\implies$  0 13 == 00001101 2  $\implies$  1 2 == 00000010

Solution:



# **Summary**



- Computers store data using bits
  - Signed integers (leftmost bit == sign)
  - IEEE-754 floating point numbers
  - Text is stored using ASCII / Unicode / other
- Binary and hexadecimal numeral systems play a key role in computing
- Developers manipulate bits in integers using bitwise operators and bit masks





# Questions?



















### **SoftUni Diamond Partners**










































# **Educational Partners**





# Trainings @ Software University (SoftUni)



- Software University High-Quality Education,
   Profession and Job for Software Developers
  - softuni.bg, softuni.org
- Software University Foundation
  - softuni.foundation
- Software University @ Facebook
  - facebook.com/SoftwareUniversity
- Software University Forums
  - forum.softuni.bg









#### License



- This course (slides, examples, demos, exercises, homework, documents, videos and other assets) is copyrighted content
- Unauthorized copy, reproduction or use is illegal
- © SoftUni <a href="https://softuni.org">https://softuni.org</a>
- © Software University <a href="https://softuni.bg">https://softuni.bg</a>

