## 1 Maxwell's Equations

Gauss's Law for Electricity (GLE)

$$\iint \vec{E} \cdot d\vec{a} = \frac{Q}{\epsilon_0}$$

$$\iiint (\nabla \cdot \vec{E}) \ dV = \frac{\iiint \rho \ dV}{\epsilon_0}$$

$$\nabla \cdot \vec{E} = \frac{\rho}{\epsilon_0}$$

Faraday's Law of Induction (FLI)

$$\int \vec{E} \cdot d\vec{l} = -\frac{d\Phi_B}{dt}$$

$$\iint (\nabla \times \vec{E}) \cdot d\vec{a} = -\frac{d}{dt} \iint \vec{B} \cdot d\vec{a}$$

$$\nabla \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$$

Lorentz Force Law (LFL)

$$\vec{F} = q\vec{E} + q\vec{v} \times \vec{B}$$

Gauss's Law for Magnetism (GLM)

$$\iint \vec{B} \cdot d\vec{a} = 0$$

$$\iint (\nabla \cdot \vec{B}) \ dV = 0$$

$$\nabla \cdot \vec{B} = 0$$

Maxwell-Ampere's Law (MAL)

$$\oint \vec{B} \cdot d\vec{l} = \mu_0 \left( I + \epsilon_0 \frac{d\Phi_E}{dt} \right)$$

$$\iint (\nabla \times \vec{B}) \cdot d\vec{a} = \mu_0 \iint \vec{J} \cdot d\vec{a} + \mu_0 \epsilon_0 \frac{d}{dt} \iint \vec{E} \cdot d\vec{a}$$

$$\nabla \times \vec{B} = \mu_0 \left( \vec{J} + \epsilon_0 \frac{\partial \vec{E}}{\partial t} \right)$$

#### Conservation of Charge (COC)

$$\begin{bmatrix} \frac{\partial}{\partial t} \end{bmatrix} \left( \nabla \cdot B = 0 \right) \leftarrow \left( \nabla \times E = -\frac{\partial B}{\partial t} \right)$$
$$\left[ \nabla \cdot \right] \left( \nabla \times E = -\frac{\partial B}{\partial t} \right) \leftarrow \left( \nabla \cdot B = 0 \right)$$

#### Laplacian

$$\nabla^2 B = -\mu_0(\nabla \times J) - \nabla \times \frac{\partial E}{\partial t}$$
$$\left[\nabla\right] \left(\nabla \cdot B = 0\right) \leftarrow \left(\nabla \times B = \mu_0 J + \frac{1}{c^2} \frac{\partial E}{\partial t}\right)$$

#### D'alambertian

#### Special Cases 1.1

Zero Fields:

$$\frac{\text{Zero Fields}:}{\partial_t B = 0 = \nabla \times E} \Rightarrow \begin{bmatrix} \nabla^2 E = \frac{\nabla \rho}{\epsilon_0} \end{bmatrix}, \begin{bmatrix} \nabla^2 B = -\mu_0(\nabla \times J) \end{bmatrix} \\ , \begin{bmatrix} \epsilon_0 \frac{\partial^2 E}{\partial t^2} = -\frac{\partial J}{\partial t} \end{bmatrix} \\ \partial_t E = 0 = \nabla \times B - \mu_0 J \Rightarrow \begin{bmatrix} \frac{\partial \rho}{\partial t} = 0 \end{bmatrix}, \begin{bmatrix} \nabla^2 B = -\mu_0(\nabla \times J) \end{bmatrix} \\ \begin{bmatrix} \frac{\partial \rho}{\partial t} = 0 \end{bmatrix}, \begin{bmatrix} \nabla^2 B = -\mu_0(\nabla \times J) \end{bmatrix}$$

• 
$$\partial_t B$$
,  $\partial_t E = 0 \Rightarrow \frac{\partial J}{\partial t}$ ,  $\frac{\partial \rho}{\partial t} = 0$  •  $\rho$ ,  $J = 0 \Rightarrow \Box^2 E$ ,  $\Box^2 B = 0$ 

From Jefimenko:

$$\frac{\partial J}{\partial t} = 0 \implies \left[ \partial_t B = 0 \right] \implies \begin{pmatrix} \frac{\partial^2 E}{\partial t^2} = 0 \\ \nabla^2 E = \frac{\nabla \rho}{\epsilon_0} \end{pmatrix}$$

$$\frac{\partial \rho}{\partial t} = 0 , \quad \frac{\partial^2 J}{\partial t^2} = 0 \implies \left[ \partial_t E = 0 \right]$$

• 
$$\frac{\partial \rho}{\partial t}$$
,  $\frac{\partial J}{\partial t} = 0 \Rightarrow \partial_t B$ ,  $\partial_t E = 0$ 

Slight rationalization:

$$\frac{\partial J}{\partial t} = 0 \implies \left[ \partial_t B = 0 \right] \implies \begin{pmatrix} \frac{\partial^2 E}{\partial t^2} = 0 \\ \nabla^2 E = \frac{\nabla \rho}{\epsilon_0} \end{pmatrix} \qquad \text{If } \frac{\partial \rho}{\partial t} = \mathbf{0} : \quad -\frac{\partial Q}{\partial t} = \oiint J \cdot da = I|_a = 0 = \frac{\partial I}{\partial a}$$

$$\text{If } \frac{\partial J}{\partial t} = \mathbf{0} : \iint \frac{\partial J}{\partial t} \cdot da = \frac{\partial I}{\partial t} = 0$$

$$\bullet \ I(a,t) = I_0$$

• 
$$\partial_t \left( E = k \int \frac{\rho \hat{\imath} dV}{\|\vec{\imath}\|^2} \right) = 0$$
  
 $\rightarrow \nabla \times B = \mu_0 J \rightarrow B = k_\mu \int \frac{I d\vec{l} \times \hat{\imath}}{\|\vec{\imath}\|^2}$ 

• 
$$\partial_t B = 0$$

$$** \left[ rac{\partial E}{\partial t} \; , \; rac{\partial B}{\partial t} = 0 \; \Leftrightarrow \; rac{\partial 
ho}{\partial t} \; , \; rac{\partial J}{\partial t} = 0 
ight] **$$

(proof?) Single charges do not constitute a current. Free charges (unaffected by external forces holding them) will always, by selfinteraction through their E-field, create an unconstant current and thus unconstant B-field. Under static conditions, a free space must have a  $\rho = 0$ .

Electrostatic Metal Conductors (when J = 0 = B)

$$\begin{split} \bullet & \rho(\vec{r}_m) = 0 \implies E = E_{!m} \\ & \left[ \underline{\vec{E}}_{!m\perp}(\vec{b}) = 0 \implies \oint_{l \in B} \vec{E} \cdot d\vec{i} = 0 \right] \Leftrightarrow \left[ \phi_{!m}(\vec{b}) = \phi_0 \right] \\ & \wedge & \vec{E}_{!m}(\vec{r}_m) \neq 0 \implies \oint_{l \in B, V_m} \vec{E} \cdot d\vec{i} \neq 0 \quad \mathbf{Z} \\ & \Rightarrow & \underline{\vec{E}}_{!m}(\vec{r}_m) = 0 \quad , \quad \phi_{!m}(\vec{r}_m) = \phi_0 \\ & \vec{E}_{!m}(\vec{r}_m) \neq 0 \quad (\text{circuit wire } J = J_0) \implies \nabla^2 E = \frac{\nabla \rho}{\sigma} \end{split}$$

# 1.2 Electrostatic/Magnetostatic Examples Using GLE

#### 1. Point Charges

$$\vec{E} = E(r)\hat{r}$$

$$\frac{Q}{\epsilon_0} = \oiint E(r)\hat{r} \cdot d\vec{a}$$

$$= E(r)\hat{r} \cdot \oiint r^2 \sin \phi |d\vec{\phi} \times d\vec{\theta}|$$

$$= E(r)\hat{r} \cdot 4\pi r^2 \hat{r}$$

$$\vec{E}(r) = \frac{Q}{4\pi\epsilon_0 r^2} \hat{r} \implies \frac{1}{4\pi\epsilon_0} \sum_i \frac{Q_i}{|\vec{z}_i|^2} \hat{z}_i$$

#### Coulomb's Law (CL):

$$\vec{E}(\vec{\mathbf{r}}) = \frac{1}{4\pi\epsilon_0} \int \frac{dQ}{|\vec{\boldsymbol{z}}|^2} \hat{\boldsymbol{z}} \qquad \vec{\mathbf{r}} \in \mathbb{R}^3, \ \vec{\boldsymbol{z}} = \vec{\mathbf{r}} - \vec{l'}$$

$$\vec{F}(\vec{\mathbf{r}}) = q\vec{E}$$

#### Using MAL

Biot-Savart Law (BSL):

(see potential,  $\vec{A}$ , for derivation)

$$\vec{B}(\vec{\mathbf{r}}) = k_{\mu} \int \frac{\vec{J}dV \times \hat{\boldsymbol{\imath}}}{|\vec{\boldsymbol{\imath}}|^2}, \qquad \vec{\mathbf{r}} \in \mathbb{R}^3, \quad \vec{\boldsymbol{\imath}} = \vec{\mathbf{r}} - \vec{l'}$$
$$= k_{\mu} \int \frac{I(\vec{v}) \ d\vec{l'} \times \hat{\boldsymbol{\imath}}}{|\vec{\boldsymbol{\imath}}|^2}$$

$$\vec{F} = q\hat{v} \times \vec{B}$$

1. Infinite Line w/ Steady Current (SC)

$$\vec{B} = B(r)\hat{\theta}$$

Use MAL

$$\mu_o I = \oint B(r)\hat{\theta} \cdot d\vec{L}$$
$$= B(r)\hat{\theta} \cdot \oint r d\vec{\theta}$$
$$= B(r)\hat{\theta} \cdot 2\pi r \hat{\theta}$$

$$\vec{B}(r) = \frac{\mu_0 I}{2\pi r} \hat{\theta}$$

cont.

## 2. Sphere w/ Constant Charge Density (CCD)

Let R be the radius.

$$\vec{E}(r) = \frac{Q(r)}{4\pi\epsilon_0 r^2} \hat{r}$$

$$Q(r) = \begin{cases} Q & (r > R) \\ Q_{r < R} = \iiint_0^r \frac{dQ}{dV} dV & (r < R) \end{cases}$$

• Conductor

$$Q_{r < R} = 0$$
  $\Rightarrow$   $\vec{E}(r) = \begin{cases} \frac{Q}{4\pi\epsilon_0 r^2} \hat{r} & (r > R) \\ 0 & (r < R) \end{cases}$ 

• Insulator w/ CCD and  $\epsilon = \epsilon_0$ 

$$Q_{r < R} = \int \frac{Q}{V} dV = Q \frac{\int dV}{V} = Q \frac{r^3}{R^3}$$

$$\Rightarrow \vec{E}(r) = \begin{cases} \frac{Q}{4\pi\epsilon_0 r^2} \hat{r} & (r > R) \\ \frac{Qr}{4\pi\epsilon_0 R^3} \hat{r} & (r < R) \end{cases}$$

Use BSL

$$\vec{B}(r) = \frac{\mu_0 I}{4\pi} \int \frac{d\vec{z} \times \hat{\boldsymbol{\imath}}}{|\vec{\boldsymbol{\imath}}|^2}$$

$$= \frac{\mu_0 I}{4\pi} \int_{-\infty}^{\infty} \frac{d\vec{z} \times \hat{\boldsymbol{\imath}}}{r^2 + z^2}$$

$$= \frac{\mu_0 I}{4\pi} \int_{-\infty}^{\infty} \frac{d\vec{z} \times (r\hat{r} - z\hat{z})}{(r^2 + z^2)^{3/2}}$$

$$= \frac{\mu_0 I r}{4\pi} \int_{-\infty}^{\infty} \frac{dz}{(r^2 + z^2)^{3/2}} \hat{\theta}$$

$$= \frac{\mu_0 I r}{4\pi} \frac{z}{r^2 \sqrt{r^2 + z^2}} \Big|_{-\infty}^{\infty} \hat{\theta}$$

$$= \frac{\mu_0 I}{2\pi r} \hat{\theta}$$

#### Constant Field Solutions (Capacitor/Solenoid)

# 3. Two Infinite Parallel Planes Capacitor w/ CCD (+Q, -Q)

$$\vec{E} = E(z)\hat{z}$$

$$\frac{Q}{\epsilon_0} = \oiint E(z)\hat{z} \cdot d\vec{a}$$

$$= E(z)\hat{z} \cdot \oiint xy |d\vec{x} \times d\vec{y}|$$

$$= E(z)\hat{z} \cdot xy\hat{z}$$

$$\vec{E}(z) = \frac{1}{\epsilon_0} \frac{dQ}{dA} \hat{z} = \frac{\sigma}{\epsilon_0} \hat{z}$$

#### 4. One Infinite Plane w/ CCD

$$\vec{E} = E(z)\hat{z}$$

$$\frac{Q}{\epsilon_0} = \iint E(z)\hat{z} \cdot d\vec{a}$$

$$= E(z)\hat{z} \cdot 2 \iint xy |d\vec{x} \times d\vec{y}|$$

$$= E(z)\hat{z} \cdot 2xy\hat{z}$$

$$\vec{E}(z) = \frac{1}{2\epsilon_0} \frac{dQ}{dA} \hat{z} = \frac{\sigma}{2\epsilon_0} \hat{z}$$

#### 2. Infinite Long Solenoid Coil w/ SC

Let R be the coil radius.  $\vec{B} = B(r)\hat{z} = B(r < R)\hat{z}$ 

$$\mu_o NI = \oint B(r)\hat{z} \cdot d\vec{L}$$
$$= (B_{r < R})\hat{z} \cdot \oint d\vec{L}$$
$$= (B_{r < R})\hat{z} \cdot L\hat{z}$$

$$\vec{B}(r) = \begin{cases} \frac{\mu_0 IN}{L} \hat{z} = \mu_0 I n_l \ \hat{z} & (0 < r < R) \\ 0 & (r > R) \end{cases}$$

#### 3. Closed, Thin Solenoid Ring w/SC

Let  $R_l$  be the ring radius and  $R_c$  be the coil radius.

$$\vec{B} = B(r)\hat{\theta} = B(R_l - R_c < r < R_l + R_c)\hat{\theta} \approx B(R_l)\hat{\theta}$$

$$\mu_o NI = \oint B(r)\hat{\theta} \cdot d\vec{L}$$
$$= B(r)\hat{\theta} \cdot 2\pi R_l \ \hat{\theta}$$

$$\vec{B}(r) = \begin{cases} \frac{\mu_0 IN}{2\pi R_l} \hat{\theta} & (R_{l-c} < r < R_{l+c}) \\ 0 & \text{else} \end{cases}$$

#### Integrate w/ CFL and BSL

#### 5. Ring w/ CCD centered at origin O

Let R be the ring radius,  $\lambda$  the charge density, and  $\phi$  be  $\angle OzR$ .

$$E(0,0,z)\hat{z} = \frac{1}{4\pi\epsilon_0} \int \frac{dq}{z^2} \vec{z}$$

$$\vec{E}(0,0,z) = \frac{1}{4\pi\epsilon_0} \int \frac{\lambda(Rd\theta)}{\imath^2} \vec{\imath}$$

$$= \frac{k\lambda}{z^2 + R^2} \int_0^{2\pi} Rd\theta \cos\phi \,\hat{z}$$

$$= \frac{k\lambda(2\pi R)z}{(z^2 + R^2)^{3/2}} \hat{z}$$

$$= \frac{k\lambda}{D} \frac{2\pi R}{D} \cos\phi \ \hat{z}$$

#### 4. Ring w/ SC centered at origin O

Let R be the ring radius and  $\phi$  be  $\angle O_{\text{rigin}}zR$ .

$$B(0,0,z)\hat{z} = \frac{\mu_0 I}{4\pi} \int \frac{d\vec{l} \times \hat{z}}{|\vec{z}|^2}$$

$$\vec{B}(0,0,z) = \frac{\mu_0 I}{4\pi} \int \frac{Rd\vec{\theta} \times \hat{z}}{z^2}$$

$$= \frac{k_\mu I}{z^2 + R^2} \int Rd\theta \, \hat{\theta} \times \frac{z\hat{z} - R\hat{r}}{\sqrt{z^2 + R^2}} \qquad \text{or} \quad \frac{k_\mu I}{z^2 + R^2} \int_0^{2\pi} Rd\theta \, \sin\phi \, \hat{z}$$

$$= \frac{k_\mu IR}{(z^2 + R^2)^{3/2}} \left[ 2\pi R\hat{z} + z \int_0^{2\pi} \hat{r}d\theta \right] \quad \text{or} \quad \frac{k_\mu I}{z^2 + R^2} \int_0^{2\pi} Rd\theta \, \frac{R}{\sqrt{z^2 + R^2}} \, \hat{z}$$

$$= \frac{k_\mu I(2\pi R)R}{(z^2 + R^2)^{3/2}} \, \hat{z}$$

$$= \frac{k_\mu I}{D} \frac{2\pi R}{D} \sin\phi \, \hat{z}$$

## 6. Line Charge w/ CCD and one edge at the origin OLet L be the line length, $\lambda$ the charge density, and $\theta_0$ be $\angle OyL$ .

$$E_{y}(0,0,y)\hat{y} = \frac{1}{4\pi\epsilon_{0}} \int \frac{dq}{\epsilon^{2}} \vec{z}_{y}$$

$$E_{y}(0,0,y) = k \int \frac{\lambda dx}{\epsilon^{2}} \vec{z}_{y}$$

$$= k\lambda \int \frac{dx}{y^{2} + x^{2}} \cos \theta \quad , \qquad x = y \tan \theta$$

$$= \frac{k\lambda}{y^{2}} \int_{0}^{\theta_{0}} \frac{y \sec^{2} \theta}{1 + \tan^{2} \theta} \cos \theta$$

$$= \frac{k\lambda}{y} \int_{0}^{\theta_{0}} \cos \theta = \frac{k\lambda}{y} \sin \theta_{0}$$

$$= \left[ \frac{k\lambda L}{y\sqrt{y^{2} + L^{2}}} \right] = \left[ \frac{k\lambda}{y} \sin \theta_{0} \right]$$

Use this result to find Finite Line Charge and Square Ring.

# 5. Finite Wire w/ SC and one edge at the origin O

Let L be the wire length and  $\theta_0$  be  $\angle OyL$ .

$$B_{z}(0,0,y)\hat{z} = k_{\mu}I \int \frac{d\vec{l} \times \hat{z}}{|\vec{z}|^{2}}$$

$$B_{z}(0,0,y)\hat{z} = k_{\mu}I \int \frac{d\vec{x} \times \hat{z}}{|\vec{z}|^{2}}$$

$$= k_{\mu}I \int \frac{dx}{y^{2} + x^{2}} \sin(\theta + 90) , \quad x = y \tan \theta$$

$$= \frac{k_{\mu}I}{y^{2}} \int_{0}^{\theta_{0}} \frac{y \sec^{2} \theta}{1 + \tan^{2} \theta} \cos \theta$$

$$= \frac{k_{\mu}I}{y} \int_{0}^{\theta_{0}} \cos \theta = \frac{k_{\mu}I}{y} \sin \theta_{0}$$

$$= \frac{k_{\mu}IL}{y\sqrt{y^{2} + L^{2}}} = \frac{k_{\mu}I}{y} \sin \theta_{0}$$

Use this result to find Finite Wire and Square Wire.

#### 1.3 Field Energies

The sum of the work to move a collection of charges considering the potential from each other charge comes out to be

$$W = rac{1}{2} \sum_i q_i V(r_i)$$

E-field Energy (electrostatic...)

$$E = \frac{1}{2}CV^2 = \frac{1}{2}VQ$$

$$W_{\text{vol}} = \frac{1}{2}\iiint V\rho \ d\tau = \frac{\epsilon_0}{2}\iiint V(\nabla \cdot \vec{E}) \ d\tau$$

$$= \frac{\epsilon_0}{2}\iiint \vec{E} \cdot (\vec{E}) + \nabla \cdot (V\vec{E}) \ d\tau$$

$$= \left[\frac{\epsilon_0}{2}\iiint \vec{E}^2 \ d\tau + \frac{\epsilon_0}{2}\iint (V\vec{E}) \cdot d\vec{a}\right]$$

$$W_E = \frac{\epsilon_0}{2}\iiint \vec{E}^2 \ d\tau \quad (\text{if } \rho = 0 \text{ at } \infty)$$

B-field Energy

$$E = \frac{1}{2}LI^{2} = \frac{1}{2}\Phi_{B}I = \frac{1}{2}\oint \vec{A} \cdot \vec{I} \, dl$$

$$W_{\text{vol}} = \frac{1}{2}\iiint \vec{A} \cdot \vec{J} \, d\tau = \frac{1}{2\mu_{0}}\iiint \vec{A} \cdot (\nabla \times \vec{B}) \, d\tau$$

$$= \frac{1}{2\mu_{0}}\iiint \vec{B} \cdot (\vec{B}) - \nabla \cdot (\vec{A} \times \vec{B}) \, d\tau$$

$$= \frac{1}{2\mu_{0}}\iiint \vec{B}^{2} \, d\tau - \frac{1}{2\mu_{0}}\oiint (\vec{A} \times \vec{B}) \cdot d\vec{a}$$

$$W_{B} = \frac{1}{2\mu_{0}}\iiint \vec{B}^{2} \, d\tau \quad (\text{if } \vec{I} = 0 \text{ at } \infty)$$

#### Circuits/Ohm's Law

$$\begin{array}{c} \underline{\text{Ohm's Law}} \\ \text{In Ohmic material,} \end{array} \rightarrow \begin{array}{c} \sigma \text{: Conductivity} \\ J \approx \sigma(E+v\times B) \Rightarrow \hline \hline \\ I = VI \end{array}$$
 
$$\overline{ \begin{array}{c} Example: \text{Wire w/ Two Plates} \\ \hline \\ I = (\sigma E)A = \left(\frac{\sigma A}{L}\right)V \quad \Rightarrow \quad V = I\left(\frac{L}{\sigma A}\right) = IR \end{array}$$

Open Circuit :  $R = \infty$ Short Circuit: R = 0

#### AC Filters

Low Pass (Non-Zero  $\overline{\text{Probe}}$ ): High Pass (Non-Zero  $\overline{\text{Probe}}$ ):

Band Pass (Zero Probe):

 $\bullet$   $R\overline{C}$ 

 $\bullet$   $C\overline{R}$ 

 $\bullet$   $R\overline{LC}$ 

•  $L\overline{R}$ 

 $\bullet$   $R\overline{L}$ 

• Bandwidth =  $\left(\text{FWHM} = 2\beta = \frac{b}{m}\right) = \frac{R}{L}$ 

#### Other Components

$$->|-\>$$
 Diode | One Way Voltage (if > Bias Voltage)   
= | > - Op-Amp | V\_1 - V\_2 \propto V\_{\rm OA} (Clipping If Too Large  $V_{\rm OA}$ )   
= |)- And   
=) > - Or

#### De Morgan's Law

$$\bullet \ \overline{A \cdot B} = \overline{A} + \overline{B}$$

$$\bullet \ \overline{A+B} = \overline{A} \cdot \overline{B}$$

#### 1.5 Quasistatic (FLI)

Force on Wire in B-Field :

EMF:

Mutual Inductance:

$$F = qv \times B$$

$$F = LI \times B$$

$$\mathcal{E} = -\frac{d\Phi_B}{dt} = \oint \vec{E} \cdot d\vec{l}$$

Flux Through B:  $\overline{\Phi_B = M \cdot I_A}$ 

Flux Through A:  $\Phi_A = M \cdot I_B$ 

### Faraday's Law

1. Lorentz:

Square Circuit with  $\vec{v}(t)$  leaving Constant B-Field (out)

I is out

2. Faraday:

Constant B-Field (out) with  $-\vec{v}(t)$ leaving Square Circuit

I is out

3. Faraday:

Square Circuit in Increasing B-Field (out)

I is in

### **Examples:**

B-Field Work:

$$(\vec{v} \cdot \vec{l} = 0) \rightarrow W_B = \int \vec{F} \cdot d\vec{l}$$
  
=  $\int (q\vec{v} \times \vec{B}) \cdot d\vec{l}$ 

(magnetic fields do no work)

Velocity of wire in (1.): 
$$I(t)R = V(t) = \left| \frac{d\Phi_B}{dt} \right| = Bhv(t)$$

$$F_B(t) = -hI(t)B$$
$$= -\frac{B^2h^2v(t)}{R}$$

$$F = ma(t)$$

$$m\frac{dv}{dt} = F_B + F_{\text{ext}} = F_{\text{ext}} - \frac{B^2 h^2 v(t)}{R}$$

### 2 Potentials and Fields

#### 2.1 Maxwell's Equations for Potentials

#### 1. GLM for Potentials (GLMP)

$$\nabla \cdot \vec{B} = 0$$

$$\nabla \cdot (\nabla \times \vec{A}) = 0 , \qquad \vec{A'} = \vec{A} + \nabla \lambda$$

$$\vec{B} = \nabla \times \vec{A} \implies \Phi_B = \oint \vec{A} \cdot d\vec{l}$$

#### 3. GLE for Potentials (GLEP)

$$\nabla \cdot \vec{E} = \frac{\rho}{\epsilon_0}$$
$$-\nabla^2 V - \frac{\partial (\nabla \cdot \vec{A})}{\partial t} = \frac{\rho}{\epsilon_0}$$
$$\Box^2 V - \frac{\partial}{\partial t} (\partial_\mu A^\mu) = \frac{\rho}{\epsilon_0}$$

#### 2. FLI for Potentials (FLIP)

$$\nabla \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$$

$$\nabla \times \vec{E} = \nabla \times \left(0 - \frac{\partial \vec{A}}{\partial t}\right)$$

$$\vec{E} = -\nabla V - \frac{\partial \vec{A}}{\partial t} , \qquad \mathbf{V'} = \mathbf{V} + \frac{\partial \lambda}{\partial t}$$

#### 4. MAL for Potentials (MALP)

$$\nabla \times \vec{B} - \frac{1}{c^2} \frac{\partial \vec{E}}{\partial t} = \mu_0 \vec{J}$$

$$\frac{1}{c^2} \frac{\partial^2 \vec{A}}{\partial t^2} - \nabla^2 \vec{A} + \nabla \left( \frac{1}{c^2} \frac{\partial V}{\partial t} + \nabla \cdot \vec{A} \right) = \mu_0 \vec{J}$$

$$\Box^2 \vec{A} + \nabla (\partial_\mu A^\mu) = \mu_0 \vec{J}$$

#### Field Energy (see Capacitor/Solenoid in Circuits):

$$\boxed{W_E = \frac{1}{2} \iiint V \rho \ d\tau} = \frac{\epsilon_0}{2} \int E^2 \ d\tau \ (\text{if } \rho = 0 \text{ at } \infty)$$

$$\boxed{W_B = \frac{1}{2} \iiint \vec{A} \cdot \vec{J} \, d\tau} = \frac{1}{2\mu_0} \int B^2 \, d\tau \quad (\text{if } \vec{J} = 0 \text{ at } \infty)$$

#### 2.2 Cases and Freedoms

$$\vec{E} = -\nabla V - \frac{\partial \vec{A}}{\partial t}$$

 $\vec{B} = \nabla \times \vec{A}$ 

In the electrostatic case,

Electrostatics: 
$$\nabla \times E = \partial_t B = 0$$

$$-\nabla^2 V - \frac{\partial (\nabla \cdot \vec{A})}{\partial t} = \frac{\rho}{\epsilon_0}$$
$$\frac{1}{c^2} \frac{\partial^2 \vec{A}}{\partial t^2} - \nabla^2 \vec{A} + \nabla \left( \frac{1}{c^2} \frac{\partial V}{\partial t} + \nabla \cdot \vec{A} \right) = \mu_0 \vec{J}$$

Freedom may be chosen to what  $\nabla \cdot \vec{A}$  equals:

Coulomb Gauge: 
$$\nabla \cdot \vec{A} = 0$$

• Magnetostatics:  $\partial_t E = 0 \iff \nabla \times B = \mu_0 J$ 

$${
m Lorenz~Gauge:}~~ 
abla \cdot ec{A} = -rac{1}{c^2}rac{\partial V}{\partial t} ~\Leftrightarrow ~ \partial_{\mu}A^{\mu} = 0$$

In general,  $\vec{A}$  and V can be [gauge] transformed while keeping  $\vec{E}$  and  $\vec{B}$  the same by

$$V' = V - \frac{d\lambda}{dt}$$
 (\lambda is a scalar function) 
$$\vec{A'} = \vec{A} + \nabla \lambda$$

#### **Electrostatic Potentials**

Electrostatics:  $\partial_t \vec{B} = 0$ .

$$\nabla \times \vec{E} = 0 \implies \oint \vec{E} \cdot d\vec{l} = 0$$

If  $B = \nabla \times A = \nabla \times (A' + \nabla \lambda) = 0$ , then let  $A' = -\nabla \lambda \iff \lambda = -\int A' \cdot dl$ 

- $A=0 \rightarrow \frac{\partial A}{\partial t}=0$
- $E = -\nabla (V \frac{\partial \lambda}{\partial t}) \frac{\partial A'}{\partial t} = -\nabla V$

$$\int_{a}^{b} \nabla \vec{V} \cdot d\vec{l} = \left[ V(\vec{\mathbf{r}}) \right]_{a}^{b} = -\int_{a}^{b} \vec{E} \cdot d\vec{l} = W_{E}/q$$

$$V(\vec{\mathbf{r}}) = -\int \vec{E} \cdot d\vec{l} + V_0$$

and from this (or GLEP)

Poisson Equation: 
$$abla^2 V = -rac{
ho(ec{r'})}{\epsilon_0}$$

Poisson Equation: 
$$\nabla^2 V = -\frac{\rho(\vec{r'})}{\epsilon_0}$$
$$\rho_{\infty} = 0 \implies \vec{V}(\vec{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\rho(\vec{r'})}{\epsilon} d\tau'$$

#### Coulomb Gauge & Magnetostatic Potentials

Coulomb Guage: Choose  $\left( 
abla \cdot \vec{A} = 0 \right)$ 

Using GLEP,

Poisson Equation: 
$$\nabla^2 V = -\frac{\rho(\vec{r'},t)}{\epsilon_0}$$

$$\rho_{\infty} = 0 \implies V(\vec{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\rho(\vec{r'},t)}{\imath} d\tau'$$

$$ho_{\infty} = 0 \; \Rightarrow \; V(\vec{\mathbf{r}}) = rac{1}{4\pi\epsilon_0} \int rac{
ho(ec{r'},t)}{\imath} \; d au'$$

If charges move, V updates immediately - not at light speed. Only  $\vec{E}$  can be physically measured, and updates at light speed.  $\vec{A}$  is difficult to find using MALP except for special cases like Magnetostatics.

As always, GLMP says

$$oldsymbol{\Phi}_B = \oint ec{A} \cdot dec{l}$$

Magnetostatics:  $\partial_t \vec{E} = 0$ 

Using MALP,

Poisson Equation: 
$$\nabla^2 \vec{A} = -\mu_0 \vec{J}(\vec{r}')$$

Poisson Equation: 
$$abla^2 \vec{A} = -\mu_0 \vec{J}(\vec{r'})$$
 $\vec{J}_{\infty} = 0 \Rightarrow \vec{A}(\vec{r}) = k_{\mu} \int \frac{\vec{J}(\vec{r'})}{\imath} d\tau'$ 

#### 2.2.1 Potential Examples

#### 1. Point Charges

Reference Choice:  $V(\infty) = 0$ 

$$V(r) = -\int_{\infty}^{r} \frac{kQ}{(r')^2} dr' = \frac{Q}{4\pi\epsilon_0} \frac{1}{r}$$

$$V(ec{{f r}}) \; = \; rac{1}{4\pi\epsilon_0} \sum_i rac{Q_i}{arepsilon_i}$$

Coulomb Potential:  $V(\vec{\mathbf{r}}) = \frac{1}{4\pi\epsilon_0} \int \frac{dq}{|\vec{\mathbf{z}}_i|}$ 

Work:  $W = \frac{1}{2} \sum q_i V(\vec{\mathbf{r}}_i)$ 

1.

2.

#### 2. Sphere

Reference Choice:  $V(\infty) = 0$ 

Let R be the radius.

$$V(r) = -\int_{\infty}^{r} \vec{E}(r') \cdot d\vec{r'}$$

• Conductor

$$E(r) = \begin{cases} \frac{kQ}{r^2} \\ 0 \end{cases} \Rightarrow V(r) = \begin{cases} \frac{Q}{4\pi\epsilon_0 r} & (r > R) \\ \frac{Q}{4\pi\epsilon_0 R} & (r < R) \end{cases}$$

• Insulator w/ CCD and  $\epsilon = \epsilon_0$ 

$$E(r) = \begin{cases} \frac{kQ}{r^2} \\ \frac{kQr}{R^3} \end{cases} \Rightarrow V(r) = \begin{cases} \frac{Q}{4\pi\epsilon_0 r} & (r > R) \\ \frac{Q}{4\pi\epsilon_0 R} + \frac{Qr'^2}{8\pi\epsilon_0 R^3} \Big|_r^R & (r < R) \end{cases}$$

1.

**2**.

#### Charges at $\infty$

#### 3. (Infinite) Parallel Plate Capacitor

Reference Choice: V(h) = 0

Let the Capacitor Height be h

$$V(z) = -\int_{h}^{z} \frac{\sigma}{\epsilon_{0}} \hat{z} \cdot d\vec{z} = \frac{\sigma(h-z)}{\epsilon_{0}} \quad (0 \le z \le h)$$

#### 4. (Infinite) Single Plate w/ CCD

Reference Choice: V(0) = 0

$$V(z) = -\int_0^z \frac{\sigma}{2\epsilon_0} \hat{z} \cdot d\vec{z} = -\frac{\sigma z}{2\epsilon_0} \quad (0 \le z < \infty)$$

Try  $V(\infty) = 0$ . (A charge distribution stretching to infinity DNE, so choose a diff. reference point.)

#### 5. Infinite Line w/ CCD

Reference Choice: V(1) = 0

$$V(r) = -\int_{1}^{r} \frac{\lambda}{2\pi r \epsilon_{0}} \hat{r} \cdot d\vec{r}$$
$$= -\frac{\lambda}{2\pi \epsilon_{0}} \ln r$$

Try  $V(\infty) = 0$  (same problem above).

3.

4.

#### 2.3 Multipole Expansion

$$\mathbf{z}^{2} = r^{2} + (r')^{2} - 2(\mathbf{r} \cdot \mathbf{r}') \qquad \frac{1}{\mathbf{z}} = \frac{1}{r} (1 + \epsilon)^{-1/2}$$

$$= r^{2} \left[ 1 + \frac{r'}{r} \left( \frac{r'}{r} - 2 \frac{\mathbf{r} \cdot \mathbf{r}'}{r'r} \right) \right] \qquad \Rightarrow \qquad = \frac{1}{r} \sum_{n=0}^{\infty} \left( \frac{\mathbf{r}'}{r} \right)^{n} \mathbf{P}_{n} \left( \hat{\mathbf{r}'} \cdot \hat{\mathbf{r}} \right) \qquad \text{(Legendre Polynomials)}$$

$$= r^{2} (1 + \epsilon)$$

$$V(\vec{\mathbf{r}}) = \frac{1}{4\pi\epsilon_0} \int \frac{1}{\imath} \rho(\vec{r'}) d\tau'$$
$$= \left[ \frac{1}{4\pi\epsilon_0} \sum_{n} \frac{1}{r^{n+1}} \int (r')^n P_n(\cos\alpha) \rho(\vec{r'}) d\tau' \right]$$

$$= \frac{1}{4\pi\epsilon_0} \begin{bmatrix} \frac{1}{r} \int \rho(\vec{r'})d\tau' + \frac{1}{r^2} \int \vec{r'} \cdot \hat{\mathbf{r}} \ \rho(\vec{r'})d\tau' \\ + \frac{1}{r^3} \int (r')^2 P_2(\hat{r'} \cdot \hat{\mathbf{r}}) \ \rho(\vec{r'})d\tau' + \frac{1}{r^4} \int \dots \end{bmatrix}$$

$$V_{\text{mon}} = \frac{1}{4\pi\epsilon_0 r} \int \rho(\vec{r'}) d\tau'$$

$$V_{\text{dip}} = \frac{1}{4\pi\epsilon_0 r^2} \left( \int \vec{r'} \ \rho(\vec{r'}) d\tau' \right) \cdot \hat{\mathbf{r}} = \frac{\vec{\mathbf{p}} \cdot \hat{\mathbf{r}}}{4\pi\epsilon_0 r^2}$$

V is the dipole term.  $\mathbf{p}$  is the dipole moment.

$$\vec{A}(\vec{\mathbf{r}}) = k_{\mu} \int \frac{1}{\imath} \vec{J}(\vec{r'}) d\tau'$$

$$= k_{\mu} \sum_{n} \frac{1}{r^{n+1}} \int (r')^{n} P_{n}(\cos \alpha) \vec{J}(\vec{r'}) d\tau'$$

$$= k_{\mu} \begin{bmatrix} \frac{1}{r} \int \vec{J}(\vec{r'}) d\tau' + \frac{1}{r^2} \int \vec{r'} \cdot \hat{\mathbf{r}} \ \vec{J}(\vec{r'}) d\tau' \\ + \frac{1}{r^3} \int (r')^2 P_2(\hat{r'} \cdot \hat{\mathbf{r}}) \ \vec{J}(\vec{r'}) d\tau' + \frac{1}{r^4} \int \dots \end{bmatrix}$$

$$A_{\text{mon}} = \frac{\mu_0 I}{4\pi r} \oint dl' = 0$$
Steady current: 
$$A_{\text{dip}} = \frac{k_{\mu}}{r^2} I \int \vec{r'} \cdot \hat{\mathbf{r}} \ dl' = \frac{k_{\mu}}{r^2} I \int d\vec{a'} \times \hat{\mathbf{r}}$$

$$= \frac{k_{\mu}}{r^2} (I\vec{a}) \times \hat{\mathbf{r}} = \frac{\mu_0 \vec{\mathbf{m}} \times \hat{\mathbf{r}}}{4\pi r^2}$$

A is the dipole term.  $\mathbf{m}$  is the dipole moment.

#### **Ideal Dipoles**

Let dipole (2 charges)  $\vec{\mathbf{p}} = p\hat{z} = 2dq\hat{z}$  and centered at the origin.

 $\lim d \to 0, \ q \to \infty$ :

$$V(\vec{\mathbf{r}}) = \frac{1}{4\pi\epsilon_0} \sum_{n=0}^{\infty} \frac{d^n P_n(\cos\alpha) q + (-d)^n P_n(\cos\alpha) (-q)}{4\pi\epsilon_0 r^{n+1}}$$

$$= \frac{1}{4\pi\epsilon_0} \sum_{n=0}^{\infty} \frac{P_n(\cos\alpha) q d^n}{r^{n+1}} [1 + (-1)^n]$$

$$= \frac{1}{4\pi\epsilon_0} \sum_{m=0}^{\infty} \frac{P_m(\cos\alpha)}{r^{2m+2}} (2qd) d^{2m}$$

$$= \frac{1}{4\pi\epsilon_0} \sum_{m=0}^{\infty} \frac{P_m(\cos\alpha)}{r^{2m+2}} p d^{2m}$$

$$= \frac{1}{4\pi\epsilon_0} \frac{P_0(\cos\alpha)}{r^2} p + 0 + 0 + \dots$$

Ideal Dip: 
$$V_{\text{dip}}(\vec{\mathbf{r}}) = \frac{1}{4\pi\epsilon_0} \frac{\vec{\mathbf{p}} \cdot \hat{\boldsymbol{\imath}}}{\boldsymbol{\imath}^2}$$

Let dipole (ring)  $\vec{\mathbf{m}} = m\hat{z} = Ia\hat{z}$  and centered at the origin.

 $\lim a = \pi d^2 \to 0, I \to \infty$ :

$$\vec{A}(\vec{\mathbf{r}}) = k_{\mu} \sum_{n=0}^{\infty} \frac{Id^n}{r^{n+1}} \int P_n(\cos \alpha) \ d\vec{l'}$$

$$= k_{\mu} \left( \begin{array}{c} \frac{I}{r} \int d\vec{l'} + \frac{I}{r^2} \int (d\hat{r'} \cdot \hat{\mathbf{r}}) d\vec{l'} \\ + \frac{Id^2}{r^3} \int \left[ \frac{3}{2} \left( 1 + 2 \frac{d\hat{r'} \cdot \hat{\mathbf{r}}}{d} + 1 \right) - \frac{1}{2} \right] d\vec{l'} \\ + Id^2 \sum_{n=3}^{\infty} \frac{d^{n-2}}{r^{n+1}} \int P_n(\hat{r'} \cdot \hat{\mathbf{r}}) d\vec{l'} \end{array} \right)$$

$$= k_{\mu} \left( 0 + \frac{I\pi d^{2}}{r^{2}} (\hat{z} \times \hat{\mathbf{r}}) + \frac{3I\pi d^{3}}{r^{3}} (\hat{z} \times \hat{\mathbf{r}}) + \frac{m}{\pi} (0 + ...) \right)$$

$$= k_{\mu} \left( 0 + \frac{m}{r^2} (\hat{z} \times \hat{\mathbf{r}}) + 0 + 0 + \dots \right)$$

Ideal Dip: 
$$\vec{A}_{\text{dip}}(\vec{\mathbf{r}}) = k_{\mu} \frac{\vec{\mathbf{m}} \times \hat{\boldsymbol{\imath}}}{{\boldsymbol{\imath}}^2}$$

2.3.1 Multipole Examples

3.

4.

## 3 Electrodynamics in Matter

#### 3.1 Ideal Dipoles

$$\vec{\mathbf{p}} = \int r' \cdot \rho(r') \ d\tau'$$

$$\vec{F}_{\text{dip}} = qE \Big|_{\vec{r}}^{\vec{r}+\vec{d}} = q\Delta \vec{E} \qquad U_{\text{ES dip}} = qV \Big|_{\vec{r}}^{\vec{r}+\vec{d}} = q\Delta V$$

$$\approx \left[ q \sum_{i} \left( \nabla E_{i} \cdot \vec{d} \right) \hat{i} \right] \qquad = q \int_{\vec{r}}^{\vec{r}+\vec{d}} - \vec{E} \cdot d\vec{l}$$

$$\vec{F}_{\text{dip}} = (\vec{\mathbf{p}} \cdot \nabla) \vec{E} \qquad U_{\text{ES dip}} = -\vec{\mathbf{p}} \cdot \vec{E}$$

$$\vec{N}_{\text{center}} = r \times F = \vec{d} \times q\vec{E}$$

$$\vec{N}_{\text{dip}} = \vec{\mathbf{p}} \times \vec{E}$$

Polarization: 
$$\vec{P} = \frac{d\vec{\mathbf{p}}}{d\tau}$$
  $\left(\frac{\hat{\imath}}{\imath^2} = \nabla' \frac{1}{\imath}\right)$ 

$$V(\vec{\mathbf{r}}) = \frac{1}{4\pi\epsilon_0} \int_{\nu} \frac{\vec{P}(\vec{r'}) \cdot \hat{\boldsymbol{\imath}}}{\boldsymbol{\imath}^2} d\tau'$$

$$= \frac{1}{4\pi\epsilon_0} \int_{\nu} \frac{-\nabla' \cdot \vec{P}(\vec{r'})}{\boldsymbol{\imath}} d\tau' + \frac{1}{4\pi\epsilon_0} \int_{S} \frac{\vec{P}(\vec{r'}) \cdot \hat{\boldsymbol{n}}}{\boldsymbol{\imath}} da'$$

$$\left[\rho_b = -\nabla \cdot \vec{P}\right] \qquad \sigma_b = \vec{P} \cdot \hat{\boldsymbol{n}}$$

$$|\vec{\mathbf{m}} = \sum I\vec{a}|$$

$$\vec{F}_{\text{sqr. dip}} = q\vec{v} \times \vec{B}$$

$$= \pm IL\vec{x} \times B\hat{z}$$

$$= \pm ILB \hat{y}$$

$$\vec{V}_{\text{dip}} = 2\left[\frac{\pm \vec{W}}{2} \times \pm ILB\hat{y}\right]$$

$$= I(LW) \sin \theta B \hat{x}$$

$$\vec{N}_{\text{dip}} = \vec{m} \times \vec{B}$$

#### 3.2 Maxwell's Equations in Matter

GLE in Matter (GLEM)

$$\nabla \cdot \epsilon_0 \vec{E} = \rho = \rho_b + \rho_f$$
$$= -\nabla \cdot \vec{P} + \nabla \cdot D$$

$$\nabla \cdot \left( \epsilon_0 \vec{E} + \vec{P} \right) = \nabla \cdot D$$

$$ec{D} = \epsilon_0 ec{E} + ec{P}$$
 
$$- 
abla \cdot ec{P} = 
ho_b$$
 
$$abla \cdot ec{D} = 
ho_f$$
 
$$abla \cdot \hat{p} = \sigma_b$$

COC in Matter (COCM)

$$\nabla \cdot \vec{J}_p = -\frac{\partial \rho_b}{\partial t}$$
$$= \frac{\partial}{\partial t} \left( \nabla \cdot \vec{\mathbf{P}} \right)$$

$$\boxed{\frac{\partial \vec{\mathbf{P}}}{\partial t} = \vec{J_p}}$$

MAL in Matter (MALM)

$$\nabla \times \frac{1}{\mu_0} \vec{B} = \vec{J} + \epsilon_0 \frac{\partial \vec{E}}{\partial t} = \vec{J}_b + \vec{J}_f + \vec{J}_p + \epsilon_0 \frac{\partial \vec{E}}{\partial t}$$
$$= \nabla \times M + \vec{J}_f + \frac{\partial \vec{P}}{\partial t} + \epsilon_0 \frac{\partial \vec{E}}{\partial t}$$

$$abla imes \left( rac{1}{\mu_0} \vec{B} - M 
ight) = \vec{J_f} + rac{\partial}{\partial t} \left( \epsilon_0 \vec{E} + \vec{\mathbf{P}} 
ight)$$

$$\vec{H} = \frac{1}{\mu_0} \vec{B} - \vec{M}$$

$$\nabla \times \vec{H} = \vec{J_f} + \frac{\partial \vec{D}}{\partial t}$$

$$\nabla \times \vec{M} = \vec{J_b}$$

$$\vec{M} \times \hat{n} = \vec{K_b}$$

Faraday's Law of Induction (FLI)

$$\nabla \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$$

Electrostatics:  $\nabla \times \vec{D} = \nabla \times \vec{P}$ 

Gauss's Law for Magnetism (GLM)

$$\nabla \cdot \vec{B} = 0$$

$$\nabla \cdot \vec{H} = -\nabla \cdot \vec{M}$$

#### 3.3 Linear Matter

Electric Susceptibility:  $\chi_e$ 

$$\vec{P} = \chi_e \epsilon_0 \vec{E}$$

Susceptibility Tensor:

$$\vec{P} = \begin{pmatrix} \chi_{e_{xx}} & \chi_{e_{xy}} & \chi_{e_{xz}} \\ \chi_{e_{yx}} & \chi_{e_{yy}} & \chi_{e_{yz}} \\ \chi_{e_{zx}} & \chi_{e_{zy}} & \chi_{e_{zz}} \end{pmatrix} \epsilon_0 \vec{E}$$

Relative Permittivity:  $\epsilon_r = 1 + \chi_e$ 

$$\vec{D} = (1 + \chi_e)\epsilon_0 \vec{E}$$
$$= \epsilon_r \epsilon_0 \vec{E}$$
$$= \epsilon \vec{E}$$

Magnetic Susceptibility:  $\chi_m$ 

$$\vec{M} = \chi_m \vec{H}$$

Susceptibility Tensor:

$$\vec{M} = \begin{pmatrix} \chi_{m_{xx}} & \chi_{m_{xy}} & \chi_{m_{xz}} \\ \chi_{m_{yx}} & \chi_{m_{yy}} & \chi_{m_{yz}} \\ \chi_{m_{zx}} & \chi_{m_{zy}} & \chi_{m_{zz}} \end{pmatrix} \vec{H}$$

Bound Current:

$$\vec{J_b} = \nabla \times \left(\chi_m \vec{H}\right)$$
$$= \chi_m \left(\vec{J_f} + \partial_t \vec{D}\right)$$

Relative Permeability:  $\mu_r = 1 + \chi_m$ 

$$\vec{B} = (1 + \chi_m)\mu_0 \vec{H}$$
$$= \mu_r \mu_0 \vec{H}$$
$$= \mu \vec{H}$$

## 4 Boundary Conditions

$$\Delta \vec{E} = \frac{\sigma}{\epsilon_0} \hat{n}$$

1. 
$$\Delta E_{\parallel} = 0$$
 
$$\oint \vec{E} \cdot d\vec{L} = - \oiint_{0-}^{0+} \frac{\partial \vec{B}}{\partial t} \cdot d\vec{a}$$
 
$$(E_{\parallel}^{+} - E_{\parallel}^{-})L = 0$$

2. 
$$\Delta E_{\perp} = \frac{\sigma}{\epsilon_0}$$
 
$$\int \vec{E} \cdot d\vec{a} = Q/\epsilon_0$$
 
$$(E_{\perp}^+ - E_{\perp}^-)a = \frac{\sigma a}{\epsilon_0}$$

Electrostatics:  $\nabla \times \vec{E} = 0$ 

$$\boxed{\Delta V = 0} \qquad V \Big|_{0-}^{0+} = -\int_{0-}^{0+} \vec{E} \cdot dL$$

$$\Delta \frac{\partial V}{\partial n} = -\frac{\sigma}{\epsilon_0} \qquad \Delta(\nabla V) \cdot \hat{n}$$

$$oxed{\Delta ec{D}_{\parallel} = \Delta ec{P}_{\parallel}} \quad egin{equation} 
abla imes ec{D} = 
abla imes ec{P} \end{aligned}$$

$$\boxed{\Delta \vec{B} = \mu_0 \vec{K} \times \hat{n}}$$

1. 
$$\Delta B_{\perp} = 0$$
 
$$B \cdot d\vec{a} = 0$$
$$(B_{\perp}^{+} - B_{\perp}^{-})a = 0$$

2. 
$$\Delta \vec{B}_{\parallel} = \mu_0 \vec{K} \times \hat{n}$$

$$\Delta \vec{H}_{\parallel} = \vec{K}_f \times \hat{n}$$

$$\Delta B_{\parallel} L = \mu_0 K L = (\mu_0 \vec{K} \times \hat{n}) \cdot \vec{L}$$

$$\Delta A_{\parallel} = 0 \qquad \oint \vec{A} \cdot d\vec{l} = \Phi_B = 0$$

Magnetostatic:  $\nabla \cdot \vec{A} = 0$ 

$$\Delta A_{\perp} = 0 \qquad \qquad \oint_{0-}^{0+} \vec{A} \cdot d\vec{a} = 0$$

$$\Delta \frac{\partial \vec{A}}{\partial n} = -\mu_0 \vec{K}$$

$$\Delta (\nabla \times \vec{A}) = \left( -\frac{\partial A_y^+}{\partial z} + \frac{\partial A_y^-}{\partial z} \right) \hat{x} + \left( \frac{\partial A_x^+}{\partial z} - \frac{\partial A_x^-}{\partial z} \right) \hat{y}$$

$$= -\mu_0 K \hat{y}$$

## 5 Work-Energy, Radiation, and Momentum

The sum of the work to move a collection of charges considering the potential from each other charge comes out to be

$$W = rac{1}{2} \sum_i q_i V(r_i)$$

#### 5.1 Field Energies

$$W_E = \frac{\epsilon_0}{2} \int \vec{E}^2 d\tau W_B = \frac{1}{2\mu_0} \int \vec{B}^2 d\tau$$

$$U_{EB} = \frac{1}{2} \int \epsilon_0 \vec{E}^2 + \frac{1}{\mu_0} \vec{B}^2 d\tau = \frac{1}{2} \int u_{EB} d\tau$$

#### 5.2 Energy Conservation

Poynting Vector: 
$$\vec{S} = \frac{1}{\mu_0} (\vec{E} \times \vec{B}) = \frac{1}{2\mu_0} \text{Re}(\tilde{\mathbf{E}} \times \tilde{\mathbf{B}}^*)$$

$$I = \langle P_{\text{ow}}/A \rangle = \langle S \rangle = \frac{1}{2}c\epsilon_0 E^2$$

$$-P_{\text{ow}} = \frac{dW}{dT} + \frac{dU_{EB}}{dt} = -\int \vec{S} \cdot d\vec{a}$$
$$\frac{d}{dt}(u_{mech} + u_{EB}) = -\nabla \cdot \vec{S}$$

#### 5.3 Radiation

#### Accelerating Charge

Larmor Formula 
$$(v \ll c)$$
:  $P_{\text{ow}} = \left(\frac{2k_{\epsilon}}{3c^3}\right)q^2a^2$ 

#### Electric Dipole Radiation

Dipole Moment :  $\vec{\mathbf{p}}(t) = p_0 \cos(\omega t)\hat{z}$ 

Intensity: 
$$\langle S \rangle = \left(\frac{k_{\epsilon}}{8\pi c^3}\right) p_0^2 \omega^4 \frac{\sin^2 \theta}{r^2}$$

Power: 
$$\langle P \rangle_E = \left(\frac{k_{\epsilon}}{3c^3}\right) p_0^2 \omega^4$$

Magnetic Dipole Radiation: 
$$\langle P \rangle_B = \left(\frac{k_\mu}{3c^3}\right) m_0^2 \omega^4$$

#### 5.4 Momentum Conservation

$$\left(a \cdot \overleftrightarrow{T}\right)_i = \sum_n a_n T_{in}$$

$$T_{ij} = \epsilon_0 \left( E_i E_j - \frac{1}{2} \delta_{ij} E^2 \right) + \frac{1}{\mu_0} \left( B_i B_j - \frac{1}{2} \delta_{ij} B^2 \right)$$

$$F_{i} = \int f_{i} d\tau$$

$$= \oint_{S} \left( \overrightarrow{T} \cdot da \right)_{i} - \frac{1}{c^{2}} \frac{d}{dt} \int_{V} S d\tau$$

$$\frac{dP_{mech}}{dt} = \int_{V} \left( \nabla \cdot \overleftarrow{T} \right)_{i} d\tau - \frac{dP_{EM}}{dt}$$

$$\frac{d}{dt}(P_{mech} + P_{EM})_i = \int_V \left(\nabla \cdot \overleftarrow{T}\right)_i d\tau$$

$$L_{EM} = \vec{r} \times P_{EM}$$

$$\mathbf{f}_{i} = \epsilon_{0} E_{i} + (\vec{J} \times \vec{B})_{i}$$
$$= \left(\nabla \cdot \overrightarrow{T}\right)_{i} - \frac{1}{c^{2}} \frac{\partial \vec{S}_{i}}{\partial t}$$

$$\frac{\partial}{\partial t}(p_{mech})_i = \left(\nabla \cdot \overleftarrow{T}\right)_i - \frac{\partial}{\partial t}(p_{EM})_i$$

$$\frac{\partial}{\partial t}(p_{mech} + p_{EM})_i = \left(\nabla \cdot \overleftarrow{T}\right)_i$$

$$l_{EM} = \vec{r} \times p_{EM}$$

## 6 Potentials in Lorenz Gauge (nonstatic sources)

See Potentials for Recap

If choose  $\left( 
abla \cdot \vec{A} = -rac{1}{c^2} rac{\partial V}{\partial t} \iff \partial_\mu A^\mu = 0 
ight)$ 

$$egin{aligned} \Box^2 V &= rac{
ho}{\epsilon_0} \ \Box^2 ec{A} &= \mu_0 ec{J} \end{aligned}$$

Solutions satisfying these three equations (thus satisfying Maxwell's Eq.) are,

$$V(ec{\mathbf{r}},t) = rac{1}{4\pi\epsilon_0}\intrac{
ho(ec{r'},t_r)}{\imath}\;d au'$$
 $ec{A}(ec{\mathbf{r}},t) = k_\mu\intrac{ec{J}(ec{r'},t_r)}{\imath}\;d au'$ 

where  $t_r = t - \frac{\imath}{c}$ .

Notice that charges move, V and  $\vec{A}$  update at the speed of light.  $t_r = t + \frac{z}{c}$  is also a solution, though not physically real.

Using GLMP and FLIP to find the fields,

Jefimenko Equations:

$$ec{E}(ec{\mathbf{r}},t) = rac{1}{4\pi\epsilon_0}\int \left[rac{
ho(ec{\mathbf{r}},t_r)}{\imath^2}\hat{\imath} \,+rac{\dot{
ho}(ec{\mathbf{r}},t_r)}{c^2}\hat{\imath} \,-rac{\dot{ec{J}}(ec{\mathbf{r}},t_r)}{c^2\imath}
ight]d au'$$

$$ec{B}(ec{\mathbf{r}},t) = k_{\mu} \int \left[ rac{ec{J}(ec{\mathbf{r}},t_r)}{ec{\epsilon}^2} + rac{\dot{ec{J}}(ec{\mathbf{r}},t_r)}{c\, \imath} 
ight] imes \hat{\imath} \ d au'$$

It's usually easier solve for the potentials first instead of fields directly. In the electrostatic and magnetostatic limits, CL and BSL are recovered.

#### 7 EM Waves

$$f(z,t) = \operatorname{Re}[\tilde{f}(z,t)] = \operatorname{Re}[Ae^{i(kz-wt+\delta)}]$$

 $\omega$  is the same throughout! (?)

$$\frac{\lambda_1}{\lambda_2} = \frac{k_2}{k_1} = \frac{v_1}{v_2} = \frac{n_2}{n_1}$$

$$\tilde{\mathbf{f}}(\mathbf{z}, \mathbf{t}; \delta = \mathbf{0}) : \tilde{A}_I e^{i(k_1 z - wt)} + \tilde{A}_R e^{i(-k_1 z - wt)} \Rightarrow \tilde{A}_T e^{i(k_2 z - wt)}$$

$$\tilde{A}_I + \tilde{A}_R = \tilde{A}_T; \quad k_1(\tilde{A}_I - \tilde{A}_R) = k_2\tilde{A}_T$$

$$\tilde{A}_R e^{i\delta_R} = \left(\frac{v_2 - v_1}{v_2 + v_1}\right) \tilde{A}_I e^{i\delta_I}; \quad \tilde{A}_T e^{i\delta_T} = \left(\frac{2v_2}{v_2 + v_1}\right) \tilde{A}_I e^{i\delta_I}$$

$$A_R = \left(\frac{|v_2 - v_1|}{v_2 + v_1}\right) A_I; \quad A_T = \left(\frac{2v_2}{v_2 + v_1}\right) A_I$$

# 7.1 Vacuum, $\vec{v}_{||}\vec{E}_{||}\hat{z}$

$$\tilde{B}_0 = \frac{k}{w}(\hat{z} \times \tilde{E}_0) = \frac{1}{c}(\hat{z} \times \tilde{E}_0)$$

$$\vec{S} = cu_{EM}\hat{z} = c\epsilon_0 E_0^2 \cos^2(kw, wt + \delta)\hat{z}$$
$$I_{nt} = \langle S \rangle = \frac{1}{2}c\epsilon_0 E_0^2$$

$$P_{res} = \frac{I_{nt}}{c}$$

#### Linear Media 7.2

$$D = \epsilon E; \quad B = \mu H$$

$$\tilde{B}_0 = \frac{1}{v} (\hat{z} \times \tilde{E}_0)$$

$$\bullet \quad n = \sqrt{\frac{\epsilon}{\epsilon}}$$

$$\bullet \ \left[ n = \frac{c}{v} \right]$$

• 
$$n = \sqrt{\frac{\epsilon \mu}{\epsilon_0 \mu_0}} \approx \sqrt{\frac{\epsilon}{\epsilon_0}} = \sqrt{\epsilon_r}$$

$$\bullet \ k_I v_1 = k_R v_1 = k_T v_2 = \omega$$

• 
$$k_I \sin \theta_I = (k_R \sin \theta_R = k_R \sin \theta_I) = k_T \sin \theta_T$$

• Snell's Law: 
$$n_1 \sin \theta_I = n_2 \sin \theta_T$$

Fresnel's Equations Oblique Incidence  $\left(\alpha = \frac{\cos \theta_T}{\cos \theta_L} = \frac{\sqrt{1 - (n_1/n_2)^2 \sin \theta_L^2}}{\cos \theta_L}, \beta = \frac{\mu_1 v_1}{\mu_2 v_2} \approx \frac{v_1}{v_2}\right)$ 

• P-Polarized ( $E_{\parallel}$  to Plane of Incidence):

$$\tilde{E}_R = \left(\frac{\alpha - \beta}{\alpha + \beta}\right) \tilde{E}_I ; \quad \tilde{E}_T = \left(\frac{2}{\alpha + \beta}\right) \tilde{E}_I$$

$$R = \frac{I_R}{I_I} = \left(\frac{E_R}{E_I}\right)^2 = \left(\frac{\alpha - \beta}{\alpha + \beta}\right)^2$$

$$T = \frac{I_T}{I_I} = \frac{\epsilon_2 v_2}{\epsilon_1 v_1} \left(\frac{E_T}{E_I}\right)^2 \frac{\cos \theta_T}{\cos \theta_I} = \alpha \beta \left(\frac{2}{\alpha + \beta}\right)^2$$

Reflection Shift/Angles  $\left(\alpha - \beta \stackrel{?}{=} 0\right)$ :  $\tan^2 \theta_I \stackrel{?}{=} \left(\frac{n_2}{n_1}\right)^2 \frac{1-\beta^2}{1-(n_2/n_1)^2}$ 

In-Phase  $(\delta = 0, \alpha > \beta)$ :  $\tan \theta_I > n_2/n_1$ Out-of-Phase  $(\delta = \pi, \ \alpha < \beta)$ :  $\tan \theta_I < n_2/n_1$ 

Brewster's Angle (R=0):  $\left|\tan \theta_{I=b} = n_2/n_1\right|$ ,  $\left|\theta_R + \theta_T = 90\right|$ Critical Angle (T=0):  $\sin \theta_{I=c} = n_2/n_1$ ,  $\theta_R = 90$ 

• S-Polarized ( $E_{\perp}$  to Plane of Incidence):

$$\tilde{E}_R = \left(\frac{1 - \alpha\beta}{1 + \alpha\beta}\right) E_I ; \quad \tilde{E}_T = \left(\frac{2}{1 + \alpha\beta}\right) E_I$$

$$R = \frac{I_R}{I_I} = \left(\frac{E_R}{E_I}\right)^2 = \left(\frac{1 - \alpha\beta}{1 + \alpha\beta}\right)^2$$

$$T = \frac{I_T}{I_I} = \frac{\epsilon_2 v_2}{\epsilon_1 v_1} \alpha \left(\frac{E_T}{E_I}\right)^2 = \alpha\beta \left(\frac{2}{1 + \alpha\beta}\right)^2$$

Reflection Shift/Angles  $\left(1 - \alpha\beta \stackrel{?}{=} 0\right)$ :  $\alpha\beta \approx \frac{\sqrt{\beta^2 - \sin\theta_I^2}}{\cos\theta_I}$ 

In-Phase  $(\delta = 0, 1 > \alpha \beta)$ :  $n_1 > n_2$ Out-of-Phase  $(\delta = \pi, 1 < \alpha \beta)$ :  $n_2 > n_1$ 

Brewster Angle (R = 0):  $n_1 = n_2$  (None)

Critical Angle (T=0):  $\left|\sin \theta_{I=c} = n_2/n_1\right|$ ,  $\left|\theta_R = 90\right|$ (evanescent if  $> \theta_c$ )

#### 7.3 Diffraction and Interference

<u>Double Slit Interference</u>:  $(d \ll L)$ 

Maxima:  $d \sin \theta = m\lambda$ 

Minima:  $d \sin \theta = (m + \frac{1}{2})\lambda$ 

Circular Aperture: (Diameter:  $D \ll L$ )

 $\theta = \text{Twice the normal, vertical angle}$ 

1st Minima :  $D \sin \theta = 1.22\lambda$ 

Optical Path Length:  $(n_1 \to n_2, \lambda \to \frac{\lambda}{n}, v_n = f \frac{\lambda}{n})$ 

- $\delta = \frac{2\pi d}{\lambda/n} = k(nd)$
- $\Delta x_n = nd = nv\Delta t = c\Delta t$  (t, time through medium n) (2dn for thin film reflec.)

## 7.4 Lenses and Mirrors ( $\lambda \ll a$ )

Draw Picture: 1.  $\overline{f, y_{[s]}, L_{\text{ens}}} \to \overline{L_{\text{ens}}, y'_{[s']}, \infty}$ 

2.  $\overline{\infty, y_{[s]}, L_{\text{ens}}} \to \overline{f', L_{\text{ens}}, y'_{[s']}}$ 

Imaging Eq. :  $\frac{n_1}{s} + \frac{n_2}{s'} = \frac{n_2 - n_1}{R}$ 

Thin Lens Eq. :  $\frac{1}{f} = \frac{1}{s} + \frac{1}{s'}$  (Focal Length, f = f')

Lensmaker Eq. :  $\frac{1}{f} = \left(\frac{n_2}{n_1} - 1\right) \left(\frac{1}{R_1} - \frac{1}{R_2}\right)$  (R<sub>2</sub> is [-] for concave lens)

Lens Magnf. :  $M_T \equiv \frac{y'}{y} = -\frac{s'}{s} = \frac{f}{f-s}$  Virtual: f>s Real: s< f

Spherical Mirror: f = R/2

Single Slit Diffraction:  $(a \ll L, a \sim \lambda)$ 

Minima:  $a \sin \theta = m\lambda$ ,  $m \neq 0$ 

Bragg [X-Ray] Diffraction: (Atom Distance :  $d \sim \lambda$ )

 $\theta = \text{Angle from Horizontal (not vertical/normal)}$ 

• Maxima:  $(2d)\sin\theta = m\lambda$ 

Boundary Reflection:  $(n_1 \to n_2)$ 

 $n_2 < n_1: \delta += 0$ 

 $n_2 > n_1: \delta += \pi$ 

#### 7.5 Other

Rayleigh Scattering  $(\lambda \gg a)$ :  $I \propto I_0 \left(\frac{a^6}{\lambda^4}\right)$  (Dipole Radiation, polarized)

[Sound] Doppler Effect  $(v \ll c)$ :  $f_r = \left(\frac{v + v_r}{v - v_s}\right) f_s$  (frequency,  $f_s$ ) if  $f_s \to f_s$  (frequency,  $f_s \to f_s \to f_s$ )

Standing Sound Wave

• Open Pipe:  $L = n\left(\frac{\pi}{2}\right)$  (Ends are nodes/infl. pts. of 0 press.)

• Half Pipe :  $L = (2n+1) \left(\frac{\pi}{4}\right)$  (Open End is a node, Closed is an antinode/maxi. press.)

Malus's Law:  $I = I_0 \cos^2 \theta$  (polarized)  $I = I_0/2$  (unpolarized)

## 7.6 Conductor; $J_{free} \neq 0$

$$J_{free} = \sigma E$$

$$\tilde{E}(z,t) = \tilde{E}_0 e^{i(\tilde{k}z - wt)}; \quad \tilde{B}(z,t) = \tilde{B}_0 e^{i(\tilde{k}z - wt)}$$

$$\tilde{k} = k + i\kappa; \quad \tilde{k}^2 = \mu \epsilon \omega^2 + i\mu \sigma \omega$$

$$k = \omega \sqrt{\frac{\epsilon \mu}{2}} \sqrt{\sqrt{1 + \left(\frac{\sigma}{\epsilon \omega}\right)^2} + 1} \; ; \quad \kappa = \omega \sqrt{\frac{\epsilon \mu}{2}} \sqrt{\sqrt{1 + \left(\frac{\sigma}{\epsilon \omega}\right)^2} - 1}$$

Skin depth: 
$$d = \frac{1}{\kappa}$$

Wave (phase) velocity: 
$$v = \frac{\omega}{k}$$

Group velocity (carries energy): 
$$v_g = \frac{d\omega}{dk} < c$$

Index Ref: 
$$n = \frac{ck}{\omega}$$

$$\frac{B_0}{E_0} = \frac{K}{\omega} = |\tilde{k}|/\omega = \sqrt{\epsilon \mu \sqrt{1 + \left(\frac{\sigma}{\epsilon \omega}\right)^2}}$$

$$\tilde{\beta} = \frac{\mu_1 v_1}{\mu_2 \omega} \tilde{k}$$

$$\tilde{E}_R = \left(\frac{1-\tilde{eta}}{1+\tilde{eta}}\right) \tilde{E}_I; \quad \tilde{E}_T = \left(\frac{2}{1+\tilde{eta}}\right) \tilde{E}_I$$

#### 7.7 Wave Guides

$$E^{||} = 0; \quad B^{\perp} = 0$$

TE Waves:  $E_z = 0$ ; TM Waves:  $B_z = 0$ ; TEM Waves:  $E_z = B_z = 0$ 

$$E_{x} = \frac{i}{(w/c)^{2} - k^{2}} \left( k \frac{\partial E_{z}}{\partial x} + \omega \frac{\partial B_{z}}{\partial y} \right)$$

$$E_{y} = \frac{i}{(w/c)^{2} - k^{2}} \left( k \frac{\partial E_{z}}{\partial y} - \omega \frac{\partial B_{z}}{\partial x} \right)$$

$$B_{x} = \frac{i}{(w/c)^{2} - k^{2}} \left( k \frac{\partial B_{z}}{\partial x} - \frac{\omega}{c^{2}} \frac{\partial E_{z}}{\partial y} \right)$$

$$B_{Y} = \frac{i}{(w/c)^{2} - k^{2}} \left( k \frac{\partial B_{z}}{\partial Y} + \frac{\omega}{c^{2}} \frac{\partial E_{z}}{\partial X} \right)$$

Solving Rectangular Wave Guides:

TE<sub>mn≠00</sub>: 
$$\left[\frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2} + (\omega/c)^2 - k^2\right] B_z = 0$$
  
 $B_z = X(x)Y(y)$ 

$$\frac{\partial^2 X}{\partial x^2} = -k_x^2 X; \quad \frac{\partial^2 Y}{\partial y^2} = -k_y^2 Y$$
$$-k_x^2 - k_y^2 + (w/c)^2 - k^2 = 0$$

 $B_z = B_0 \cos(m\pi x/a) \cos(n\pi y/b)$ 

$$\omega < \omega_{mn} = c\pi \sqrt{(m/a)^2 + (n/b)^2}$$

TM: 
$$\left[ \frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2} + (\omega/c)^2 - k^2 \right] E_z = 0$$

## 8 Del

$$\nabla F = \left\langle \frac{\partial}{\partial r}, \frac{1}{r} \frac{\partial}{\partial \theta}, \frac{1}{r \sin \theta} \frac{\partial}{\partial \phi} \right\rangle F$$

$$\nabla \cdot \vec{A} = \frac{1}{r^2 \sin \theta} \left\langle \frac{\partial}{\partial r}, \frac{\partial}{\partial \theta}, \frac{\partial}{\partial \phi} \right\rangle \cdot r^2 \sin \theta \left\langle A_r, \frac{1}{r} A_\theta, \frac{1}{r \sin \theta} A_\phi \right\rangle$$

$$\nabla \times \vec{A} = \frac{1}{r^2 \sin \theta} \begin{vmatrix} \hat{r} & r\hat{\theta} & r \sin \theta \hat{\phi} \\ \frac{\partial}{\partial r} & \frac{\partial}{\partial \theta} & \frac{\partial}{\partial \phi} \\ A_r & rA_{\theta} & r \sin \theta A_{\phi} \end{vmatrix}$$

$$[\vec{A} \times (\vec{B} \times \vec{C})]_i = \vec{A} \cdot (B_i \vec{C}) - \vec{A} \cdot (\vec{B} C_i)$$

$$\vec{A} \times (\vec{B} \times \vec{C}) = [(\vec{A} \cdot (\vec{B} \otimes \vec{C})^T)^T - (\vec{A} \cdot \vec{B} \otimes \vec{C})^T] = (\vec{A} \otimes \vec{B}) \cdot \vec{C} - (\vec{A} \cdot \vec{B} \otimes \vec{C})^T$$
$$= (A^T (BC^T)^T)^T - (A^T BC^T)^T = (AB^T)^T C - (A^T BC^T)^T$$