# ETSI TS 132 416 V16.0.0 (2020-08)



Digital cellular telecommunications system (Phase 2+) (GSM); Universal Mobile Telecommunications System (UMTS); LTE;

Telecommunication management;
Performance Management (PM)
Integration Reference Point (IRP);
Solution Set (SS) definitions
(3GPP TS 32.416 version 16.0.0 Release 16)



# Reference RTS/TSGS-0532416vg00 Keywords GSM,LTE,UMTS

#### **ETSI**

650 Route des Lucioles F-06921 Sophia Antipolis Cedex - FRANCE

Tel.: +33 4 92 94 42 00 Fax: +33 4 93 65 47 16

Siret N° 348 623 562 00017 - NAF 742 C Association à but non lucratif enregistrée à la Sous-Préfecture de Grasse (06) N° 7803/88

#### Important notice

The present document can be downloaded from: <u>http://www.etsi.org/standards-search</u>

The present document may be made available in electronic versions and/or in print. The content of any electronic and/or print versions of the present document shall not be modified without the prior written authorization of ETSI. In case of any existing or perceived difference in contents between such versions and/or in print, the prevailing version of an ETSI deliverable is the one made publicly available in PDF format at <a href="https://www.etsi.org/deliver">www.etsi.org/deliver</a>.

Users of the present document should be aware that the document may be subject to revision or change of status.

Information on the current status of this and other ETSI documents is available at

<a href="https://portal.etsi.org/TB/ETSIDeliverableStatus.aspx">https://portal.etsi.org/TB/ETSIDeliverableStatus.aspx</a>

If you find errors in the present document, please send your comment to one of the following services: https://portal.etsi.org/People/CommitteeSupportStaff.aspx

#### **Copyright Notification**

No part may be reproduced or utilized in any form or by any means, electronic or mechanical, including photocopying and microfilm except as authorized by written permission of ETSI.

The content of the PDF version shall not be modified without the written authorization of ETSI.

The copyright and the foregoing restriction extend to reproduction in all media.

© ETSI 2020. All rights reserved.

**DECT™**, **PLUGTESTS™**, **UMTS™** and the ETSI logo are trademarks of ETSI registered for the benefit of its Members. **3GPP™** and **LTE™** are trademarks of ETSI registered for the benefit of its Members and of the 3GPP Organizational Partners.

oneM2M<sup>™</sup> logo is a trademark of ETSI registered for the benefit of its Members and of the oneM2M Partners.

GSM® and the GSM logo are trademarks registered and owned by the GSM Association.

# Intellectual Property Rights

#### **Essential patents**

IPRs essential or potentially essential to normative deliverables may have been declared to ETSI. The information pertaining to these essential IPRs, if any, is publicly available for **ETSI members and non-members**, and can be found in ETSI SR 000 314: "Intellectual Property Rights (IPRs); Essential, or potentially Essential, IPRs notified to ETSI in respect of ETSI standards", which is available from the ETSI Secretariat. Latest updates are available on the ETSI Web server (https://ipr.etsi.org/).

Pursuant to the ETSI IPR Policy, no investigation, including IPR searches, has been carried out by ETSI. No guarantee can be given as to the existence of other IPRs not referenced in ETSI SR 000 314 (or the updates on the ETSI Web server) which are, or may be, or may become, essential to the present document.

#### **Trademarks**

The present document may include trademarks and/or tradenames which are asserted and/or registered by their owners. ETSI claims no ownership of these except for any which are indicated as being the property of ETSI, and conveys no right to use or reproduce any trademark and/or tradename. Mention of those trademarks in the present document does not constitute an endorsement by ETSI of products, services or organizations associated with those trademarks.

# **Legal Notice**

This Technical Specification (TS) has been produced by ETSI 3rd Generation Partnership Project (3GPP).

The present document may refer to technical specifications or reports using their 3GPP identities. These shall be interpreted as being references to the corresponding ETSI deliverables.

The cross reference between 3GPP and ETSI identities can be found under http://webapp.etsi.org/key/queryform.asp.

# Modal verbs terminology

In the present document "shall", "shall not", "should", "should not", "may", "need not", "will", "will not", "can" and "cannot" are to be interpreted as described in clause 3.2 of the <u>ETSI Drafting Rules</u> (Verbal forms for the expression of provisions).

"must" and "must not" are NOT allowed in ETSI deliverables except when used in direct citation.

# Contents

Intell	lectual Property Rights	2
Legal	1 Notice	2
Moda	al verbs terminology	2
	word	
	duction	
1	Scope	
	References	
2		
3 3.1 3.2	Definitions and abbreviations	7
4	Solution Set definitions	
	ex A (normative): CORBA Solution Set	
A.1 A.1.1	Architectural Features	
A.1.2	•	
A.2	Mapping	
A.2.1 A.2.2	1 6	
A.2.2 A.2.3		
A.3 A.3.1	PMIRPNotification Interface  Method push (M)	
A.4	Solution Set definitions	16
A.4.1		
A.4.2 A.4.3	1	
A.4.4	1	
Anne	ex B (normative): XML definitions	25
B.1	Architectural features	25
B.1.1	Syntax for Distinguished Names	25
B.2	Mapping	25
B.3	Solution Set definitions	
B.3.1 B.3.2		
B.3.3	<u>.                                      </u>	
B.3.4	<u>.</u>	
Anne	ex C (normative): SOAP Solution Set	32
C.1	Architectural Features	32
C.1.1	Syntax for Distinguished Names	32
C.2	Mapping	
C.2.1	Operation and notification mapping	
C.2.2 C.2.2.	1 1 0	
C.2.2.	1	
C.2.2.	1 1	
C22	1.3 Fault definition	34

C.2.2.2.1       Input parameters       35         C.2.2.2.2       Output parameters       35         C.2.2.3       Fault definition       35         C.2.2.3.1       Input parameters       35         C.2.2.3.2       Output parameters       35         C.2.2.3.3       Fault definition       36         C.2.2.4.1       Operation resume MeasurementJob       36         C.2.2.4.1       Input parameters       36         C.2.2.4.2       Output parameters       36         C.2.2.4.3       Fault definition       36         C.2.2.4.5       Fault definition       36         C.2.2.5.1       Input parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.6.1       Input parameters       37         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.	C.2.2.2	Operation stopMeasurementJob	35
C.2.2.2.2       Output parameters.       .35         C.2.2.3       Operation suspendMeasurementJob       .35         C.2.2.3.1       Input parameters.       .35         C.2.2.3.2       Output parameters.       .35         C.2.2.3.3       Fault definition       .36         C.2.2.4       Operation resumeMeasurementJob.       .36         C.2.2.4.1       Input parameters.       .36         C.2.2.4.2       Output parameters.       .36         C.2.2.4.2       Output parameters.       .36         C.2.2.4.3       Fault definition       .36         C.2.2.5.1       Input parameters.       .37         C.2.2.5.2       Output parameters.       .37         C.2.2.5.3       Fault definition       .37         C.2.2.6       Operation create ThresholdMonitor       .37         C.2.2.6       Operation create ThresholdMonitor       .37         C.2.2.6.2       Output parameters.       .38         C.2.2.7       Operation delete ThresholdMonitor       .38         C.2.2.7.1       Input parameters.       .38         C.2.2.8       Operation is thresholdMonitors.       .39         C.2.2.8.1       Fault definition       .39         C.2.2.8.2	C.2.2.2.1		
C.2.2.3       Operation suspend/MeasurementJob       .35         C.2.2.3.2       Output parameters       .35         C.2.2.3.3       Fault definition       .36         C.2.2.4.1       Operation resumeMeasurementJob       .36         C.2.2.4.2       Output parameters       .36         C.2.2.4.3       Fault definition       .36         C.2.2.4.3       Fault definition       .36         C.2.2.4.3       Fault definition       .36         C.2.2.4.5       Fault definition       .36         C.2.2.5.1       Input parameters       .37         C.2.2.5.2       Output parameters       .37         C.2.2.5.2       Output parameters       .37         C.2.2.6.2       Operation create ThresholdMonitor       .37         C.2.2.6.3       Fault definition       .38         C.2.2.6.1       Input parameters       .38         C.2.2.6.2       Output parameters       .38         C.2.2.7.1       Input parameters       .38         C.2.2.7.2       Fault definition       .39         C.2.2.8       Operation ilstThresholdMonitor       .39         C.2.2.8.1       Input parameters       .39         C.2.2.9.2       Fault definition	C.2.2.2.2		
C.2.2.3.1       Input parameters.       35         C.2.2.3.2       Output parameters.       35         C.2.2.3.3       Fault definition.       36         C.2.2.4.1       Input parameters.       36         C.2.2.4.2       Output parameters.       36         C.2.2.4.3       Fault definition.       36         C.2.2.4.3       Fault definition.       36         C.2.2.5.1       Input parameters.       37         C.2.2.5.2       Output parameters.       37         C.2.2.5.2.5       Output parameters.       37         C.2.2.6.1       Input parameters.       37         C.2.2.6.2.6.1       Input parameters.       37         C.2.2.6.2.3       Fault definition.       37         C.2.2.6.3       Fault definition.       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7       Output parameters.       38         C.2.2.7.2       Output parameters.       38         C.2.2.7.3       Fault definition.       39         C.2.2.8.2       Output parameters.       39         C.2.2.8.2       Output parameters.       39	C.2.2.2.3	Fault definition	35
C.2.2.3.2       Output parameters       35         C.2.2.3.3       Fault definition       36         C.2.2.4.1       Input parameters       36         C.2.2.4.2       Output parameters       36         C.2.2.4.3       Fault definition       36         C.2.2.4.3       Fault definition       36         C.2.2.5.1       Input parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.5.3       Fault definition       37         C.2.2.5.1       Input parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.6       Operation create ThresholdMonitor       38         C.2.2.6.1       Input parameters       38         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation IsiThresholdMonitors       39         C.2.2.8       Operation suspendThresholdMonitors       39	C.2.2.3	Operation suspendMeasurementJob	35
C.2.2.4 Operation resumeMeasurementJob       36         C.2.2.4.1 Input parameters       36         C.2.2.4.2 Output parameters       36         C.2.2.4.3 Fault definition       36         C.2.2.4.5 Operation I JistMeasurementJobs       37         C.2.2.5 Operation I JistMeasurementJobs       37         C.2.2.5.1 Input parameters       37         C.2.2.5.2 Output parameters       37         C.2.2.5.3 Fault definition       37         C.2.2.6 Operation createThresholdMonitor       37         C.2.2.6.1 Input parameters       38         C.2.2.6.2 Output parameters       38         C.2.2.6.3 Fault definition       38         C.2.2.7 Operation deleteThresholdMonitor       38         C.2.2.7.1 Input parameters       38         C.2.2.7.2 Output parameters       38         C.2.2.7.2 Output parameters       38         C.2.2.8 Operation listThresholdMonitor       39         C.2.2.8 Operation listThresholdMonitors       39         C.2.2.8.1 Input parameters       39         C.2.2.9 Operation suspendThresholdMonitor       39         C.2.2.9 Operation suspendThresholdMonitor       39         C.2.2.9 Total definition       39         C.2.2.9 Total definition       40	C.2.2.3.1	Input parameters	35
C.2.2.4       Operation resumeMeasurementJob.       36         C.2.2.4.1       Input parameters       36         C.2.2.4.3       Fault definition       36         C.2.2.5       Operation 1 i st Measurement Jobs       37         C.2.2.5.1       Input parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.5.3       Fault definition       37         C.2.2.6       Operation createThresholdMonitor       37         C.2.2.6.1       Input parameters       37         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8       Operation suspendThresholdMonitors       39         C.2.2.8.2       Output parameters       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.3       Fault definition       40         C.2.2.9.3       Fault	C.2.2.3.2	Output parameters	35
C.2.2.4.1       Input parameters       .36         C.2.2.4.2       Output parameters       .36         C.2.2.5.1       Fault definition       .37         C.2.2.5.1       Input parameters       .37         C.2.2.5.2       Output parameters       .37         C.2.2.5.3       Fault definition       .37         C.2.2.6       Operation createThresholdMonitor       .37         C.2.2.6.1       Input parameters       .37         C.2.2.6.2       Output parameters       .38         C.2.2.6.3       Fault definition       .38         C.2.2.7       Operation deleteThresholdMonitor       .38         C.2.2.7       Operation deleteThresholdMonitor       .38         C.2.2.7       Output parameters       .38         C.2.2.7       Output parameters       .38         C.2.2.7       Fault definition       .39         C.2.2.8       Operation listThresholdMonitors       .39         C.2.2.8.2       Output parameters       .39         C.2.2.8.3       Fault definition       .39         C.2.2.9.1       Input parameters       .39         C.2.2.9.2       Output parameters       .40         C.2.2.9.2       Output parameters       .	C.2.2.3.3	Fault definition	36
C.2.2.4.2       Output parameters       .36         C.2.2.4.3       Fault definition       .36         C.2.2.5       Operation ListMeasurementJobs       .37         C.2.2.5.1       Input parameters       .37         C.2.2.5.2       Output parameters       .37         C.2.2.5.3       Fault definition       .37         C.2.2.6.0       Operation create ThresholdMonitor       .37         C.2.2.6.1       Input parameters       .37         C.2.2.6.2       Output parameters       .38         C.2.2.6.3       Fault definition       .38         C.2.2.7       Operation delete ThresholdMonitor       .38         C.2.2.7.1       Input parameters       .38         C.2.2.7.2       Output parameters       .38         C.2.2.7.3       Fault definition       .39         C.2.2.8       Operation listThresholdMonitors       .39         C.2.2.8.1       Input parameters       .39         C.2.2.8.2       Output parameters       .39         C.2.2.8.3       Fault definition       .39         C.2.2.9.1       Input parameters       .39         C.2.2.9.2       Output parameters       .39         C.2.2.9.3       Fault definition	C.2.2.4	Operation resumeMeasurementJob	36
C.2.2.4.3       Fault definition       36         C.2.2.5       Operation listMeasurementJobs       37         C.2.2.5.1       Input parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.5.3       Fault definition       37         C.2.2.6       Operation createThresholdMonitor       37         C.2.2.6.1       Input parameters       38         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       39         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10       Operation resumeThresholdMonitor	C.2.2.4.1	Input parameters	36
C.2.2.5       Operation listMeasurementJobs       37         C.2.2.5.1       Input parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.5.3       Fault definition       37         C.2.2.6       Operation createThresholdMonitor       37         C.2.2.6.1       Input parameters       38         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9       Operation resumeThresholdMonitor       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1	C.2.2.4.2	Output parameters	36
C.2.2.5.1       Input parameters       37         C.2.2.5.2       Output parameters       37         C.2.2.5.3       Fault definition       37         C.2.2.6       Operation createThresholdMonitor       37         C.2.2.6.1       Input parameters       37         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters<	C.2.2.4.3	Fault definition	36
C.2.2.5.2       Output parameters       37         C.2.2.5.3       Fault definition       37         C.2.2.6       Operation createThresholdMonitor       37         C.2.2.6.1       Input parameters       38         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition structure <td>C.2.2.5</td> <td>Operation listMeasurementJobs</td> <td>37</td>	C.2.2.5	Operation listMeasurementJobs	37
C.2.2.5.2       Output parameters       37         C.2.2.5.3       Fault definition       37         C.2.2.6       Operation createThresholdMonitor       37         C.2.2.6.1       Input parameters       38         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition structure <td>C.2.2.5.1</td> <td>Input parameters</td> <td>37</td>	C.2.2.5.1	Input parameters	37
C.2.2.6       Operation createThresholdMonitor       37         C.2.2.6.1       Input parameters       37         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.2.2.10.3       Fault definition       40         C.2.2.10.3       Fault definition       40	C.2.2.5.2		
C.2.2.6.1       Input parameters       37         C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.2.2.10.3       Fault definition       40         C.3.1       WSDL definition structure	C.2.2.5.3	Fault definition	37
C.2.2.6.2       Output parameters       38         C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10       Output parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.2.2.10.3       Fault definition       40         C.2.2.10.3       Fault definition       41	C.2.2.6	Operation createThresholdMonitor	37
C.2.2.6.3       Fault definition       38         C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       40         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definitions       40         C.2.2.10.3       Fault definitions       40         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"<	C.2.2.6.1	Input parameters	37
C.2.2.7       Operation deleteThresholdMonitor       38         C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       40         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3.2       Graphical Representation       41         C.3.3       WSDL definition "PMIRPSystem.wsdl"       42         Annex D (informative):       Change histo	C.2.2.6.2	Output parameters	38
C.2.2.7.1       Input parameters       38         C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.6.3	Fault definition	38
C.2.2.7.2       Output parameters       38         C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history	C.2.2.7	Operation deleteThresholdMonitor	38
C.2.2.7.3       Fault definition       39         C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.7.1	Input parameters	38
C.2.2.8       Operation listThresholdMonitors       39         C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3.1       WSDL definitions       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.7.2	Output parameters	38
C.2.2.8.1       Input parameters       39         C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.7.3	Fault definition	39
C.2.2.8.2       Output parameters       39         C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3.1       WSDL definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.8	Operation listThresholdMonitors	39
C.2.2.8.3       Fault definition       39         C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.8.1	Input parameters	39
C.2.2.9       Operation suspendThresholdMonitor       39         C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.8.2	Output parameters	39
C.2.2.9.1       Input parameters       39         C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.8.3	Fault definition	39
C.2.2.9.2       Output parameters       40         C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.9	Operation suspendThresholdMonitor	39
C.2.2.9.3       Fault definition       40         C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.9.1	Input parameters	39
C.2.2.10       Operation resumeThresholdMonitor       40         C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.9.2	Output parameters	40
C.2.2.10.1       Input parameters       40         C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.9.3	Fault definition	40
C.2.2.10.2       Output parameters       40         C.2.2.10.3       Fault definition       40         C.3 Solution Set definitions       41         C.3.1       WSDL definition structure       41         C.3.2       Graphical Representation       41         C.3.3       WSDL specification "PMIRPSystem.wsdl"       42         Annex D (informative):       Change history       52	C.2.2.10	Operation resumeThresholdMonitor	40
C.2.2.10.3 Fault definition	C.2.2.10.1	Input parameters	40
C.3 Solution Set definitions	C.2.2.10.2	Output parameters	40
C.3.1 WSDL definition structure	C.2.2.10.3	Fault definition	40
C.3.1 WSDL definition structure	C 2 Solution	on Sat definitions	41
C.3.2 Graphical Representation			
C.3.3 WSDL specification "PMIRPSystem.wsdl"			
Annex D (informative): Change history	C.3.2 C	Jiapineal Representation	41
	C.3.3 V	w SDL specification PivitkPSystem.wsdi	42
History	Annex D (	(informative): Change history	52
	History		53

#### **Foreword**

This Technical Specification has been produced by the 3<sup>rd</sup> Generation Partnership Project (3GPP).

The contents of the present document are subject to continuing work within the TSG and may change following formal TSG approval. Should the TSG modify the contents of the present document, it will be re-released by the TSG with an identifying change of release date and an increase in version number as follows:

Version x.y.z

where:

- x the first digit:
  - 1 presented to TSG for information;
  - 2 presented to TSG for approval;
  - 3 or greater indicates TSG approved document under change control.
- y the second digit is incremented for all changes of substance, i.e. technical enhancements, corrections, updates, etc.
- z the third digit is incremented when editorial only changes have been incorporated in the document.

# Introduction

The present document is part of a TS-family covering the 3<sup>rd</sup> Generation Partnership Project; Technical Specification Group Services and System Aspects; Telecommunication management; as identified below:

- 32.411: Performance Management (PM) Integration Reference Point (IRP): Requirements
- 32.412: Performance Management (PM) Integration Reference Point (IRP): Information Service (IS)
- 32.416: Performance Management (PM) Integration Reference Point (IRP): Solution Set (SS) definitions

The present document is part of a set of TSs which describe the requirements and information model necessary for the Telecommunication Management (TM) of 3G systems. The TM principles and TM architecture are specified in 3GPP TS 32.101 [1] and 3GPP TS 32.102 [2].

A 3G system is composed of a multitude of Network Elements (NE) of various types and, typically, different vendors, which inter-operate in a co-ordinated manner in order to satisfy the network users' communication requirements. Any evaluation of PLMN-system behaviour will require performance data collected and recorded by its NEs according to a schedule established by the EM.

This aspect of the management environment is termed Performance Management. The purpose of any Performance Management activity is to collect performance related data, which can be used to locate potential problems in the network.

# 1 Scope

[15]

The present document specifies the Solution Set definitions for the IRP whose semantics is specified in PM (Performance Management) IRP: Information Service 3GPP TS 32.412 [7].

This Solution Set definitions specification is related to 3GPP TS 32.412 V14.0.X.

# 2 References

The following documents contain provisions which, through reference in this text, constitute provisions of the present document.

- References are either specific (identified by date of publication, edition number, version number, etc.) or non-specific.
- For a specific reference, subsequent revisions do not apply.
- For a non-specific reference, the latest version applies. In the case of a reference to a 3GPP document (including a GSM document), a non-specific reference implicitly refers to the latest version of that document *in the same Release as the present document*.

Release as th	ne present document.
[1]	3GPP TS 32.101: "Telecommunication management; Principles and high level requirements".
[2]	3GPP TS 32.102: "Telecommunication management; Architecture".
[3]	3GPP TS 32.411: "Telecommunication management; Performance Management (PM) Integration Reference Point (IRP): Requirements".
[4]	3GPP TS 32.311: "Telecommunication management; Generic Integration Reference Point (IRP): Requirements".
[5]	3GPP TS 32.306: "Telecommunication management; Configuration Management (CM); Notification Integration Reference Point (IRP): Solution Set (SS) definitions".
[6]	3GPP TS 32.300: "Telecommunication management; Configuration Management (CM); Name convention for Managed Objects".
[7]	3GPP TS 32.412: "Telecommunication management; Performance Management (PM) Integration Reference Point (IRP): Information Service (IS)".
[8]	3GPP TS 32.312: "Telecommunication management; Generic Integration Reference Point (IRP) management: Information Service (IS)".
[9]	OMG TC Document telecom/98-11-01: "OMG Notification Service". <a href="http://www.omg.org/technology/documents/">http://www.omg.org/technology/documents/</a>
[10]	3GPP TS 32.401: "Telecommunication management; Performance Management (PM); Concept and requirements".
[11]	3GPP TS 32.336: "Telecommunication management; Notification Log (NL) Integration Reference Point (IRP): Solution Set (SS) definitions ".
[12]	3GPP TS 32.331: "Telecommunication management; Notification Log (NL) Integration Reference Point (IRP): Requirements".
[13]	3GPP TS 32.316: "Telecommunication management; Generic Integration Reference Point (IRP) management; Solution Set (SS) definitions".
[14]	3GPP TS 32.150: "Telecommunication management; Integration Reference Point (IRP) Concept and definitions".

W3C SOAP 1.1 specification (http://www.w3.org/TR/2000/NOTE-SOAP-20000508/)

[16]	W3C XPath 1.0 specification (http://www.w3.org/TR/1999/REC-xpath-19991116)
[17]	W3C WSDL 1.1 specification (http://www.w3.org/TR/2001/NOTE-wsdl-20010315)
[18]	W3C SOAP 1.2 specification ( <a href="http://www.w3.org/TR/soap12-part1/">http://www.w3.org/TR/soap12-part1/</a> )

# 3 Definitions and abbreviations

#### 3.1 Definitions

For the purposes of the present document, the terms and definitions given in 3GPP TS 32.101 [1], 3GPP TS 32.102 [2], 3GPP TS 32.401 [10], 3GPP TS 32.411 [3], 3GPP TS 32.331 [12], 3GPP TS 32.150 [14] and the following apply:

IRP document version number string (or "IRPVersion"): See 3GPP TS 32.311 [4]..

#### 3.2 Abbreviations

For the purposes of the present document, the following abbreviations apply:

CM	Configuration Management
CORBA	Common Object Request Broker Architecture
DN	Distinguished Name
EM	Element Manager
IDL	Interface Definition Language
IRP	Integration Reference Point
IS	Information Service
MOC	Managed Object Class
NE	Network Element
NL	Notification Log

OMG Object Management Group PM Performance Management

PMIRP Performance Management Integration Reference Point

SS Solution Set

WSDL Web Service Description Language XML eXtensible Markup Language

# 4 Solution Set definitions

This specification defines the following 3GPP PM IRP Solution Set definitions:

- 3GPP PM IRP CORBA SS (Annex A).
- 3GPP PM IRP XML definitions (Annex B).
- 3GPP PM IRP SOAP Solution Set (Annex C).

# Annex A (normative): CORBA Solution Set

This annex contains the CORBA Solution Set for the IRP whose semantics is specified in PM IRP: Information Service (TS 32.412 [7]).

# A.1 Architectural Features

The overall architectural feature of PM IRP is specified in 3GPP TS 32.411 [3].

This clause specifies features that are specific to the CORBA SS.

# A.1.1 Syntax for Distinguished Names

The syntax of a Distinguished Name is defined in 3GPP TS 32.300 [6].

#### A.1.2 Notifications

Notifications are sent according to the Notification IRP: CORBA SS (see 3GPP TS 32.306 [5]).

The contents of the PM IRP notifications are defined in the present document.

# A.2 Mapping

# A.2.1 Operation and Notification mapping

PM IRP: IS 3GPP TS 32.412 [7] defines semantics of operation and notification visible across the PMIRP. Table A.2.1.1 indicates mapping of these operations and notifications to their equivalents defined in this SS.

Table A.2.1.1: Mapping from IS Operations and Notification to SS equivalents

IS Operations/ notification 3GPP TS 32.412 [7]	SS Method	Qualifier
createMeasurementJob	create_measurement_job	М
stopMeasurementJob	stop_measurement_job	М
suspendMeasurementJob	suspend_measurement_job	0
resumeMeasurementJob	resume_measurement_job	0
listMeasurementJobs	list_measurement_jobs	М
createThresholdMonitor	create_threshold_monitor	0
deleteThresholdMonitor	delete_threshold_monitor	0
listThresholdMonitors	list_threshold_monitors	0
suspendThresholdMonitor	suspend_threshold_monitor	0
resumeThresholdMonitor	resume_threshold_monitor	0
getIRPVersion	get_pm_irp_versions	М
getOperationProfile (see note)	get_pm_irp_operations_profile	0
getNotificationProfile (see note)	get_pm_irp_notification_profile	0
notifyMeasurementJobStatusChanged	push_structured_events(See subclause 6.1)	М
notifyThresholdMonitorObjectCreation	push_structured_events (See subclause 6.1)	0
notifyThresholdMonitorObjectDeletion	push_structured_events (See subclause 6.1)	0
notifyThresholdMonitorStatusChanged	push_structured_events(See subclause 6.1)	0
NOTE: This operation is of ManagedGenericIRF inherits from it.	P IOC specified in 3GPP TS 32.312 [8]. The PM IRP IOC	of [7]

# A.2.2 Operation parameter mapping

The PM IRP: IS 3GPP TS 32.412 [7] defines semantics of parameters carried in operations across the PM IRP. The following tables indicate the mapping of these parameters, as per operation, to their equivalents defined in this SS.

Table A.2.2.1: Mapping from IS createMeasurementJob parameters to SS equivalents

IS Operation parameter	SS Method parameter	Qualifier
iocName	PMIRPConstDefs::MOClassName mo_class	М
iocInstanceList	PMIRPConstDefs::MOInstanceList mo_instance_list	М
measurementCategoryList	PMIRPConstDefs::MeasurementCategoryList measurement_category_list	М
granularityPeriod	PMIRPConstDefs::GranularityPeriod granularity_period	М
reportingPeriod	PMIRPConstDefs::ReportingPeriod reporting_period	М
startTime	PMIRPConstDefs::IRPTimeOpt start_time	0
stopTime	PMIRPConstDefs::IRPTimeOpt stop_time	0
schedule	PMIRPConstDefs::ScheduleOpt schedule	0
jobld	PMIRPConstDefs::JobId job_id	М
unsupportedList	PMIRPConstDefs::JUnsupportedList unsupported_list	М
priority	PMIRPConstDefs::JobPriorityOpt priority	0
reliability	PMIRPConstDefs::JobReliabilityOpt reliability	0
status	Return value of type ManagedGenericIRPConstDefs::Signal Exception: CreateMeasurementJob, ManagedGenericIRPSystem::InvalidParameter, ManagedGenericIRPSystem::ParameterNotSupported, HighWorkLoad	М

Table A.2.2.2: Mapping from IS stopMeasurementJob parameters to SS equivalents

IS Operation parameter	SS Method parameter	Qualifier
jobld	PMIRPConstDefs::JobId job_id	М
status	Return value of type PMIRPConstDefs::Result Exception: StopMeasurementJob, UnknownJob, JobCannotBeStopped	М

Table A.2.2.3: Mapping from IS suspendMeasurementJob parameters to SS equivalents

IS Operation parameter	SS Method parameter	Qualifier
jobld	PMIRPConstDefs::JobId job_id	М
status	Return value of type PMIRPConstDefs::Result Exception: SuspendMeasurementJob, UnknownJob, JobAlreadySuspended, ManagedGenericIRPSystem::OperationNotSupported	M

Table A.2.2.4: Mapping from IS resumeMeasurementJob parameters to SS equivalents

IS Operation parameter	SS Method parameter	Qualifier
jobld	PMIRPConstDefs::JobId job_id	М
status	Return value of type PMIRPConstDefs::Result Exception: ResumeMeasurementJob, UnknownJob, JobIsNotSuspended, HighWorkLoad, ManagedGenericIRPSystem::OperationNotSupported	М

Table A.2.2.5: Mapping from IS listMeasurementJobs parameters to SS equivalents

IS Operation parameter	SS Method parameter	Qualifier
jobldList	PMIRPConstDefs::JobIdList job_list_id	М
jobInfoList	PMIRPConstDefs::JobInfoList job_info_list	М
status	Return value of type PMIRPConstDefs::Result Exception: ListMeasurementJobs, ManagedGenericIRPSystem::InvalidParameter	М

Table A.2.2.6: Mapping from IS createThresholdMonitor parameters to SS equivalents

IS Operation parameter	SS Method parameter	Qualifier
iocName	PMIRPConstDefs::MOClassName mo_class	М
iocInstanceList	PMIRPConstDefs::MOInstanceList mo_instance_list	М
thresholdInfoList	PMIRPConstDefs::ThresholdInfoList threshold_info_list	М
monitorGranularityPeriod	PMIRPConstDefs::MonitorGranularityPeriod monitor_granularity_period	М
monitorId	PMIRPConstDefs::MonitorId monitor_id	М
unsupportedList	PMIRPConstDefs::MUnsupportedList unsupported_list	М
status	Return value of type ManagedGenericIRPConstDefs::Signal Exception: CreateThresholdMonitor, ManagedGenericIRPSystem::InvalidParameter, ManagedGenericIRPSystem::OperationNotSupported	M

Table A.2.2.7: Mapping from IS deleteThresholdMonitor parameters to SS equivalents

IS Operation parameter	SS Method parameter				
monitorId	PMIRPConstDefs::MonitorId monitor_id	М			
status	Return value of type PMIRPConstDefs::Result Exception: DeleteThresholdMonitor, UnknownThresholdMonitor, ManagedGenericIRPSystem::OperationNotSupported	M			

Table A.2.2.8: Mapping from IS listThresholdMonitors parameters to SS equivalents

IS Operation parameter	SS Method parameter				
monitorIdList	PMIRPConstDefs::MonitorIdList monitor_id_list	М			
monitorInfoList	PMIRPConstDefs::MonitorInfoList monitor_info_list	М			
status	Return value of type PMIRPConstDefs::Result Exception: ListThresholdMonitors, ManagedGenericIRPSystem::InvalidParameter, ManagedGenericIRPSystem::OperationNotSupported	М			

Table A.2.2.9: Mapping from IS suspendThresholdMonitor parameters to SS equivalents

IS Operation parameter	SS Method parameter			
monitorId	PMIRPConstDefs::MonitorId monitor_id	М		
status	Return value of type PMIRPConstDefs::Result Exception: SuspendThresholdMonitor, UnknownThresholdMonitor, ThresholdMonitorAlreadySuspended, ManagedGenericIRPSystem::OperationNotSupported	М		

Table A.2.2.10: Mapping from IS resumeThresholdMonitor parameters to SS equivalents

IS Operation parameter	SS Method parameter				
monitorId	MIRPConstDefs::MonitorId monitor_id				
status	Return value of type PMIRPConstDefs::Result Exception: ResumeThresholdMonitor, UnknownThresholdMonitor, ThresholdMonitorIsNotSuspended, ManagedGenericIRPSystem::OperationNotSupported	M			

Table A.2.2.11: Mapping from IS getIRPVersion parameters to SS equivalents

IS Operation parameter	SS Method parameter	Qualifier
versionNumberSet	Return value of type ManagedGenericIRPConstDefs::VersionNumberSet	М
status	Exception: GetPMIRPVersions	М

Table A.2.2.12: Mapping from IS getOperationProfile parameters to SS equivalents

IS Operation parameter	SS Method parameter		
iRPVersion	ManagedGenericIRPConstDefs::VersionNumber pm_irp_version	М	
operationNameProfile, operationParameterProfile	Return value of type ManagedGenericIRPConstDefs::MethodList		
status	Exception: GetPMIRPOperationsProfile, ManagedGenericIRPSystem::OperationNotSupported, ManagedGenericIRPSystem::InvalidParameter	М	

Table A.2.2.13: Mapping from IS getNotificationProfile parameters to SS equivalents

IS Operation parameter	SS Method parameter		
iRPVersion	ManagedGenericIRPConstDefs::VersionNumber pm_irp_version	М	
notificationNameProfile, notificationParameterProfile	Return value of type ManagedGenericIRPConstDefs::MethodList		
status	Exception: GetPMIRPNotificationProfile, ManagedGenericIRPSystem::OperationNotSupported, ManagedGenericIRPSystem::InvalidParameter	M	

# A.2.3 Notification parameter mapping

The PM IRP: IS 3GPP TS 32.412 [7] defines semantics of parameters carried in notifications. The following table indicates the mapping of these parameters to their OMG CORBA Structured Event (defined in OMG Notification Service [9]) equivalents. The composition of OMG Structured Event, as defined in the OMG Notification Service [9], is:

```
Header
Fixed Header
domain_name
type_name
event_name
Variable Header

Body
filterable_body_fields
remaining_body
```

The following tables list all OMG Structured Event attributes in the second column. The first column identifies the PM IRP: IS 3GPP TS 32.412 [7] defined notification parameters.

Table A.2.3.1: Mapping for notifyMeasurementJobStatusChanged

IS Parameters	OMG CORBA Structured Event attribute	Qualifier	Comment
There is no corresponding IS attribute.	domain_name	М	It carries the IRP document version number string. See subclause 3.1. It indicates the syntax and semantics of the Structured Event as defined by the present document.
notificationType	type_name	М	This is constant string "notifyMeasurementJobStatusChanged".
There is no corresponding IS attribute.	event_name	M	It carries no information.
There is no corresponding IS attribute.	Variable Header		
objectClass, objectInstance	One NV pair of filterable_body_fields	M	NV stands for name-value pair. Order arrangement of NV pairs is not significant. The name of NV-pair is always encoded in string.
			Name of this NV pair is the MANAGED_OBJECT_INSTANCE of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is a string. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
notificationId	One NV pair of remaining_body	М	Name of NV pair is the NOTIFICATION_ID of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is a long. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
eventTime	One NV pair of filterable_body_fields	М	Name of NV pair is the EVENT_TIME of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is IRPTime. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
systemDN	One NV pair of filterable_body_fields	М	Name of NV pair is the SYSTEM_DN of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is a string. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
jobld	One NV pair of filterable_body_fields	М	Name of NV pair is the JOB_ID of PMIRPNotifications::notifyMeasurementJobStatusChanged.
			Value of NV pair is JobId of module PMIRPConstDefs.
jobStatus	One NV pair of remaining_body	М	Name of NV pair is the JOB_STATUS of PMIRPNotifications::notifyMeasurementJobStatusChanged.
			Value of NV pair is JobStatus of module PMIRPConstDefs.
reason	One NV pair of remaining_body	0	Name of NV pair is the REASON of PMIRPNotifications::notifyMeasurementJobStatusChanged.
			Value of NV pair is a string.

 $\textbf{Table A.2.3.2: Mapping for} \ \texttt{notifyThresholdMonitorObjectCreation}$ 

IS Parameters	OMG CORBA Structured Event attribute	Qualifier	Comment
There is no corresponding IS attribute.	domain_name		It carries the IRP document version number string. See subclause 3.1. It indicates the syntax and semantics of the Structured Event as defined by the present document.

IS Parameters	OMG CORBA Structured Event attribute	Qualifier	Comment
notificationType	type_name	М	This is constant string "notifyThresholdMonitorObjectCreation".
There is no corresponding IS attribute.	event_name	M	It carries no information.
There is no corresponding IS attribute.	Variable Header		
objectClass, objectInstance	One NV pair of filterable_body_fields	М	NV stands for name-value pair. Order arrangement of NV pairs is not significant. The name of NV-pair is always encoded in string.
			Name of this NV pair is the MANAGED_OBJECT_INSTANCE of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is a string. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
notificationId	One NV pair of remaining body	М	Name of NV pair is the NOTIFICATION_ID of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is a long. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
eventTime	One NV pair of filterable_body_fields	М	Name of NV pair is the EVENT_TIME of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is IRPTime. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
systemDN	One NV pair of filterable_body_fields	М	Name of NV pair is the SYSTEM_DN of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is a string. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
monitorId	One NV pair of remaining body	М	Name of NV pair is the MONITOR_ID of module PMIRPNotifications::notifyThresholdMonitorObjectCreation.
			Value of NV pair is MonitorId of module PMIRPConstDefs.
monitorGranularityPeriod	One NV pair of remaining body	M	Name of NV pair is the MONITOR_GRANULARITY_PERIOD of module PMIRPNotifications::notifyThresholdMonitorObjectCreation.
		_	Value of NV pair is MonitorGranularityPeriod of module PMIRPConstDefs.
thresholdMonitorStatus	One NV pair of remaining body	М	Name of NV pair is the MONITOR_STATUS of module PMIRPNotifications::notifyThresholdMonitorObjectCreation.
			Value of NV pair is MonitorStatus of module PMIRPConstDefs.

Table A.2.3.3: Mapping for notifyThresholdMonitorObjectDeletion

IS Parameters	OMG CORBA Structured Event attribute	Qualifier	Comment
There is no corresponding IS attribute.	domain_name	M	It carries the IRP document version number string. See subclause 3.1. It indicates the syntax and semantics of the Structured Event as defined by the present document.
notificationType	type_name	M	This is constant string "notifyThresholdMonitorObjectDeletion".
There is no corresponding IS attribute.	event_name	M	It carries no information.
There is no corresponding IS attribute.	Variable Header		
objectClass, objectInstance	One NV pair of filterable_body_fields	M	NV stands for name-value pair. Order arrangement of NV pairs is not significant. The name of NV-pair is always encoded in string.  Name of this NV pair is the MANAGED_OBJECT_INSTANCE of interface AttributeNameValue of module NotificationIRPConstDefs.  Value of NV pair is a string. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
notificationId	One NV pair of remaining body	М	Name of NV pair is the NOTIFICATION_ID of interface AttributeNameValue of module NotificationIRPConstDefs.  Value of NV pair is a long. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
eventTime	One NV pair of filterable_body_fields	М	Name of NV pair is the EVENT_TIME of interface AttributeNameValue of module NotificationIRPConstDefs.  Value of NV pair is IRPTime. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
systemDN	One NV pair of filterable_body_fields	М	Name of NV pair is the SYSTEM_DN of interface AttributeNameValue of module NotificationIRPConstDefs.  Value of NV pair is a string. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
monitorId	One NV pair of filterable_body_fields	М	Name of NV pair is the MONITOR_ID of PMIRPNotifications::notifyThresholdMonitorObjectDeletion.  Value of NV pair is MonitorId of module PMIRPConstDefs.
			Talle 5. T. Pall le Memberia di Medale I Milita Collettolo.

Table A.2.3.4: Mapping for notifyThresholdMonitorStatusChanged

IS Parameters	OMG CORBA Structured Event attribute	Qualifier	Comment
There is no corresponding IS attribute.	domain_name	M	It carries the IRP document version number string. See subclause 3.1. It indicates the syntax and semantics of the Structured Event as defined by the present document.
notificationType	type_name	М	This is constant string "notifyThresholdMonitorStatusChanged".
There is no corresponding IS attribute.	event_name	M	It carries no information.
There is no corresponding IS attribute.	Variable Header		
objectClass, objectInstance	One NV pair of filterable_body_fields	M	NV stands for name-value pair. Order arrangement of NV pairs is not significant. The name of NV-pair is always encoded in string.
			Name of this NV pair is the MANAGED_OBJECT_INSTANCE of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is a string. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
notificationId	One NV pair of remaining_body	M	Name of NV pair is the NOTIFICATION_ID of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is a long. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
eventTime	One NV pair of filterable_body_fields	M	Name of NV pair is the EVENT_TIME of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is IRPTime. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
systemDN	One NV pair of filterable_body_fields	М	Name of NV pair is the SYSTEM_DN of interface AttributeNameValue of module NotificationIRPConstDefs.
			Value of NV pair is a string. See corresponding table in Notification IRP: CORBA SS (3GPP TS 32.306 [5]).
monitorId	One NV pair of filterable_body_fields	М	Name of NV pair is the MONITOR_ID of PMIRPNotifications::notifyThresholdMonitorStatusChanged
			Value of NV pair is MonitorId of module PMIRPConstDefs.
monitorStatus	One NV pair of remaining_body	М	Name of NV pair is the MONITOR _STATUS of PMIRPNotifications::notifyThresholdMonitorStatusChanged
			Value of NV pair is MonitorStatus of module PMIRPConstDefs.
reason	One NV pair of remaining_body	0	Name of NV pair is the REASON of PMIRPNotifications::notifyThresholdMonitorStatusChanged
			Value of NV pair is a string.

# A.3 PMIRPNotification Interface

OMG CORBA Notification push operation is used to realise the notification of PMIRP Notifications. All the notifications in this interface are implemented using this push\_structured\_event method.

# A.3.1 Method push (M)

- NOTE 1: The push\_structured\_events method takes an input parameter of type EventBatch as defined in the OMG CosNotification module (OMG Notification Service [9]). This data type is the same as a sequence of Structured Events. Upon invocation, this parameter will contain a sequence of Structured Events being delivered to IRPManager by IRPAgent to which it is connected.
- NOTE 2: The maximum number of events that will be transmitted within a single invocation of this operation is controlled by IRPAgent wide configuration parameter.
- NOTE 3: The amount of time the supplier (IRPAgent) of a sequence of Structured Events will accumulate individual events into the sequence before invoking this operation is controlled by IRPAgent wide configuration parameter as well.
- NOTE 4: IRPAgent may push EventBatch with only one Structured Event.

# A.4 Solution Set definitions

#### A.4.1 IDL definition structure

Clause A.4.2 defines the constants and types used by the PM IRP.

Clause A.4.3 defines the operations which are performed by the PM IRP agent.

Clause A.4.4 defines the notifications which are performed by the PM IRP agent.

# A.4.2 IDL specification "PMIRPConstDefs.idl"

```
//File: PMIRPConstDefs.idl
#ifndef _PM_IRP_CONST_DEFS_IDL_
#define _PM_IRP_CONST_DEFS_IDL_
#include <TimeBase.idl>
// This statement must appear after all include statements
#pragma prefix "3gppsa5.org"
/* ## Module: PMIRPConstDefs
This module contains commonly used definitions for PM IRP
______
module PMIRPConstDefs
{
   enum Result {OK, FAILURE};
  typedef string MOClassName;
  typedef string MOInstance;
  typedef sequence<MOInstance> MOInstanceList;
   typedef string MeasurementCategory;
   typedef sequence<MeasurementCategory> MeasurementCategoryList;
   typedef unsigned long GranularityPeriod; //The unit is minute.
   typedef unsigned long ReportingPeriod; //The unit is minute.
  typedef TimeBase::UtcT UTCTime;
  union IRPTimeOpt switch(boolean)
      case TRUE: UTCTime value;
  struct Time24
      unsigned short hour; // 0-23
      unsigned short minute; // 0-59
   struct IntervalOfDay
     Time24 interval_start_time;
     Time24 interval_stop_time;
   };
   typedef sequence<IntervalOfDay> DailyScheduling;
  const short SUNDAY = 1;
   const short MONDAY = 2;
   const short TUESDAY = 4;
   const short WEDNESDAY = 8;
  const short THURSDAY = 16;
  const short FRIDAY = 32;
  const short SATURDAY = 64;
   typedef short DaysOfWeek;
  // Bit mask of week days,
// e.g. "SUNDAY(1) and WEDNESDAY(8)" is encoded as 9.
   struct WeeklySchedulingElement
   {
      DaysOfWeek days;
     DailyScheduling intervals_of_day;
   typedef sequence<WeeklySchedulingElement> WeeklyScheduling;
   enum ScheduleType { DAILY, WEEKLY };
   union Schedule switch (ScheduleType)
      case DAILY: DailyScheduling daily_scheduling;
     case WEEKLY: WeeklyScheduling weekly_scheduling;
   };
   union ScheduleOpt switch(boolean)
   {
      case TRUE: Schedule value;
```

```
typedef unsigned long JobId;
typedef sequence<JobId> JobIdList;
struct JUnsupported
   MOInstance mo_instance;
  MeasurementCategory measurement_category;
  string reason;
};
typedef sequence<JUnsupported> JUnsupportedList;
* Defines the name of an attribute of a Managed Object
typedef string MOAttributeName;
enum JobStatus {SCHEDULED, ACTIVE, SUSPENDED, STOPPED};
enum JobPriority {LOW, MEDIUM, HIGH};
union JobPriorityOpt switch (boolean)
{
   case TRUE: JobPriority value;
};
union JobReliabilityOpt switch (boolean)
{
  case TRUE: JobReliability value;
};
typedef string JobReliability;
struct JobInfo
   JobId job_id;
  MOClassName mo_class;
  MOInstanceList mo_instance_list;
  {\tt MeasurementCategoryList\ measurement\_category\_list;}
  GranularityPeriod granularity_period;
  ReportingPeriod reporting_period;
   IRPTimeOpt start_time;
   IRPTimeOpt stop_time;
  ScheduleOpt schedule;
  JobStatus job_status;
  JobPriorityOpt job_priority;
  JobReliabilityOpt job_reliability;
};
typedef sequence<JobInfo> JobInfoList;
typedef string MeasurementTypeName;
typedef string SubCounterName;
typedef short ProbableCause; //THRESHOLD_CROSSED = 351;
typedef string SpecificProblem;
typedef any ThresholdValue;
enum Severity {WARNING, MINOR, MAJOR, CRITICAL};
union Hysteresis switch(boolean)
{
  case TRUE: long long_value;
  case FALSE: float float_value;
};
enum Direction {INCREASING, DECREASING};
struct ThresholdPackElement
{
  ThresholdValue threshold_value;
  Severity severity_;
  Hysteresis hysteresis_;
};
typedef sequence<ThresholdPackElement> ThresholdPack;
struct ThresholdInfo
{
   MeasurementTypeName measurement_type_name;
   SubCounterName sub_counter_name;
  ProbableCause probable_cause;
   SpecificProblem specific_problem;
  Direction direction_;
  ThresholdPack threshold_pack;
};
typedef sequence<ThresholdInfo> ThresholdInfoList;
typedef GranularityPeriod MonitorGranularityPeriod;// time period is based on 5 minutes.
typedef unsigned long MonitorId;
struct MUnsupported
```

```
{
     MOInstance mo_instance;
     MeasurementTypeName measurement_type_name;
     SubCounterName sub_counter_name;
     string reason;
   };
   typedef sequence<MUnsupported> MUnsupportedList;
   enum MonitorStatus {M_SUSPENDED, M_ACTIVE};
   typedef sequence<MonitorId> MonitorIdList;
   typedef string _EventType; // The value is "Quality of Service Alarm"
   struct MonitorInfo
     MonitorId monitor_id;
     MOClassName mo_class;
     MOInstanceList mo_instance_list;
     MonitorGranularityPeriod monitor_granularity_period;
     ThresholdInfoList threshold_info_list;
     MonitorStatus threshold_monitor_status;
     _EventType event_type;
   };
   typedef sequence<MonitorInfo> MonitorInfoList;
   * This block identifies attributes which are included as part of the
   * PMIRP. These attribute values should not
   * clash with those defined for the attributes of notification
   * header (see IDL of Notification IRP).
   interface AttributeNameValue
      const string JOB_ID = "JOB_ID";
     const string JOB_STATUS = "JOB_STATUS";
     const string REASON = "REASON";
     const string MONITOR_ID = "MONITOR_ID";
      const string MONITOR_STATUS = "MONITOR_STATUS";
      const string MONITOR_GRANULARITY_PERIOD = "MONITOR_GRANULARITY_PERIOD";
     const string MONITOR_EVENT_TYPE = "MONITOR_EVENT_TYPE";
     const string PROBABLE_CAUSE = "PROBABLE_CAUSE";
     const string SPECIFIC_PROBLEM = "SPECIFIC_PROBLEM";
     const string DIRECTION = "DIRECTION";
#endif // _PM_IRP_CONST_DEFS_IDL_
```

### A.4.3 IDL specification "PMIRPSystem.idl"

```
//File: PMIRPSystem.idl
#ifndef _PM_IRP_SYSTEM_IDL_
#define _PM_IRP_SYSTEM_IDL_
#include <ManagedGenericIRPSystem.idl>
#include <ManagedGenericIRPConstDefs.idl>
#include <PMIRPConstDefs.idl>
// This statement must appear after all include statements
#pragma prefix "3gppsa5.org"
/* ## Module: PMIRPSystem
This module contains the specification of all operations of PM IRP Agent.
______
module PMIRPSystem
{
   ^{\star} The reason specifies whether EM or NE has high workload. The value shall be one
   * of following: emCpuBusy; emHDShortage, emLowMemory, {neCpuBusy, neObjectInstList},
   * {neHDShortage neObjectInstList}, {neLowMemory, neObjectInstList}, maxJobReached,
   * otherReason.
   ^{\star} In the case the reason is a tuple, the first element is the string such as
   \mbox{\tt *"NE\_CPU\_BUSY"} followed by a comma, then followed by a sequence of DN where
   * each DN is separated by its adjacent DN, if any, by a colon. The DN is formatted
   * as described in 32.300.
   exception HighWorkLoad { string reason; };
   interface HighWorkLoadExceptionReason
      const string EM_CPU_BUSY = "EM_CPU_BUSY";
      const string EM_HD_SHORTAGE = "EM_HD_SHORTAGE";
      const string EM_LOW_MEMORY = "EM_LOW_MEMORY";
      const string NE_CPU_BUSY = "NE_CPU_BUSY";
      const string NE_HD_SHORTAGE = "NE_HD_SHORTAGE";
      const string NE_LOW_MEMORY = "NE_LOW_MEMORY";
      const string MAX_JOB_REACHED = "MAX_JOB_REACHED";
      const string OTHER_REASON = "OTHER_REASON";
   exception UnknownJob { string reason; };
   exception JobCannotBeStopped { string reason; };
   exception JobAlreadySuspended { string reason; };
exception JobIsNotSuspended { string reason; };
   exception UnknownThresholdMonitor { string reason; };
   exception ThresholdMonitorAlreadySuspended { string reason; };
   exception ThresholdMonitorIsNotSuspended { string reason; };
   * System fails to complete the operation. System can provide reason
   * to qualify the exception. The semantics carried in reason
   * is outside the scope of this IRP.
   exception GetPMIRPVersions { string reason; };
   exception GetPMIRPOperationsProfile { string reason; };
   exception GetPMIRPNotificationProfile { string reason; };
   exception CreateMeasurementJob { string reason; };
   exception StopMeasurementJob { string reason; };
   exception SuspendMeasurementJob { string reason; };
   exception ResumeMeasurementJob { string reason; };
   exception ListMeasurementJobs { string reason; };
   exception CreateThresholdMonitor { string reason; };
   exception DeleteThresholdMonitor { string reason; };
   exception ListThresholdMonitors { string reason; };
   exception SuspendThresholdMonitor { string reason; };
   exception ResumeThresholdMonitor { string reason; };
   interface PMIRP
   {
      * Return the list of all supported PM IRP versions.
      ManagedGenericIRPConstDefs::VersionNumberSet get_pm_irp_versions (
      raises (GetPMIRPVersions);
```

```
* Return the list of all supported operations and their supported
\mbox{\scriptsize *} parameters for a specific PM IRP version.
ManagedGenericIRPConstDefs::MethodList get_pm_irp_operations_profile (
   in ManagedGenericIRPConstDefs::VersionNumber pm_irp_version
raises (GetPMIRPOperationsProfile,
        ManagedGenericIRPSystem::OperationNotSupported,
        ManagedGenericIRPSystem::InvalidParameter);
/**
* Return the list of all supported notifications and their supported
* parameters for a specific PM IRP version.
{\tt ManagedGenericIRPConstDefs::MethodList\ get\_pm\_irp\_notification\_profile}
   in ManagedGenericIRPConstDefs::VersionNumber pm_irp_version
raises (GetPMIRPNotificationProfile,
        ManagedGenericIRPSystem::OperationNotSupported,
        ManagedGenericIRPSystem::InvalidParameter);
* Request to create a MeasurementJob through Itf-N.
ManagedGenericIRPConstDefs::Signal create_measurement_job (
   in PMIRPConstDefs::MOClassName mo_class,
   \hbox{in $PMIRPConstDefs::} \verb|MOInstanceList| mo_instance_list|,\\
   in PMIRPConstDefs::MeasurementCategoryList measurement_category_list,
   in PMIRPConstDefs::GranularityPeriod granularity_period,
   in PMIRPConstDefs::ReportingPeriod reporting_period,
   in PMIRPConstDefs::IRPTimeOpt start_time,
   in PMIRPConstDefs::IRPTimeOpt stop_time,
   in PMIRPConstDefs::ScheduleOpt schedule,
   in PMIRPConstDefs::JobPriorityOpt priority,
   in PMIRPConstDefs::JobReliabilityOpt reliability,
   out PMIRPConstDefs::JobId job_id,
   out PMIRPConstDefs::JUnsupportedList unsupported_list
raises (CreateMeasurementJob,
        ManagedGenericIRPSystem::InvalidParameter,
        ManagedGenericIRPSystem::ParameterNotSupported,
        HighWorkLoad);
* Request to stop a MeasurementJob through Itf-N, after which,
* the MeasurementJob will still be visible via Itf-N. Whether
* the MeasurementJob is thoroughly removed immediately from
* the managed system is vendor specific.
PMIRPConstDefs::Result stop_measurement_job (
   in PMIRPConstDefs::JobId job_id)
raises (StopMeasurementJob,
       UnknownJob,
        JobCannotBeStopped);
* Request to suspend a MeasurementJob
PMIRPConstDefs::Result suspend_measurement_job (
   in PMIRPConstDefs::JobId job_id)
raises (SuspendMeasurementJob,
        UnknownJob,
        JobAlreadySuspended,
        ManagedGenericIRPSystem::OperationNotSupported);
* Request to resume a MeasurementJob
PMIRPConstDefs::Result resume_measurement_job (
  in PMIRPConstDefs::JobId job_id)
raises (ResumeMeasurementJob,
        UnknownJob,
        JobIsNotSuspended,
        HighWorkLoad,
        ManagedGenericIRPSystem::OperationNotSupported);
```

```
* Request to list the information of all or of specified
      * MeasurementJobs
      PMIRPConstDefs::Result list_measurement_jobs (
         in PMIRPConstDefs::JobIdList job_list_id,
         out PMIRPConstDefs::JobInfoList job_info_list)
      raises (ListMeasurementJobs,
             ManagedGenericIRPSystem::InvalidParameter);
      * Request to create a ThresholdMonitor to define the threshold
      * for some specific measurementTypes or subCounters
      ManagedGenericIRPConstDefs::Signal create_threshold_monitor (
         in PMIRPConstDefs::MOClassName mo_class,
         in PMIRPConstDefs::MOInstanceList mo_instance_list,
         in PMIRPConstDefs::ThresholdInfoList threshold_info_list,
         in PMIRPConstDefs::MonitorGranularityPeriod monitor_granularity_period,
         out PMIRPConstDefs::MonitorId monitor_id,
         out PMIRPConstDefs::MUnsupportedList unsupported_list)
      raises (CreateThresholdMonitor,
              ManagedGenericIRPSystem::InvalidParameter,
              ManagedGenericIRPSystem::OperationNotSupported);
      /**
      * Request to delete a specified ThresholdMonitor
      PMIRPConstDefs::Result delete_threshold_monitor (
         in PMIRPConstDefs::MonitorId monitor_id)
      raises (DeleteThresholdMonitor,
              UnknownThresholdMonitor,
              ManagedGenericIRPSystem::OperationNotSupported);
      /**
      * Request to list detailed information about all or
      * specified ThresholdMonitors
      PMIRPConstDefs::Result list_threshold_monitors (
         in PMIRPConstDefs::MonitorIdList monitor_id_list,
         out PMIRPConstDefs::MonitorInfoList monitor_info_list)
      raises (ListThresholdMonitors,
              ManagedGenericIRPSystem::InvalidParameter,
              ManagedGenericIRPSystem::OperationNotSupported);
      /**
      * Request to suspend a ThresholdMonitor
      PMIRPConstDefs::Result suspend_threshold_monitor (
         in PMIRPConstDefs::MonitorId monitor_id)
      raises (SuspendThresholdMonitor,
              UnknownThresholdMonitor,
              ThresholdMonitorAlreadySuspended,
              ManagedGenericIRPSystem::OperationNotSupported);
      * Request to resume a ThresholdMonitor
      PMIRPConstDefs::Result resume threshold monitor (
         in PMIRPConstDefs::MonitorId monitor_id)
      raises (ResumeThresholdMonitor,
              UnknownThresholdMonitor,
              ThresholdMonitorIsNotSuspended,
              ManagedGenericIRPSystem::OperationNotSupported);
   };
};
#endif // _PM_IRP_SYSTEM_IDL_
```

# A.4.4 IDL specification "PMIRPNotifications.idl"

```
// File: PMIRPNotifications.idl
#ifndef _PM_IRP_NOTIFICATIONS_IDL_
#define _PM_IRP_NOTIFICATIONS_IDL_
#include <PMIRPConstDefs.idl>
#include <NotificationIRPNotifications.idl>
// This statement must appear after all include statements
#pragma prefix "3gppsa5.org"
/* ## Module: PMIRPNotifications
This module contains the specification of all notifications of PM IRP Agent.
______
* /
module PMIRPNotifications
{
   * Constant definitions for the notifyMeasurementJobStatusChanged notification
   interface NotifyMeasurementJobStatusChanged: NotificationIRPNotifications::Notify
      const string EVENT_TYPE = "notifyMeasurementJobStatusChanged";
      \mbox{\scriptsize \star} This constant defines the name of the jobId property.
      \mbox{\scriptsize \star} The data type for the value of this property
      * is PMIRPConstDefs::JobId.
      const string JOB_ID = PMIRPConstDefs::AttributeNameValue::JOB_ID;
      * This constant defines the name of the jobStatus property.
      * The data type for the value of this property
      * is PMIRPConstDefs::JobStatus.
      const string JOB_STATUS = PMIRPConstDefs::AttributeNameValue::JOB_STATUS;
      * This constant defines the name of the reason property.
      ^{\star} The data type for the value of this property is string.
      const string REASON = PMIRPConstDefs::AttributeNameValue::REASON;
   };
   * Constant definitions for the notifyThresholdMonitorObjectCreation notification
   interface \ {\tt NotifyThresholdMonitorObjectCreation:}
     NotificationIRPNotifications::Notify
      const string EVENT_TYPE = "notifyThresholdMonitorObjectCreation";
      * This constant defines the name of the monitorId property,
      * which is transported in the filterable_body fields.
      * The data type for the value of this property
      * is PMIRPConstDefs::MonitorId.
      const string MONITOR_ID = PMIRPConstDefs::AttributeNameValue::MONITOR_ID;
      ^{\star} This constant defines the name of the monitorGranularityPeriod property,
      ^{\star} which is transported in the filterable_body fields.
      * The data type for the value of this property
      * is PMIRPConstDefs::MonitorGranularityPeriod.
      const string MONITOR_GRANULARITY_PERIOD =
        PMIRPConstDefs::AttributeNameValue::MONITOR_GRANULARITY_PERIOD;
      * This constant defines the name of the thresholdMonitorStatus property,
      * which is transported in the filterable_body fields.
      * The data type for the value of this property
      * is PMIRPConstDefs::MonitorStatus.
      const string MONITOR STATUS =
         PMIRPConstDefs::AttributeNameValue::MONITOR STATUS;
```

```
};
   * Constant definitions for the notifyThresholdMonitorObjectDeletion notification
   interface NotifyThresholdMonitorObjectDeletion:
      NotificationIRPNotifications::Notify
      const string EVENT_TYPE = "notifyThresholdMonitorObjectDeletion";
      * This constant defines the name of the monitorId property,
      \mbox{\ensuremath{^{\star}}} which is transported in the filterable_body fields.
      * The data type for the value of this property
      * is PMIRPConstDefs::MonitorId.
      const string MONITOR_ID = PMIRPConstDefs::AttributeNameValue::MONITOR_ID;
   };
   * Constant definitions for the notifyThresholdMonitorStatusChanged notification
   interface NotifyThresholdMonitorStatusChanged: NotificationIRPNotifications::Notify
      const string EVENT_TYPE = "notifyThresholdMonitorStatusChanged";
      * This constant defines the name of the monitorId property.
      * The data type for the value of this property
      * is PMIRPConstDefs::MonitorId.
      const string MONITOR_ID = PMIRPConstDefs::AttributeNameValue::MONITOR_ID;
      \mbox{\scriptsize \star} This constant defines the name of the monitor
Status property.
      * The data type for the value of this property
      * is PMIRPConstDefs::MonitorStatus.
      const string MONITOR_STATUS = PMIRPConstDefs::AttributeNameValue::MONITOR_STATUS;
      * This constant defines the name of the reason property.
      ^{\star} The data type for the value of this property is string.
      const string REASON = PMIRPConstDefs::AttributeNameValue::REASON;
   };
};
#endif // _PM_IRP_NOTIFICATIONS_IDL_
```

# Annex B (normative): XML definitions

This annex specifies the XML definitions for the Performance Management (PM) Integration Reference Point (IRP) as it applies to Itf-N, in accordance with PM IRP IS definitions in 3GPP TS 32.412 [7], for usage with the SOAP Solution Set in Annex C as well as Notification Log IRP XML definitions in 3GPP TS 32.336 [11].

# B.1 Architectural features

The overall architectural feature of PM IRP is specified in 3GPP TS 32.412 [7].

This clause specifies features that are specific to the XML Schema definitions.

# B.1.1 Syntax for Distinguished Names

The syntax of a Distinguished Name is defined in 3GPP TS 32.300 [6].

# B.2 Mapping

Not present in the current version of this specification.

# B.3 Solution Set definitions


#### B.3.1 XML definition structure


Clause B.3.2 provides a graphical representation of the XML elements.


Clause B.3.3 provides XML definitions of PM IRP notifications as defined in 3GPP TS 32.412 [7].


Clause B.3.4 provides XML definitions of PM IOC as defined in 3GPP TS 32.412 [7].

# B.3.2 Graphical Representation









# B.3.3 XML Schema "pMIRPNotif.xsd"

```
<?xml version="1.0" encoding="UTF-8"?>
    3GPP TS 32.416 PMIRP Notification XML Schema
   pMIRPNotif.xsd
<schema xmlns:xp="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#pMIRPNotif"</pre>
xmlns:xe="http://www.3gpp.org/ftp/specs/archive/32_series/32.306#notification"
xmlns:xai="http://www.3gpp.org/ftp/specs/archive/32_series/32.111-6#alarmIRPIOCs"
xmlns:xpi="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#pMIRPIOCs"
xmlns="http://www.w3.org/2001/XMLSchema"
targetNamespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#pMIRPNotif"
elementFormDefault="qualified" attributeFormDefault="unqualified">
    <import namespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.306#notification"/>
    <import namespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#pMIRPIOCs"/>
    <import namespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.111-6#alarmIRPIOCs"/>
    <simpleType name="QoSEventType">
        <restriction base="xai:EventType">
            <enumeration value="Quality Of Service Alarm"/>
        </restriction>
    </simpleType>
    <complexType name="NotifyMeasurementJobStatusChanged">
        <complexContent>
            <extension base="xe:Notification">
                <sequence>
                    <element name="body">
                        <complexType>
                             <sequence>
                                 <element name="JobId" type="xpi:JobId"/>
                                 <element name="JobStatus" type="xpi:JobStatus"/>
                                 <element name="Reason" type="xpi:JobStatusChangedReasons"</pre>
minOccurs="0"/>
                             </sequence>
                        </complexType>
                    </element>
                </sequence>
            </extension>
        </complexContent>
    </complexType>
    <complexType name="NotifyThresholdMonitorObjectCreation">
        <complexContent>
            <extension base="xe:Notification">
                <sequence>
                    <element name="body">
                        <complexType>
                             <sequence>
                                 <element name="MonitorId" type="xpi:MonitorId"/>
                                 <element name="MonitorGranularityPeriod"</pre>
type="xpi:MonitorGranularityPeriod"/>
                                 <element name="EventType" type="xp:QoSEventType"/>
                                 <element name="ProbableCause" type="xpi:TcProbableCause"/>
                                 <element name="SpecificProblem" type="xpi:SpecificProblem"/>
                                 <element name="Direction" type="xpi:Direction"/>
                                 <element name="ThresholdMonitorStatus"</pre>
type="xpi:ThresholdMonitorStatus"/>
                             </sequence>
                         </complexType>
                    </element>
                </sequence>
            </extension>
        </complexContent>
    </complexType>
    <complexType name="NotifyThresholdMonitorObjectDeletion">
        <complexContent>
            <extension base="xe:Notification">
                <sequence>
                    <element name="body">
                         <complexType>
                             <sequence>
                                <element name="MonitorId" type="xpi:MonitorId"/>
                            </sequence>
                         </complexType>
                    </element>
                </sequence>
            </extension>
```

```
</complexContent>
    </complexType>
    <complexType name="NotifyThresholdMonitorStatusChanged">
        <complexContent>
            <extension base="xe:Notification">
                <sequence>
                     <element name="body">
                         <complexType>
                             <sequence>
                                 <element name="MonitorId" type="xpi:MonitorId"/>
                                 <element name="MonitorStatus" type="xpi:ThresholdMonitorStatus"/>
                                 <element name="Reason" type="xpi:MonitorStatusChangedReasons"</pre>
minOccurs="0"/>
                             </sequence>
                         </complexType>
                    </element>
                </sequence>
            </extension>
        </complexContent>
    </complexType>
    <element name="NotifyMeasurementJobStatusChanged" type="xp:NotifyMeasurementJobStatusChanged"/>
    <element name="NotifyThresholdMonitorObjectCreation"</pre>
type="xp:NotifyThresholdMonitorObjectCreation"/>
   <element name="NotifyThresholdMonitorObjectDeletion"</pre>
type="xp:NotifyThresholdMonitorObjectDeletion"/>
    <element name="NotifyThresholdMonitorStatusChanged"</pre>
type="xp:NotifyThresholdMonitorStatusChanged"/>
</schema>
```

# B.3.4 XML Schema "pMIRPIOCs.xsd"

```
<?xml version="1.0" encoding="UTF-8"?>
    3GPP TS 32.416 Performance Management IRP IOC XML Schema
   pMIRPIOCs.xsd
<schema xmlns:xpi="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#pMIRPIOCs"</pre>
xmlns:xe="http://www.3gpp.org/ftp/specs/archive/32_series/32.306#notification"
xmlns:xai="http://www.3gpp.org/ftp/specs/archive/32_series/32.111-6#alarmIRPIOCs"
xmlns="http://www.w3.org/2001/XMLSchema"
targetNamespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#pMIRPIOCs"
elementFormDefault="qualified" attributeFormDefault="unqualified">
    <import namespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.306#notification"/>
    <import namespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.111-6#alarmIRPIOCs"/>
    <!-- Type definitions -->
    <simpleType name="JobId">
        <restriction base="string">
            <minLength value="1"/>
        </restriction>
    </simpleType>
    <simpleType name="JobStatus">
        <restriction base="string">
            <enumeration value="Scheduled"/>
            <enumeration value="Active"/>
            <enumeration value="Suspended"/>
            <enumeration value="Stopped"/>
        </restriction>
    </simpleType>
    <simpleType name="JobStatusChangedReason">
        <restriction base="string">
            <enumeration value="failToReadMeasurementTypesForExtendedProlongPeriod"/>
            <enumeration value="internalProblem"/>
            <enumeration value="stopMeasurementJob"/>
            <enumeration value="stopTimeReached"/>
            <enumeration value="resumeMeasurementJob"/>
            <enumeration value="suspendMeasurementJob"/>
            <enumeration value="startTimeReached"/>
            <enumeration value="suspendMeasurementJobBySystem"/>
        </restriction>
    </simpleType>
    <complexType name="JobStatusChangedReasons">
            <element name="Reason" type="xpi:JobStatusChangedReason" maxOccurs="unbounded"/>
        </sequence>
    </complexType>
    <simpleType name="MonitorStatusChangedReason">
        <restriction base="string">
            <enumeration value="ResumeThresholdMonitor"/>
            <enumeration value="SuspendThresholdMonitor"/>
        </restriction>
    </simpleType>
    <complexType name="MonitorStatusChangedReasons">
        <sequence>
            <element name="Reason" type="xpi:MonitorStatusChangedReason" maxOccurs="unbounded"/>
    </complexType>
    <simpleType name="MonitorId">
        <restriction base="string">
            <minLength value="1"/>
        </restriction>
    </simpleType>
    <complexType name="DailyScheduling">
        <sequence minOccurs="0">
            <element name="intervalStart" type="time"/>
            <element name="intervalEnd" type="time"/>
        </sequence>
        <!-- This element type is allowed to be empty -->
    </complexType>
    <simpleType name="WeekDay">
        <restriction base="string">
            <enumeration value="Monday"/>
            <enumeration value="Tuesday"/>
            <enumeration value="Wednesday"/>
            <enumeration value="Thursday"/>
            <enumeration value="Friday"/>
```

```
<enumeration value="Saturday"/>
            <enumeration value="Sunday"/>
        </restriction>
   </simpleType>
    <complexType name="WeekDays">
            <element name="day" type="xpi:WeekDay" maxOccurs="7"/>
        </sequence>
   </complexType>
    <complexType name="WeeklyScheduling">
        <sequence>
            <element name="days" type="xpi:WeekDays" minOccurs="0"/>
            <element name="dailyScheduling" type="xpi:DailyScheduling" minOccurs="0"/>
    </complexType>
   <simpleType name="GranularityPeriod">
        <restriction base="string">
            <enumeration value="5 Minutes"/>
            <enumeration value="15 Minutes"/>
            <enumeration value="30 Minutes"/>
            <enumeration value="1 Hour"/>
            <enumeration value="12 Hours"/>
            <enumeration value="24 Hours"/>
        </restriction>
   </simpleType>
   <simpleType name="MonitorGranularityPeriod">
        <restriction base="xpi:GranularityPeriod"/>
    </simpleType>
   <simpleType name="JobGranularityPeriod">
        <restriction base="xpi:GranularityPeriod"/>
    </simpleType>
    <simpleType name="JobReportingPeriod">
        <restriction base="positiveInteger"/>
        <!-- The legal value is in number of minutes and otherwise according to jobReportingPeriod
of 3GPP TS 32.412 -->
    </simpleType>
   <simpleType name="JobStartTime">
        <restriction base="dateTime"/>
   </simpleType>
   <simpleType name="JobStopTime">
        <restriction base="dateTime"/>
    </simpleType>
   <complexType name="JobSchedule">
        <choice>
            <element name="dailyScheduling" type="xpi:DailyScheduling"/>
            <element name="weeklyScheduling" type="xpi:WeeklyScheduling"/>
        </choice>
   </complexType>
    <simpleType name="JobPriority">
        <restriction base="string">
            <enumeration value="Low"/>
            <enumeration value="Medium"/>
            <enumeration value="High"/>
        </restriction>
   </simpleType>
   <simpleType name="PrabableCausePM">
        <restriction base="string">
            <enumeration value="Threshold Crossed"/>
        </restriction>
   </simpleType>
   <simpleType name="Direction">
        <restriction base="string">
           <enumeration value="Increasing"/>
            <enumeration value="Decreasing"/>
        </restriction>
   </simpleType>
    <simpleType name="QoSEventType">
        <restriction base="xai:EventType">
            <enumeration value="Quality Of Service Alarm"/>
        </restriction>
    </simpleType>
    <simpleType name="TcProbableCause">
        <restriction base="xai:ProbableCause">
            <enumeration value="Threshold Crossed"/>
        </restriction>
   <simpleType name="SpecificProblem">
        <restriction base="string"/>
```

```
</simpleType>
   <simpleType name="ThresholdMonitorStatus">
        <restriction base="string">
            <enumeration value="Active"/>
            <enumeration value="Suspended"/>
        </restriction>
   </simpleType>
   <simpleType name="ThresholdSeverity">
        <restriction base="string">
            <enumeration value="Warning"/>
            <enumeration value="Minor"/>
            <enumeration value="Major"/>
            <enumeration value="Critical"/>
        </restriction>
    </simpleType>
   <simpleType name="JobReliability">
        <restriction base="string"/>
            <enumeration value="True"/>
            <enumeration value="False"/>
        </restriction>
   </simpleType>
   <!-- Attributes of the MeasurementJob IOC -->
   <element name="jobId" type="xpi:JobId"/>
   <element name="jobGranularityPeriod" type="xpi:JobGranularityPeriod"/>
   <element name="jobReportingPeriod" type="xpi:JobReportingPeriod"/>
   <element name="jobStatus" type="xpi:JobStatus"/>
   <element name="jobPriority" type="xpi:JobPriority"/>
   <element name="jobReliability" type="xpi:JobReliability"/>
   <!-- Attributes of the JobMeasurementSchedule IOC -->
   <element name="jobStartTime" type="xpi:JobStartTime"/>
   <element name="jobStopTime" type="xpi:JobStopTime"/>
    <element name="jobSchedule" type="xpi:JobSchedule"/>
   <!-- Attributes of the MeasuredAttribute IOC -->
   <element name="measurementTypeName" type="string"/>
   <!-- Attributes of the MeasurementReader IOC -->
    <element name="measurementResultValue" type="anyType"/>
   <element name="probableCause" type="xpi:TcProbableCause"/>
   <element name="specificProblem" type="xpi:SpecificProblem"/>
<element name="direction" type="xpi:Direction"/>
   <!-- Attributes of the Monitor IOC -->
    <element name="monitorId" type="string"/>
   <element name="monitorGranularityPeriod" type="xpi:GranularityPeriod"/>
   <!-- Attributes of the ThresholdMonitor IOC -->
   <element name="thresholdMonitorStatus" type="xpi:ThresholdMonitorStatus"/>
   <!-- Attributes of the ThresholdLevel IOC -->
   <element name="thresholdValue" type="string"/>
<element name="thresholdSeverity" type="xpi:ThresholdSeverity"/>
    <element name="hysteresis" type="string"/>
</schema>
```

# Annex C (normative): SOAP Solution Set

This annex specifies the SOAP Solution Set for the IRP whose semantics are specified in PM IRP: Information Service (3GPP TS 32.412[7]).

# C.1 Architectural Features

The overall architectural feature of the Performance Management (PM) IRP is specified in 3GPP TS 32.412 [7]. This clause specifies features that are specific to the SOAP Solution Set.

The SOAP 1.1 specification [15] and WSDL 1.1 specification [17] are supported.

The SOAP 1.2 specification [18] is supported optionally.

This specification uses "document" style in WSDL file.

This specification uses "literal" encoding style in WSDL file.

The filter language used in the SS is the XPath Language (see W3C XPath 1.0 specification [16]). IRPAgents may throw a FilterComplexityLimit fault when a given filter is too complex.

The PM IRP SOAP SS uses the Notification IRP SOAP SS of 3GPP TS 32.306 [5]. The IRPAgent shall support the push interface model, which means that the IRPAgent sends PM notifications to the IRPManager as soon as new events occur. The IRPManager does not need to check ("pull") for events.

Relevant definitions are imported from the PM IRP XML definitions of Annex B.

This specification uses a number of namespace prefixes throughout that are listed in Table C.1.1.

 PREFIX
 NAMESPACE

 (no prefix)
 http://schemas.xmlsoap.org/wsdl/

 soap
 http://schemas.xmlsoap.org/wsdl/soap/

 pMIRPSystem
 http://specs/archive/32\_series/32.416#PMIRPSystem

 pMIRPData
 http://www.3gpp.org/ftp/specs/archive/32\_series/32.416#PMIRPData

 xpi
 http://www.3gpp.org/ftp/specs/archive/32\_series/32.416#pMIRPIOCs

 xn
 http://www.3gpp.org/ftp/specs/archive/32\_series/32.626#genericNrm

 genericIRPSystem
 http://www.3gpp.org/ftp/specs/archive/32\_series/32.316#GenericIRPSystem

Table C.1.1: Prefixes and Namespaces used in this specification

# C.1.1 Syntax for Distinguished Names

The syntax of a Distinguished Name is defined in 3GPP TS 32.300 [6].

# C.2 Mapping

# C.2.1 Operation and notification mapping

The PM IRP IS (3GPP TS 32.412 [7]) defines the operations and their semantics.

Table C.2.1 maps the operations defined in the PM IRP IS to their equivalent port type and binding operations in this Solution Set (SS).

Table C.2.1 also maps the notifications of the PM IRP IS, as well as inherited operations.

Table C.2.1 also qualifies if an operation is Mandatory (M) or Optional (O).

Table C.2.1: Mapping from IS Operation to SS Equivalents

IS Operation in 3GPP TS 32.412 [7]	SS: Operation for WSDL port type and WSDL binding	SS: Port of PMIRPService	Qualifier
createMeasurementJob	createMeasurementJob (note 1)	PMIRPPort	М
stopMeasurementJob	stopMeasurementJob (note 1)	PMIRPPort	М
suspendMeasurementJob	suspendMeasurementJob (note 1)	PMIRPPort	0
resumeMeasurementJob	resumeMeasurementJob (note 1)	PMIRPPort	0
listMeasurementJobs	listMeasurementJobs (note 1)	PMIRPPort	М
createThresholdMonitor	createThresholdMonitor (note 1)	PMIRPPort	M (note 4 a)
deleteThresholdMonitor	deleteThresholdMonitor (note 1)	PMIRPPort	M (note 4 a)
listThresholdMonitors	listThresholdMonitors (note 1)	PMIRPPort	M (note 4 a)
suspendThresholdMonitor	suspendThresholdMonitor (note 1)	PMIRPPort	M (note 4 b)
resumeThresholdMonitor	resumeThresholdMonitor (note 1)	PMIRPPort	M (note 4 b)
notifyMeasurementJobStatusChanged	notify (note 2)	NotificationIRPNtfPort	М
notifyThresholdMonitorObjectCreation	notify (note 2)	NotificationIRPNtfPort	M (note 4 c)
notifyThresholdMonitorObjectDeletion	notify (note 2)	NotificationIRPNtfPort	M (note 4 c)
notifyThresholdMonitorStatusChanged	notify (note 2)	NotificationIRPNtfPort	0
getIRPVersion (note 3)	See TS 32.316 [13]	GenericIRPPort	M
getOperationProfile (note 3)	See TS 32.316 [13]	GenericIRPPort	0
getNotificationProfile (note 3)	See TS 32.316 [13]	GenericIRPPort	0
NOTE 1: The operation is under the port type pMIRPSystem:PMIRPPortType and under the binding pMIRPSystem:PMIRPBinding.			
NOTE 2: The IS equivalent maps to a	NOTE 2: The IS equivalent maps to an XML definition specified in Annex B, and this being an input parameter to the		
operation notify under the port type ntfIRPNtfSystem:NotificationIRPNtf and under the binding			
ntfIRPNtfSystem:NotificationIRPNtf of 3GPP TS 32.306 [5]. This binding is linked to a port of the			of the
PMIRPService as indicated i	PMIRPService as indicated in the table above.		
NOTE 3: The IS operation is inherited	NOTE 3: The IS operation is inherited from the ManagedGenericIRP IOC specified in 3GPP TS 32.312 [8].		

- NOTE 3: The IS operation is inherited from the ManagedGenericIRP IOC specified in 3GPP TS 32.312 [8].

  This inheritance is by the PMIRP IOC of 3GPP TS 32.412 [7] inheriting from the ManagedGenericIRP IOC.

  The corresponding binding is linked to a port of the PMIRPService as indicated in the table above.
- NOTE 4: a) Mandatory if the optional PMIRPOperations\_2 interface (see the PM IRP IS clause 7.4) is supported. b) Mandatory if the optional PMIRPOperations\_3 interface (see the PM IRP IS clause 7.5) is supported. c) Mandatory if the optional PMIRPNotification\_2 interface (see the PM IRP IS clause 7.7) is supported.

# C.2.2 Operation parameter mapping

The PM IRP IS (3GPP TS 32.412 [7]) defines semantics of parameters carried in the operations. The tables below show the mapping of these parameters, as per operation, to their equivalents defined in this SS.

# C.2.2.1 Operation createMeasurementJob

#### C.2.2.1.1 Input parameters

Table C.2.2.1.1: Mapping from IS createMeasurementJob input parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
iOCName	iOCName	М
iOCInstanceList	iOCInstanceList	М
measurementCategoryList	measurementCategoryList	М
granularityPeriod	granularityPeriod	М
reportingPeriod	reportingPeriod	М
startTime	startTime	0
stopTime	stopTime	0
schedule	schedule	0
priority	priority	0
reliability	reliability	0

#### C.2.2.1.2 Output parameters

Table C.2.2.1.2: Mapping from IS createMeasurementJob output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
jobId	jobId	М
unsupportedList	unsupportedList	М
status	status	M

#### C.2.2.1.3 Fault definition

Table C.2.2.1.3: Mapping from IS createMeasurementJob exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
invalidStartTime	InvalidStartTime	М
invalidStopTime	InvalidStopTime	M
invalidSchedule	InvalidSchedule	M
invalidGranularityPeriod	InvalidGranularityPeriod	М
invalidReportingPeriod	InvalidReportingPeriod	M
highWorkLoad	HighWorkLoad	М
invalidPriority	InvalidPriority	M
noValidMeasurementType	NoValidMeasurementType	М
invalidReliability	InvalidReliability	М

#### C.2.2.2 Operation stopMeasurementJob

#### C.2.2.2.1 Input parameters

Table C.2.2.2.1: Mapping from IS stopMeasurementJob input parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
JobId	jobId	M

#### C.2.2.2.2 Output parameters

Table C.2.2.2.2: Mapping from IS stopMeasurementJob output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
Status	status	М

#### C.2.2.2.3 Fault definition

Table C.2.2.2.3: Mapping from IS stopMeasurementJob exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
unknownJob	UnknownJob	M
jobCannotBeStopped	JobCannotBeStopped	М

# C.2.2.3 Operation suspendMeasurementJob

#### C.2.2.3.1 Input parameters

Table C.2.2.3.1: Mapping from IS suspendMeasurementJob input parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
jobId	jobId	M

#### C.2.2.3.2 Output parameters

Table C.2.2.3.2: Mapping from IS suspendMeasurementJob output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
status	status	М

#### C.2.2.3.3 Fault definition

Table C.2.2.3.3: Mapping from IS suspendMeasurementJob exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
unknownJob	UnknownJob	M
jobAlreadySuspended	JobAlreadySuspended	М

## C.2.2.4 Operation resumeMeasurementJob

#### C.2.2.4.1 Input parameters

Table C.2.2.4.1: Mapping from IS resumeMeasurementJob input parameters to SS equivalents

	IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
ĺ	jobId	jobId	M

#### C.2.2.4.2 Output parameters

Table C.2.2.4.2: Mapping from IS resumeMeasurementJob output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
status	status	M

#### C.2.2.4.3 Fault definition

Table C.2.2.4.3: Mapping from IS resumeMeasurementJob exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
unknownJob	UnknownJob	M
jobIsNotSuspended	JobIsNotSuspended	M
highWorkLoad	HighWorkLoad	M

### C.2.2.5 Operation listMeasurementJobs

#### C.2.2.5.1 Input parameters

Table C.2.2.5.1: Mapping from IS listMeasurementJobs input parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
jobIdList	jobIdList	M

#### C.2.2.5.2 Output parameters

Table C.2.2.5.2: Mapping from IS listMeasurementJobs output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
jobInfoList	jobInfoList	M
status	status	М

#### C.2.2.5.3 Fault definition

Table C.2.2.5.3: Mapping from IS listMeasurementJobs exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
invalidJobIdList	InvalidJobIdList	M

## C.2.2.6 Operation createThresholdMonitor

#### C.2.2.6.1 Input parameters

Table C.2.2.6.1: Mapping from IS createThresholdMonitor input parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
iOCName	iOCName	M
iOCInstanceList	iOCInstanceList	M
thresholdInfoList	thresholdInfoList	М
monitorGranularityPeriod	monitorGranularityPeriod	M

#### C.2.2.6.2 Output parameters

Table C.2.2.6.2: Mapping from IS createThresholdMonitor output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
monitorId	monitorId	M
unsupportedList	unsupportedList	М
status	status	M

#### C.2.2.6.3 Fault definition

Table C.2.2.6.3: Mapping from IS createThresholdMonitor exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
invalidClassOrInstances	InvalidClassOrInstances	М
invalidGranularityPeriod	InvalidGranularityPeriod	М
noValidMeasurementType	NoValidMeasurementType	М
invalidNumberOfThresholdPackElements	InvalidNumberOfThresholdPackElements	М
invalidOrderOfThresholdPackElements	InvalidOrderOfThresholdPackElements	М
invalidDirection	InvalidDirection	М

## C.2.2.7 Operation deleteThresholdMonitor

#### C.2.2.7.1 Input parameters

Table C.2.2.7.1: Mapping from IS deleteThresholdMonitor input parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
monitorId	monitorId	М

#### C.2.2.7.2 Output parameters

Table C.2.2.7.2: Mapping from IS deleteThresholdMonitor output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
status	status	М

#### C.2.2.7.3 Fault definition

Table C.2.2.7.3: Mapping from IS deleteThresholdMonitor exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
${\tt unknownThresholdMonitor}$	UnknownThresholdMonitor	М

## C.2.2.8 Operation listThresholdMonitors

#### C.2.2.8.1 Input parameters

Table C.2.2.8.1: Mapping from IS listThresholdMonitors input parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
monitorIdList	monitorIdList	M

#### C.2.2.8.2 Output parameters

Table C.2.2.8.2: Mapping from IS listThresholdMonitors output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
status	status	M

#### C.2.2.8.3 Fault definition

Table C.2.2.8.3: Mapping from IS listThresholdMonitors exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
invalidMonitorIdList	InvalidMonitorIdList	M

## C.2.2.9 Operation suspendThresholdMonitor

#### C.2.2.9.1 Input parameters

Table C.2.2.9.1: Mapping from IS suspendThresholdMonitor input parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
monitorIdList	monitorIdList	M

#### C.2.2.9.2 Output parameters

Table C.2.2.9.2: Mapping from IS suspendThresholdMonitor output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
status	status	М

#### C.2.2.9.3 Fault definition

Table C.2.2.9.3: Mapping from IS suspendThresholdMonitor exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
unknownThresholdMonitor	UnknownThresholdMonitor	M
thresholdMonitorAlreadySuspended	ThresholdMonitorAlreadySuspended	М

## C.2.2.10 Operation resumeThresholdMonitor

#### C.2.2.10.1 Input parameters

Table C.2.2.10.1: Mapping from IS resumeThresholdMonitor input parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding input message under corresponding port type operation as indicated in Table C.2.1	Qualifier
monitorId	monitorId	M

#### C.2.2.10.2 Output parameters

Table C.2.2.10.2: Mapping from IS resumeThresholdMonitor output parameters to SS equivalents

IS Operation parameter	SS WSDL type sub-element used in corresponding output message under corresponding port type operation as indicated in Table C.2.1	Qualifier
status	status	М

#### C.2.2.10.3 Fault definition

Table C.2.2.10.3: Mapping from IS resumeThresholdMonitor exceptions to SS equivalents

Assertion name	SS WSDL type enumeration value used in corresponding fault message under corresponding port type operation as indicated in Table C.2.1	Qualifier
unknownThresholdMonitor	UnknownThresholdMonitor	M
thresholdMonitorIsNotSuspended	ThresholdMonitorIsNotSuspended	M

## C.3 Solution Set definitions

#### C.3.1 WSDL definition structure

Clause C.3.2 provides a graphical representation of the PM IRP service.

Clause C.3.3 defines the services which are supported the PM IRP agent.

## C.3.2 Graphical Representation

The WSDL structure is depicted in Figure C.3.2 below depicting port type, binding and service. The port type contains port type operations, which again contains input, output and fault messages. The binding contains binding operations, which have the same name as the port type operations. The binding connects to a port inside the service.




Figure C.3.2: Performance Management IRP SOAP Solution Set WSDL structure

## C.3.3 WSDL specification "PMIRPSystem.wsdl"

```
<?xml version="1.0" encoding="UTF-8"?>
    3GPP TS 32.416 Performance Management (PM) IRP SOAP Solution Set
<definitions xmlns="http://schemas.xmlsoap.org/wsdl/"</pre>
xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/
xmlns:pMIRPSystem="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#PMIRPSystem"
xmlns:pMIRPData="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#PMIRPData"
xmlns:xpi="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#pMIRPIOCs"
xmlns:xn="http://www.3gpp.org/ftp/specs/archive/32_series/32.626#genericNrm"
xmlns:genericIRPSystem="http://www.3gpp.org/ftp/specs/archive/32_series/32.316#GenericIRPSystem"
targetNamespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#PMIRPSystem">
namespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.306#NotificationIRPNtfSystem"/>
    <import namespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.316#GenericIRPSystem"/>
        <schema targetNamespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#PMIRPData"</pre>
xmlns="http://www.w3.org/2001/XMLSchema">
            <import namespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#pMIRPIOCs"/>
           <import namespace="http://www.3gpp.org/ftp/specs/archive/32_series/32.626#genericNrm"/>
            <!-- The following types are defined for the PM IRP operations -->
           <simpleType name="OperationStatusTwo">
                <restriction base="string">
                   <enumeration value="Success"/>
                    <enumeration value="Failure"/>
                </restriction>
            </simpleType>
            <simpleType name="OperationStatusThree">
                <restriction base="string">
                   <enumeration value="Success"/>
                    <enumeration value="Failure"/>
                   <enumeration value="PartialSuccess"/>
               </restriction>
            </simpleType>
           <complexType name="JobIdList">
               <sequence>
                   <element ref="xpi:jobId" minOccurs="0" maxOccurs="unbounded"/>
                </sequence>
            </complexType>
            <complexType name="JobInfoElement">
                <sequence>
                    <element ref="xpi:jobId"/>
                    <element ref="xpi:jobGranularityPeriod"/>
                   <element ref="xpi:jobReportingPeriod"/>
                   <element ref="xpi:jobStatus"/>
                    <element ref="xpi:jobPriority"/>
                    <element ref="xpi:jobReliability"/>
                   <element ref="xpi:jobStartTime"/>
                   <element ref="xpi:jobStopTime"/>
                    <element ref="xpi:jobSchedule"/>
                    <element name="iOCName" type="string"/>
                    <element name="iOCInstanceList" type="xn:dnList"/>
                   <element name="measurementCategoryList"</pre>
type="pMIRPData:MeasurementCategoryList"/>
               </sequence>
            </complexType>
            <complexType name="JobInfoList">
               <sequence>
                    <element name="jobInfoElement" type="pMIRPData:JobInfoElement" minOccurs="0"</pre>
maxOccurs="unbounded"/>
               </sequence>
           </complexType>
            <complexType name="MeasurementCategoryList">
                   <element ref="xpi:measurementTypeName" minOccurs="1" maxOccurs="unbounded"/>
               </sequence>
            </complexType>
            <complexType name="MonitorIdList">
                   <element ref="xpi:monitorId" minOccurs="0" maxOccurs="unbounded"/>
               </sequence>
            </complexType>
```

```
<complexType name="MonitorInfoElement">
                <sequence>
                    <element ref="xpi:monitorId"/>
                    <element ref="xpi:monitorGranularityPeriod"/>
                     <element ref="xpi:thresholdMonitorStatus"/>
                     <element name="iOCName" type="string"/>
                    <element name="iOCInstanceList" type="xn:dnList"/>
                    <element name="thresholdInfoList" type="pMIRPData:ThresholdInfoList"/>
                </sequence>
            </complexType>
            <complexType name="MonitorInfoList">
                <sequence>
                    <element name="monitorInfoElement" type="pMIRPData:MonitorInfoElement"</pre>
minOccurs="0" maxOccurs="unbounded"/>
                </sequence>
            </complexType>
            <complexType name="ThresholdLevel">
                <sequence>
                    <element ref="xpi:thresholdValue"/>
                     <element ref="xpi:thresholdSeverity"/>
                    <element ref="xpi:hysteresis"/>
                </sequence>
            </complexType>
            <complexType name="ThresholdLevelList">
                <sequence>
                    <element name="thresholdPackElement" type="pMIRPData:ThresholdLevel"</pre>
minOccurs="1" maxOccurs="4"/>
                </sequence>
            </complexType>
            <complexType name="ThresholdInfoElement">
                <sequence>
                    <element ref="xpi:measurementTypeName"/>
                     <element ref="xpi:probableCause"/>
                     <element ref="xpi:specificProblem"/>
                     <element ref="xpi:direction"/>
                     <element name="thresholdPack" type="pMIRPData:ThresholdLevelList"/>
                </sequence>
            </complexType>
            <complexType name="ThresholdInfoList">
                <sequence>
                    <element name="ThresholdInfoElement" minOccurs="0" maxOccurs="unbounded"/>
                </sequence>
            </complexType>
            <complexType name="UnsupportedMeasurement1">
                <sequence>
                    <element name="objectInstance" type="xn:dn"/>
                     <element ref="xpi:measurementTypeName"/>
                    <element name="reason" type="string"/>
                </sequence>
            </complexType>
            <complexType name="UnsupportedList1">
                <sequence>
                     <element name="unsupportedMeasurement" type="pMIRPData:UnsupportedMeasurement1"</pre>
minOccurs="0" maxOccurs="unbounded"/>
                </sequence>
            </complexType>
            <complexType name="UnsupportedMeasurement2">
                     <element name="objectClass" type="string"/>
                     <element name="objectInstance" type="xn:dn"/>
                    <element ref="xpi:measurementTypeName"/>
                    <element name="reason" type="string"/>
                </sequence>
            </complexType>
            <complexType name="UnsupportedList2">
                <sequence>
                    <element name="unsupportedMeasurement" type="pMIRPData:UnsupportedMeasurement2"</pre>
minOccurs="0" maxOccurs="unbounded"/>
                </sequence>
            </complexType>
            <!-- createMeasurementJob Request-->
            <element name="createMeasurementJob">
                <complexType>
                     <sequence>
                         <element name="iOCName" type="xn:dn"/>
                         <element name="iOCInstanceList" type="xn:dnList"/>
                        <element name="measurementCategoryList"</pre>
type="pMIRPData:MeasurementCategoryList"/>
```

```
<element name="granularityPeriod" type="xpi:JobGranularityPeriod"/>
             <element name="reportingPeriod" type="xpi:JobReportingPeriod"/>
<element name="startTime" type="xpi:JobStartTime" minOccurs="0"/>
             <element name="stopTime" type="xpi:JobStopTime" minOccurs="0"/>
<element name="schedule" type="xpi:JobSchedule" minOccurs="0"/>
<element name="priority" type="xpi:JobPriority" minOccurs="0"/>
             <element name="reliability" type="xpi:JobReliability" minOccurs="0"/>
         </sequence>
    </complexType>
</element>
<!-- createMeasurementJob Response -->
<element name="createMeasurementJobResponse">
    <complexType>
         <sequence>
             <element ref="xpi:jobId"/>
             <element name="unsupportedList" type="pMIRPData:UnsupportedList1"/>
             <element name="status" type="pMIRPData:OperationStatusThree"/>
         </sequence>
    </complexType>
</element>
<!-- createMeasurementJob Fault -->
<element name="createMeasurementJobFault">
    <simpleType>
         <restriction base="string">
             <enumeration value="InvalidStartTime"/>
             <enumeration value="InvalidStopTime"/>
             <enumeration value="InvalidSchedule"/>
             <enumeration value="InvalidGranularityPeriod"/>
             <enumeration value="InvalidReportingPeriod"/>
             <enumeration value="HighWorkLoad"/>
             <enumeration value="InvalidPriority"/>
             <enumeration value="InvalidReliability"/>
             <enumeration value="NovalidMeasurementTypeName"/>
         </restriction>
    </simpleType>
</element>
<!-- stopMeasurementJob Request -->
<element name="stopMeasurementJob">
    <complexType>
        <sequence>
             <element ref="xpi:jobId"/>
        </sequence>
    </complexType>
</element>
<!-- stopMeasurementJob Response -->
<element name="stopMeasurementJobResponse">
    <complexType>
        <sequence>
             <element name="status" type="pMIRPData:OperationStatusTwo"/>
         </sequence>
    </complexType>
</element>
<!-- stopMeasurementJob Fault -->
<element name="stopMeasurementJobFault">
    <simpleType>
         <restriction base="string">
             <enumeration value="UnknownJob"/>
             <enumeration value="JobCannotBeStopped"/>
         </restriction>
    </simpleType>
</element>
<!-- suspendMeasurementJob Request -->
<element name="suspendMeasurementJob">
    <complexType>
        <sequence>
             <element ref="xpi:jobId"/>
        </sequence>
    </complexType>
</element>
<!-- suspendMeasurementJob Response -->
<element name="suspendMeasurementJobResponse">
    <complexType>
        <sequence>
             <element name="status" type="pMIRPData:OperationStatusTwo"/>
         </sequence>
    </complexType>
</element>
<!-- suspendMeasurementJob Fault -->
```

```
<element name="suspendMeasurementJobFault">
    <simpleType>
        <restriction base="string">
            <enumeration value="UnknownJob"/>
            <enumeration value="JobAlreadySuspended"/>
        </restriction>
    </simpleType>
</element>
<!-- resumeMeasurementJob Request -->
<element name="resumeMeasurementJob">
    <complexType>
        <sequence>
            <element ref="xpi:jobId"/>
        </sequence>
    </complexType>
</element>
<!-- resumeMeasurementJob Response -->
<element name="resumeMeasurementJobResponse">
    <complexType>
       <sequence>
            <element name="status" type="pMIRPData:OperationStatusTwo"/>
        </sequence>
    </complexType>
</element>
<!-- resumeMeasurementJob Fault -->
<element name="resumeMeasurementJobFault">
    <simpleType>
        <restriction base="string">
            <enumeration value="UnknownJob"/>
            <enumeration value="JobIsNotSuspended"/>
            <enumeration value="HighWorkLoad"/>
        </restriction>
    </simpleType>
</element>
<!-- listMeasurementJobs Request -->
<element name="listMeasurementJobs">
    <complexType>
       <sequence>
            <element name="jobIdList" type="pMIRPData:JobIdList"/>
        </sequence>
    </complexType>
</element>
<!-- listMeasurementJobs Response -->
<element name="listMeasurementJobsResponse">
    <complexType>
        <sequence>
            <element name="jobInfoList" type="pMIRPData:JobInfoList"/>
            <element name="status" type="pMIRPData:OperationStatusTwo"/>
        </sequence>
    </complexType>
</element>
<!-- listMeasurementJobs Fault -->
<element name="listMeasurementJobsFault">
       <restriction base="string">
            <enumeration value="InvalidJobIdList"/>
        </restriction>
    </simpleType>
</element>
<!-- createThresholdMonitor Request -->
<element name="createThresholdMonitor">
    <complexType>
        <sequence>
            <element name="iOCName" type="string"/>
            <element name="iOCInstanceList" type="xn:dnList"/>
            <element name="thresholdInfoList" type="pMIRPData:ThresholdInfoList"/>
            <element ref="xpi:monitorGranularityPeriod"/>
        </sequence>
    </complexType>
</element>
<!-- createThresholdMonitor Response -->
<element name="createThresholdMonitorResponse">
    <complexType>
        <sequence>
            <element ref="xpi:monitorId"/>
            <element name="unsupportedList" type="pMIRPData:UnsupportedList2"/>
            <element name="status" type="pMIRPData:OperationStatusThree"/>
        </sequence>
```

```
</complexType>
</element>
<!-- createThresholdMonitor Fault -->
<element name="createThresholdMonitorFault">
    <simpleType>
        <restriction base="string">
            <enumeration value="InvalidClassOrInstances"/>
            <enumeration value="InvalidGranularityPeriod"/>
            <enumeration value="NoValidMeasurementType"/>
            <enumeration value="InvalidNumberOfThresholdPackElements"/>
            <enumeration value="InvalidOrderOfThresholdPackElements"/>
            <enumeration value="InvalidDirection"/>
        </restriction>
    </simpleType>
</element>
<!-- deleteThresholdMonitor Request -->
<element name="deleteThresholdMonitor">
    <complexType>
        <sequence>
           <element ref="xpi:monitorId"/>
        </sequence>
    </complexType>
</element>
<!-- deleteThresholdMonitor Response -->
<element name="deleteThresholdMonitorResponse">
    <complexType>
        <sequence>
            <element name="status" type="pMIRPData:OperationStatusTwo"/>
        </sequence>
    </complexType>
</element>
<!-- deleteThresholdMonitor Fault -->
<element name="deleteThresholdMonitorFault">
    <simpleType>
        <restriction base="string">
            <enumeration value="UnknownThresholdMonitor"/>
        </restriction>
    </simpleType>
</element>
<!-- listThresholdMonitors Request -->
<element name="listThresholdMonitors">
    <complexType>
       <sequence>
            <element name="monitorIdList" type="pMIRPData:MonitorIdList"/>
        </sequence>
    </complexType>
</element>
<!-- listThresholdMonitors Response -->
<element name="listThresholdMonitorsResponse">
    <complexType>
        <sequence>
            <element name="monitorInfoList" type="pMIRPData:MonitorInfoList"/>
            <element name="status" type="pMIRPData:OperationStatusTwo"/>
        </sequence>
    </complexType>
</element>
<!-- listThresholdMonitors Fault -->
<element name="listThresholdMonitorsFault">
    <simpleType>
        <restriction base="string">
            <enumeration value="InvalidMonitorIdList"/>
        </restriction>
    </simpleType>
</element>
<!-- suspendThresholdMonitor Request -->
<element name="suspendThresholdMonitor">
    <complexType>
        <sequence>
            <element ref="xpi:monitorId"/>
        </sequence>
    </complexType>
<!-- suspendThresholdMonitor Response -->
<element name="suspendThresholdMonitorResponse">
    <complexType>
            <element name="status" type="pMIRPData:OperationStatusTwo"/>
        </sequence>
```

```
</complexType>
        </element>
        <!-- suspendThresholdMonitor Fault -->
        <element name="suspendThresholdMonitorFault">
            <simpleType>
                <restriction base="string">
                    <enumeration value="UnknownThresholdMonitor"/>
                    <enumeration value="ThresholdMonitorAlreadySuspended"/>
                </restriction>
            </simpleType>
        </element>
        <!-- resumeThresholdMonitor Request -->
        <element name="resumeThresholdMonitor">
            <complexType>
                <sequence>
                   <element ref="xpi:monitorId"/>
                </sequence>
            </complexType>
        </element>
        <!-- resumeThresholdMonitor Response -->
        <element name="resumeThresholdMonitorResponse">
            <complexType>
                <sequence>
                    <element name="status" type="pMIRPData:OperationStatusTwo"/>
                </sequence>
            </complexType>
        </element>
        <!-- resumeThresholdMonitor Fault -->
        <element name="resumeThresholdMonitorFault">
            <simpleType>
                <restriction base="string">
                    <enumeration value="UnknownThresholdMonitor"/>
                    <enumeration value="ThresholdMonitorIsNotSuspended"/>
                </restriction>
            </simpleType>
        </element>
    </schema>
</types>
<message name="createMeasurementJob">
    <part name="parameter" element="pMIRPData:createMeasurementJob"/>
<message name="createMeasurementJobResponse">
    <part name="parameter" element="pMIRPData:createMeasurementJobResponse"/>
</message>
<message name="createMeasurementJobFault">
    <part name="parameter" element="pMIRPData:createMeasurementJobFault"/>
</message>
<message name="stopMeasurementJob">
    <part name="parameter" element="pMIRPData:stopMeasurementJob"/>
</message>
<message name="stopMeasurementJobResponse">
   <part name="parameter" element="pMIRPData:stopMeasurementJobResponse"/>
</message>
<message name="stopMeasurementJobFault">
   <part name="parameter" element="pMIRPData:stopMeasurementJobFault"/>
</message>
<message name="suspendMeasurementJob">
    <part name="parameter" element="pMIRPData:suspendMeasurementJob"/>
</message>
<message name="suspendMeasurement.JobResponse">
    <part name="parameter" element="pMIRPData:suspendMeasurementJobResponse"/>
<message name="suspendMeasurementJobFault">
    <part name="parameter" element="pMIRPData:suspendMeasurementJobFault"/>
</message>
<message name="resumeMeasurementJob">
    <part name="parameter" element="pMIRPData:resumeMeasurementJob"/>
</message>
<message name="resumeMeasurementJobResponse">
    <part name="parameter" element="pMIRPData:resumeMeasurementJobResponse"/>
<message name="resumeMeasurementJobFault">
   <part name="parameter" element="pMIRPData:resumeMeasurementJobFault"/>
</message>
<message name="listMeasurementJobs">
    <part name="parameter" element="pMIRPData:listMeasurementJobs"/>
</message>
<message name="listMeasurementJobsResponse">
```

```
<part name="parameter" element="pMIRPData:listMeasurementJobsResponse"/>
    </message>
    <message name="listMeasurementJobsFault">
        <part name="parameter" element="pMIRPData:listMeasurementJobsFault"/>
    <message name="createThresholdMonitor">
        <part name="parameter" element="pMIRPData:createThresholdMonitor"/>
    </message>
    <message name="createThresholdMonitorResponse">
        <part name="parameter" element="pMIRPData:createThresholdMonitorResponse"/>
    </message>
    <message name="createThresholdMonitorFault">
        <part name="parameter" element="pMIRPData:createThresholdMonitorFault"/>
    <message name="deleteThresholdMonitor">
       <part name="parameter" element="pMIRPData:createThresholdMonitorFault"/>
    </message>
    <message name="deleteThresholdMonitorResponse">
        <part name="parameter" element="pMIRPData:deleteThresholdMonitorResponse"/>
    </message>
    <message name="deleteThresholdMonitorFault">
        <part name="parameter" element="pMIRPData:deleteThresholdMonitorFault"/>
    <message name="listThresholdMonitors">
        <part name="parameter" element="pMIRPData:listThresholdMonitors"/>
    </message>
    <message name="listThresholdMonitorsResponse">
        <part name="parameter" element="pMIRPData:listThresholdMonitorsResponse"/>
    </message>
    <message name="listThresholdMonitorsFault">
        <part name="parameter" element="pMIRPData:listThresholdMonitorsFault"/>
    </message>
    <message name="suspendThresholdMonitor">
        <part name="parameter" element="pMIRPData:suspendThresholdMonitor"/>
    </message>
    <message name="suspendThresholdMonitorResponse">
        <part name="parameter" element="pMIRPData:suspendThresholdMonitorResponse"/>
    </message>
    <message name="suspendThresholdMonitorFault">
        <part name="parameter" element="pMIRPData:suspendThresholdMonitorFault"/>
    </message>
    <message name="resumeThresholdMonitor">
        <part name="parameter" element="pMIRPData:resumeThresholdMonitor"/>
    <message name="resumeThresholdMonitorResponse">
        <part name="parameter" element="pMIRPData:resumeThresholdMonitorResponse"/>
    </message>
    <message name="resumeThresholdMonitorFault">
        <part name="parameter" element="pMIRPData:resumeThresholdMonitorFault"/>
    </message>
    <portType name="PMIRPPortType">
        <operation name="createMeasurementJob">
            <input message="pMIRPSystem:createMeasurementJob"/>
            <output message="pMIRPSystem:createMeasurementJobResponse"/>
            <fault name="createMeasurementJobFault"
message="pMIRPSystem:createMeasurementJobFault"/>
        </operation>
        <operation name="stopMeasurementJob">
            <input message="pMIRPSystem:stopMeasurementJob"/>
            <output message="pMIRPSystem:stopMeasurementJobResponse"/>
            <fault name="stopMeasurementJobFault" message="pMIRPSystem:stopMeasurementJobFault"/>
        </operation>
        <operation name="suspendMeasurementJob">
            <input message="pMIRPSystem:suspendMeasurementJob"/>
            <output message="pMIRPSystem:suspendMeasurementJobResponse"/>
            <fault name="suspendMeasurementJobFault"
message="pMIRPSystem:suspendMeasurementJobFault"/
        </operation>
        <operation name="resumeMeasurementJob">
            <input message="pMIRPSystem:resumeMeasurementJob"/>
            <output message="pMIRPSystem:resumeMeasurementJobResponse"/>
            <fault name="resumeMeasurementJobFault"
message="pMIRPSystem:resumeMeasurementJobFault"/>
        </operation>
        <operation name="listMeasurementJobs">
            <input message="pMIRPSystem:listMeasurementJobs"/>
            <output message="pMIRPSystem:listMeasurementJobsResponse"/>
            <fault name="listMeasurementJobsFault" message="pMIRPSystem:listMeasurementJobsFault"/>
```

```
</operation>
        <operation name="createThresholdMonitor">
            <input message="pMIRPSystem:createThresholdMonitor"/>
            <output message="pMIRPSystem:createThresholdMonitorResponse"/>
            <fault name="createThresholdMonitorFault"</pre>
message="pMIRPSystem:createThresholdMonitorFault"/>
        </operation>
        <operation name="deleteThresholdMonitor">
            <input message="pMIRPSystem:deleteThresholdMonitor"/>
            <output message="pMIRPSystem:deleteThresholdMonitorResponse"/>
            <fault name="deleteThresholdMonitorFault"</pre>
message="pMIRPSystem:deleteThresholdMonitorFault"/>
        </operation>
        <operation name="listThresholdMonitors">
            <input message="pMIRPSystem:listThresholdMonitors"/>
            <output message="pMIRPSystem:listThresholdMonitorsResponse"/>
            <fault name="listThresholdMonitorsFault"</pre>
message="pMIRPSystem:listThresholdMonitorsFault"/>
        </operation>
        <operation name="suspendThresholdMonitor">
            <input message="pMIRPSystem:suspendThresholdMonitor"/>
            <output message="pMIRPSystem:suspendThresholdMonitorResponse"/>
            <fault name="suspendThresholdMonitorFault"</pre>
message="pMIRPSystem:suspendThresholdMonitorFault"/>
        </operation>
        <operation name="resumeThresholdMonitor">
            <input message="pMIRPSystem:resumeThresholdMonitor"/>
            <output message="pMIRPSystem:resumeThresholdMonitorResponse"/>
            <fault name="resumeThresholdMonitorFault"
message="pMIRPSystem:resumeThresholdMonitorFault"/>
        </operation>
    </portType>
    <operation name="createMeasurementJob">
            <soap:operation</pre>
soapAction="http://www.3qpp.org/ftp/specs/archive/32_series/32.416#createMeasurementJob"
style="document"/>
            <input>
                <soap:body use="literal"/>
            </input>
            <output>
                <soap:body use="literal"/>
            </output>
            <fault name="createMeasurementJobFault">
                <soap:fault name="createMeasurementJobFault" use="literal"/>
            </fault>
        </operation>
        <operation name="stopMeasurementJob">
            <soap:operation
soapAction="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#stopMeasurementJob"
style="document"/>
            <input>
                <soap:body use="literal"/>
            </input>
            <output>
                <soap:body use="literal"/>
            <fault name="stopMeasurementJobFault">
                <soap:fault name="stopMeasurementJobFault" use="literal"/>
            </fault>
        </operation>
        <operation name="suspendMeasurementJob">
            <soap:operation</pre>
soapAction="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#suspendMeasurementJob"
style="document"/>
            <input>
                <soap:body use="literal"/>
            </input>
            <output>
                <soap:body use="literal"/>
            </output>
            <fault name="suspendMeasurementJobFault">
                <soap:fault name="suspendMeasurementJobFault" use="literal"/>
            </fault>
        </operation>
        <operation name="resumeMeasurementJob">
```

```
<soap:operation</pre>
soapAction="http://www.3qpp.org/ftp/specs/archive/32_series/32.416#resumeMeasurementJob"
style="document"/>
            <input>
                <soap:body use="literal"/>
            </input>
            <output>
                <soap:body use="literal"/>
            </output>
            <fault name="resumeMeasurementJobFault">
                <soap:fault name="resumeMeasurementJobFault" use="literal"/>
            </fault>
        </operation>
        <operation name="listMeasurementJobs">
            <soap:operation</pre>
soapAction="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#listMeasurementJobs"
style="document"/>
            <input>
                <soap:body use="literal"/>
            </input>
            <output>
                <soap:body use="literal"/>
            </output>
            <fault name="listMeasurementJobsFault">
                <soap:fault name="listMeasurementJobsFault" use="literal"/>
            </fault>
        </operation>
        <operation name="createThresholdMonitor">
            <soap:operation</pre>
soapAction="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#createThresholdMonitor"
style="document"/>
            <input>
                <soap:body use="literal"/>
            </input>
            <output>
                <soap:body use="literal"/>
            </output>
            <fault name="createThresholdMonitorFault">
                <soap:fault name="createThresholdMonitorFault" use="literal"/>
            </fault>
        </operation>
        <operation name="deleteThresholdMonitor">
            <soap:operation</pre>
soapAction="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#deleteThresholdMonitor"
style="document"/>
            <input>
                <soap:body use="literal"/>
            </input>
            <output>
                <soap:body use="literal"/>
            </output>
            <fault name="deleteThresholdMonitorFault">
                <soap:fault name="deleteThresholdMonitorFault" use="literal"/>
            </fault>
        </operation>
        <operation name="listThresholdMonitors">
            <soap:operation</pre>
soapAction="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#listThresholdMonitors"
style="document"/>
            <input>
                <soap:body use="literal"/>
            </input>
            <output>
                <soap:body use="literal"/>
            </output>
            <fault name="listThresholdMonitorsFault">
                <soap:fault name="listThresholdMonitorsFault" use="literal"/>
            </fault>
        </operation>
        <operation name="suspendThresholdMonitor">
            <soap:operation</pre>
soapAction="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#suspendThresholdMonitor"
style="document"/>
            <input>
                <soap:body use="literal"/>
            </input>
            <output>
                --
<soap:body use="literal"/>
```

```
</output>
                                   <fault name="suspendThresholdMonitorFault">
                                              <soap:fault name="suspendThresholdMonitorFault" use="literal"/>
                                   </fault>
                        </operation>
                        <operation name="resumeThresholdMonitor">
                                   <soap:operation</pre>
\verb|soapAction="http://www.3gpp.org/ftp/specs/archive/32_series/32.416 \\ \verb|#resumeThresholdMonitor"| \\ \verb|soapAction="http://www.3gpp.org/ftp/specs/archive/32_series/32.416 \\ \verb|weight="http://www.3gpp.org/ftp/specs/archive/32_series/32.416 \\ \verb|weight="http://www.3gpp.org/ftp/specs/archive/32_series/32_series/32.416 \\ \verb|weight="http://www.3gpp.org/ftp/specs/archive/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32_series/32
style="document"/>
                                   <input>
                                              <soap:body use="literal"/>
                                   </input>
                                   <output>
                                               <soap:body use="literal"/>
                                   </output>
                                   <fault name="resumeThresholdMonitorFault">
                                              <soap:fault name="resumeThresholdMonitorFault" use="literal"/>
                                   </fault>
                       </operation>
           </binding>
           <service name="PMIRPService">
                       <port name="PMIRPPort" binding="pMIRPSystem:PMIRPBinding">
                                   <soap:address location="http://www.3gpp.org/ftp/specs/archive/32_series/32.416#PMIRP"/>
                       <port name="GenericIRPPort" binding="genericIRPSystem:GenericIRPBinding">
                                  <soap:address
location="http://www.3gpp.org/ftp/specs/archive/32_series/32.316#GenericIRP"/>
                       </port>
                       <port name="NotificationIRPNtfPort" binding="ntfIRPNtfSystem:NotificationIRPNtf">
                                  <soap:address
location="http://www.3gpp.org/ftp/specs/archive/32_series/32.306#NotificationIRPNtf"/>
                     </port>
           </service>
</definitions>
```

# Annex D (informative): Change history

	Change history						
Date	Meeting	TDoc	CR	Rev	Cat	Subject/Comment	New version
2010-09	SA#49	SP-100518				Presentation to SA for Information and Approval	1.0.0
2010-10						Publication	10.0.0
2011-03	SA-51	SP-110095	001	1		Add the missing exception in create measurement operation - Align with 32.412 PM IRP Information Service	10.1.0
2012-09	SA-57	-	-	-		Automatic upgrade from previous Release version 10.1.0	11.0.0
2013-06	SA-60	SP-130266	003	-		PM IRP SS Remove iRPId	11.1.0
2014-09	SA-65	SP-140559	004	-		Update the link from Solution Set to Information Service due to the end of Release 12	12.0.0
2016-01	-	-	-	-		Update to Rel-13 version (MCC)	13.0.0
2016-06	SA#72	SP-160407	0005	-	F	Update the link from IRP Solution Set to IRP Information Service	13.1.0
2017-03	SA#75	SP-170141	0006	3	В	Add attributes corresponding to updated IS for operation "Create measurement job" related to measurement job reliability	14.0.0
2018-06	-	=	-	-	-	Update to Rel-15 version (MCC)	15.0.0
2020-07	-	-	-	-	-	Update to Rel-16 version (MCC)	16.0.0

## History

	Document history					
V16.0.0 August 2020 Publication						