C1_W3_Lab_2_custom-dense-layer

February 3, 2025

1 Ungraded Lab: Building a Custom Dense Layer

In this lab, we'll walk through how to create a custom layer that inherits the Layer class. Unlike simple Lambda layers you did previously, the custom layer here will contain weights that can be updated during training.

1.1 Imports

```python
[1]: try:
         # %tensorflow_version only exists in Colab.
         %tensorflow_version 2.x
     except Exception:
         pass

     import tensorflow as tf
     import numpy as np
```

1.2 Custom Layer with weights

To make custom layer that is trainable, we need to define a class that inherits the Layer base class from Keras. The Python syntax is shown below in the class declaration. This class requires three functions: `__init__()`, `build()` and `call()`. These ensure that our custom layer has a *state* and *computation* that can be accessed during training or inference.

```python
[2]: # inherit from this base class
     from tensorflow.keras.layers import Layer

     class SimpleDense(Layer):

         def __init__(self, units=32):
             '''Initializes the instance attributes'''
             super(SimpleDense, self).__init__()
             self.units = units

         def build(self, input_shape):
```

```python
        '''Create the state of the layer (weights)'''
        # initialize the weights
        w_init = tf.random_normal_initializer()
        self.w = tf.Variable(name="kernel",
            initial_value=w_init(shape=(input_shape[-1], self.units),
                                 dtype='float32'),
            trainable=True)

        # initialize the biases
        b_init = tf.zeros_initializer()
        self.b = tf.Variable(name="bias",
            initial_value=b_init(shape=(self.units,), dtype='float32'),
            trainable=True)

    def call(self, inputs):
        '''Defines the computation from inputs to outputs'''
        return tf.matmul(inputs, self.w) + self.b
```

Now we can use our custom layer like below:

```python
[3]: # declare an instance of the class
     my_dense = SimpleDense(units=1)

     # define an input and feed into the layer
     x = tf.ones((1, 1))
     y = my_dense(x)

     # parameters of the base Layer class like `variables` can be used
     print(my_dense.variables)
```

```
[<tf.Variable 'simple_dense/kernel:0' shape=(1, 1) dtype=float32,
numpy=array([[0.02778218]], dtype=float32)>, <tf.Variable 'simple_dense/bias:0'
shape=(1,) dtype=float32, numpy=array([0.], dtype=float32)>]
```

Let's then try using it in simple network:

```python
[4]: # define the dataset
     xs = np.array([-1.0,  0.0, 1.0, 2.0, 3.0, 4.0], dtype=float)
     ys = np.array([-3.0, -1.0, 1.0, 3.0, 5.0, 7.0], dtype=float)


     # use the Sequential API to build a model with our custom layer
     my_layer = SimpleDense(units=1)
     model = tf.keras.Sequential([my_layer])

     # configure and train the model
     model.compile(optimizer='sgd', loss='mean_squared_error')
     model.fit(xs, ys, epochs=500,verbose=0)
```

```python
# perform inference
print(model.predict([10.0]))

# see the updated state of the variables
print(my_layer.variables)
```

```
[[18.981703]]
[<tf.Variable 'sequential/simple_dense_1/kernel:0' shape=(1, 1) dtype=float32,
numpy=array([[1.997348]], dtype=float32)>, <tf.Variable
'sequential/simple_dense_1/bias:0' shape=(1,) dtype=float32,
numpy=array([-0.99177784], dtype=float32)>]
```

[ ]: