Random walk model of order 2 (RW2)

Parametrization

The random walk model of order 2 (RW2) for the Gaussian vector $\mathbf{x} = (x_1, \dots, x_n)$ is constructed assuming independent second-orderincrements:

$$\Delta^2 x_i = x_i - 2 \ x_{i+1} + x_{i+2} \sim \mathcal{N}(0, \tau^{-1})$$

The density for **x** is derived from its n-2 second-order increments as

$$\pi(\mathbf{x}|\tau) \propto \tau^{(n-2)/2} \exp\left\{-\frac{\tau}{2} \sum_{i} (\Delta^2 x_i)^2\right\}$$
 (1)

$$= \tau^{(n-2)/2} \exp\left\{-\frac{1}{2}\mathbf{x}^T \mathbf{Q} \mathbf{x}\right\}$$
 (2)

where $\mathbf{Q} = \tau \mathbf{R}$ and \mathbf{R} is the structure matrix reflecting the neighbourhood structure of the model. It is also possible to define a *cyclic* version of the RW2 model.

Hyperparameters

The precision parameter τ is represented as

$$\theta = \log \tau$$

and the prior is defined on θ .

Specification

The RW2 model is specified inside the f() function as

```
f(<whatever>,model="rw2",values=<values>,cyclic=<TRUE,FALSE>,
```

The (optional) argument values is a numeric or factor vector giving the values assumed by the covariate for which we want the effect to be estimated. See the example for RW1 for an application.

Hyperparameter spesification and default values

hyper

theta

```
name log precision
short.name prec
prior loggamma
param 1 5e-05
initial 4
fixed FALSE
to.theta function(x) log(x)
from.theta function(x) exp(x)
```

constr TRUE

nrow.ncol FALSE

augmented FALSE

```
aug.factor 1
aug.constr
n.div.by
n.required FALSE
set.default.values FALSE
pdf rw2

Example

n=100
z=seq(0,6,length.out=n)
y=sin(z)+rnorm(n,mean=0,sd=0.5)
data=data.frame(y=y,z=z)

formula=y~f(z,model="rw2")
result=inla(formula,data=data,family="gaussian")
```

Notes

The RW2 is a intrinsic with rank deficiency 2.

There model also supports irregular locations or values.