# **SHAPES**

**Blend Shape Editor for Maya®** 

**User Guide** 

Version 2.0

### **Preface**

SHAPES assists in setting up regular blend shapes and corrective shapes.

It allows for sculpting new shapes in a posed state of the model and creates the driving relationship for each target either trough set driven keys, the weight driver node, which is provided as a plugin, or shape combos.

In-between shapes can be easily created and interactively adjusted to enhance the corrective shape.

SHAPES also allows for mirroring targets and comes with a variety of tools for splitting, merging, duplicating and more.

SHAPES only works with mesh objects.

# **General Notes**

#### Plug-Ins

The plugin *SHAPESTools* is required for using SHAPES. It is provided with the script and loaded automatically when running the tool.

In case a scene is set up utilizing the weight driver node, which is part of the SHAPESTools plugin, and the scene is to be passed on to a third party, the separate available WeightDriver plugin can be downloaded for free from the SHAPES website to allow full compatibility.

#### **Performance**

When working with multiple weight driver nodes in the scene it is advised to either hide these nodes or turn off the drawing for the cone and the weight as these will slow down the scene if used in larger amounts.


#### Compatibility

The weight driver node only displays in the default viewport for Maya 2013.5 and earlier. Viewport 2.0 compatibility is supported for Maya 2014 and later.

#### Workflow

SHAPES currently doesn't support undo.


# **Interface Overview**



- 1. Select the mesh that needs editing. Valid meshes can be bound to a skin cluster node but this is no requirement.
- 2. Displays the blend shape node being edited.
- Buttons to resize the target and driver list.
- 4. The target list, displaying all shapes of the currently selected blend shape node.
- 5. Value filtering options to display active targets.
- 6. Driver button column (left column): Each button creates or removes the corresponding shape driver and displays the type of incoming connection for each shape. Colored dots indicate other connections (keyframe, direct connections or expressions)
  - Combo button column (center column): Create or delete a shape combo.
- 7. Weight button column (right column): Displays if a shape is weighted and opens the Shape Weights folder.
- 8. The channel slider shows and edits the value of the currently selected shape.
- 9. The tweak button enters the sculpt mode for the selected shape to make adjustments to the model.
- 10. Delete the selected shape.
- 11. Edit weight maps for the selected shapes.
- 12. Create keyframes for selected shapes for corrective animation.
- 13. Defines the type of shape driver used for the current shape or a new shape before entering sculpt mode.
- 14. Sort the driver list alphabetically and search for a given string.
- 15. The list of all joints found in the skeletal hierarchy of the connected skin cluster. Skin joints appear with a red joint icon.
- 16. The parent joint is the direct parent of the selected driving joint for the shape and only needed for using the weight driver node.

- 17. Attributes for defining the shape driver.
- 18. Enters sculpt mode or exits it if already in sculpt mode.
- 19. Control the display of the original mesh while in sculpt mode.
- 20. SHAPES Brush settings. These will only display when sculpting in Maya is enabled but also can be turned off.

# **Context Menus**



- 21. Rename or select the current blend shape node.
- 22. Button tooltips.
- 23. Rename the target shape.
- 24. Target list filtering and labels.
- 25. Mirror Actions.
- 26. Target Actions.
- 27. Create a new in-between for the selected shape.
- 28. Weight driver actions.
- 29. Set a custom slider range for the selected shape.
- 30. Select the highlighted node in the scene or choose the respective list item based on the scene selection. Add or remove custom nodes from the driver list.

# **Contents**

What's New in Versio	n 2.0	11
Installation		14
Running SHAPES		15
Known Issues		15
Selecting a Mesh		16
Mesh Validation		16
	Intermediate Shapes	16
	Symmetry	17
Working With a Simp	le Mesh	17
Enter Sculpt Mode		18
Exit Sculpt Mode		19
Editing the Target We	eight	20
	Set Slider Range	20
	Unlinking Driven Targets	21
In-betweens		22
	Adding In-betweens	22
	Editing the In-Between Position	22
Tweak an Existing Target or In-Between		23
Other Ways to Add a	Target or In-Between	23
	Add Selection As New Default Target	23
	Add Selection As New Posed Target	24
	Add Selection As New Default In-Between	24
	Add Selection As New Posed In-Between	25
	Add Original Mesh As New Target	25
	Add Current Mesh As New Target	25

Sculpt with Mudbox		26
	Auto Apply Shape	26
Sculpt with ZBrush		26
	Auto Apply Shape	27
Sculpt Outside Maya		27
scurpt outside maya		
	Export As FBX	27
	Custom Export	28
Target List		29
	Reordering	29
	Order Below	29
	Grouping	29
	Labels	30
	Add a Label	30
	Fdit Labels	30
	Filter by Label	31
	Filter by Values	31
Mirror Target shapes		32
	Full Mirror	32
	Mirror Direction	32
	Mirror Actions	77
	Symmetrize	33
	Flip Mirror	33
	Create Opposite	33
	Match Opposite	33
	Identifiers	34
	Mirror with Shape Drivers	34
	Mirror with Shape Combos	34
	Mirror with Behavior	35
Mirror Modes		36
	Order Based Mirror	36

	Symmetry Edge	36
	Set Symmetry Edge	37
	Symmetry Edge Errors	
	Limitations	37
	Position Based Mirror	37
	Tolerance	38
Shape Drivers		39
	Creating a New Shape with a Shape Driver	39
	Weight Driver Attributes	40
	Driver List	40
	Parent Joint	40
	Axis	40
	Range	
	Center	
	Type	
	Twist / Twist Range	41
	SetDrivenKey Attributes	
	Attribute	41
	Start/End	
	Type	
	Infinity	41
	Exiting the Sculpt Mode and Adding a Shape Driver	42
	Working With a Shape Driver	
	Deactivating/Activating the Weight Driver Node	42
	Custom Reader Position for the Weight Driver Node	43
	Assigning a Shape Driver to an Existing Shape	44
	Removing a Shape Driver	
	Overriding the Confirmation Dialogue	
	Updating Existing Driver Attributes	
	Ignore Skin Joints	
	Add New Nodes to the Driver List	
	Auto Add Unlisted Driver	
	Remove Nodes from the Driver List	
	Filter by Driver Type	47
Shape Combos		48

	Creating a Shape Combo	49
	Editing a Shape Combo	50
	Deleting a Shape Combo	51
Channel Actions		52
	Split Shape	52
	Merge Selected	53
	Swap Selected	53
	Extract	53
	Duplicate	54
Corrective Animatio	on	55
	Set Up	55
	Animation	56
Shape Weights		58
	Show the Weights Interface	59
	Button Actions	59
Groups		61
Helper Attribute		61
Create Attributes From Selection  Bake Current Mesh To Original  Bake Tweaks To Original  Cleanup Tweak Node  Export Node Data		62
		62
		63
		63
		64
Update Mesh From	Selection	65
Remove Orphan Tai	rget	66
Reset Target List		66
Python Commands		66

THE SOFTWARE PRODUCT IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OF THIRD-PARTY RIGHTS. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE SOFTWARE PRODUCT IS WITH YOU.

NEITHER BRAVE RABBIT NOR ITS SUPPLIERS WARRANT THAT THE FUNCTIONS CONTAINED IN THE SOFTWARE PRODUCT WILL MEET YOUR REQUIREMENTS OR THAT THE OPERATION OF THE SOFTWARE PRODUCT WILL BE UNINTERRUPTED OR ERROR-FREE. BRAVE RABBIT IS NOT OBLIGATED TO PROVIDE ANY UPDATES TO THE SOFTWARE.

IN NO EVENT SHALL THE AUTHOR OF THIS SOFTWARE PRODUCT BE LIABLE FOR ANY SPECIAL, CONSEQUENTIAL, INCIDENTAL, DIRECT OR INDIRECT DAMAGES WHATSOEVER (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, FOR PERSONAL INJURY, LOSS OF BUSINESS INFORMATION, OR ANY OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR INABILITY TO USE THIS PRODUCT, EVEN IF THE AUTHOR OF THIS SOFTWARE PRODUCT IS AWARE OF THE POSSIBILITY OF SUCH DAMAGES AND KNOWN DEFECTS, ANY CLAIM BY A THIRD PARTY AND EVEN IF THE REMEDY FAILS OF ITS ESSENTIAL PURPOSE.

Maya® is a registered trademark of Autodesk Inc. in the United States and/or other countries worldwide. Mudbox® is a registered trademark of Autodesk Inc. in the United States and/or other countries worldwide. Pixologic™ and ZBrush® are registered trademarks of Pixologic, Inc.

Mac OS® is a registered trademark of Apple Inc.

Microsoft® and Windows® are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

# What's New in Version 2.0

### Shape Weights ➤

New support for editing blend shape weights per target shape, including copy, paste, invert, mirror, trim, crop, export and import.

#### Editable Multi-Source Combos ➤

Combos have been revisited and now allow for any number of driving shapes and the difference between Shape Based Combos and Driver Based Combos has been dropped. Also Combos are now editable.

### **Selection Tracking** ➤

Item tracking makes it easy to create a combo between shapes which are spread across a long list of targets.

# Groups ➤

Target shapes can now be parented to each other to build hierarchies. A new group attribute can be used for organization when working with many target shapes.

see also Grouping >

### **Set Values For Multiple Target Shapes** ➤

When multiple target channels are selected changing the channel slider modifies the target value for the current selection if they are not driven otherwise.

# Set Slider Range ➤

Each slider range can be edited to exceed the default range between 0 and 1. Multiple target channels can be set at once.

### Filter By Values ➤

When having the target list filtered by target values the filtering can now be cleared with the clean button of the search by name field.

Value filtering now also displays the active shapes with color coding and can be set to live to always show the current target value.

# Other Ways to Add a Target or In-Between ➤

New actions allow to add externally sculpted target shapes as in-betweens along with adding the default mesh or the currently deformed state as a new target.

### Sculpt Display Options ➤

New display options for the sculpt mode include indication of the active sculpt mode to avoid false tweaking of the mesh and assignment of the default material to the sculpt mesh.

### **Key With Current Value** ➤

New keying button for keying the selected channel with the current value.

# Bake Current Mesh To Original ➤

Any target shape can be used to bake the current topology to the base mesh, allowing to update the model after design changes.

#### Bake Tweaks To Original ➤

Mesh edits stored on the tweak node can now be applied to the original mesh to allow mesh updates even if blend shape targets have been created.

### Cleanup Tweak Node ➤

The cleanup process has been updated.

### Update Mesh From Selection ➤

Update the blend shape setup after topology changes to the mesh without loosing any existing blend shape work.

### Remove Orphan Target ➤

When deleting target shapes it's possible that an empty weight[...] item remains in the target list. This action allows to easily remove this attribute.

## Target List Reset ➤

Resets the target list appearance and brings all target channels back to the order how they appear on the blend shape node.

#### **Editable Side Identifiers** ➤

Side identifiers can be edited for the mirror process.

### **Custom Weight Driver Reader Position** ➤

Define a custom source position for the weight driver's target vector when working with 'flat' hierarchies.

# Installation

SHAPES installs as a module to reduce the need to manually copy all necessary files to the target directories.

To install the SHAPES module unzip the downloaded archive and choose the folder which represents your Maya version.

- 1. Copy the contained SHAPES folder to a location of your choice. It doesn't necessarily have to be in your Maya user directory.
- 2. Within the SHAPES folder you find the **SHAPES.mod** file which contains all necessary information about the module. Open the file in a text editor and edit the sample path at the end of the line to match the path where you copied the SHAPES folder from step 1.

Please note that the path must end with the name of the SHAPES folder itself.

- 3. Save the changes.
- 4. Place a copy of the **SHAPES.mod** file in the **modules** folder of your Maya user directory. If such folder doesn't exist create a new folder with the name modules.

#### Windows

C:\Users\USERNAME\Documents\maya\2014x64\modules

#### OS X

/Users/USERNAME/Library/Preferences/Autodesk/maya/ 2014-x64/modules

#### Linux

/home/USERNAME/maya/2014-x64/modules

5. Restart Maya.

# **Running SHAPES**

To add a shelf button to the currently active shelf type the following command in the command line and execute it:

```
SHAPES install
```

Alternatively you can manually create a shelf button.

Open the script editor with a new MEL tab.

Enter the following lines and optionally middle-mouse drag these to the shelf to create a shelf button:

```
SHAPES;
evalDeferred("dockControl -e -r SHAPESDock");
```

You can use the provided icon to decorate your shelf button.


# **Known Issues**

SHAPES has not been tested with third party skinning plugins.

SHAPES is currently not compatible with plug-ins from Anzovin Studio.

Based on the steps taken during the work with SHAPES it can happen that the target list doesn't refresh correctly. If you experience unexpected results after i.e. deleting target shapes try to manually refresh the target list by right-clicking the target list and choosing **Refresh**.

# Selecting a Mesh



Select the mesh and click the **Select** button at the top of the UI.

The name of the mesh will appear in the **Skin Mesh** field.

The selection can be of two types:

- Simple meshes without a blend shape node, skin cluster or any other node.
- Skinned meshes bound to a skeleton.
- 2. After successfully loading the mesh the first blend shape node will be listed in the **Node** pulldown menu, if it exists.
- 3. Right-clicking the pulldown menu allows for selecting the current blend shape node or to rename it.

# Mesh Validation

#### **Intermediate Shapes**

When the mesh object is chosen, SHAPES will check for valid geometry, in particular if a shape node is present and if the intermediate object is a valid mesh.

Intermediate objects are present, if the mesh is already deformed.

However, it is possible that the mesh contains more than one intermediate shape node due to various actions.

If more than one intermediate shape is present SHAPES will inform you with the option to delete it.

Deleting additional intermediate shapes is necessary in order to load the mesh.

#### Symmetry

During the mesh validation process SHAPES also gathers information about the line of symmetry if **Menu > Mirror > Order Based Mirror** is enabled (default).

The line of symmetry of a mesh is defined by an edge which has both vertices placed at the zero coordinate of the defined mirror axis.

If no edge of the mesh meets this requirement the symmetry process will fail.

In this case the symmetry edge can be defined manually.

See Mirror Modes for details.


Also, with **Order Based Mirror** enabled the mesh needs to be only one shell.

If a mesh is build with more than one shell the validation process will inform you and disable **Order Based Mirror**.

# Working With a Simple Mesh

Simple meshes can be used right away for sculpting. No skin cluster or a previously assigned blend shape node is necessary.

# **Enter Sculpt Mode**



Click the Enter Sculpt Mode button at the bottom of the

SHAPES will immediately put you in sculpt mode to create the first blend shape target.


The sculpt mode automatically:


- creates a copy of the defined mesh and names it newCorrective. It appears at the same hierarchy level right next to the source mesh.
- displays the sculpt mesh in isolation mode.
- enables the SHAPES Brush.
- displays buttons in the HUD to exit or cancel the sculpt mode.
- displays the camera gate mask in green to indicate sculpt mode.
- applies the default lambert material to the sculpt mesh to avoid any shader interference which might compromise the display of frozen areas when using the SHAPES Brush.

All display settings can be individually controlled via **SHAPES Menu > Sculpt:** 

- Auto Enable Brush
- Show HUD Buttons
- Show Frame
- Use Default Material
- Isolated Sculpt Mode
- 2. To better compare the original and the currently sculpted shape use one of the provided buttons:
  - Toggle Shape toggles between the display of the original shape or the currently sculpted shape
  - Toggle X-Ray displays the sculpted shape in x-ray and shows the original shape.

# **Exit Sculpt Mode**





- 1. To exit the sculpt mode press either the Exit Sculpt Mode button at the bottom of the UI or the Exit Sculpt Mode HUD button.
- 2. To cancel the sculpt mode use the Cancel HUD button or go to Menu > Sculpt > Cancel Sculpt Mode.

Canceling the sculpt mode deletes the sculpted mesh but still creates a new blend shape node.

After exiting the sculpt mode the sculpted shape will be added as a new target to the current blend shape node and gets listed in the target list, right below the blend shape node pulldown menu.

3. To rename the new target double click the target and enter a new name.

Renaming a target will automatically rename the connected driver and combo nodes if these exist.

# **Editing the Target Weight**



1. Select the target to edit from the target list.

The Base channel will appear in the Channels folder.

The slider controls the weight of the blend shape target. It is directly controlling the blend shape target weight and also updates itself when driving the target weight through any kind of connection (Note: except for Maya 2014 SAP SP1 due to a blend shape node bug)

2. Click the **Set** button to set the slider to the channel's value.

In case of the base channel this will be 1.0. If the target has any in-between shapes the value will be the position of the in-between shape.

If the target is connected to a driving node, clicking the **Set** button will temporarily disconnect the driver. See also Unlinking Driven Targets for more information.

3. Use the Trash Icon to remove the target after a confirmation dialog.

The dialog can be bypassed by deactivating Menu > **Options > Confirm Delete.** 

It's also possible to set multiple target shapes at once by selecting all target shapes to edit and then setting the channel slider.

Note, that only non-driven targets will be affected.

Clicking the **Trash** button with multiple target shapes selected deletes all targets.

# **Set Slider Range**

By default the slider for each target has a range between 0 and 1.

Though this range is usually sufficient enough you can edit the range to also increase the effect of the target shape or to inverse it.

> To edit the slider range for one or more selected target shapes:

- 1. Select the target shape/s in the list you want to edit.
- 2. Right-click the Base slider and choose **Set Range**... from the menu.
- 3. Enter a new range for the slider. The given range must match the format <min>-<max>.

#### Example:

Enter -1-2 to set the range to start at -1 and end at 2, allowing for a negative effect as well as the double positive shape.

4. Click **OK** to set the new range or press **Default** to set the default range of 0-1.

# Unlinking Driven Targets

If a target shape is connected to a driving node, for example an animation curve or set driven key, the Base channel slider will always return to the value from the driving node after it has been released with the mouse. This behavior is due to the nature of connections in Maya.

If you need to temporarily disable the dependency right-click the Base slider label and choose Unlink from the menu. The connection will be broken allowing you to freely set the value of the target shape.

The connection will be re-established if:

- the currently active target shape is re-selected in the target list
- the target list is refreshed
- a new mesh is loaded

A target shape will also be unlinked automatically if the Set button is clicked to set the target shape to it's maximum value in order to tweak it.

### In-betweens

### Adding In-betweens



1. If you want to add an in-between shape right-click the Base slider and choose Add In-between.

If the base slider is either at 0 or 1 the default in-between value will be set to 0.5.

You can also set the Base slider to the value of where the in-between should be added.

2. A new slider appears. It also allows to redefine the position of the in-between.

Note, that the value of the Base slider is instrumental for generating the in-between regardless of the position of the in-between slider, which only defines where the inbetween will be positioned.

- 3. Click the Enter Sculpt Mode button to sculpt the inbetween shape.
- 4. After exiting the sculpt mode the new in-between is added and a new slider will appear in the **Channels** folder defining the position of the in-between.

# **Editing the In-Between Position**

Drag the slider of the in-between to re-define the position within the base target range.

This can be used to adjust how the shape transitions between the different shapes.

# Tweak an Existing Target or In-Between

1. If a target or in-between shape needs additional sculpting click the **Set** button to the right of the slider. This sets the slider to the value of the according shape and the button will change to Tweak.

In case the target is connected to a driving node, clicking the **Set** button will temporarily disconnect the driver. See also Unlinking Driven Targets for more information.

- 2. Click the Tweak button to enter sculpting mode and reshape the target.
- 3. After applying your edits exit the sculpt mode to update the blend shape target.

# Other Ways to Add a Target or In-Between

If you want to add an existing mesh as a target or in-between which has been modeled not using the SHAPES interface or if you want to create a new target shape from the currently deformed state you can access the command through the Edit Menu.

#### Add Selection As New Default Target

Adds the selected mesh as a new target shape without respecting any other deformation, such as skinning. It's basically the same as manually adding the blend shape target through the Maya menu.

If the model is not in an undeformed state when adding the new target you might not get the expected result when activating the target.

After applying the shape the mesh gets deleted from the scene.

#### Add Selection As New Posed Target

Adds the selected mesh as a new target shape while taking any other deformation into account.

Use this if you have modeled your new target shape from a posed state of your model.

This command performs additional calculations to correctly apply the new shape when the model is in a deformed state. It undergoes the same process like any sculpted shape when exiting the sculpt mode.

After applying the shape the mesh gets deleted from the scene.

#### Add Selection As New Default In-Between

This menu item appears in place of Add Selection As New Default Target when you are currently in the process of adding a new in-between.

Adds the selected mesh as a new in-between shape without respecting any other deformation, such as skinning. It's basically the same as manually adding the blend shape in-between through the Maya menu.

If the model is not in an undeformed state when adding the new in-between you might not get the expected result when activating the target.

1. If you want to add an already existing in-between shape right-click the Base slider and choose Add In-between.

If the base slider is either at 0 or 1 the default in-between value will be set to 0.5

You can also set the Base slider to the value of where the in-between should be added.

2. A new slider appears. It also allows to redefine the position of the in-between.

Note, that the value of the Base slider is instrumental for generating the in-between regardless of the position of

> the in-between slider, which only defines where the inbetween will be positioned.

- 3. Select your mesh in the scene which should be added as the in-between shape.
- 4. Go to Menu > Edit > Add Selection As New Default In-Between.
- 5. The selected mesh will be added as the in-between and deleted from the scene.

#### Add Selection As New Posed In-Between

This menu item appears in place of Add Selection As New Posed Target when you are currently in the process of adding a new in-between.

Adds the selected mesh as a new in-between shape while taking any other deformation into account.

Use this if you have modeled your new in-between shape from a posed state of your model.

This command performs additional calculations to correctly apply the new shape when the model is in a deformed state. It undergoes the same process like any sculpted shape when exiting the sculpt mode.

See Add Selection As New Default In-Between on how to perform the command.

#### Add Original Mesh As New Target

Creates a new target shape from the original, undeformed mesh.

#### **Add Current Mesh As New Target**

Creates a new target shape from the currently deformed state of the mesh.

# **Sculpt with Mudbox**

SHAPES allows for using Mudbox for the sculpting process. This feature is only available if Mudbox is installed and the Maya file menu contains the Send to Mudbox menu item.

To enable sculpting with Mudbox go to Menu > Sculpt and activate Sculpt In Mudbox. This will automatically send the corrective mesh to Mudbox.

The SHAPES Brush buttons at the bottom of the UI will be hidden when using Mudbox.

After finishing sculpting in Mudbox and sending the mesh back to Maya SHAPES will delete all unnecessary shading nodes and assign the default lambert shader to the mesh.

**Auto Apply Shape** 

With this option enabled the mesh coming from Mudbox will be automatically applied as a new shape and the sculpting mode exited.

# Sculpt with ZBrush

SHAPES allows for using ZBrush for the sculpting process. This feature is only available if ZBrush is installed and the default ZBrush install path exists.

#### Windows

C:/Users/Public/Pixologic/

/Users/Shared/Pixologic/

To enable sculpting with ZBrush go to Menu > Sculpt and activate Sculpt In ZBrush. This will automatically send the corrective mesh to ZBrush.

The SHAPES Brush buttons at the bottom of the UI will be hidden when using ZBrush.

> After finishing sculpting in ZBrush and sending the mesh back to Maya SHAPES will delete all unnecessary shading nodes and assign the default lambert shader to the mesh.

#### **Auto Apply Shape**

With this option enabled the mesh coming from ZBrush will be automatically applied as a new shape and the sculpting mode exited.

# **Sculpt Outside Maya**

If sculpting in an external application is preferred it can be easily done with SHAPES.

### Export As FBX

To enable sculpting with the FBX option go to Menu > Sculpt and activate Export As FBX. This will automatically export the corrective mesh as a FBX file.

The Enter Sculpt Mode button label will change to Export As FBX and the maya sculpt tool buttons at the bottom of the UI will be hidden.

When using FBX export for the first time SHAPES will ask you for a path to store the FBX file.

By default this will be the data subfolder of the current project but you can also use any other location.

The path will be remembered by SHAPES until the project changes.

After exporting via FBX the mesh is saved as newCorrective.fbx at the defined path and the sculpt mode button label will change to Import From FBX.

After finishing with the external sculpting the mesh can be re-imported by clicking the **Import From FBX** button, which also directly applies it to the blend shape node.

The import process assumes that the final shape has been saved to the same location and with the same file name as after the export.

# **Custom Export**

To enable sculpting with the custom export option go to **Menu > Sculpt** and activate **Custom Export**.

This allows you to export the corrective shape individually with the file format of your choice.

When using custom export the corrective shape is selected and placed at the world hierarchy level.

With this selection active use the regular Maya export or any custom export option to save the mesh.

After manually re-importing the modeled shape click the **Exit Sculpt Mode** button to add it to the blend shape node.

# **Target List**

SHAPES provides several functions which help improve the workflow with a large number of target shapes.

## Reordering

For better organization of corrective shapes it is possible to reorder the target list by dragging an item with the middle mouse button.

Note, that reordering the target items in the list does not actually change the order of the attributes on the blend shape node but rather stores the user defined order on a custom attribute on the node.

#### **Order Below**

As the target list grows reordering via drag & drop can become quite tedious.

In this case you can use the Order Below... option to easily place the selected item right underneath the next target item clicked.

#### Grouping

It is also possible to create hierarchies of corrective shapes by dragging items on top of each other with the middle mouse button.

Note, that despite of the hierarchical order all shapes still act independent from each other. Setting the channel value of a hierarchical parent shape does not influence the values of the child shapes.

You can also add group items to the target list to organize the target shapes. See **Groups** for details.

#### Labels

Each item in the target list can be color coded for keeping track of individual items or visually group target shapes.

SHAPES has a pre-defined set of labels but which can be individually changed or extended to a total of 12 labels.

#### Add a Label

- Select a target shape in the list, right-click and choose a label for the item. The combo button of the selected item will receive the label color.
- To clear a label select No Label from the right-click menu.

#### **Edit Labels**

○ ○ ○ Label Preferences Animated Label2 Corrective Label4 Helper Attribute Label6 Label7 Shape Combo Label9 **Driver Combo** Shape Fix Label12 Default Labels

To edit the list of available labels

- 1. select a target shape in the list, right-click and choose Labels... from the bottom of the menu.
- 2. The Label Preferences window will open listing all currently set labels and colors.
- 3. Edit the label you want to change. Any label which is not labeled Label[1-12] will appear as valid label in the rightclick menu of the target list.
- 4. To clear a label name double-click the label name and delete the name followed by pressing the Enter key. The label name will revert to the numbered label name.
- 5. Click the **Default Labels** button to reset all labels to their default names.

### Filter by Label

To filter the target list to show only all targets associated with a specific label

1. select the target shape in the list which is assigned to the type of label you want to filter.

2. Right-click and choose Filter By Labels from the menu.

The same process applies when the list should be unfiltered.

## Filter by Values




There are three options to filter the target list to indicate or only show all active channels:

- 1. Live Show Active Shapes doesn't filter the list but rather indicates the current channels values live. The indicators will update with every scene change, i.e. time change or value change.
- 2. Show Only Active Shapes shows all target shapes which currently have a channel value other than 0.
- 3. Show Only Shapes At Maximum shows all target shapes which currently have a channel value of 1 or greater.
- Click the Clear button at the top of the target list to unfilter the list and show all target shapes.

When the list is filtered a colored dot indicates the value of the listed channels.

- Green: active value between 0 and 1
- Yellow: active with a value of 1
- Red: active with a value above 1
- Blue: active with a value below 0

# **Mirror Target shapes**



Shapes can be mirrored on various ways.

The Mirror options are available through Menu > Mirror.

The mirror process is independent from the underlying mirror mode. See Mirror Mode for details.

#### **Full Mirror**

Target shapes extending over the line of symmetry will get fully mirrored to the other side if enabled.

Turning this option off ignores all points on the far side of the model restricting shapes to one side of the symmetry line.

#### **Mirror Direction**

By default the mirroring is performed from positive X to negative X, assuming the workflow of starting on the left side of the model first and then mirroring the shapes over to the right side.

### **Mirror Actions**

To mirror a shape right-click the target channel you want to mirror and choose between the following options:

**Symmetrize** 

Makes a shape symmetrical, applying the vertex positions of the source side to the target side.

This action does not create a new target shape.

Flip Mirror

Flips the shape across the line of symmetry taking all points into account resulting in a reversed shape.

This action does not create a new target shape.

**Create Opposite** 

Copies the entire blend shape channel, including its inbetweens, to a new channel for the other side of the model.

This option is only available for the base shape of each target. In-betweens can only be copied to the other side as part of the entire blend shape channel.

**Match Opposite** 

After making adjustments to a shape on one side of the model this action can be used to apply the same edit to the shape on the other side.

This option is also available for each in-between shape making it possible to update single in-betweens on the opposite side.

The process requires correctly named target channels in order to find the sibling of the shape.

#### **Identifiers**

SHAPES has a pre-set list of side identifiers used for the mirroring process, which is necessary to automatically set or find the name of the mirrored shape.

In some cases it might be necessary to edit the list to make it usable for a custom workflow.

Edit the list through Menu > Mirror > Set Mirror Identifiers...

To add custom identifiers to the list enter the respective labels in the fields. Please note, that all labels must be coming in pairs and are comma separated.

The list can be reset by clicking the **Default** button.

# Mirror with Shape Drivers

If a shape is copied to the other side to create a new shape sibling the connected shape driver is mirrored as well.

The behavior of the mirrored shape driver depends on the type of driver and if the joint is positioned at the center of the model or on an explicit side.

After mirroring it might be necessary to adjust the shape driver for the correct result.

# **Mirror with Shape Combos**

When mirroring a shape which is the target for a shape combo the combo relationship will be mirrored as well.

However, if the mirror source shape is driven by a combo based on a shape restricted to one side of the model the sibling for the shape must exist prior to mirroring.

The mirror process only creates a mirrored combo relationship but not the actual combo driver.

If a target shape is mirrored which acts as a combo driver no outgoing combo connections will be mirrored.

Only incoming combos are respected for the mirror process.

#### Mirror with Behavior

By default behavior-style mirroring is anticipated.

This usually means that the same control values produce symmetrical results even when used on opposite sides. For example selecting both arms of the character and setting a positive rotation value rotates both arms down.

However, some character rigs are build in an orientationstyle manner and have to be treated differently.

If you work with a rig that doesn't support behavior-style mirroring, i.e. Rapid Rig or Advanced Skeleton, the behavior mirroring must be turned off through

#### • Menu > Mirror > Drivers Mirror With Behavior

Please note that non-behavior mirroring with shape drivers is not yet fully supported and might not work in all cases.

# **Mirror Modes**

SHAPES has two basic modes for performing the mirror process.

- Order Based Mirror
- Position Based Mirror

Each mode has it's own advantages and disadvantages and can have an impact on the mirror result or even the success of the mirror process.

#### **Order Based Mirror**

This mode is the default setting of SHAPES.

The mirror process is based on the vertex order of the mesh which allows to even work with shapes which are not 100% symmetrical.

Please note that even this makes it possible to work with asymmetrical meshes there is no guarantee that the mirrored result works as expected in all cases.

A symmetrical mesh is always the best starting point for a successful mirror.

#### Symmetry Edge

The order based mirroring relies on a symmetry center defined by an edge which has both vertices placed at the zero coordinate of the set mirror axis.

SHAPES tries to automatically find the symmetry edge during the mesh evaluation process when loading the object.

If the symmetry edge has been found it will be listed as a menu item at Menu > Mirror > Define Symmetry Center > Symmetry Edge: ...

Selecting this menu item selects the edge component of the mesh.

#### **Set Symmetry Edge**

If you want to set a different edge component as the symmetry edge:

- Select the edge of the shape you want to use as the symmetry edge.
- Select Menu > Mirror > Define Symmetry Center > Set Symmetry Edge.

#### **Symmetry Edge Errors**

If the mesh evaluation process fails to find a valid symmetry edge and reports an error, perform the Set Symmetry Edge process to manually set the symmetry edge and reload the mesh.

#### Limitations

Order based mirroring can not be used if the mesh is composed of more than one shell.

If the selected mesh has more than one shell the mesh evaluation process will give a warning and order based mirroring will be disabled.

#### **Position Based Mirror**

If Order Based Mirror is disabled the mirror process will be based on the position of the vertices.

The advantage of position based mirroring is that the mesh is not limited to one shell only.

The drawback of position based mirroring is that the mesh needs to be fully symmetrical in order to find the vertices on the other side of the model.

A symmetrical mesh is always the best starting point for a successful mirror.

If a model is not perfectly symmetrical the mirror process tries to find the corresponding vertex on the other side of the model based on distance.

In case of slightly asymmetrical shapes it is possible that the mirroring will find the wrong mirror vertices which results in a falsely mirrored shape.

> The mirror process will fail if the no mirrored vertex is found within the range of 0.01 units (default) from the mirrored source position.

The tolerance value can be set manually.

#### **Tolerance**

If the mirror process fails or results in unexpected mirrored shapes it is possible that the default value for finding mirrored vertices are incompatible with the geometry.

In this case try to adjust the tolerance value by going to Menu > Mirror > Set Mirror Tolerance....

Setting the tolerance value too high might also result in expected mirrored shapes.

There is no guarantee that the mirror process will work in all cases.

# **Shape Drivers**

If the model is bound to a skeleton with a skin cluster a shape driver can be added to control the shape for the current pose when creating new shapes. Alternatively the shape driver can also be added later.

Shape drivers can be either regular set driven keys or via the weight driver node, which is supplied with SHAPES.

By default no shape driver is created.

### Creating a New Shape with a Shape Driver



To create a new shape with a shape driver enable

Menu > Options > Auto Add Shape Driver.

By default this option is turned off to prevent that the new shape is connected to a shape driver if shape driver settings are still present from a previous target shape selection.

Usually it is more convenient to first create the target shape and set up the shape driver in a separate step (see Assigning a Shape Driver to an Existing Shape).

Before entering sculpt mode to create a new shape define the shape driver attributes in the **Shape Driver** folder.

- 1. Set the driver to either Weight Driver or SetDrivenKey. The available parameters will change accordingly.
- 2. The driver list will show all joints of the model. Joints used for skinning will appear with a red joint icon.
- 3. You can optionally search for the driving node.
- 4. Select the driving node from the driver list. Double clicking the joint name will select the node in the scene.
- 5. Adjust the attributes for the shape driver if needed.

You can right-click the driver list for more selection options.

### **Weight Driver Attributes**

The weight driver is a vector reader which determines the output weight by a target vector rather than a joint angle.

**Driver List** 

The selected joint in the driver list defines the current axis of the pose and the pose angle. A locator will be parented to this joint serving as a target vector for the weight driver.

**Parent Joint** 

This field is automatically populated when selecting a joint in the list. It is the direct parent of the selection and will be used to parent the weight driver node to. You can also select a different node in the scene and click the **Select** button.

**Axis** 

The selection is defined by the down/first axis of the selected joint in the list and used to define the direction for the weight driver. If the joint orientation is not set up properly the assumed axis might not be correct and must be changed manually.

Range


This value shows the current joint rotation related to the pose. It defines the radius of the cone of influence with the current pose at its center and the neutral pose at the edge of the cone.

Center

A value larger then 0 will widen the center area of the weight driver where the resulting weight value will be 1, allowing for some motion within the target angle without sacrificing the weight value.

Type

Defines how the resulting weight values will be interpolated between 0 and 1.



#### **Twist / Twist Range**

With this enabled the resulting weight of the weight driver is also dependent of the orientation of the target locator. If the target vector is positioned in a way that the output weight would be 1 but the target locator has a rotation value matching the twist value or greater the output weight would still be 0.

The Twist Range defines how far the target locator can twist in either direction affecting the output weight.

## SetDrivenKey Attributes

This defines a regular Maya based set driven key relationship between the selected joint and the target shape.

#### **Attribute**

A list of all key-able attributes of the selected driver. Changing the attribute selection updates the **Start/End** fields with the attribute values at the time of selection.


If the attribute list gets too long in case of many custom attributes on the driver node the list can be filtered through enabling Menu > Options > Ignore Zero Attributes to only list attributes which are currently active.

#### Start/End

The **End** field shows the attribute value of the selected driver and attribute at the time of the driver selection.

#### Type

Defines the types of keyframe interpolation used to build the set driven keyframe curve.



#### Infinity

Sets the pre/post infinity for the set driven keyframe curve.

## **Exiting the Sculpt Mode and Adding a Shape Driver**

If the **Shape Driver** options have been properly set up the driving relationship will be automatically created when the sculpt mode is exited.

## Working With a Shape Driver

When a shape is controlled either by a weight driver node or set driven keyframe the target channel slider will always reflect the target weight.

If the slider is moved manually the driving influence of the shape driver is temporarily disabled, allowing for testing the influence of the current shape.

If the slider is dropped the shape driver will re-gain its influence and the slider will be set back to the current value of the shape driver.

If you need to temporarily disable the dependency right-click the Base slider label and choose **Unlink** from the menu. The connection will be broken allowing you to freely set the value of the target shape.

See also **Unlinking Driven Targets** for more information.

## **Deactivating/Activating the Weight Driver Node**

Any weight driver node can be deactivated to see the effect of the blend shape without the control of the driving weight.

To deactivate or re-activate the according driver right-click the **Base** channel of the selected target and choose **Deactivate Weight Driver**. The weight driver will be bypassed and the weight will be set to 0.

You can also use **Menu > Display** to control the visibility of the weight driver nodes or to activate/deactivate all weight drivers in the scene.

## **Custom Reader Position for the Weight Driver Node**

The output value of the weight driver node is based on a target vector defined between the position of the weight driver node and a locator.

In most cases this setup is sufficient and doesn't require any manual input.

However, if a rig consists of a 'flat' hierarchy it might be necessary to have the weight driver node in a particular part of the rig but referring to some other node to be used as the source point of the target vector.

To define a custom source position for an existing weight driver

- 1. select the weight driver driven target shape in the list you want to edit.
- 2. Select the node in the scene which should be used as the new source position for the weight driver.
- 3. Choose Menu > Tools > Set Weight Driver Source Position.

The command output will display the established connection.

### Assigning a Shape Driver to an Existing Shape



If a shape driver hasn't been assigned to a shape at the time of sculpting it is possible to add the driver afterwards.

- Select the shape in the target list to add the shape driver
- 2. In the **Shape Driver** folder set the driver to either **Weight** Driver or SetDrivenKey. The available parameters will change accordingly.
- 3. Select the driving node from the driver list.
- 4. Adjust the attributes for the shape driver if needed.
- 5. Click the left button of the shape in the target list. The tooltip will display Create shape driver.
- 6. A dialogue shows, asking to confirm creating the shape driver.
- 7. After confirming the process the shape driver will be setup immediately and the icon for the selected driver type will display on the button; an arrow for a weight driver node and a key symbol for set driven key.

### Removing a Shape Driver

If a shape driver should be no longer associated with a target shape

- 1. click the (left) shape driver button of the target shape in the list, which displays the symbol of the shape driver.
- 2. Confirm the deletion of the node.

### Overriding the Confirmation Dialogue

Creating and deleting shape drivers, as well as setting up and removing combos has been streamlined as much as possible.

However, the process has been made so easy that it's almost too easy to create new or delete existing relationships with one click.

In order to avoid accidental connections or disconnections the confirmation dialogue has been included.

If needed the dialogue can be overridden be disabling Menu > Options > Confirm Button Action.

## Updating Existing Driver Attributes

If a target shape is selected which is driven by a shape driver the shape driver folder will reflect the current settings of the driving node.

Changing any of the settings related to the current driver will automatically update the driver.

## **Ignore Skin Joints**

When loading a mesh with a skin cluster all joints will be added to the driver list which are influencing the skin or are within the same hierarchy as the skinning joints.

If listing all joints is not necessary or if the number of joints is very large and adding all joints is not favored the automatic listing can be ignored.

> To ignore the listing of skin joints disable the option found in Menu > Options > Auto List Joints On Load.

#### Add New Nodes to the Driver List

If a node which should act as a shape driver but is not listed in the driver list it can be added by

· selecting the node in the scene you want to add, rightclick the driver list and choose Add From Scene.

#### **Auto Add Unlisted Driver**

New nodes can automatically be added if the option Menu > Options > Auto Add Unlisted Driver is enabled.

- Select the node in the scene you want to add, right-click the driver list and choose Select From Scene.
- If the node is not already listed it will be added and then selected in the driver list.

If a target is selected which is driven by node not listed in the driver list and the option Auto Add Unlisted Driver is enabled the driving node will be added to the driver list.

#### Note

If the driver list is filtered, either by name or by type, and a new driver is added to the list but not matching the filtering it will not be displayed until the filtering is cleared.

#### Remove Nodes from the Driver List

If you want to remove a node from the driver list

right-click the driver list and choose Remove From List.

## Filter by Driver Type

You can filter the driver list by the type of driver to quickly find a certain node by type rather than by name.

- To filter the driver list click the button to the left of the driver name to display only drivers which match the node type of the clicked button.
- To un-filter the list click any icon button of the driver list.

#### Note

If the driver list is filtered, either by name or by type, and a new driver is added to the list but not matching the filtering it will not be displayed until the filtering is cleared.

## **Shape Combos**

A very important part in working with corrective shapes is the creation of specific relationships between shapes.

For example, a smile shape might work well with the mouth closed but might doesn't give the expected result when the mouth is opened.

Therefore a new corrective shape is needed to fix the smile with the mouth in its opened state but only when the smile is active.

Shape combos allow for the creation of such relationships.

In the above example of the smile the smile corrective for the open mouth would need to be driven by the joint that creates the open mouth pose.

The shape combo would then create the relationship between this driven pose and the state of the smile shape.


Combos can have any number of driving shapes controlling one target shape.

If the target shape is already driven by a shape driver this connection will also be part of the combo.

Combos can be edited at any time, allowing for adding or removing driving shapes and also defining a new target shape.

### **Creating a Shape Combo**





To set up a shape combo between two shapes

- 1. select any number of shapes from the target list which should control the combo.
- 2. Additionally select the target shape which should be driven. The last selected target shape will always be the driven shape by the combo.
- 3. Click on any middle button in the target list. The button tooltip will display Create combo.
- 4. After confirming the combo creation the shape combo driver items in the list will display a muted combo symbol, indicating that it's controlling a shape combo. The combo target item in the list will display a blue combo symbol on the left button, indicating that it's being influenced by a shape combo.

If the target list gets too long it can become harder to select a consecutive list of target shapes to create a combo. Especially in combination with the search function.

In this case item tracking can be used to store each separately chosen target shape in a list which is then used to create the combo.

To set up a shape combo using item tracking

- select each target to be used as the combo driver individually and choose **Track Item** from the target list right-click menu.
- 2. Select the combo target item last and also choose Track Item from the right-click menu.
- 3. Click on any middle button in the target list. The button tooltip will display Create combo.
- 4. After confirming the combo creation the new combo has been set up with the items previously selected.

> If the driven shape is also controlled by a shape driver the combo icon will display a little triangle in the lower right corner.

Moving the mouse over the muted combo source button will display the combo target shapes in the tooltip.

Moving the mouse over the left combo driver button of the target shape the tooltip will display the shape name of the combo sources.

Each target shape can be used as the source for multiple shape combos but each target can only be controlled by one driver.

### **Editing a Shape Combo**



- 1. Click the left button displaying the combo symbol of the target shape to edit the driving combo.
- 2. After confirming and entering the edit mode the target list highlights the participating target shapes:
  - combo drivers are displayed in green
  - the combo target is highlighted in red
- A: To add new target shapes to the combo select one or more items in the list and click the Add To Combo button below the target list.
- B: To remove target shapes from the combo select one or more items in the list and click the Remove From Combo button below the target list.
- C: To define a different target shape select a new item in the list and click the Set Combo Target button below the target list.
- D: To update the combo and leave the edit mode click the Update Combo button.

• E: To cancel the edit mode and discard any changes click the Cancel button.

## **Deleting a Shape Combo**

- 1. Click the left button displaying the combo symbol of the target shape that should be removed from the combo relationship.
- 2. After confirming the action the combo is deleted and the original shape driver re-connected to the target shape, if any.

### **Channel Actions**

When a target shape is selected in the target list various target actions are available from the slider right-click menu in the **Channels** folder.

### **Split Shape**

This action splits a target shape into separate shapes for the left and right side.

Splitting a shape is an interactive process which allows you to define the position and blending of the two resulting shapes.

#### To split a shape:

- 1. Select the target shape in the list you want to split.
- 2. Right-click the Base slider and choose **Split Shape** from the menu.

The two resulting shapes for the left and right side will be created and listed underneath the source shape in the target list.

The shape for the left side is set to 1 to visualize the result of the split shape sliders.

Below the **Channels** folder the **Split Shape** folder shows the split shape sliders and the commit button.

- Adjust the **Blend** slider to define how far the blending will extend from the center position to the left and right side. The value of the blend slider represents Maya scene units.
- Adjust the Center slider to define the center position of the blending. A positive value moves the center in positive direction of the defined axis (Menu > Mirror > Axis).

The **Blend** value is centered around this **Center** value.

5. After adjusting the blend values click the **Commit Shapes** button to transfer the blend values to the shape for the right side.



### Merge Selected

If you need to combine two or more shapes into one you can use this action.

1. Select any number of target shapes in the list you want to use for the merging process.

2. Right-click the Base slider and choose Merge Selected from the menu.

A new shape will be created and listed right below the first selected target.

Merging two or more shapes takes the current value of each shape. If the source shapes should be combined in their full state you need to set them to 1 before merging.

### **Swap Selected**

Allows you to exchange the blend shape data between the two selected target shapes. Only the shape information will be replaced while any connections to the targets will remain.

This makes it easy to replace an already existing shape with an updated version without the need to rebuild all the related connections and driving relationships.

- 1. Select the two shapes which you would like to use to replace each other.
- 2. Right-click the Base slider and choose **Swap Selected** from the menu.

#### **Extract**

Right-click the Base or in-between slider of a target in the Channels folder and select Extract from the menu.

The blend shape target data is used to create a new mesh resembling the selected shape.

# **Duplicate**

Right-click the Base slider of a target in the Channels folder and select **Duplicate** from the menu.

The blend shape target data is then copied to a new target and appears directly underneath the selected item in the list.

### **Corrective Animation**

SHAPES has a basic toolset for setting up and working with corrective animation.

Corrective animation comes into play after the actual animation process. At this point the animated geometry is the result based on skin clusters, blend shapes and many other deformers and nodes allowing to put the mesh in to a particular pose. But no matter how much effort has been put into the setup and rigging of the model there will always be specific poses which will not work correctly or were not anticipated during rigging. Or maybe the current pose should be pushed just a little further and the given controls don't allow for this modification.

Corrective animation can be used in these situations to create a better and stronger pose or to iron out deformation problems in specific areas.

Animated correctives are just simple blend shapes which blend in and out at specific frames helping you to model the final result while being in the current pose - something that SHAPES does anyway.

## Set Up

Preparing for corrective animation is very simple. You can either use your already existing blend shape node and use the animation features of SHAPES or you can add an additional blend shape node to carry only the shapes used for corrective animation.

To create a new blend shape node for corrective animation:

- 1. Select the last blend shape node from the **Node** pulldown menu at the top of the window.
- 2. Select Menu > Edit > Add Blend Shape Node After Current.

It's also possible to create a blend shape node at the front of the chain with Menu > Edit > Add Blend Shape Node but adding one after the last blend shape node in the chain is more logical.

If you want to add a new blend shape node manually make sure that it's ordered before the skin cluster node if one exists. This is important for extracting the corrective shape based on the current pose of the model.

#### **Animation**

Open the Animation folder of the interface to expose the controls to set and delete keyframes for the currently selected target shapes.

Opening the Animation folder automatically selects the current blend shape node so that you can see any related keyframes in the time slider of the Maya interface.

Selecting a shape from the target list while the Animation folder is open selects any connected animation curve node to only display keyframes relating to the current selection.

# 1. Key Selected With Zero Weight

Sets a keyframe for the selected shapes with a weight value of 0.

#### 2. Key Selected With Current Weight

Sets a keyframe for the selected shapes with the current weight value.

#### 3. Key Selected With Full Weight

Sets a keyframe for the selected shapes with a weight value of 1.

#### 4. Remove Key At Current Frame

Deletes the keyframe for the selected shapes at the current time and sets the weight to 0.

#### 5. Remove All Keys

Deletes all keyframes for the selected shapes and sets their weight to 0.

#### 6. Key Selected With Range

Sets a keyframe for the selected shapes with a weight value of 1 at the current frame and also creates bracketing keyframes with a weight of 0 before and after. The range is defined by the **Pre/Pose** range value.



### 7. Pre/Post Range

Defines how far apart the pre/post keyframes are from the current time when setting a shape keyframe with range.

#### 8. Remove Key In Range

Deletes the keyframe for the selected shapes at the current time and sets the weight to 0.

SHAPES will also look at neighboring keyframes with a value of 0 and deletes these as well. The distance of these bracketing keyframes does not have to match the value of the **Pre/Post** field, only the keyframe value of 0 is considered.

If a neighboring keyframe is not 0 it will not get removed.

## **Shape Weights**

SHAPES directly supports easy editing of blend shape weight maps per target shape.

The default Maya paint blend shape weights tool is used to assign the vertex weights.

A target shape with weight assignment will be indicated by a 'w' on the weight button (third button) in the target list.

All weight map actions, excluding export, work on several selected target shapes at once.

Note, that in order to use the weight map actions, for example trim or invert, a weight map must be already assigned to a target shape, meaning that the weight button displays the 'w'.

If you want to perform a weight map action to newly painted weights and the 'w' is not displayed yet make sure that you first leave the painting mode by clicking on the Paint Weights button. This assigns the painted weights to the target and lets you use the weight map action.

#### NOTE:

Painting blend shape weights with the tool settings open is not recommended and doesn't work properly in conjunction with SHAPES.

KEEP THE MAYA TOOL SETTINGS WINDOW CLOSED WHEN PAINTING SKIN WEIGHTS WITH SHAPES.


Having the tool settings open overrides the current shape selection in the target list of the SHAPES window and sets the paint operation to only work on the deformer weight rather than a specific target.

Another disadvantage using the tool settings window is that Maya by default only allows to paint weights for the first blend shape node, even if more than one blend shape node is present in the history of the mesh.

### **Show the Weights Interface**

To access the weights tools click the right weights button of a shape in the target list or open the Shape Weights folder manually.

#### **Button Actions**



#### 1. Weights Button

Displays if a target shape has weights. Clicking the button opens the Shape Weights folder if collapsed.

#### 2. Paint Weights

Toggles the paint blend shape weights tool for the selected target shape.

#### 3. Copy

Copies the weights from the current shape to the clipboard.

#### 4. Paste

Pastes the weights from the clipboard to the current shape.

#### 5. Invert/Mirror

Inverts the weight assignment. Right-click the button for mirroring the weights. The axis is defined by the mirror axis in Menu > Mirror.

#### 6. Trim/Crop Negative

Sets the weight value to 1 for all vertices which are on the negative axis of the model. The axis is defined by the mirror axis in Menu > Mirror.

As the result the painted weights will only appear on the positive side of the model.

Right-click the button to Crop the weights on the negative axis by settings the weight value to 0.

#### 7. Trim/Crop Positive

Sets the weight value to 1 for all vertices which are on the positive axis of the model. The axis is defined by the mirror axis in Menu > Mirror.

As the result the painted weights will only appear on the negative side of the model.

Right-click the button to **Crop** the weights on the positive axis by setting the weight value to 0.

#### 8. Export

Export the weights to a weight map file located at data/ SHAPES/weights/<nodeName> of the current project. The weight map will also be shown in the weight list.

During Sculpt Mode this button saves the currently frozen areas from the SHAPES Brush to a weight map for later use.

#### 9. Import

Imports the selected weight map file in the weight list to the current target shape.

During Sculpt Mode this button loads a previously stored weight map and uses it to define frozen areas for the SHAPES Brush.

#### 10. Freeze and Delete

Bakes the current weight map to the target shape and deletes the weight assignment.


#### 11. Delete

Remove all weight assignment form the current target shape.

#### 12. Delete Weight Map

Right-click a selected weight map entry in the weight list and choose Delete to remove the file from disk.

## **Groups**



To better organize the target shape list it is possible to create hierarchies of targets.

Even though it is possible to parent targets directly to each other (but without any dependencies) it is more efficient to use a dedicated grouping item to create logical groups of various target shapes.

A group attribute is a custom attribute on the blend shape node similar to the helper attribute but it appears without a slider in the Channels folder.

To add a group attribute select **Menu > Edit > Add Group**. The attribute is added to the blend shape node and listed in the target list.

Drag the target items you want to add to the group onto the group item with the middle mouse button.

## **Helper Attribute**

In some situations it can be necessary to add an additional attribute to either use for a controlling mechanism or to simply use as a divider to organize large amounts of target shapes.

The shape helper attribute is a custom attribute on the blend shape node which can be utilized for many needs.

To add a shape helper attribute select Menu > Edit > Add Shape Helper Attribute.

The attribute is added to the blend shape node and listed in the target list.

Note, that the selected helper attribute is labeled *Helper* with it's slider in the Channels folder and setting the slider to 1 doesn't switch the **Set** button to *Tweak*.

## **Create Attributes From Selection**

This function allows for creating custom attributes from the selected items in the target list on the selected node in the scene with existing connections.

It can be useful to create animatable attributes on controllers without having to animate the blend shape channels directly.

- 1. Select a node in the scene you want to add attributes to.
- 2. Select one or more target shapes in the target list.
- 3. Select Menu > Edit > Create Attributes From Selection.
- 4. A new window will appear allowing you to define the range of the attribute which will be created and the shape value range it will control.

If **Limit To Range** is selected both value ranges will be limited.

5. Click Add Attributes to add the attributes to the selected node.

# **Bake Current Mesh To Original**

While building a blend shape setup it might be necessary to update the base mesh due to a modified or updated design. This usually poses problems because this might interfere with the blend shape targets already created.

This option allows to update the base mesh keeping the already existing target shapes intact, which will then act on top of the replaced base mesh.

To apply the current shape to the original mesh go to Menu > Edit > Bake Current Mesh To Original.

Note, that any other mesh editing, especially altering the density of the mesh will not be respected and is not supported due to how blend shapes work.

## **Bake Tweaks To Original**

While building a rig and the related deformation it might be necessary to update the original model due to design changes or other reasons.

Usually changing the basic geometry poses undesirable results when blend shapes and skin deformations are already in place.

Since SHAPES always looks at the original mesh when creating or editing a target shape, edits stored on the tweak node are ignored, thus leading to differences between the base shape and the new or edited target shape.

To permanently apply the edits stored on the tweak node to the original mesh go to Menu > Tools > Bake Tweaks To Original.

Note, that only the point position offsets stored on the tweak node will be applied to the original mesh. Any other mesh editing, especially altering the density of the mesh will not be respected.

## **Cleanup Tweak Node**

During the creative sculpt process it can happen that the mesh is modified assuming an active sculpt mode which actually is not the case.

As a result the modeled changes are stored in the tweak node of the mesh's history resulting in unpredictable and unwanted sculpt results further down the line.

If this is the case this action can be used to unwanted vertex offsets from the current tweak node.

If you experience that after sculpting a new shape or tweaking an existing one the result after exiting the sculpt mode doesn't match your actual work you have done it is possible that you previously made changes to mesh while not being in sculpt mode.

In this case go to Menu > Tools > Cleanup Tweak Node to remove the offsets.

> If, for some reason, your node network misses a tweak node the process will inform you and give you the option to recreate the tweak node and all related nodes.

Please save your work before executing this command. It cannot be guaranteed that this will work in all cases and solve the issue.

## **Export Node Data**

If it is necessary to rebuild the rig because of fundamental changes you can export the entire blend shape setup including all set driven keys, weight driver nodes, combos and direct connections and apply the setup back into a fresh scene.

All blend shape targets will be extracted and saved as a Maya ASCII file and all target information will be written to a MEL file.

Both files are saved to

data/SHAPES/setup

of the current project.

Note, that the process will not export any animation curves or expressions.

To export the blend shape setup go to Menu > Tools > **Export Node Data** 

To import the blend shape setup go to Menu > Tools > Import Node Data... and select the blend shape setup from the submenu you want to import.

This simply sources the MEL file created during the export process.

Please also note that there is no guarantee that the process will be successful under any circumstances. It is always recommended to save the scene prior any update.

## **Update Mesh From Selection**

If it becomes necessary to rebuild the rig because of topology changes to the mesh it is possible to transfer the entire blend shape setup onto the updated mesh, as well as rebuild the skin information through the default Maya Copy Skin Weights function in a unified process.

The update process utilizes the Export/Import Node Data functionality of SHAPES, but only stores the files temporarily and deletes them afterwards.

To update the blend shape setup with a new mesh

- 1. select the mesh in the scene which should replace the existing mesh with the blend shape node
- 2. go to Menu > Tools > Update Mesh From Selection

The process will now:

- create new target shapes with the updated mesh
- export the entire blend shape setup and delete all related drivers and connections
- export the new target shapes and removes them from the scene
- check for an existing skin cluster; if present it offers to update it; also, if the new mesh is already bound to a skeleton updating the skin cluster can be skipped as well
- import the blend shape setup to the new mesh
- ask the user to keep the previous mesh; if kept the blend shape node will remain intact but without any driving relationships

Note, that the process will not maintain animation curves or expressions.

Please also note that there is no guarantee that the process will be successful under any circumstances. It is always recommended to save the scene prior any update.

## **Remove Orphan Target**

When deleting a target shape it can happen that the process doesn't finish as expected and a weight[...] entry is still left in the target list. This can happen in rare occasions.

These orphan attributes are possible to influence the performance of SHAPES and should be removed.

In case such a left over entry named weight[...] appears in the target list select it and choose Menu > Tools > Remove Orphan Target. This should permanently delete the item in the list.

Again, there haven been incidences where the selected item appears with the name temp. If this happens, select this item in the list and click the trash icon in the Channels folder.

# **Reset Target List**

Resets the target list appearance and brings all target channels back to the order how they appear on the blend shape node.

Choose Menu > Tools > Reset Target List.

This clears all custom ordering of target shapes, as well as parenting, labels and ranges.

## **Python Commands**

The following python commands can be used to control SHAPES functions via hotkeys:

SHAPES.SHAPES\_sculpt.toggleSculptModeDisplay('shape')

SHAPES.SHAPES\_sculpt.toggleSculptModeDisplay('xray')