

# Memory management

**Module 5**


**Lecture**

---

**Operating systems 2020**

**1DT003, 1DT044 and 1DT096**

# Course timelines



Period 3				Modul 4			Modul 5			Modul 6			Modul 7			Modul 8	
	W	D	Date	OS	OSPP	DSP	OS	OSPP	DSP	OS	OSPP	DSP	OS	OSPP	DSP	OSPP	DSP
9	Mo		2020-02-24			T		L (KM)									
	Tu		2020-02-25			T		L (KM)									
	We		2020-02-26						L (KM)								
	Th		2020-02-27	S								L (KM)					
	Fr		2020-02-28		S	W				L (KM)							
10	Mo		2020-03-02					2 x L (LÅ)		W							
	Tu		2020-03-03	C				T		W							
	We		2020-03-04								L (LÅ)						
	Th		2020-03-05	Tr	C + Tr								L (LÅ)	W			
	Fr		2020-03-06	Sr	Sr	T + S				W				W	W		
11	Mo		2020-03-09					C	S								W
	Tu		2020-03-10					CL									
	We		2020-03-11		Cr + Ch												
	Th		2020-03-12	Avlyst dag (DV/IT)					S				Pc	W			
	Fr		2020-03-13	Annan tenta (DV/IT)					Sr				Pc		W		
12	Mo		2020-03-16	Avlyst dag (DV/F)				Sr + Tr									W
	Tu		2020-03-17	Annan tenta (DV/F)				CLr+Cr+Ch									
	We		2020-03-18	Avlyst dag						Sr							
	Th		2020-03-19	Tentamen									E	E			E
	Fr		2020-03-20						Sr			Pcr	Pcr + Dpr			L (LÅ)	

# Background

Human user



Human user



Human user



Process A



Process B



Process B




• • • • •

Process Z





The operating systems **controls the hardware** and **coordinates its use** among the various application programs for the various user. An operating system provides an **environment for the execution of programs**.

## Computer hardware




# A typical computer system





# Process creation

To run a program, the operating system must **fetch** the program **executable from disk** and place the program in a **new process** in **main memory** for it to be run.



# Process control block (PCB)

The operating system must allocate memory for the process control block.

# **Process Control Block (PCB)**

The process control block (PCB) is a data structure in the operating system kernel containing the information needed to manage a particular process.

Source [https://en.wikipedia.org/wiki/Process\\_control\\_block](https://en.wikipedia.org/wiki/Process_control_block)


2018-01-21

In brief, the PCB serves as the repository for any information that may vary from process to process.


# Process control block (PCB)

Must allocate  
memory for a  
new PCB

# Example of information stored in the PCB




# Example of information stored in the PCB



# Process memory space


In addition to a PCB, the operating system must allocate a new memory space for each new process. This memory space is often referred to as the process **memory image**.

# Static memory allocation




The operating system must allocates a blob of memory for the new process memory image.

# Static memory allocation




The allocated memory image is divided into the following segments:

- ▶ text
- ▶ data
- ▶ heap
- ▶ stack



# Ready

After the operating system has allocated a PCB and memory image for the new process it is ready to execute and changes state from new to ready.



- ▶ An **executable** must be brought (from disk) into memory and placed within a **process** for it to be run.
- ▶ Main **memory** and **registers** are the only storage CPU can access directly.
- ▶ **Register** access in one CPU clock (or less).
- ▶ **Main memory** can take many cycles.
- ▶ **Cache** sits between main memory and CPU registers.
- ▶ Must enforce **memory protection** between processes.

Human user



Human user



Human user



Process A



Process B



Process B




• • • • •


Process Z



The operating systems **controls the hardware** and **coordinates** its use among the various application programs for the various user. An operating system provides an **environment for the execution of programs**.





## Computer hardware





1

How can the available memory be allocated by the various processes?



Human user



Non-interactive  
process with no  
human user

Human user



Human user



**Process A**



**Process B**






**Process B**




• • • • •

**Process Z**



**2**  
**Must enforce  
memory  
protection  
between  
process images.**



# Single contiguous allocation

Single contiguous allocation is the simplest memory management technique. All the computer's memory, usually with the exception of a small portion reserved for the operating system, is available to the single application.




# Single contiguous allocation

- ▶ MS-DOS (released 1981) is an example of a system which allocates memory in this way.
- ▶ An **embedded system** running a single application might also use this technique.
- ▶ A system using single contiguous allocation may still **multitask** by **swapping** the contents of memory to switch among users. Sometimes the term **single-tasking** is used instead of multi-tasking for such systems.




- ★ MS-DOS (acronym for Microsoft Disk Operating System) is a operating system for x86-based personal computers mostly developed by Microsoft and initially **released 1981**.
- ★ During its lifetime, several competing products were released for the x86 platform, and MS-DOS went through eight versions, until **development ceased in 2000**.
- ★ MS-DOS is a **single-tasking** operating system.

- ▶ MS-DOS is a single-tasking operating system. It has a command interpreter that is invoked when the computer is started.
- ▶ MS-DOS simply loads a program into memory, writing over most of the command interpreter to give the program as much memory as possible.
- ▶ When the program terminates, the small portion of the command interpreter that was not overwritten resumes execution. Its first task is to reload the rest of the command interpreter from disk.



# Swapping

A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution.



# Swapping

A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution.

- ▶ **Backing store** – fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images.
- ▶ **Roll out, roll in** – swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed.
- ▶ Major part of swap time is **transfer time**; total transfer time is directly proportional to the amount of memory swapped
- ▶ Modified versions of swapping are found on many systems (i.e., UNIX, Linux, and Windows).
- ▶ System maintains a **ready queue** of ready-to-run processes which have memory images on disk.

# Memory resident

Certain programs, can be marked as being memory resident, which means that the operating system is not permitted to swap them out to a storage device; they will always remain in memory.

# Memory resident

Certain programs, can be marked as being memory resident, which means that the operating system is not permitted to swap them out to a storage device; they will always remain in memory.

The programs and data used most frequently are the ones that should be memory resident.

This includes central portions of the operating system and special programs, such as calendars and calculators, that you want to be able to access immediately.

The **resident set size** is the portion of a process's memory that is held in RAM. The rest of the memory exists in swap or the filesystem (never loaded or previously unloaded parts of the executable).

# Partitioned allocation

Partitioned allocation divides primary memory into multiple memory partitions, usually contiguous areas of memory.

# Partitioned allocation

- ▶ Partitioned allocation divides primary memory into multiple memory partitions, **usually contiguous** areas of memory.
- ▶ Each partition might contain all the information for a specific job or task.
- ▶ Memory management consists of allocating a partition to a job when it starts and unallocating it when the job ends.

Main memory usually divided into two partitions: one for the operating system and one for all the processes in the system.

low  
address

Resident **operating system**,  
usually held in low memory with  
interrupt vector.

User **processes** held in high  
memory.

high  
address


# Logical address space

A logical address is the address at which a memory cell appears to reside from the perspective of an executing application program.


## Process control block

Process id (PID)
Process state (new, ready, running, waiting or terminated)
CPU Context
I/O status information
Memory management information
CPU scheduling information

## Main memory



## Process memory image



A pair of **base** and **limit** registers define a process **logical address space**.

low  
addresses

# Main memory

**Physical** memory  
addresses



CPU



high  
addresses


# Logical and physical memory addresses

## Currently executing process

Logical memory addresses

Address

0



Address  
**Max**



**CPU**

## Main memory

Physical memory  
addresses

P1

P2

P3

stack



heap

data

text

stack



heap

data


text


# Memory management unit (MMU)

The MMU is a computer hardware unit having all memory references passed through itself, primarily performing the **translation** of **logical memory addresses** to **physical addresses**.

# A simple MMU for partitioned contiguous allocation


Separate value for each process.






- ▶ Dynamic relocation using a **relocation register**.
- ▶ MMU maps **logical addresses to physical addresses**.
- ▶ The value in the relocation register is added to every address generated by a user process at the time it is sent to memory.
- ▶ The user program deals with logical addresses; it never sees the real physical addresses.

Must check if the address is within the boundaries of the process memory image.



# Contiguous Allocation



Relocation and limit registers used to protect


Main memory usually divided into two partitions:

- ★ Resident operating system, usually held in low memory with interrupt vector.
- ★ User processes then held in high memory


- ★ user processes from each other
- ★ operating-system code and data from user processes
  - ▶ Relocation register contains value of smallest physical address
  - ▶ Limit register contains range of logical addresses – each logical address must be less than the limit register
  - ▶ MMU maps logical address dynamically

**Dynamic  
memory  
management**


Three process occupies all available memory.




Process 8 terminates and leaves a free hole.




Process 9 allocates part of the hole left by process 8 and the hole of free memory shrinks.



The hole of free memory gets smaller and smaller





**Hole** – block of available free memory.

**Holes** of various size are **scattered** throughout memory.


When a process arrives, it is **allocated memory from a hole large enough** to accommodate it.

Operating system maintains information about:

- ▶ Allocated partitions.
- ▶ Free partitions (holes).

# Dynamic storage allocation problem

How to **satisfy** a request of **size n** from a **list of free holes**?



- ▶ **First-fit:** Allocate the first hole that is big enough
- ▶ **Best-fit:** Allocate the smallest hole that is big enough; must search entire list, unless ordered by size
  - ▶ Produces the smallest leftover hole
- ▶ **Worst-fit:** Allocate the largest hole; must also search entire list
  - ▶ Produces the largest leftover hole


Simulations show that first-fit and best-fit performs better than worst-fit in terms of speed and storage utilization.

# Fragmentation

Fragmentation is a phenomenon in which storage space is used inefficiently, reducing capacity and often performance.

# Fragmentation

Fragmentation is a phenomenon in which storage space is used inefficiently, reducing capacity and often performance.



- ▶ **Fragmentation** leads to storage space being "wasted", and the term also refers to the wasted space itself.
- ▶ **Internal fragmentation:** allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used.
- ▶ **External fragmentation:** total memory space exists to satisfy a request, but it is not contiguous.



**What to do  
about external  
fragmentation?**

# Compaction

Move all processes to one end of the address space producing one large hole at the other end of the address space.

# Compaction

Move all processes to one end of the address space producing one large hole at the other end of the address space.




**When** should compaction be done?

This method can be **expensive**  
(takes long time).

Compaction makes a process memory  
image **move around** in the physical  
memory during run time.

# Address binding


Address binding is the process of mapping the program's logical (or virtual addresses) to corresponding physical memory addresses.



A **compiler** is computer software that transforms computer code written in one programming language (the source language) into another programming language (the target language).

Source: [https://en.wikipedia.org/wiki/Logical\\_address](https://en.wikipedia.org/wiki/Logical_address)


2018-02-21



The **linker** or link editor is a computer program that takes one or more object files generated by a compiler and combines them into single executable file, library file or another object file.

Source: [https://en.wikipedia.org/wiki/Linker\\_\(computing\)](https://en.wikipedia.org/wiki/Linker_(computing))


2018-02-21



The **loader** reads the contents of the executable file containing the program instructions (and static data) into memory.

Once loading is complete, the operating system starts the program by passing control to the loaded program code.

# Binding of instructions and data to physical memory addresses




Address binding can take place at the following stages.

**Compile time**

**Load time**

**Run time**

# Binding of instructions and data to physical memory addresses




If binding delayed until run time the process can be moved during its execution.

Need hardware support for address maps (e.g., base and limit registers)

**Run time**




# Swapping



If swapping is used, a process may move around in the physical memory during run time.

# Compaction

Move all processes to one end of the address space producing one large hole at the other end of the address space.



**When** should compaction be done?

This method can be **expensive**  
(takes long time).

Compaction makes a process memory  
image **move around** in the physical  
memory during run time.

# Paging

# Paged memory management

Paged allocation divides the computer's primary memory into **fixed-size** units called page **frames**, and the program's logical (or virtual) address space into **pages** of the **same size**.

The hardware memory management unit **maps pages to frames**.

The **physical** memory can be **allocated non-contiguous** on a page basis while the logical address space appears contiguous.

Assume we need to allocate a 4 byte logical memory space.

In the logical address space we store the values A, B, C, D.

We address each byte with a two bit binary address.

Logical address space		
Address	Byte	
0	0	A
0	1	B
1	0	C
1	1	D

Due to external fragmentation, we might not be able to find four consecutive (contiguous) bytes of physical memory. But **what if** we can find holes of two consecutive bytes in the physical memory?

If we cut the logical address space in two halves, each half will be two bytes.

Logical address space		
Address	Byte	
0	0	A
0	1	B
1	0	C
1	1	D

A pair of scissors is shown on the left side, positioned to cut across the second and third columns of the table, illustrating the division of the logical address space into two halves of two bytes each.


Two bytes

Two bytes

Let's call each half a **page**.

Now the **first bit** of the logical binary address uniquely identifies the **page**.

The **second bit** of the logical address numbers the bytes within each page, we call this the page **offset**.



Assume we have a 8 byte physical memory. We need 3 bits to address the physical memory ( $2^3 = 8$ ). The lowest address = 000 and the highest address 111.

Divide the physical memory into **frames** of the same size (two bytes) as the pages. Number of frames =  $8/2 = 4$ . We number the frames in binary: 00, 01, 10, 11.

The two most significant bits will be the **frame** number.

Physical address space					
Address		Byte			
Frame	Offset				
0	0	0	W		
0	0	1	X	Frame 0	Already allocated to another process.
0	1	0		Frame 1	Free hole.
0	1	1			
1	0	0	Y	Frame 2	Already allocated to another process.
1	0	1	Z		
1	1	0		Frame 3	Free hole.
1	1	1			

We use a **page table** to map a logical page number to an empty physical frame.

Logical address space		
Address		Byte
Page	Offset	
0	0	A
0	1	B
1	0	C
1	1	D

Page table	
Page	Frame
0	?
1	?

Physical address space			
Address		Byte	
Frame	Offset		
0	0	0	W
0	0	1	X
0	1	0	
0	1	1	
1	0	0	Y
1	0	1	Z
1	1	0	
1	1	1	

In this example, page 0 is placed in frame 01 and page 1 is placed in frame 11.

Logical address space		
Address		Byte
Page	Offset	
0	0	A
0	1	B
1	0	C
1	1	D

Page table	
Page	Frame
0	01
1	11

Physical address space			
Address		Byte	
Frame	Offset		
0	0	0	W
0	0	1	X
0	1	0	A
0	1	1	B
1	0	0	Y
1	0	1	Z
1	1	0	C
1	1	1	D

The **physical** memory can be **allocated non-contiguous** on a page basis while the logical address space appears contiguous.

If we double the size of the logical address space from 4 bytes to 8 bytes, we could keep the 2 byte page/frame size and double the number of pages from 2 to 4 (A) or keep using 2 pages and double the page/frame size from 2 to 4 bytes (B).

**A**

Logical address space		
Address		
Page	Offset	
0	0	0
0	0	1
0	1	0
0	1	1
1	0	0
1	0	1
1	1	0
1	1	1

**B**

Logical address space		
Address		
Page	Offset	
0	0	0
0	0	1
0	1	0
0	1	1
1	0	0
1	0	1
1	1	0
1	1	1

The two most significant bits of the logical address identifies the page number and the least significant bit is the offset.




The most significant bit of the logical address identifies the page number and the two least significant bits is the offset.

We can generalize this method for arbitrary sized logical address spaces and arbitrary sized physical address spaces.

Let **P** = number of pages and **F** = number of frames.


The size of both the logical address space and the physical address space will be a multiple of the page/frame size.

When allocating a new page we can use any free frame. The physical memory can be allocated non-contiguous on a page basis while the logical address space appears contiguous.



For a logical address space of size  $2^m$  and a page/frame size of  $2^n$ , how many pages do we have?

$$P = \frac{2^m}{2^n} = 2^{m-n}$$




page of size  $2^n$

page of size  $2^n$

The **m - n** most significant bits of the logical address will identify the **page number**.


The **n least significant** bits of the logical address will be the page/frame **offset**.





# Decimal hens and eggs


1000 hens, each with a 3 digit decimal number 000, 001, ..., 999 and 100 baskets numbered 00, 01, ..., 99.



In which basket should eggs from hen 372 be placed? If we use a simple **direct mapped** scheme, put egg from hen 372 in basket  $372 \bmod 100 = 72 = 372 \bmod 10^2 = 2$  last digits of  $372 = 72$ .

# Binary hens and eggs


32 hens, each with a 5 bit binary number 00000, 00001, ..., 11111 and 8 baskets numbered 000, 001, ..., 111.



In which basket should eggs from hen 10110 be placed? If we use a simple **direct mapped** scheme, put egg from hen 10110 in basket  $101100 \bmod 8 = 10110 \bmod 2^3 = 3$  last bits of 10110 = 110.

# Addressing the memory

To address the memory, how many bits do we need?



To address  $2^m$  locations, we need a **m** bit address.

$A =$  m bit address

# Frames

Physical memory of size  **$2^m$  bytes** divide into frames of size  **$2^n$  bytes** each.

Memory	
$2^m$ bytes	
Frame	Size (bytes)
0	$2^n$
1	$2^n$
2	$2^n$
[ $2^{(m-n)}$ ] - 1	$2^n$

We number the frames 0, 1, ...  
How many frames do we get?

$$\frac{\text{Size of memory}}{\text{Size of frame}} = \frac{2^m}{2^n} = 2^{m-n}$$

We number the frames  
 $0, 1, \dots, [2^{(m-n)}] - 1$

# Pick a frame (address translation)

How can we map a logical address as seen by the CPU to a physical frame in memory?

Memory	
$2^m$ bytes	
Frame	Size (bytes)
0	$2^n$
1	$2^n$
2	$2^n$
$[2^{(m-n)}] - 1$	$2^n$

To address  $2^m$  locations, we need a **m** bit address.

A =

m bit address

To which of the  $(m - n)$  frames should an address be mapped?

- ▶ Could map address A to frame  $A \bmod (m-n)$ , i.e., use the  $(m-n)$  least significant bits of address A as frame number.
- ▶ But what if we use the  $(n-m)$  most significant bits instead?

# Pick a frame (address translation)

How can we map a logical address as seen by the CPU to a physical frame of size  $2^n$  in memory of size  $2^m$ ?

$m$  bit logical address seen by the CPU

A =



Frame size =  $2^n \Leftrightarrow m-n$  frames.

Use  $m-n$  high order bits to pick a frame.

frame number

???

A =




What does the  $n$  least significant bits mean?

Memory	
$2^m$ bytes	
Frame	Size (bytes)
0	$2^n$
1	$2^n$
2	$2^n$
[ $2^{(m-n)} - 1$	$2^n$

Use **m-n** high order bits to pick a **frame**.

The **n** least significant bits denotes the **byte offset** within the frame.



Memory	
2 <sup>m</sup> bytes	
Frame	Size (bytes)
0	2 <sup>n</sup>
1	2 <sup>n</sup>
2	2 <sup>n</sup>
3	2 <sup>n</sup>
...	...
[2 <sup>(m-n)</sup> ] - 1	2 <sup>n</sup>


Each frame is  $2^n$  bytes.

We number the bytes in a frame  $0, 1, 2, \dots, 2^n - 1$

Byte  $d$  within frame  $f$ .

- ▶ Using this scheme, a logical address will always be mapped to the same physical frame.


- ▶ The physical memory must still be allocated as a sequence of contiguous frames.



# Pages and frames

A solution that allows for non-contiguous allocation of physical frames.

- ▶ **Logical** address space divided into fixed sized **pages**.
- ▶ **Physical** memory divided into **frames** of the same fixed size as the pages.




Memory	
$2^m$ bytes	
Frame	Size (bytes)
0	$2^n$
1	$2^n$
2	$2^n$
$\vdots$	$\vdots$
0	$2^n$
1	$2^n$
2	$2^n$
3	$2^n$
$\vdots$	$\vdots$
$d$ frame offset	$2^n - 1$
$\vdots$	$\vdots$
$[2^{(m-n)}] - 1$	$2^n$

# Page table



A page lookup table maps logical pages to physical frames.

Page table	
Page	Frame
0	33
1	7111
↓	↓
127	42
↓	↓
$[2^{(m-n)}] - 1$	5666



**Page table**

Page	Frame
0	33
1	7111
↓	↓
127	42
↓	↓
$[2^{(m-n)}] - 1$	5666




# Paged memory management

- ▶ Logical address space of a process can be **noncontiguous**; process is **allocated physical memory whenever the latter is available**.
- ▶ Divide **physical memory** into fixed-sized blocks called **frames** (size is power of 2, between 512 bytes and 8,192 bytes).
- ▶ Divide **logical memory** into blocks of same size called **pages**.
- ▶ Keep track of all **free frames**.
  - To run a program of size  $n$  pages, need to find  $n$  free frames and load program.
- ▶ Set up a **page table** to translate logical to physical addresses.
- ▶ **Internal fragmentation** possible.
- ▶ **No external fragmentation**.


# Address translation scheme

Logical address generated by CPU is divided into:


- ▶ **Page number (p)** – used as an index into a page table which contains base address of each frame in physical memory
- ▶ **Page offset (d)** – combined with base address to define the physical memory address that is sent to the memory unit.



For given logical address space  $2^m$  and page size  $2^n$



## Currently executing process




logical  
memory



CPU

## Physical memory

frame  
number



page table

**Example:** 32 byte physical memory and 4-byte pages.

## How many frames?

$$(32 \text{ bytes}) / [(4 \text{ bytes})/\text{frame}] = 8 \text{ frames}$$


## How large physical address?

$$_2\log(32) = _2\log(2^5) = 5 \text{ bit address}$$

## How is the physical address divided into frame number and frame offset?

$$_2\log(8) = _2\log(2^3) = 3 \text{ bits for frame number}$$

$$_2\log(4) = _2\log(2^2) = 2 \text{ bits for frame offset}$$



Physical memory 32 bytes		
byte	frame	offset
0	0	0
1		1
2		2
3		3
4		0
5		1
6		2
7		3
8	1	0
9		1
10		2
11		3
12		0
13		1
14		2
15		3
16	2	0
17		1
18		2
19		3
20		0
21		1
22		2
23		3
24	3	0
25		1
26		2
27		3
28		0
29		1
30		2
31		3

# 32 byte physical memory and 4 byte logical pages


Logical memory	
Page	Byte content
0	a
	b
	c
	d
1	e
	f
	g
	h
2	i
	j
	k
	l
3	m
	n
	o
	p

Page table	
p	f
0	5
1	6
2	1
3	2


Physical Memory 32 bytes			
byte	frame	offset	content
0	0	0	
1		1	
2		2	
3		3	
4		0	i
5		1	j
6		2	k
7		3	l
8	1	0	m
9		1	n
10		2	o
11		3	p
12		0	
13		1	
14		2	
15		3	
16	2	0	
17		1	
18		2	
19		3	
20		0	a
21		1	b
22		2	c
23		3	d
24	3	0	e
25		1	f
26		2	g
27		3	h
28		0	
29		1	
30		2	
31		3	

# List of free frames

Before allocation






After allocation



# Memory protection

Memory protection between processes implemented by associating a **valid bit** with each entry in the per process page table.



- ▶ **valid** indicates that the associated page is in the process' logical address space, and is thus a legal page.
- ▶ **invalid** indicates that the page is not in the process' logical address space.

# Shared pages





Paging makes it possible for processes to share parts of their memory space with each other.

## Shared code

- ▶ One copy of **read-only** (reentrant) code shared among processes (i.e., text editors, compilers, window systems).
- ▶ Shared code must appear in same location in the logical address space of all processes.

## Private code and data

- ▶ Each process keeps a separate copy of the code and data.
- ▶ The pages for the private code and data can appear anywhere in the logical address space.



# fork() & copy-on-write

Paging makes it possible for the child to initially share pages with its parent.

# On Linux

```
$> man fork
```

Under Linux, **fork()** is implemented using **copy-on-write** pages, so the only penalty that it incurs is the time and memory required to duplicate the parent's page tables, and to create a unique task structure for the child.


Copy-on-write finds its main use in sharing the virtual memory of operating system processes, in the implementation of the **fork** system call.

Typically, the process does not modify any memory and immediately executes a new process, replacing the address space entirely.<sup>1</sup>


Thus, it would be wasteful to copy all of the process's memory during a fork, and instead the **copy-on-write** technique is used.

- 1) Typically the child immediately replaces the memory image using `exec()`.

After **fork()** the parent and child shares all pages.



If the parent modifies page C after **fork()**, a copy-on-write of page C is triggered.



Obviously only pages that can be modified even need to be labeled as copy-on-write. Code [text] segments can simply be shared.

Some systems provide an alternative to the **fork()** system call called a virtual memory fork, **vfork()**.

In this case the parent is suspended, and the child uses the parent's memory pages. This is very fast for process creation, but requires that the child not modify any of the shared memory pages before performing the **exec()** system call.

In essence this addresses the question of which process executes first after a call to fork, the parent or the child. With **vfork()**, the parent is suspended, allowing the child to execute first until it calls **exec()**, sharing pages with the parent in the meantime.

The **vfork()** function has the same effect as **fork()**, except that the behavior is undefined if the process created by **vfork()** either modifies any data other than a variable of type **pid\_t** used to store the return value from **vfork()**, or returns from the function in which **vfork()** was called, or calls any other function before successfully calling **\_exit()** or one of the **exec()** family of functions.

Source: <http://man7.org/linux/man-pages/man2/vfork.2.html>

2020-03-07



Both Linux and macOS implements the **vfork()** system call.


# Translation lookaside buffer

A translation lookaside buffer (TLB) is a memory **cache** that is used to reduce the time taken to access a user memory location.

The TLB stores the recent translations of virtual memory to physical memory.

# Paging hardware with TLB

A **translation lookaside buffer** (TLB) is a **cache** that memory management **hardware** uses to improve virtual address translation speed.



# Effective access time (1)

Use the hit ratio and the relative access times to measure the performance.

$$\alpha = \text{hit ratio} = \frac{\# \text{ TLB hits}}{\# \text{ TLB hits} + \# \text{ TLB misses}}$$

$\alpha \rightarrow 1$  when  $\# \text{ TLB misses} \rightarrow 0$

$\alpha \rightarrow 0$  when  $\# \text{ TLB hits} \ll \# \text{ TLB misses}$

# Effective access time (2)

Access probabilities

$$P(\text{TLB hit}) = \alpha$$

$$P(\text{TLB miss}) = (1 - \alpha)$$

Assume the following memory access times.

- ▶ Associative TLB lookup =  $\epsilon$  time unit.
- ▶ Memory cycle time = 1 ms.

# Effective access time (3)

Effective access time (EAT).

$$\text{EAT} = P(\text{TLB hit}) \cdot (1 + \varepsilon)\alpha + P(\text{TLB miss}) \cdot \frac{(2 + \varepsilon)(1 - \alpha)}{2 + \varepsilon - \alpha}$$

↓

▶  $\varepsilon$  for TLB lookup  
▶ 1 ms for memory access


↓

▶  $\varepsilon$  for TLB  
▶ 1 ms for in memory page table lookup access  
▶ 1 ms for memory access

# Virtual memory

Virtual memory provides an idealized abstraction of the physical memory which creates the illusion of a larger virtual memory than the physical memory.

Virtual memory  
(per process)



Virtual memory combines active RAM and inactive memory on disk to form a **large range of virtual contiguous addresses**.

Using **paging** a process can conceptually use more memory than might be physically available.

Pages are **swapped in** from disk to RAM and **swapped out** from RAM dynamically.

Virtual memory is an integral part of a modern computer architecture; implementations usually require **hardware support**, typically in the form of a memory management unit built into the CPU.

# Learn more in the following self study material

**Page table  
implementation**

**Module 5 self study material**

**Operating systems 2020**

**1DT003, 1DT044 and 1DT096**

Spring 2020

karl.marklund@it.uu.se

Uppsala university

**Segmentation**

**Module 5 self study material**

**Operating systems 2020**

**1DT003, 1DT044 and 1DT096**

Spring 2020

karl.marklund@it.uu.se

Uppsala university