Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- Principles of congestion control
- TCP congestion control



TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

-flow control


receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

application process Application removing data from TCP socket buffers TCP socket receiver buffers **TCP** code code from sender

receiver protocol stack

TCP flow control

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust
 RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow




TCP receiver-side buffering

TCP flow control

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust
 RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow

flow control: # bytes receiver willing to accept




TCP segment format

TCP connection management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)




```
application


connection state: ESTAB
connection Variables:
  seq # client-to-server
        server-to-client
   rcvBuffer size
   at server,client

network
```

Agreeing to establish a connection

2-way handshake:






Q: will 2-way handshake always work in network?


- variable delays
- retransmitted messages (e.g. req_conn(x)) due to message loss
- message reordering
- can't "see" other side

2-way handshake scenarios






2-way handshake scenarios



2-way handshake scenarios



TCP 3-way handshake


Client state

clientSocket = socket(AF INET, SOCK STREAM) LISTEN clientSocket.connect((serverName, serverPort)) choose init seq num, x send TCP SYN msq SYNSENT SYNbit=1, Seq=x choose init seq num, y send TCP SYNACK msg, acking SYN SYNbit=1, Seq=y ACKbit=1; ACKnum=x+1 received SYNACK(x) indicates server is live; **ESTAB** send ACK for SYNACK; this segment may contain ACKbit=1, ACKnum=y+1 client-to-server data received ACK(y) indicates client is live

Server state

serverSocket = socket(AF INET, SOCK STREAM) serverSocket.bind(('', serverPort)) serverSocket.listen(1) connectionSocket, addr = serverSocket.accept() LISTEN SYN RCVD **ESTAB**


TCP 3-way handshake FSM



Closing a TCP connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

Closing a TCP connection



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



Principles of congestion control

Congestion:

• informally: "too many sources sending too much data too fast for

network to handle"

- manifestations:
 - long delays (queueing in router buffers)
 - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!




congestion control: too many senders, sending too fast


flow control: one sender too fast for one receiver

Simplest scenario:


- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed



Q: What happens as arrival rate λ_{in} approaches R/2?




maximum per-connection throughput: R/2




large delays as arrival rate λ_{in} approaches capacity


- one router, *finite* buffers
- sender retransmits lost, timed-out packets
 - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
 - transport-layer input includes retransmissions : $\lambda'_{in} \ge \lambda_{in}$



Idealization: perfect knowledge


sender sends only when router buffers available






Idealization: some perfect knowledge


- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost



Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost







R/2

Realistic scenario: un-needed duplicates


- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered





Realistic scenario: un-needed duplicates

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered




"costs" of congestion:


- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
 - decreasing maximum achievable throughput

- four senders
- multi-hop paths
- timeout/retransmit

 \underline{Q} : what happens as λ_{in} and λ_{in} increase?

A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput \rightarrow 0







another "cost" of congestion:


when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!


Causes/costs of congestion: insights


- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream












Approaches towards congestion control

End-end congestion control:


- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



TCP congestion control: AIMD

 approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

Additive Increase Multiplicative <u>D</u>ecrease increase sending rate by 1 cut sending rate in half at maximum segment size every each loss event RTT until loss detected Sending rate **AIMD** sawtooth behavior: probing TCP sender for bandwidth

time

TCP AIMD: more


Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD a distributed, asynchronous algorithm has been shown to:
 - optimize congested flow rates network wide!
 - have desirable stability properties

TCP congestion control: details



TCP sending behavior:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes


TCP rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

- TCP sender limits transmission: LastByteSent- LastByteAcked < cwnd
- cwnd is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = 1 MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received

summary: initial rate is slow, but ramps up exponentially fast




TCP: detecting, reacting to loss

- loss indicated by timeout:
 - cwnd set to 1 MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly

(do not set cwnd to "half window + 3" as shown in textbook)

TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)


TCP: from slow start to congestion avoidance



Implementation:

- variable ssthresh (slow start threshold)
- on loss event, **ssthresh** is set to 1/2 of **cwnd** just before loss event

Summary: TCP congestion control



TCP throughput

- avg. TCP throughput as function of window size, RTT?
 - ignore slow start, assume there is always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is ¾ W
 - avg. thruput is 3/4W per RTT

avg TCP throughput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec

TCP over "long, fat pipes"

- example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:


TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of L = 2·10⁻¹⁰
 - a very small loss rate!
- versions of TCP for long, high-speed scenarios

Explicit congestion notification (ECN)


TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
 - policy to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



TCP fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Q: is TCP Fair?

Example: two competing TCP sessions:

- additive increase gives slope of 1, as throughput increases
- multiplicative decrease decreases throughput proportionally



Is TCP fair? -

A: Yes, under idealized assumptions:

- same RTT
- fixed number of sessions only in congestion avoidance

Fairness: must all network apps be "fair"?

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss
- there is no "Internet police" policing use of congestion control

Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this, e.g., link of rate R with 9 existing connections:
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2

Chapter 3: summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation, implementation in the Internet
 - UDP
 - TCP

Up next:

- leaving the network "edge" (application, transport layers)
- into the network "core"
- two network-layer chapters:
 - data plane
 - control plane