Урок 06. Настройка роутеров и РС

1. Настраиваем DHCP на роутерах.

Настраиваем интерфейс. Задаем пул адресов. Добавляем роутер по умолчанию. Добавляем DNS сервер. Сохраняем настройки.

1. 1. Router0

Router>enable

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface fa0/0

Router(config-if)#ip addr 10.0.1.1 255.255.255.0

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip dhcp pool pool.10.0.1

Router(dhcp-config)#network 10.0.1.1 255.255.255.0

Router(dhcp-config)#default-router 10.0.1.1

Router(dhcp-config)#dns-server 8.8.8.8

Router(dhcp-config)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#write

Building configuration...

[OK]

1. 2. Router1

Router>enable

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface fa0/0

Router(config-if)#ip addr 10.0.2.1 255.255.255.0

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip dhcp pool pool.10.0.2

Router(dhcp-config)#network 10.0.2.1 255.255.255.0

Router(dhcp-config)#default-router 10.0.2.1

Router(dhcp-config)#dns-server 8.8.8.8

Router(dhcp-config)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#write

Building configuration...

[OK]

1. 3. Router2

Router>enable

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface fa0/0

Router(config-if)#ip addr 10.0.3.1 255.255.255.0

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#ip dhcp pool pool.10.0.3

Router(dhcp-config)#network 10.0.3.1 255.255.255.0

Router(dhcp-config)#default-router 10.0.3.1

Router(dhcp-config)#dns-server 8.8.8.8

Router(dhcp-config)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#write

Building configuration...

[OK]

- 2. На всех компьютерах сетей устанавливаем получение IP по DHCP (Config -> DHCP)
- 3. Проверяем DHCP:

дожидаемся получения IP и пингуем каждый PC в подсети с каждого PC в подсети.

4. Настраиваем на роутерах RIP2 маршрутизацию. Статические маршруты (назначены в практическом задании к уроку 4) имеют преимущество перед динамическими маршрутами RIP, поэтому вначале удаляем.

4. 1. Router0

Router>enable

Router#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

- C 172.16.0.0/16 is directly connected, FastEthernet5/0
- C 172.17.0.0/16 is directly connected, FastEthernet4/0
- C 192.168.1.0/24 is directly connected, FastEthernet0/0
- S 192.168.2.0/24 [1/0] via 172.17.0.2
- S 192.168.3.0/24 [1/0] via 172.16.0.2

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#no ip route 192.168.2.0 255.255.255.0

Router(config)#no ip route 192.168.3.0 255.255.255.0

Router(config)#route rip

Router(config-router)#version 2

Router(config-router)#network 10.0.1.0

Router(config-router)#network 172.16.0.0

Router(config-router)#network 172.17.0.0

Router(config-router)#no auto-summary

Router(config-router)#exit

Router(config)#exit

Router#write

Building configuration...

[OK]

4. 2. Router1

Router>enable

Router#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

- C 172.17.0.0/16 is directly connected, FastEthernet4/0
- C 172.18.0.0/16 is directly connected, FastEthernet5/0
- S 192.168.1.0/24 [1/0] via 172.17.0.1
- C 192.168.2.0/24 is directly connected, FastEthernet0/0
- S 192.168.3.0/24 [1/0] via 172.18.0.2

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#no ip route 192.168.1.0 255.255.255.0

Router(config)#no ip route 192.168.3.0 255.255.255.0

Router(config)#route rip

Router(config-router)#version 2

Router(config-router)#network 10.0.2.0

Router(config-router)#network 172.17.0.0

Router(config-router)#network 172.18.0.0

Router(config-router)#no auto-summary

Router(config-router)#exit

Router(config)#exit

Router#write

Building configuration...

[OK]

4. 3. Router2

Router>enable

Router#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

- C 172.16.0.0/16 is directly connected, FastEthernet5/0
- C 172.18.0.0/16 is directly connected, FastEthernet4/0
- S 192.168.1.0/24 [1/0] via 172.16.0.1
- S 192.168.2.0/24 [1/0] via 172.18.0.1
- C 192.168.3.0/24 is directly connected, FastEthernet0/0

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#no ip route 192.168.1.0 255.255.255.0

Router(config)#no ip route 192.168.2.0 255.255.255.0

Router(config)#route rip

Router(config-router)#version 2

Router(config-router)#network 10.0.3.0

Router(config-router)#network 172.16.0.0

Router(config-router)#network 172.18.0.0

Router(config-router)#no auto-summary

Router(config-router)#exit

Router(config)#exit

Router#write

Building configuration...

[OK]

5. Проверяем:

Пингуем с каждого РС одной подсети каждый РС других подсетей.