

Applied Linear Algebra

Norm and Distance

Devi Prasad M
Manipal School of Information Sciences
Manipal

August 2026

The *Euclidean norm* of an n -vector $\mathbf{x}$, denoted $\|\mathbf{x}\|$, is the squareroot of the sum of the squares of its elements,

$$\begin{aligned}\|\mathbf{x}\| &= \sqrt{x_1^2 + x_2^2 + \cdots + x_n^2} \\ &= \sqrt{\mathbf{x}^T \mathbf{x}} \\ &= \|\mathbf{x}\|_2\end{aligned}$$

This is also called as the *magnitude* of a vector.

We will avoid calling it the *length* of a vector.

$$\|\mathbf{0}\| = 0$$

$$\|\mathbf{e}_i\| = 1$$

$$\|[c]\| = c$$

$$\|\mathbf{1}_n\| = \sqrt{n}$$

we use terms such as a *small* norm and *large* norm when we want to compare the magnitudes of vectors.

- Nonnegative homogeneity. $\|\beta \mathbf{x}\| = |\beta| \|\mathbf{x}\|$
- Nonnegativity. $\|\mathbf{x}\| \geq 0$
- Definiteness. $\|\mathbf{x}\| = 0$ only if $\mathbf{x} = \mathbf{0}$.
- Triangle inequality. $\|\mathbf{x} + \mathbf{y}\| \leq \|\mathbf{x}\| + \|\mathbf{y}\|$.

- Nonnegative homogeneity. $\|\beta \mathbf{x}\| = |\beta| \|\mathbf{x}\|$
- Nonnegativity. $\|\mathbf{x}\| \geq 0$
- Definiteness. $\|\mathbf{x}\| = 0$ only if $\mathbf{x} = \mathbf{0}$.
- Triangle inequality. $\|\mathbf{x} + \mathbf{y}\| \leq \|\mathbf{x}\| + \|\mathbf{y}\|$.

Quiz:

Example for triangle inequality?

a norm is a function from a real or complex vector space to the non-negative real numbers that behaves in certain ways like the distance from the origin: it commutes with scaling, obeys a form of the triangle inequality, and is zero only at the origin.

Definition

General Norm A *general norm* is any real-valued function of an n -vector that satisfies the four properties listed above.

Two examples of general norms:

$$\textbf{1-norm} \quad \|x\|_1 = |x_1| + \cdots + |x_n|$$

$$\textbf{Infinity-norm} \quad \|x\|_\infty = \max\{|x_1|, \dots, |x_n|\}$$

Infinity norm $\|\cdot\|_\infty$ is extensively used in ML-DSA, NIST's PQC signature scheme.

Root Mean Square Value

The norm is related to the root-mean-square (RMS) value of an n -vector $\mathbf{x}$:

$$\begin{aligned}\text{rms}(\mathbf{x}) &= \sqrt{\frac{x_1^2 + \cdots + x_n^2}{n}} \\ &= \frac{\|\mathbf{x}\|}{\sqrt{n}}\end{aligned}$$

The RMS value of a vector $\mathbf{x}$ is useful when comparing norms of vectors with different dimensions.

The RMS value tells us what a 'typical' value of $|x_i|$ is.

If all the entries of a vector are close to α , then the RMS value of the vector is $|\alpha|$.

- 1805 — Adrien-Marie Legendre. His criterion was to make the sum of the squares of the errors as small as possible.
- Karl Pearson is generally credited with introducing the term “root-mean-square” in 1895, although the underlying mathematical quantity, and even root-mean-square deviation, predates the terminology.
- Pearson’s important contribution was to name and formalize terminology around it.
- In his 1893 lectures, he introduced *standard deviation* as a replacement for the older *root mean square* error.

If $\mathbf{a}$ and $\mathbf{b}$ are n -vectors,

$$\mathbf{dist}(\mathbf{a}, \mathbf{b}) = \|\mathbf{a} - \mathbf{b}\|$$

The *RMS deviation* between vectors $\mathbf{a}$ and $\mathbf{b}$ is

$$\begin{aligned} \text{RMSD} &= \sqrt{\frac{1}{n} \sum_{i=1}^n (a_i - b_i)^2} \\ &= \frac{\mathbf{dist}(\mathbf{a}, \mathbf{b})}{\sqrt{n}} \end{aligned}$$

For most choices of $\mathbf{b}$, however, there is no n -vector $\mathbf{x}$ for which $\mathbf{Ax} = \mathbf{b}$. As a compromise, we seek an $\mathbf{x}$ for which $\mathbf{r} = \mathbf{Ax} - \mathbf{b}$, which we call the *residual* (for the equations $\mathbf{Ax} - \mathbf{b}$), is as small as possible.

We should choose $\mathbf{x}$ so as to minimize the norm of the residual, $\mathbf{Ax} - \mathbf{b}$.

Minimizing the norm of the residual and its square are the same, so we can just as well minimize

$$\|Ax - b\|^2 = \|r\|^2 = r_1^2 + \cdots + r_m^2,$$

the sum of squares of the residuals.