

Accessing External Services

🐧 11 minute read 🗸 page test

Because all outbound traffic from an Istio-enabled pod is redirected to its sidecar proxy by default, accessibility of URLs outside of the cluster depends on the configuration of the proxy. By default, Istio configures the Envoy proxy to pass through requests

- for unknown services. Although this provides a convenient way to get started with Istio, configuring stricter control is usually preferable.
- This task shows you how to access external services in three different ways:
- 1. Allow the Envoy proxy to pass requests through to services that are not configured inside the mesh.
- 2. Configure service entries to provide controlled access to external services.

3. Completely bypass the Envoy proxy for a specific

range of IPs.


Before you begin

- Set up Istio by following the instructions in the Installation guide. Use the demo configuration profile or otherwise enable Envoy's access logging.
- Deploy the sleep sample app to use as a test source for sending requests. If you have automatic sidecar injection enabled, run the following command to deploy the sample app:

```
$ kubectl apply -f @samples/sleep/sleep.yaml@
```

Otherwise, manually inject the sidecar before deploying the sleep application with the following command:

```
$ kubectl apply -f <(istioctl kube-inject -f @samples/sleep
/sleep.yaml@)</pre>
```



• Set the SOURCE_POD environment variable to the

name of your source pod:

Envoy passthrough to external services

Istio has an installation option,
meshConfig.outboundTrafficPolicy.mode, that configures
the sidecar handling of external services, that is,

Istio proxy lets calls to unknown services pass through. If the option is set to REGISTRY ONLY, then the Istio proxy blocks any host without an HTTP service or service entry defined within the mesh. ALLOW ANY is the default value, allowing you to start evaluating

Istio guickly, without controlling access to external services. You can then decide to configure access to

external services later.

those services that are not defined in Istio's internal service registry. If this option is set to ALLOW ANY, the

- 1. To see this approach in action you need to ensure that your Istio installation is configured with the
 - meshConfig.outboundTrafficPolicy.mode option set to

ALLOW_ANY. Unless you explicitly set it to REGISTRY_ONLY mode when you installed Istio, it is probably enabled by default.

Run the following command to verify that meshConfig.outboundTrafficPolicy.mode option is set to ALLOW_ANY or is omitted:

```
$ kubectl get istiooperator installed-state -n istio-system
-o jsonpath='{.spec.meshConfig.outboundTrafficPolicy.mode}
'
ALLOW_ANY
```

You should either see ALLOW_ANY or no output (default ALLOW_ANY).

If you have explicitly configured REGISTRY_ONLY mode, you can change it by rerunning your original istictl install command with the changed setting, for example:

\$ istioctl install <flags-you-used-to-install-Is
tio> --set meshConfig.outboundTrafficPolicy.mode
=ALLOW_ANY

 Make a couple of requests to external HTTPS services from the SOURCE_POD to confirm successful 200 responses:

```
$ kubectl exec "$SOURCE_POD" -c sleep -- curl -sSI https://
www.google.com | grep "HTTP/"; kubectl exec "$SOURCE_POD"
-c sleep -- curl -sI https://edition.cnn.com | grep "HTTP/"
HTTP/2 200
HTTP/2 200
```

from your mesh.

This simple approach to access external services, has

Congratulations! You successfully sent egress traffic

the drawback that you lose Istio monitoring and control for traffic to external services. The next section shows you how to monitor and control your mesh's access to external services.

Controlled access to external services

Using Istio ServiceEntry configurations, you can access any publicly accessible service from within your Istio cluster. This section shows you how to configure

access to an external HTTP service, httpbin.org, as well as an external HTTPS service, www.google.com without

losing Istio's traffic monitoring and control features.

Change to the blocking-by-

default policy

To demonstrate the controlled way of enabling access to external services, you need to change the meshConfig.outboundTrafficPolicy.mode option from the ALLOW_ANY mode to the REGISTRY_ONLY mode.

You can add controlled access to services that are already accessible in ALLOW_ANY mode. This way, you can start using Istio features on some external services without blocking any others. Once you've configured all of

```
your services, you can then switch the mode to REGISTRY_ONLY to block any other unintentional accesses.
```

option to REGISTRY_ONLY.

If you used an IstioOperator CR to install Istio, add the following field to your configuration:

1. Change the meshConfig.outboundTrafficPolicy.mode

```
spec:
  meshConfig:
  outboundTrafficPolicy:
    mode: REGISTRY ONLY
```

Otherwise, add the equivalent setting to your original istictl install command, for example:

2. Make a couple of requests to external HTTPS services from SOURCE_POD to verify that they are now blocked:

```
$ kubectl exec "$SOURCE_POD" -c sleep -- curl -sI https://w
ww.google.com | grep "HTTP/"; kubectl exec "$SOURCE_POD" -
c sleep -- curl -sI https://edition.cnn.com | grep "HTTP/"
command terminated with exit code 35
command terminated with exit code 35
```



It may take a while for the configuration change to propagate, so you might still get successful connections. Wait for several seconds and then retry the last command.

Access an external HTTP service

 Create a ServiceEntry to allow access to an external HTTP service.

> DNS resolution is used in the service entry below as a security measure. Setting the resolution to NONE opens a possibility for attack. A malicious client could pretend that it's accessing httpbin.org by setting it in the HOST header, while really connecting to a different IP (that is not associated with httpbin.org). The Istio sidecar proxy will trust the HOST header, and incorrectly allow the traffic,

IP address of a different host. That host can be a malicious site, or a legitimate site, prohibited by the mesh security policies. With DNS resolution, the sidecar proxy

even though it is being delivered to the

With DNS resolution, the sidecar proxy will ignore the original destination IP address and direct the traffic to httpbin.org, performing a DNS query to get an IP address of httpbin.org.

```
metadata:
       name: httpbin-ext
     spec:
       hosts:
       - httpbin.org
       ports:
       - number: 80
         name: http
         protocol: HTTP
       resolution: DNS
       location: MESH EXTERNAL
     E0F
2. Make a request to the external HTTP service from
   SOURCE POD:
```

\$ kubectl apply -f - <<EOF

kind: ServiceEntry

apiVersion: networking.istio.io/v1alpha3

```
$ kubectl exec "$SOURCE_POD" -c sleep -- curl -sS http://ht
tpbin.org/headers
  "headers": {
    "Accept": "*/*",
    "Host": "httpbin.org",
    "X-Envoy-Decorator-Operation": "httpbin.org:80/*",
    . . .
```

Note the headers added by the Istio sidecar proxy: X-Envoy-Decorator-Operation.

3. Check the log of the sidecar proxy of ${\tt SOURCE_POD:}$

\$ kubectl logs "\$SOURCE_POD" -c istio-proxy | tail
[2019-01-24T12:17:11.640Z] "GET /headers HTTP/1.1" 200 - 0
599 214 214 "-" "curl/7.60.0" "17fde8f7-fa62-9b39-8999-3023
24e6def2" "httpbin.org" "35.173.6.94:80" outbound|80||httpb
in.org - 35.173.6.94:80 172.30.109.82:55314 -

Note the entry related to your HTTP request to httpbin.org/headers.

Access an external HTTPS service

Create a ServiceEntry to allow access to an

external HTTPS service.

```
$ kubectl apply -f - <<EOF
apiVersion: networking.istio.io/v1alpha3
kind: ServiceEntrv
metadata:
  name: google
spec:
  hosts:
  - www.google.com
  ports:
  - number: 443
    name: https
    protocol: HTTPS
  resolution: DNS
  location: MESH EXTERNAL
FOF
```

2. Make a request to the external HTTPS service

from SOURCE_POD:

\$ kubectl exec "\$SOURCE_POD" -c sleep -- curl -sSI https://

3. Check the log of the sidecar proxy of SOURCE_POD:

www.google.com | grep "HTTP/"

HTTP/2 200

```
$ kubectl logs "$SOURCE_POD" -c istio-proxy | tail
[2019-01-24T12:48:54.977Z] "- - -" 0 - 601 17766 1289 - "-"
"-" "-" "-" "172.217.161.36:443" outbound|443||www.google.
com 172.30.109.82:59480 172.217.161.36:443 172.30.109.82:59
478 www.google.com
```

Note the entry related to your HTTPS request to www.google.com.

Manage traffic to external services

Similar to inter-cluster requests, Istio routing rules can also be set for external services that are accessed using ServiceEntry configurations. In this example, you

set a timeout rule on calls to the httpbin.org service.

 From inside the pod being used as the test source, make a curl request to the /delay endpoint of the httpbin.org external service:

```
null -sS -w "%{http_code}\n" http://httpbin.org/delay/5
200
real 0m5.024s
user 0m0.003s
sys 0m0.003s

The request should return 200 (OK) in
```

\$ kubectl exec "\$SOURCE_POD" -c sleep -- time curl -o /dev/

approximately 5 seconds.2. Use kubectl to set a 3s timeout on calls to the

httpbin.org external service:

```
apiVersion: networking.istio.io/v1alpha3
kind: VirtualService
metadata:
  name: httpbin-ext
spec:
  hosts:
    - httpbin.org
  http:
  - timeout: 3s
    route:
      - destination:
          host: httpbin.org
        weight: 100
EOF
```

\$ kubectl apply -f - <<EOF

3. Wait a few seconds, then make the *curl* request again:

```
$ kubectl exec "$SOURCE_POD" -c sleep -- time curl -o /dev/
null -sS -w "%{http_code}\n" http://httpbin.org/delay/5
504
real    0m3.149s
user    0m0.004s
sys    0m0.004s
```

This time a 504 (Gateway Timeout) appears after 3 seconds. Although httpbin.org was waiting 5 seconds, Istio cut off the request at 3 seconds.

Cleanup the controlled access to external services

\$ kubectl delete serviceentry httpbin-ext google
\$ kubectl delete virtualservice httpbin-ext --ignore-not-found=t
rue

Direct access to external services

If you want to completely bypass Istio for a specific IP range, you can configure the Envoy sidecars to prevent them from intercepting external requests. To set up the bypass, change either the

global.proxy.excludeIPRanges configuration option and update the istio-sidecar-injector configuration map using the kubectl apply command. This can also be configured on a pod by setting corresponding annotations such as

global.proxy.includeIPRanges or the

traffic.sidecar.istio.io/includeOutboundIPRanges. After updating the istio-sidecar-injector configuration, it affects all future application pod deployments.

Unlike Envoy passthrough to external services, which uses the ALLOW_ANY traffic policy to

passthrough calls to unknown services, this approach completely bypasses the sidecar, essentially disabling all of Istio's features for the specified IPs. You cannot incrementally add service entries for specific destinations,

instruct the Istio sidecar proxy to

as you can with the ALLOW_ANY approach.

Therefore, this configuration approach is only recommended as a last resort when, for performance or other reasons, external access cannot be configured using the sidecar.

These IP range values depend on the platform where your cluster runs.

global.proxy.includeIPRanges configuration option to the IP range or ranges used for internal cluster services.

A simple way to exclude all external IPs from being

redirected to the sidecar proxy is to set the

Determine the internal IP ranges for your platform

Set the value of values.global.proxy.includeIPRanges according to your cluster provider.

IBM Cloud Private

 Get your service_cluster_ip_range from IBM Cloud Private configuration file under cluster/config.yaml:

```
$ grep service_cluster_ip_range cluster/config.yaml
```

The following is a sample output:

```
service_cluster_ip_range: 10.0.0.1/24
```

2. Use --set
 values.global.proxy.includeIPRanges="10.0.0.1/24"

Use --set

values.global.proxy.includeIPRanges="172.30.0.0/16\,172.

IBM Cloud Kubernetes Service

Google Container Engine

21.0.0/16\,10.10.10.0/24"

(GKE)

The ranges are not fixed, so you will need to run the gcloud container clusters describe command to

gcloud container clusters describe command to determine the ranges to use. For example:

```
$ gcloud container clusters describe XXXXXXX --zone=XXXXXX | gre
p -e clusterIpv4Cidr -e servicesIpv4Cidr
clusterIpv4Cidr: 10.4.0.0/14
servicesIpv4Cidr: 10.7.240.0/20
```

values.global.proxy.includeIPRanges="10.4.0.0/14\,10.7.2

40.0/20"

Azure Container Service(ACS)

Use --set

values.global.proxy.includeIPRanges="10.244.0.0/16\,10.2

40.0.0/16

Minikube, Docker For Desktop, Bare Metal

Use --set

The default value is 10.96.0.0/12, but it's not fixed.
Use the following command to determine your actual

```
value:
```

```
$ kubectl describe pod kube-apiserver -n kube-system | grep 'ser
vice-cluster-ip-range'
    --service-cluster-ip-range=10.96.0.0/12
```

values.global.proxy.includeIPRanges="10.96.0.0/12"

Configuring the proxy bypass

Remove the service entry and virtual service previously deployed in this guide.

Update your istio-sidecar-injector configuration map using the IP ranges specific to your platform. For example, if the range is 10.0.0.1/24, use the following command:

s.global.proxy.includeIPRanges="10.0.0.1/24"

Use the same command that you used to install Istio

\$ istioctl install <flags-you-used-to-install-Istio> --set value

values.global.proxy.includeIPRanges="10.0.0.1/24".

and add --set

Access the external services

Because the bypass configuration only affects new deployments, you need to terminate and then redeploy the sleep application as described in the

Before you begin **section.**

and redeploying the sleep application, the Istio sidecar will only intercept and manage internal

After updating the istio-sidecar-injector configmap

requests within the cluster. Any external request

bypasses the sidecar and goes straight to its intended destination. For example:

```
$ kubectl exec "$SOURCE_POD" -c sleep -- curl -sS http://httpbin
 .org/headers
   "headers": {
     "Accept": "*/*",
     "Host": "httpbin.org",
Unlike accessing external services through HTTP or
```

HTTPS, you don't see any headers related to the Istio sidecar and the requests sent to external services do not appear in the log of the sidecar. Bypassing the Istio sidecars means you can no longer monitor the access to external services.

Cleanup the direct access to external services

Update the configuration to stop bypassing sidecar proxies for a range of IPs:

```
$ istioctl install <flags-you-used-to-install-Istio>
```

Understanding what happened In this task you looked at three ways to call external services from an Istio mesh:1. Configuring Envoy to allow access to any external service.

external service inside the mesh. This is the recommended approach.3. Configuring the Istio sidecar to exclude external

2. Use a service entry to register an accessible

IPs from its remapped IP table.

The first approach directs traffic through the Istio sidecar proxy, including calls to services that are

unknown inside the mesh. When using this approach, you can't monitor access to external services or take advantage of Istio's traffic control features for them. To easily switch to the second approach for specific services, simply create service entries for those external services. This process allows you to initially access any external service and then later decide whether or not to control access, enable traffic monitoring, and use traffic control features as needed. The second approach lets you use all of the same Istio service mesh features for calls to services inside or outside of the cluster. In this task, you learned how to rule for calls to an external service.

The third approach bypasses the Istio sidecar proxy,

monitor access to external services and set a timeout

server. However, configuring the proxy this way does require cluster-provider specific knowledge and configuration. Similar to the first approach, you also

giving your services direct access to any external

configuration. Similar to the first approach, you also lose monitoring of access to external services and you can't apply Istio features on traffic to external services.

Security note

Note that configuration examples in this task do not enable secure egress traffic control in Istio. A malicious application can bypass the Istio sidecar proxy and access any external service without Istio control.

To implement egress traffic control in a more secure way, you must direct egress traffic through an egress

gateway and review the security concerns described in the additional security considerations section.

Cleanup

Shutdown the sleep service:

\$ kubectl delete -f @samples/sleep/sleep.yaml@