Customizing the installation configuration

Prerequisites

7 minute read

Download the Istio release.
 Perform any necessary platform-specific setup.
 Check the Requirements for Pods and Services.

Before you begin, check the following prerequisites:

complete API for customizing the configuration.

• The IstioOperator API

In addition to installing any of Istio's built-in configuration profiles, istioctl install provides a

The configuration parameters in this API can be set individually using --set options on the command line.

For example, to enable debug logging in a default configuration profile, use this command: \$ istioctl install --set values.global.logging.level=debug

Alternatively, the IstioOperator configuration can be specified in a YAML file and passed to isticctl using

the -f option: \$ istioctl install -f samples/operator/pilot-k8s.yaml

For backwards compatibility, the previous Helm installation options, with the exception of Kubernetes resource settings, are also fully supported. To set them on the command line, prepend the option name with "values.". For example, the following command overrides the pilot.traceSampling Helm configuration option:

```
$ istioctl install --set values.pilot.traceSampling=0
.1
```

Helm values can also be set in an IstioOperator CR (YAML file) as described in Customize Istio settings using the Helm API, below.

If you want to set Kubernetes resource settings, use the IstioOperator API as described in Customize Kubernetes settings.

#### Identify an Istio component

The IstioOperator API defines components as shown in the table below:

Components

pilot	
ingressGateways	
egressGateways	
cni	
istiodRemote	
The configurable settings for each of these	
components are available in the API under components.	

base

change (to false) the enabled setting for the pilot component, use --set components.pilot.enabled=false or set it in an IstioOperator resource like this:

<component name>. For example, to use the API to

apiVersion: install.istio.io/v1alpha1

kind: IstioOperator

components:
 pilot:

spec:

```
enabled: false

All of the components also share a common API for changing Kubernetes-specific settings, under components, <component name>, k8s, as described in the
```

Ç

following section.

#### Customize Kubernetes settings

The IstioOperator API allows each component's Kubernetes settings to be customized in a consistent way.

Each component has a KubernetesResourceSpec, which allows the following settings to be changed. Use this list to identify the setting to customize:

 Resources 2. Readiness probes 3. Replica count 4. HorizontalPodAutoscaler PodDisruptionBudget 6. Pod annotations 7. Service annotations 8. ImagePullPolicy 9. Priority class name Node selector 1. Affinity and anti-affinity

3. Toleration
4. Strategy
5. Env
6. Pod security context
All of these Kubernetes settings use the Kubernetes

2. Service

Pilot:

used for reference.

The following example overlay file adjusts the resources and horizontal pod autoscaling settings for

API definitions, so Kubernetes documentation can be

```
apiVersion: install.istio.io/v1alpha1
 kind: IstioOperator
 spec:
   components:
     pilot:
       k8s:
         resources:
           requests:
             cpu: 1000m # override from default 500m
             memory: 4096Mi # ... default 2048Mi
         hpaSpec:
           maxReplicas: 10 # ... default 5
           minReplicas: 2 # ... default 1
Use isticated install to apply the modified settings to
the cluster:
```

\$ istioctl install -f samples/operator/pilot-k8s.yaml

# Customize Istio settings using the Helm API

The IstioOperator API includes a pass-through interface to the Helm API using the values field.

The following YAML file configures global and Pilot settings through the Helm API:

```
apiVersion: install.istio.io/v1alpha1
kind: IstioOperator
spec:
  values:
   pilot:
     traceSampling: 0.1 # override from 1.0
   global:
     monitoringPort: 15014
```

Helm and IstioOperator APIs, including Kubernetes resources, namespaces and enablement settings. The Istio community recommends using the IstioOperator API as it is more consistent, is validated, and follows the community graduation process.

Some parameters will temporarily exist in both the

### **Configure gateways**

essgateway

Gateways are a special type of component, since multiple ingress and egress gateways can be defined.

In the IstioOperator API, gateways are defined as a list type. The default profile installs one ingress gateway, called istio-ingressgateway. You can inspect the default

values for this gateway:

\$ istioctl profile dump --config-path components.ingressGateways
\$ istioctl profile dump --config-path values.gateways.istio-ingr

These commands show both the IstioOperator and

together to define the generated gateway resources. The built-in gateways can be customized just like any other component.

Helm settings for the gateway, which are used

From 1.7 onward, the gateway name must always be specified when overlaying. Not specifying any name no longer defaults to

A new user gateway can be created by adding a new

istio-ingressgateway **Or** istio-egressgateway.

# list entry:

apiVersion: install.istio.io/v1alpha1

```
kind: IstioOperator
spec:
  components:
    ingressGateways:
      - name: istio-ingressgateway
        enabled: true
      - namespace: user-ingressgateway-ns
        name: ilb-gateway
        enabled: true
        k8s:
          resources:
            requests:
              cpu: 200m
          serviceAnnotations:
            cloud.google.com/load-balancer-type: "internal"
          service:
```

```
port: 8060
targetPort: 8060
name: tcp-citadel-grpc-tls
port: 5353
name: tcp-dns
```

ports:

Note that Helm values (spec.values.gateways.istioingressgateway/egressgateway) are shared by all ingress/egress gateways. If these must be customized per gateway, it is recommended to use a separate IstioOperator CR to generate a manifest for the user

gateways, separate from the main Istio installation:

```
kind: IstioOperator
spec:
  profile: empty
  components:
    ingressGateways:
      - name: ilb-gateway
        namespace: user-ingressgateway-ns
        enabled: true
        # Copy settings from istio-ingressgateway as needed.
  values:
    gateways:
      istio-ingressgateway:
        debug: error
```

#### Advanced install

apiVersion: install.istio.io/v1alpha1

#### customization

# Customizing external charts and profiles

The istioctl install, manifest generate and profile commands can use any of the following sources for charts and profiles:

 compiled in charts. This is the default if no -manifests option is set. The compiled in charts are

- the same as those in the manifests/ directory of the Istio release .tgz.charts in the local file system, e.g., istioctl
  - install --manifests istio-1.11.3/manifests
- https://github.com/istio/istio/releases/download/1.1 1.3/istio-1.11.3-linux-arm64.tar.gz

• charts in GitHub, e.g., istioctl install --manifests

Local file system charts and profiles can be customized by editing the files in manifests. For extensive changes, we recommend making a copy of the manifests directory and make changes there. Note,

however, that the content layout in the manifests

directory must be preserved.

Profiles, found under manifests/profiles/, can be edited and new ones added by creating new files with

the desired profile name and a .yaml extension.

istioctl scans the profiles subdirectory and all profiles found there can be referenced by name in the IstioOperatorSpec profile field. Built-in profiles are overlaid on the default profile YAML before user overlays are applied. For example, you can create a new profile file called custom1.yaml which customizes

some settings from the default profile, and then apply

a user overlay file on top of that:

In this case, the custom1.yaml and user-overlay.yaml files

will be overlaid on the default.yaml file to obtain the final values used as the input for manifest generation.

\$ istioctl manifest generate --manifests mycharts/ --set profile

In general, creating new profiles is not necessary since a similar result can be achieved by passing multiple overlay files. For example, the command above is equivalent to passing two user overlay files:

\$ istioctl manifest generate --manifests mycharts/ -f manifests/

profiles/custom1.yaml -f path-to-user-overlay.yaml

Creating a custom profile is only required if you need to refer to the profile by name through the IstioOperatorSpec.

#### Patching the output manifest

The IstioOperator CR, input to istioctl, is used to generate the output manifest containing the

Kubernetes resources to be applied to the cluster. The output manifest can be further customized to add, modify or delete resources through the

Istiooperator overlays API, after it is generated but before it is applied to the cluster.

The following example overlay file (patch.yaml)

demonstrates the type of output manifest patching that can be done:

```
apiVersion: install.istio.io/v1alpha1
kind: IstioOperator
spec:
    profile: empty
    hub: docker.io/istio
    tag: 1.1.6
    components:
        pilot:
        enabled: true
        namespace: istio-control
```

```
overlays:
          - kind: Deployment
            name: istiod
            patches:
              # Select list item by value
              - path: spec.template.spec.containers.[name:discov
ery].args.[30m]
                value: "60m" # overridden from 30m
              # Select list item by key:value
              - path: spec.template.spec.containers.[name:discov
ery].ports.[containerPort:8080].containerPort
                value: 1234
              # Override with object (note | on value: first lin
e)
              - path: spec.template.spec.containers.[name:discov
ery].env.[name:POD NAMESPACE].valueFrom
                value: I
                  fieldRef:
                    apiVersion: v2
```

k8s:

```
# Deletion of map item
              - path: spec.template.spec.containers.[name:discov
 ery].securityContext

    kind: Service

            name: istiod
            patches:
              - path: spec.ports.[name:https-dns].port
                value: 11111 # OVERRIDDEN
Passing the file to istioctl manifest generate -f
patch.yaml applies the above patches to the default
profile output manifest. The two patched resources
```

will be modified as shown below (some parts of the

fieldPath: metadata.myPath

- path: spec.template.spec.containers.[name:discov

# Deletion of list item

ery].env.[name:REVISION]

# resources are omitted for brevity):

apiVersion: apps/v1

```
kind: Deployment
metadata:
  name: istind
spec:
  template:
    spec:
      containers:
      - args:
        - 60m
        env:
        - name: POD NAMESPACE
          valueFrom:
            fieldRef:
              apiVersion: v2
              fieldPath: metadata.myPath
        name: discovery
```

```
apiVersion: v1
 kind: Service
 metadata:
  name: istiod
 spec:
  ports:
   - name: https-dns
    port: 11111
Note that the patches are applied in the given order.
Each patch is applied over the output from the
```

previous patch. Paths in patches that don't exist in

the output manifest will be created.

ports:

containerPort: 1234

### List item path selection

Both the isticctl --set flag and the k8s.overlays field in Isticoperator CR support list item selection by [index], [value] or by [key:value]. The -set flag also creates any intermediate nodes in the path that are missing in the resource.